# 配置 DNS 服务器

## StorageGRID

NetApp
May 03, 2022

This PDF was generated from https://docs.netapp.com/zh-cn/storagegrid-116/maintain/modifying-dns-configuration-for-single-grid-node.html on May 03, 2022. Always check docs.netapp.com for the latest.

# 目录

配置 DNS 服务器 . . . . . 1
修改单网格节点的 DNS 配置 . . . . . 1

# 配置 DNS 服务器

## 您可以添加，删除和更新域名系统（DNS）服务器，以便使用完全限定域名（FQDN）主机名，而不是 IP 地址。

您需要什么？ **#8217**；将需要什么

- 您必须使用登录到网格管理器 支持的 Web 浏览器。
- 您必须具有维护或根访问权限。
- 您必须具有要配置的 DNS 服务器的 IP 地址。

通过指定 DNS 服务器信息，您可以对电子邮件或 SNMP 通知和 AutoSupport 使用完全限定域名（FQDN）主机名，而不是 IP 地址。建议至少指定两个 DNS 服务器。

> 为 DNS 服务器提供 2 到 6 个 IP 地址。通常，选择每个站点在发生网络隔离时可在本地访问的 DNS 服务器。这是为了确保已隔离的站点可以继续访问 DNS 服务。配置网格范围的 DNS 服务器列表后，您可以 进一步自定义每个节点的 DNS 服务器列表。

如果省略 DNS 服务器信息或 DNS 服务器信息配置不正确，则会在每个网格节点的 SSM 服务上触发 DNST 警报。如果 DNS 配置正确且新服务器信息已到达所有网格节点，则警报将清除。

步骤

1. 选择 * 维护 * > * 网络 * > * DNS 服务器 * 。
2. 在服务器部分中，根据需要添加更新或删除 DNS 服务器条目。

   最佳做法是，每个站点至少指定两个 DNS 服务器。最多可以指定六个 DNS 服务器。

3. 单击 * 保存 * 。

# 修改单网格节点的 DNS 配置

## 您可以运行一个脚本，为每个网格节点配置不同的 DNS ，而不是在整个部署中全局配置域名系统（Domain Name System， DNS）。

通常，您应使用网格管理器上的 * 维护 * > * 网络 * > * DNS 服务器 * 选项来配置 DNS 服务器。只有在需要为不同网格节点使用不同 DNS 服务器时，才可使用以下脚本。

1. 登录到主管理节点：
   a. 输入以下命令： `ssh admin@ primary_Admin_Node_IP_`
   b. 输入 `passwords.txt` 文件中列出的密码。
   c. 输入以下命令切换到 root： `su -`
   d. 输入 `passwords.txt` 文件中列出的密码。

      以 root 用户身份登录时，提示符将从 `$` 更改为 `#` 。

   e. 将 SSH 专用密钥添加到 SSH 代理。输入： `ssh-add`

f. 输入 `passwords.txt` 文件中列出的 SSH 访问密码。

2. 【登录到要使用自定义 DNS 配置更新的节点： `ssh node_ip_address`
3. 运行 DNS 设置脚本： `setup_resolv.rb` 。

   此脚本将以支持的命令列表进行响应。

```
Tool to modify external name servers

available commands:
  add search <domain>
               add a specified domain to search list
               e.g.> add search netapp.com
  remove search <domain>
               remove a specified domain from list
               e.g.> remove search netapp.com
  add nameserver <ip>
               add a specified IP address to the name server list
               e.g.> add nameserver 192.0.2.65
  remove nameserver <ip>
               remove a specified IP address from list
               e.g.> remove nameserver 192.0.2.65
  remove nameserver all
               remove all nameservers from list
  save         write configuration to disk and quit
  abort        quit without saving changes
  help         display this help message


Current list of name servers:
    192.0.2.64
Name servers inherited from global DNS configuration:
    192.0.2.126
    192.0.2.127
Current list of search entries:
    netapp.com

Enter command [`add search <domain>|remove search <domain>|add
nameserver <ip>`]
              [`remove nameserver <ip>|remove nameserver
all|save|abort|help`]
```

4. 添加为网络提供域名服务的服务器的 IPv4 地址： `add <nameserver IP_address>`
5. 重复 `add nameserver` 命令以添加名称服务器。
6. 按照提示输入其他命令时的说明进行操作。

7. 保存所做的更改并退出应用程序： `save`
8. 关闭服务器上的命令 Shell ： `exit`
9. 对于每个网格节点，重复中的步骤 登录到节点 到 关闭命令 Shell。
10. 如果不再需要对其他服务器进行无密码访问，请从 SSH 代理中删除私钥。输入： `ssh-add -D`

**Copyright Information**

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

**Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.