重新開機網格節點
StorageGRID

NetApp
May 17, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/storagegrid-116/maintain/rebooting-grid-node-from-grid-manager.html on May 17, 2022. Always check docs.netapp.com for the latest.

目錄

重新開機網格節點 1
從Grid Manager重新開機網格節點 1
從命令Shell重新開機網格節點 2

重新開機網格節點

您可以從Grid Manager或從節點的命令Shell重新開機網格節點。

當您重新開機網格節點時、節點會關閉並重新啟動。所有服務都會自動重新啟動。

如果您打算重新開機儲存節點、請注意下列事項：

- 如果ILM規則指定「雙重認可」的擷取行為、或規則指定「平衡」、而且無法立即建立所有必要的複本、StorageGRID 則由部門立即將任何新擷取的物件提交至同一站台上的兩個儲存節點、並於稍後評估ILM。如果您想要在特定站台重新開機兩個以上的儲存節點、在重新開機期間可能無法存取這些物件。
- 為了確保您可以在儲存節點重新開機時存取所有物件、請先停止在站台上擷取物件約一小時、再重新啟動節點。

管理StorageGRID

從Grid Manager重新開機網格節點

從Grid Manager重新啟動網格節點時、會在目標節點上發出「重新開機」命令。

您需要的是 **#8217** ；需要的是什麼

- 您將使用登入Grid Manager 支援的網頁瀏覽器。
- 您具有「維護」或「根」存取權限。
- 您有資源配置通關密碼。

步驟

1. 選擇*節點*。
2. 選取您要重新開機的網格節點。
3. 選取*工作*索引標籤。



4. 選擇*重新開機*。

   隨即顯示確認對話方塊。



   如果您要重新開機主管理節點、確認對話方塊會提醒您、當服務停止時、瀏覽器與Grid Manager的連線將會暫時中斷。

5. 輸入資源配置通關密碼、然後按一下*確定*。
6. 等待節點重新開機。

   服務可能需要一些時間才能關機。

   當節點重新開機時、「節點」頁面左側會出現灰色圖示（管理性關閉）。當所有服務重新啟動、且節點已成功連線至網格時、「節點」頁面應顯示正常狀態（節點名稱左側沒有圖示）、表示沒有警示處於作用中狀態、且節點已連線至網格。

從命令Shell重新開機網格節點

如果您需要更密切地監控重新開機作業、或是無法存取Grid Manager、您可以登入網格節點、然後從命令Shell執行Server Manager重新開機命令。

您必須擁有「passwors.txt」檔案。

1. 登入網格節點：

   a. 輸入下列命令：「sh admin@*grid_node_ip*`」

b. 輸入「passwords.txt」檔案中所列的密碼。

c. 輸入下列命令以切換至root：「u -」

d. 輸入「passwords.txt」檔案中所列的密碼。

以root登入時、提示會從「$」變更為「#」。

2. 或者、停止服務：「ervice servermanager stop」

   停止服務是選用的步驟、但建議您採取此步驟。服務關機最多需要15分鐘、您可能想要遠端登入系統、以監控關機程序、然後再於下一步重新開機節點。

3. 重新開機網格節點：「reboot」（重新開機）

4. 登出命令Shell：「exit」

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.