管理不受信任的用戶端網路
StorageGRID

NetApp
May 03, 2022

This PDF was generated from https://docs.netapp.com/zh-tw/storagegrid-116/admin/managing-untrusted-client-networks.html on May 03, 2022. Always check docs.netapp.com for the latest.

目錄

管理不受信任的用戶端網路 1
管理不受信任的用戶端網路：總覽 1
指定節點的用戶端網路不受信任 1

管理不受信任的用戶端網路

管理不受信任的用戶端網路：總覽

如果您使用的是用戶端網路、StorageGRID 只有在明確設定的端點上接受傳入用戶端流量、才能保護不受惡意攻擊的安全。

依預設、每個網格節點上的用戶端網路為_truste_。也就是StorageGRID 根據預設、不信任所有可用外部連接埠上每個網格節點的傳入連線（請參閱中的外部通訊資訊 網路準則）。

您可以StorageGRID 指定每個節點上的用戶端網路為_不受信任_、藉此減少對您的作業系統進行惡意攻擊的威脅。如果節點的用戶端網路不受信任、則節點只接受明確設定為負載平衡器端點之連接埠上的傳入連線。請參閱設定負載平衡器端點。

範例1：閘道節點僅接受HTTPS S3要求

假設您希望閘道節點拒絕用戶端網路上除HTTPS S3要求以外的所有傳入流量。您可以執行下列一般步驟：

1. 從「負載平衡器端點」頁面、在連接埠443上設定S3 over HTTPS的負載平衡器端點。
2. 在「不受信任的用戶端網路」頁面中、指定閘道節點上的用戶端網路不受信任。

儲存組態之後、除了連接埠443上的HTTPS S3要求和ICMP回應（ping）要求之外、閘道節點用戶端網路上的所有傳入流量都會捨棄。

範例2：儲存節點傳送S3平台服務要求

假設您想要從儲存節點啟用傳出S3平台服務流量、但想要防止任何傳入連線到用戶端網路上的該儲存節點。您可以執行以下一般步驟：

- 在「不受信任的用戶端網路」頁面中、指出儲存節點上的用戶端網路不受信任。

儲存組態之後、儲存節點不再接受用戶端網路上的任何傳入流量、而是繼續允許傳出要求至Amazon Web Services。

指定節點的用戶端網路不受信任

如果您使用的是用戶端網路、則可以指定每個節點的用戶端網路是否受信任或不受信任。您也可以為新增至擴充中的新節點指定預設設定。

您需要的是 **#8217** ；需要的是什麼

- 您將使用登入Grid Manager 支援的網頁瀏覽器。
- 您擁有root存取權限。
- 如果您希望管理節點或閘道節點僅接受明確設定的端點上的傳入流量、則表示您已定義負載平衡器端點。

> 如果尚未設定負載平衡器端點、現有的用戶端連線可能會失敗。

步驟

1. 選擇*組態*>*安全性*>*不受信任的用戶端網路*。

   「不受信任的用戶端網路」頁面會列出StorageGRID 您的整個作業系統中的所有節點。如果節點上的用戶端網路必須信任、則「不可用原因」欄會包含一個項目。



2. 在「設定新節點預設」區段中、指定在擴充程序中將新節點新增至網格時、應採用的預設設定。

   - 信任：在擴充中新增節點時、其用戶端網路是受信任的。
   - 不受信任：在擴充中新增節點時、其用戶端網路不受信任。您可以視需要返回此頁面、變更特定新節點的設定。

   > 此設定不會影響StorageGRID 到您的不完善系統中現有的節點。

3. 在「選取不受信任的用戶端網路節點」區段中、選取只允許用戶端連線到明確設定的負載平衡器端點的節點。

   您可以選取或取消選取標題中的核取方塊、以選取或取消選取所有節點。

4. 選擇*保存*。

   新的防火牆規則會立即新增並強制執行。如果尚未設定負載平衡器端點、現有的用戶端連線可能會失敗。

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.