启用 Storage Replication Adapter

VSC, VASA Provider, and SRA 9.7

NetApp
June 03, 2022

This PDF was generated from https://docs.netapp.com/zh-cn/vsc-vasa-provider-sra-97/deploy/task-configure-sra-on-srm-appliance.html on June 03, 2022. Always check docs.netapp.com for the latest.

目录

启用 Storage Replication Adapter 1
在 SRM 设备上配置 SRA 2
更新Storage Replication Adapter (SRA)凭据 2

启用 Storage Replication Adapter

Virtual Storage Console (VSC)、VASA Provider和Storage Replication Adapter (SRA)虚拟设备提供了一个选项、可用于在VSC中使用SRA功能来配置灾难恢复。

开始之前

- 您必须已设置 vCenter Server 实例并配置 ESXi 。
- 您必须已部署VSC、VASA Provider和SRA虚拟设备。
- 只有在要配置 Site Recovery Manager （ SRM ）灾难恢复解决方案时，您才能下载适用于 SRA 插件的 `.msi` 文件或适用于 SRM 设备的 `.tar.gz` 文件。

  "Site Recovery Manager 安装和配置 Site Recovery Manager 8.2" 了解更多信息。

您可以灵活地启用 VASA Provider 和 SRA 功能，从而仅执行企业所需的工作流。

步骤

1. 登录到 VMware vSphere 的 Web 用户界面。
2. 在vSphere Client中、单击菜单：菜单[虚拟存储控制台]。
3. 单击 * 设置 * 。
4. 单击 * 管理设置 * 选项卡中的 * 管理功能 * 。
5. 在 * 管理功能 * 对话框中，选择要启用的 SRA 扩展。
6. 输入VSC、VASA Provider和SRA虚拟设备的IP地址以及管理员密码、然后单击*应用*。
7. 您可以使用以下方法之一部署 SRA ：

选项	Description
对于Windows SRM	a. 双击已下载的 SRA 插件的 `.msi` 安装程序。 b. 按照屏幕上的说明进行操作。 c. 输入已部署虚拟设备的IP地址和密码。
适用于SRM设备	a. 访问SRM设备页面、然后转到SRM设备的*存储复制适配器*页面。 b. 单击 * 新建适配器 * 。 c. 将SRA插件的.tar.gz安装程序上传到SRM。 d. 重新扫描适配器以验证SRM *存储复制适配器*页面中的详细信息是否已更新。

您必须从 vSphere Client 中注销，然后重新登录以验证选定扩展是否可配置。

- 相关信息 *

配置 Storage Replication Adapter 以进行灾难恢复

在 SRM 设备上配置 SRA

部署 SRM 设备后，您应在 SRM 设备上配置 SRA 。成功配置 SRA 后， SRM 设备便可与 SRA 进行通信以进行灾难恢复管理。您应将VSC、VASA Provider和SRA凭据(IP地址和管理员密码)的虚拟设备存储在SRM设备中、以启用SRM设备与SRA之间的通信。

您应将`tar.gz`文件上传到SRM设备。

在 SRM 设备上配置 SRA 会将 SRA 凭据存储在 SRM 设备中。

步骤

1. 使用管理员帐户使用 putty 登录到 SRM 设备。
2. 使用命令 `su root` 切换到 root 用户
3. 在日志位置输入命令以获取SRA `docker ps -l`使用的Docker ID
4. 要登录到此容器ID、请输入命令`docker exec -it -u SRM <container id> sh`
5. 使用以下命令为SRM配置VSC、VASA Provider和SRA IP地址和密码虚拟设备：`perl command.pl -i <va-ip> administrator <va-password>`

   此时将显示一条成功消息，确认存储凭据已存储。SRA 可以使用提供的 IP 地址，端口和凭据与 SRA 服务器进行通信。

更新Storage Replication Adapter (SRA)凭据

要使 SRM 能够与 SRA 通信，如果您修改了 SRA 凭据，则应更新 SRM 服务器上的 SRA 凭据。

您应已执行 " 在 SRM 设备上配置 SRA " 主题中所述的步骤。

在 SRM 设备上配置 SRA

步骤

1. 使用以下命令删除```d/SRM/SRA目录的内容：
   a. cd /SRM/SRA
   b. rm -rf *
2. 执行 perl 命令以使用新凭据配置 SRA ：
   a. CD /SRM/SRA
   b. Perl command.pl -i <va-ip> administrator <va-password>

版权信息

版权所有©2022 NetApp、Inc.。保留所有权利。Printed in the U.S.版权所涵盖的本文档的任何部分不得以任何形式或任何手段复制、包括影印、录制、 磁带或存储在电子检索系统中—未经版权所有者事先书面许可。

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

本软件由NetApp按"原样"提供、不含任何明示或默示担保、包括但不限于适销性和特定用途适用性的默示担保、特此声明不承担任何责任。IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice.NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp.The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S.patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

商标信息

NetApp、NetApp标识和中列出的标记 http://www.netapp.com/TM 是NetApp、Inc.的商标。其他公司和产品名称可能是其各自所有者的商标。