

Faculdade de Ciências e Tecnologias

## Redes de Comunicação - Licenciatura em Engenharia Informática

# SISTEMA DE TURMAS ONLINE COM A PILHA TCP/IP

Trabalho Realizado por: Nuno Batista e Miguel Martins

1 Endereços das redes	2
2 Comandos de configuração usados para cada dispositivo	2

## 1 - Endereços das redes

#### • Rede A: 193.137.100.0/25

- Broadcast: 193.137.100.127

- Endereços disponíveis: 193.137.100.1 - 193.137.100.126

#### • Rede B: 193.137.100.128/25

- Broadcast B: 193.137.100.255

- Endereços disponíveis: 193.137.100.129 - 193.137.100.254

#### • Rede C: 193.137.101.0/24

- Broadcast B: 193.137.101.255

- Endereços Disponíveis: 193.137.101.1 - 193.137.101.254

#### • Rede D: 10.5.2.0/26

- Broadcast D: 10.5.2.63

- Endereços disponíveis: 10.5.2.1 - 10.5.2.62

# 2 - Comandos de configuração usados para cada dispositivo

#### Router 1:

```
interface FastEthernet0/0
ip address 193.137.100.126 255.255.255.128
no shutdown
exit

interface FastEthernet0/1
ip address 193.137.101.254 255.255.255.0
no shutdown
exit

ip route 193.137.100.128 255.255.255.128 193.137.101.253
end
copy running-config startup-config
```

#### Router 2:

```
conf t
interface FastEthernet0/0
ip address 193.137.101.253 255.255.255.0
no shutdown
exit
interface FastEthernet0/1
ip address 193.137.100.254 255.255.255.128
no shutdown
exit
ip route 193.137.100.0 255.255.255.128 193.137.101.254
end
copy running-config startup-config
```

#### Router 3:

```
conf t
interface FastEthernet0/0
ip address 193.137.101.252 255.255.255.0
no shutdown
exit
interface FastEthernet0/1
ip address 10.5.2.62 255.255.255.192
no shutdown
exit
access-list 1 permit 10.5.2.0 0.0.0.63
ip nat inside source list 1 interface FastEthernet0/0 overload
interface FastEthernet0/1
ip nat inside
exit
interface FastEthernet0/0
ip nat outside
exit
ip route 193.137.100.128 255.255.255.128 193.137.101.253
ip route 193.137.100.0 255.255.255.128 193.137.101.254
copy running-config startup-config
```

Durante a configuração dos containers, foram alterados diretamente os ficheiros de configuração da seguinte maneira:

#### Cliente 1:

```
# Static config for eth0
auto eth0
iface eth0 inet static
   address 10.5.2.1
   netmask 255.255.255.192
   gateway 10.5.2.62
```

#### Cliente 2:

# Static config for eth0
auto eth0
iface eth0 inet static
 address 10.5.2.2
 netmask 255.255.255.192
 gateway 10.5.2.62

#### Cliente 3:

# Static config for eth0
auto eth0
iface eth0 inet static
 address 193.137.100.129
 netmask 255.255.255.128
 gateway 193.137.100.254

#### Servidor:

# Static config for eth0
auto eth0
iface eth0 inet static
 address 193.137.100.1
 netmask 255.255.255.128
 gateway 193.137.100.126