DFDS AUTO REFRESH EVERY 5 MINUTES

DFDS OPERATORS

USER_DFDS

NAME (single line of text)
SIGNATURE (image)
LastSavedAt (date and time)
MAIL (single line of text)
ROLE (choice)
- OPERATOR
- SUPERVISOR
- DEPUTY
- ADMIN

APPROVAL (Yes/No)
TEAM (choice)
- AUDREY
- ERIC
- SANDRA
- STEPHANIE
- VANESSA

COMMUNICATION

COMMUNICATION

NAME (single line of text)
DFDS SUP / DEPUTY / ADMIN
SaveAt (date and time)
MESSAGE_TO (Choice)
- TEAM
- OPERATOR
- ALL

TEAM (choice)
- AUDREY
- ERIC
- SANDRA
- STEPHANIE
- VANESSA

DISPLAY (Yes/No)
MESSAGE (Multiple lines of text)

PARKING CHECK

PARKING CHECK

DFDS_NAME (single line of text)
DATE_TIME (date and time)
TYPE_ITEM (choice)
- COMMENT
- CHECK

PARKING (choice)
- UNACC
- ACC

ID_CHECK_UNACC (single line of text)
ID_CHECK_ACC (single line of text)
ID_UNACC (single line of text)
UNIT (single line of text)
ID_ACC (single line of text)
PLACE (single line of text)
ACC_REG (single line of text)
COMMENTS (multiple lines of text)

DEPARTURES DATAS

DATA DEPARTURE

This list manages all sailing operational information and defines the parking grouping strategy used by the Slot Suggestion Engine.

Identification
ID_DEPARTURE (single line of text)
Departure session identifier used for grouping trailers linked to the same sailing.
Navigation
SHIP (single line of text)
Ship name.
VOYAGE (single line of text)
Voyage reference.
DEPARTURE_FROM (choice)
Departure port.
- DKK
- ROS

DEPARTURE_TO (choice)
Arrival port / destination.
- DKK
- ROS

Schedule
EDD_ETD (date and time)
Scheduled departure date/time.
Main departure date/time used by the parking suggestion engine.
ADD_ATD (date and time)
Actual departure date/time.
EDA_ETA (date and time)
Estimated arrival date/time.
ADA_ATA (date and time)
Actual arrival date/time.
TYPE_SAVE_DEPARTURE (choice)
Indicates how the departure record was saved.
- Manual
- Auto

TYPE_SAVE_ARRIVAL (choice)
Indicates how the arrival record was saved.
- Manual
- Auto

Operational Status
LOADING_ACC_STATUS (choice)
Loading status.
- Started
- Pause
- In progress
- Completed

LOADING_UNACC_STATUS (choice)
Loading status.
- Started
- Pause
- In progress
- Completed

LOADING_TRADE_STATUS (choice)
Loading status.
- Started
- Pause
- In progress
- Completed

DISCHARGE_ACC_STATUS (choice)
Loading status.
- Started
- Pause
- In progress
- Completed

DISCHARGE_UNACC_STATUS (choice)
Loading status.
- Started
- Pause
- In progress
- Completed

STATUS_DEPARTURE (choice)
Overall operational status of the departure.
- Planned
- Alongside
- Sailed
- Cancel

BERTH_STATUS (Choice)
Berth / quay status used by the automatic allocation engine.
- Not Arrived
- Alongside
- Ready to Sail
- Sailed

DELAYED (Yes/No)
Suggestion
IS_ACTIVE_FOR_PARKING (Yes/No)
System-calculated field indicating whether the departure is relevant for parking allocation.
PARKING_CONCURRENCY_GROUP (single line of text)
System-generated identifier for concurrent departure groups.
AUTO_LOADING_PRIORITY (number)
System-calculated priority ranking for allocation logic.
Comments
COMMENTS (multiple lines of text)
Operational comments related to the departure plan.

NO SHOW

DATA NO SHOW

ID_DEPARTURE (single line of text)
DATE_TIME (date and time)
TYPE (choice)
- UNACC
- ACC

RELEASENO (single line of text)
AGENT_NAME (single line of text)
VEHREGNO (single line of text)
UNITNO (single line of text)
HAZ (Yes/No)
DFDS_NAME (single line of text)

VESSEL_DKK

This list stores the static structural definition of vessels operating on the DKK routes.

This list defines the fixed operational characteristics of each vessel, including theoretical meter capacity and default parking strategy assumptions.

It does not store voyage data, real-time loading information, or runtime parking allocation.

It is maintained manually only when vessel configuration changes.

SHIP (singel line of text)
Vessel name
VESSEL_ID (singel line of text)
Internal vessel reference code.
IsActive (Yes/No)
Indicates whether the vessel is currently operating on the route.
ROUTE (Choice)
- DKK_ROS

COMMENTS (multiple lines of text)
Operational notes regarding deck configuration, loading constraints or seasonal variations.

DOCUMENTS

DOCUMENTS

TYPE (Choice)
- DROPS
- HAZ
- INBOUND DROPS
- MANIFEST
- PETS
- TICKETS
- SAFESEAS
- MANIFEST

ID_DEPARTURE (single line of text)
Attachments (attachments)
SaveAt (date and time)
DFDS_NAME (single line of text)

DISCHARGE

DATA DISCHARGE

ID_DEPARTURE (single line of text)
ID_DISCH_UNACC (single line of text)
ID_DISCH_ACC (single line of text)
ID_PAUSE_UNACC (single line of text)
ID_PAUSE_ACC (single line of text)
ID_END_PAUSE_UNACC (single line of text)
ID_END_PAUSE_ACC (single line of text)
ID_END_UNACC (single line of text)
ID_END_ACC (single line of text)
DATE_TIME (date and time)
START (Yes/No)
PAUSE (Yes/No)
END_PAUSE (Yes/No)
END (Yes/No)
NB_UNITS (number)
TYPE (choice)
- ACC
- UNACC

TYPE_SAVE (choice)
- MANUAL
- AUTO

DFDS_NAME (single line of text)

LOADING

DATA LOADING

ID_DEPARTURE (single line of text)
ID_LOAD_UNACC (single line of text)
ID_LOAD_ACC (single line of text)
ID_LOAD_TRADE (single line of text)
ID_PAUSE_UNACC (single line of text)
ID_PAUSE_ACC (single line of text)
ID_PAUSE_TRADE (single line of text)
ID_END_PAUSE_UNACC (single line of text)
ID_END_PAUSE_ACC (single line of text)
ID_END_PAUSE_TRADE (single line of text)
ID_END_UNACC (single line of text)
ID_END_ACC (single line of text)
ID_END_TRADE (single line of text)
DATE_TIME (date and time)
START (Yes/No)
PAUSE (Yes/No)
END_PAUSE (Yes/No)
END (Yes/No)
NB_UNITS (number)
TYPE (choice)
- ACC
- UNACC
- TRADE

TYPE_SAVE (choice)
- MANUAL
- AUTO

DFDS_NAME (single line of text)

UNACC PARKING MANAGEMENT

UNACC PARKING MANAGEMENT

Architecture Overview
The UNACC Parking Management application is designed to orchestrate and control the full operational lifecycle of unaccompanied trailers within the terminal environment, from check-in to final loading or exit.
The solution is built on a modular and scalable data architecture leveraging six core SharePoint lists, each serving a distinct and clearly defined responsibility within the system:
PARKING_UNACC
Central operational table managing the live lifecycle of each trailer (status, location, timestamps, transitions)
DATA_CHECKIN_UNACC
Inspection and intake dataset capturing trailer characteristics, compliance checks, photos, signatures, and damage reporting
DATA_DEPARTURE
Dynamic sailing dataset driving operational context, including departure scheduling, berth status, and concurrency grouping logic
SLOT_PARKING_UNACC
Real-time representation of physical parking slots, including availability, constraints, and current occupancy
PARKING_BLOCK_MASTER
Static configuration layer defining parking strategy rules (block structure, allowed types, overflow rules, operational constraints)
PARKING_BLOCK_ALLOCATION
System-generated runtime layer dynamically allocating parking capacity across concurrent departures based on priority scoring and real-time conditions

Core Capabilities Enabled
This architecture provides a fully data-driven parking orchestration engine enabling:
. Real-time operational visibility
End-to-end tracking of trailer position, status, and lifecycle across the terminal
. Dynamic slot allocation intelligence
Automated parking suggestions based on:
- trailer type compatibility
- live slot availability
- block allocation strategy
- departure priority scoring

. Multi-departure concurrency management
Automatic grouping and distribution of trailers across simultaneous sailings without manual intervention
. Full auditability & traceability
Immutable lifecycle tracking ensuring complete historical visibility for each trailer (no deletion, only state transitions)
. Configurable and scalable architecture
Rapid extension to new routes, terminals, or operational rules via configuration (no application redesign required)
. Adaptive parking strategy engine
Real-time recalculation of block allocation driven by:
departure status changes
time-to-departure evolution
slot occupancy events
operational constraints

PARKING UNACC

This list represents the live operational status of each trailer present on the terminal.

Items are never deleted.
Only status, location and timestamps are updated to maintain a full historical audit trail.

Identification
UNIT (single line of text)
Unique trailer/unit number.
ID_UNACC (single line of text)
Unique trailer identifier used to link records across lists.
ID_DEPARTURE (single line of text)
Departure session identifier used for grouping trailers linked to the same sailing.
ID_DEP_FORWARD (single line of text)
Departure session identifier used for grouping forward trailers
Classification
TYPE (choice)
Operational trailer type used for parking compatibility and process rules.
- HAZ
- PLUG
- STAND_BY
- UNACC
- IMPORT

PLUG (Yes/No)
TEMPERATURE (single line of text)
Temperature requirement or setting when relevant.
Current Parking Position
PLACE (single line of text)
Current parking place assigned to the trailer.
ZONE (choice)
Current operational parking zone of the trailer.
- HAZ
- PLUG
- STAND_BY
- UNACC
- IMPORT

BLOCK (choice)
Current parking block assigned to the trailer.
- 100
- 200
- 300
- 400
- 500
- 600
- 700
- 800
- 900

Slot Suggestion Tracking
SUGGESTED_PLACE (single line of text)
Parking place suggested by the slot suggestion engine.
SUGGESTED_BLOCK (choice)
Block suggested by the slot suggestion engine.
- 100
- 200
- 300
- 400
- 500
- 600
- 700
- 800
- 900

SUGGESTION_SCORE (number)
Numerical score calculated by the engine for the selected parking suggestion.
SUGGESTION_REASON (multiple lines of text)
Explanation of why the slot was suggested.
MANUAL_OVERRIDE (Yes/no)
Indicates whether the operator manually selected another place instead of using the suggested one.
OVERRIDE_REASON (multiple line of text)
Mandatory justification when a suggested slot is not used.
Operational Timeline
DATE_TIME_ARRIVAL (date and time)
Arrival date and time of the trailer on terminal.
DATE_TIME_CHECKPARKING (date and time)
Date and time when parking check or confirmation was performed.
LOADING_DATE_TIME (date and time)
Date and time when loading process started.
LOADED_DATE_TIME (date and time)
Date and time when loading was completed.
DISCHARGED_DATE_TIME (date and time)
Date and time when the trailer was discharged.
PICK_UP_DATE_TIME (date and time)
Date and time when the trailer wospicked-up.
STAND_BY_DATE_TIME (date and time)
Date and time when the trailer was stand-by status was last modified
LAST_STATUS_DATE_TIME (date and time)
Date and time of the latest status update.
Operational References
NAME_CHECKPARKING (single line of text)
LOADER_NAME (single line of text)
Name of the operator who loaded the trailer.
DISCHARGER_NAME (single line of text)
Name of the operator who discharged the trailer.
PICK_UP_NAME (single line of text)
Name of the operator who change the pick up status
STAND_BY_NAME (single line of text)
Name of the operator who change the trailer in stand-by status.
ID_CHECK_UNACC (single line of text)
Reference ID of the parking check operation.
ID_LOAD_UNACC (single line of text)
Reference ID for the loading action.
ID_DISCH_UNACC (single line of text)
Reference ID for the discharge action.
Departure Information
DEPARTURE_DATE_TIME (date and time)
Scheduled departure date and time linked to the trailer.
Status
STATUS (choice)
Current operational status of the trailer.
- CONFIRMED
- STAND_BY
- LOADING
- LOADED
- PROBLEM
- IMPORT
- GONE

SHORT_SHIPPED (Yes/No)
Trailers that could not be loaded on previous departure
FORWARD_SHIPPED (Yes/No)
Trailers scheduled for the next departure that have been dispatched

DATA CHECKIN UNACC

This list stores detailed check-in inspection data for trailers, including operational details, photos, signatures, and damage information.

This list is the main inspection source used when the trailer arrives on terminal.

Identification
UNIT (single line of text)
Trailer/unit number.
ID_UNACC (single line of text)
Unique trailer identifier shared across all related lists.
ID_DEPARTURE (single line of text)
Departure session identifier used for grouping trailers linked to the same sailing.
DRIVER_ID (image)
Photo of the driver's ID
Departure Planning
DEPARTURE_DATE_TIME (date and time)
Scheduled departure date and time linked to the trailer.
Trailer Classification
PLUG_IN (Yes/No)
Indicates whether the trailer is a plug-in.
TEMPERATURE (single line of text)
Required temperature or temperature-related information.
HAZ (Yes/No)
Indicates whether the trailer is hazardous.
STAND_BY (Yes/No)
Indicates whether the trailer is a stand-by.
REGULAR (Yes/No)
Indicates whether the trailer is regular.
Check-in Details
PLACE (single line of text)
Current parking place assigned to the trailer.
PORTDATA (choice)
- DUNKERQUE
- ROSSLARE

Port data reference or import information.
CHECKIN_DATE_TIME (date and time)
Arrival date and time of the trailer on terminal.
DFDS_NAME (single line of text)
Name of DFDS operator who did the checkin
Inspection Controls
LASHINGPOINTS (choice)
Inspection result for lashing points.
- 6
- 4

SPAREWHEEL (choice)
Indicates whether a spare wheel is present.
- YES
- NO

NOTE (multiple lines of text)
General inspection note.
Photos
RIGHTPHOTO (image)
Reference to the right side photo.
LEFTPHOTO (image)
Reference to the left side photo.
REARPHOTO (image)
Reference to the rear side photo.
FRONTPHOTO (image)
Reference to the front side photo.
Signatures
DRIVER_SIGN (image)
Reference to driver signature.
DFDS_SIGN (image)
Reference to DFDS operator signature.
Damage Zones (Structured Fields)
Each zone represents presence or description of damage (choice)
DAMAGE_A
DAMAGE_B
DAMAGE_C
DAMAGE_D
DAMAGE_E
DAMAGE_F
DAMAGE_G
DAMAGE_H
DAMAGE_I
DAMAGE_J
DAMAGE_L
DAMAGE_M
DAMAGE_N
DAMAGE_O
DAMAGE_P
DAMAGE_Q
DAMAGE_R
DAMAGE_S
DAMAGE_T
DAMAGE_U
Damage Photos
DAMAGEPHOTO_A
DAMAGEPHOTO_B
...
DAMAGEPHOTO_U
Editing
EDIT (Yes/No)
Indicates whether the record has been edited after original submission.
NBREDIT (number)
Stores the number of edits performed on the record.
STATUS (choice)
Status of the check-in form.
- Draft
- Submitted

Audit
MODIFIED_ON (date and time)
Last modification timestamp.
MODIFIED_BY (single line of text)
User who last modified the record.

SLOT PARKING UNACC

This list represents one physical parking place.

Each item represents a parking place.

Each place is managed as an independent slot.

PLACE_NUMBER (number)
Unique parking place number.
ZONE (choice)
Unique parking place number.
- HAZ
- PLUG
- STAND_BY
- UNACC
- IMPORT

BLOCK (choice)
Parking block assigned to the place.
- 100
- 200
- 300
- 400
- 500
- 600
- 700
- 800
- 900

IsActive (Yes/No)
Indicates whether the parking place is available for use.
IsFree (Yes/No)
Indicates whether the place is currently free.
INCENDIE (Yes/No)
Indicates whether the place is unavailable due to fire restriction.
SAFETY_HAZ (Yes/No)
Indicates whether the place is unavailable due to safety restriction.
UNIT (single line of text)
Unit currently occupying the place.
ID_UNACC (single line of text)
Unique trailer identifier linked to the occupying trailer.
ID_DEPARTURE (single line of text)
Departure identifier linked to the allocation.
STATUS (choice)
Operational status of the place.
- CONFIRMED
- STAND_BY
- LOADING
- LOADED
- PROBLEM
- FREE

IS_BLOCKED (Yes/No)
Indicates whether the place is manually blocked for operational reasons.
LAST_ASSIGNED_DATE_TIME (Date and Time)
Last date/time when a trailer was assigned to the place.
LAST_RELEASED_DATE_TIME (Date and Time)
Last date/time when the place became free again.
COMMENTS (Multiple lines of text)
Operational comments related to the place.

PARKING BLOCK ALLOCATION

This list stores stores the automatic runtime allocation of parking blocks between active concurrent departures.

This list is system-generated.
Operators should not manage it manually.

TITLE (singel line of text)
Unique allocation record identifier.
BLOCK (choice)
Block covered by the allocation.
- 100
- 200
- 300
- 400
- 500
- 600
- 700
- 800
- 900

ZONE (choice)
Zone linked to the block allocation.
- HAZ
- PLUG
- STAND_BY
- UNACC
- IMPORT

TRAILER_TYPE (choice)
Trailer type covered by the allocation.
- HAZ
- PLUG
- STAND_BY
- UNACC
- IMPORT

ID_DEPARTURE (singel line of text)
Departure identifier linked to the allocation.
PARKING_CONCURRENCY_GROUP (single line of text)
System-generated identifier for concurrent departure groups.
SHIP (single line of text)
Ship linked to the allocation.
DEPARTURE_DATE_TIME (date and time)
Departure date/time linked to the allocation.
STATUS_DEPARTURE (choice)
Live status of the departure at calculation time.
- Planned
- Alongside
- Sailed
- Cancel

ALLOCATION_PRIORITY (Number)
Relative priority of the departure inside the automatic allocation engine.
ALLOCATED_SLOT_COUNT (number)
Number of places currently allocated to this departure in the block.
ALLOCATED_PERCENT (number)
Percentage of block capacity allocated to this departure.
USED_SLOT_COUNT (number)
Number of places already used in the block for this departure.
FREE_SLOT_COUNT (number)
Number of available places still remaining for this departure in the block.
FIRST_SLOT (number)
Indicates the first slot to be used
LAST_SLOT (number)
Indicates the last slot to be used
IS_ACTIVE_ALLOCATION (Yes/No)
Indicates whether the allocation is currently active.
CALCULATED_ON (Date and Time)
Timestamp of the last automatic calculation.
CALCULATION_REASON (Multiple lines of text)
Explanation of the automatic allocation result

PARKING BLOCK MASTER

This list defines what a block is for.
It does not store live occupancy and it is not manually adjusted for each departure.

TITLE (singel line of text)
Unique block master identifier.
BLOCK (choice)
Parking block identifier.
- 100
- 200
- 300
- 400
- 500
- 600
- 700
- 800
- 900

ZONE (choice)
Zone linked to the block allocation.
- HAZ
- PLUG
- STAND_BY
- UNACC
- IMPORT

TRAILER_TYPE (choice)
Trailer type covered by the allocation.
- HAZ
- PLUG
- STAND_BY
- UNACC
- IMPORT

IsActive (Yes/No)
Indicates whether the block is active.
IS_SPLIT_ALLOWED (Yes/No)
Indicates whether the block may be automatically divided between multiple active departures of the same trailer type.
IS_OVERFLOW_BLOCK (Yes/No)
Indicates whether the block may be used as overflow capacity.
TYPE_OVERFLOW_ALLOWED (multi choice)
Indicates with which type the block may be used as overflow capacity.
- HAZ
- PLUG
- STAND_BY
- UNACC
- IMPORT

RESERVED_FOR_SPECIAL_USE (Yes/No)
Indicates whether the block is reserved for a specific operational use.
COMMENTS (Multiple lines of text)
Operational comments describing the block.

UNIT DISCHARGE DKK

UNIT_REG (single line of text)
ID_DEPARTURE (single line of text)
DATE_TIME_ADD (date and time)
DFDS_NAME_ADD (single line of text)
DATE_TIME_CHECKED (date and time)
CHECKED (Yes/No)
DFDS_NAME_CHECKED (single line of text)

ACC PARKING

ACC CHECKIN

ACC_REG (single line of text)
DATE_TIME (date and time)
ID_DEPARTURE (single line of text)
ID_FORWARD (single line of text)
ID_ACC (single line of text)
ID_LOAD_ACC (single line of text)
ID_CHECK_ACC (single line of text)
TYPE (choice)
- HAZ
- HAZ PLUG
- STAND_BY_16M
- 18M
- LOW_WIDE
- TOURISTS_HIGH
- TOURISTS_CARS
- SMALL8M
- SMALL6_8M
- 16M
- SMALL_PLUG
- PLUG
- SOLO PICK UP

PLUG_TYPE (choice)
- PLUG
- DIESEL

LANE (choice)
- 1
- 2
- 3
- 4
- 5
- 6
- 7
- 8
- 9
- 10
- 11
- 12
- 13
- 14
- 15
- 16
- 17
- 18

POSITION (number)
STATUS (choice)
- CONFIRMED
- STAND_BY
- LOADED
- PROBLEM

Attachments (attachements)
Driver's ID
NB_PASSENGER (number)
DFDS_NAME (single line of text)
DFDS_LOADER (single line of text)

ACC PARKING

PRESSET (Yes/No)
IsActive (Yes/No)
MULTI_TYPE (Yes/No)
TYPE_1 (choice)
- HAZ
- HAZ PLUG
- STAND_BY_16M
- 18M
- LOW_WIDE
- LOW_WIDE
- TOURISTS_HIGH
- TOURISTS_CARS
- SMALL8M
- SMALL6_8M
- 16M
- SMALL_PLUG
- PLUG
- SOLO PICK UP

TYPE_2 (choice)
- HAZ
- HAZ PLUG
- STAND_BY_16M
- 18M
- LOW_WIDE
- LOW_WIDE
- TOURISTS_HIGH
- TOURISTS_CARS
- SMALL8M
- SMALL6_8M
- 16M
- SMALL_PLUG
- PLUG
- SOLO PICK UP

STAND_BY (Yes/No)
LANE (choice)
- 1
- 2
- 3
- 4
- 5
- 6
- 7
- 8
- 9
- 10
- 11
- 12
- 13
- 14
- 15
- 16
- 17
- 18

NUMBER_OF_PLACES (number)
RESERVED (Yes/No)
ID_DEPARTURE (single line of text)
DFDS_NAME (single line of text)

DFDS UNACC PARKING BLOCK ALLOCATION ENGINE

If a departure already has occupied slots in a block,
the engine must preserve those occupied slots and only increase or decrease the surrounding free allocation.

UNACC / HAZ / PLUG-IN use dynamic block allocation.
IMPORT / STAND_BY use FIFO free slot assignment.



DFDS UNACC SLOT SUGGESTION ENGINE



DFDS UNACC SLOT SCORING LOGIC



MENU - ARCHITECTURE PROCESS



COMMUNICATION - ARCHITECTURE PROCESS



DOCUMENTS- ARCHITECTURE PROCESS



SETTINGS- ARCHITECTURE PROCESS



DFDS DEPARTURE - ARCHITECTURE PROCESS


DEPARTURE
CREATE BOOKING
CREATE BOOKING
CREATE BOOKING

SET DISCHARGE / LOADING- ARCHITECTURE PROCESS



PARKING UNACC - ARCHITECTURE PROCESS



CHECKIN UNACC - ARCHITECTURE PROCESS



PICK UP UNACC - ARCHITECTURE PROCESS



CHECK UNACC PARKING - ARCHITECTURE PROCESS



DISCHARGE TUGS UNACC - ARCHITECTURE PROCESS



DISCHARGE OPERATOR UNACC - ARCHITECTURE PROCESS



LOADING ACC- ARCHITECTURE PROCESS



STAND BY - ARCHITECTURE PROCESS



PARKING ACC - ARCHITECTURE PROCESS



CHECKIN ACC - ARCHITECTURE PROCESS



CHECK ACC PARKING - ARCHITECTURE PROCESS



STAND BY UNACC - ARCHITECTURE PROCESS



LOADING ACC- ARCHITECTURE PROCESS