NixOS virtual machines

Contents

- What will you learn?
- What do you need?
- Starting from a default NixOS configuration
- Creating a QEMU based virtual machine from a NixOS configuration
- Running Sway as Wayland compositor on a VM
- References
- Next steps

One of the most important features of NixOS is the ability to configure the entire system declaratively, including packages to be installed, services to be run, as well as other settings and options.

NixOS configurations can be used to test and use NixOS using a virtual machine, independent of an installation on a "bare metal" computer.

What will you learn?

This tutorial serves as an introduction creating NixOS virtual machines. Virtual machines are a practical tool for experimenting with or debugging NixOS configurations.

What do you need?

- A Linux system with virtualisation support
- (optional) A graphical environment for running a graphical virtual machine
- A working Nix installation
- Basic knowledge of the Nix language



A NixOS configuration is a Nix language function following the NixOS module convention. For a thorough treatment of the module system, check the Module system deep dive tutorial.

Starting from a default NixOS configuration



Mote

You can also skip this section and copy the sample configuration for this tutorial into a file configuration.nix in the current directory.

Use the nixos-generate-config command to create a configuration file that contains some useful defaults and configuration suggestions. The configuration produced from the following setup also is used for the NixOS minimal ISO image:

```
nix-shell -I nixpkgs=channel:nixos-24.05 -p "$(cat <<EOF</pre>
    pkgs = import <nixpkgs> { config = {}; overlays = []; };
    iso-config = pkgs.path + /nixos/modules/installer/cd-dvd/installation-cd-minima
    nixos = pkgs.nixos iso-config;
 in nixos.config.system.build.nixos-generate-config
EOF
)"
```

Detailed explanation



Create a NixOS configuration in your working directory:

```
[nix-shell:~]$ nixos-generate-config --dir ./
```



By default, when no |--dir | is specified, the generated configuration file is written to /etc/nixos/configuration.nix , which typically requires | sudo | permissions.

In the working directory you will then find two files

1. hardware-configuration.nix is specific to the hardware nix-generate-config is being run on.

You can ignore that file for this tutorial because it has no effect inside a virtual machine.

2. configuration.nix contains various suggestions and comments for the initial setup of a desktop computer.

The default NixOS configuration without comments is:

```
1 { config, pkgs, ... }:
2 {
3  imports = [ ./hardware-configuration.nix ];
4
5  boot.loader.systemd-boot.enable = true;
6  boot.loader.efi.canTouchEfiVariables = true;
7
8  system.stateVersion = "24.05";
9 }
```

To be able to log in, add the following lines to the returned attribute set:

```
1  users.users.alice = {
2   isNormalUser = true;
3   extraGroups = [ "wheel" ];
4  };
```

Note

A configuration generated with <code>nixos-generate-config</code> contains this user configuration commented out.

Additionally, you need to specify a password for this user. For the purpose of demonstration only, you specify an insecure, plain text password by adding the <code>initialPassword</code> option to the user configuration:

```
1 initialPassword = "test";
```

We add two lightweight programs as an example:

```
1 environment.systemPackages = with pkgs; [
2 cowsay
3 lolcat
```



Do not use plain text passwords outside of this example unless you know what you are doing. See initialHashedPassword or ssh.authorizedKeys for more secure alternatives.

This tutorial focuses on testing NixOS configurations on a virtual machine. Therefore you will remove the reference to hardware-configuration.nix:

```
- imports = [ ./hardware-configuration.nix ];
```

Sample configuration

The complete configuration.nix file looks like this:

```
1 { config, pkgs, ... }:
   boot.loader.systemd-boot.enable = true;
 4 boot.loader.efi.canTouchEfiVariables = true;
 6 users.users.alice = {
     isNormalUser = true;
     extraGroups = [ "wheel" ]; # Enable 'sudo' for the user.
 8
     initialPassword = "test";
9
10 };
11
12 environment.systemPackages = with pkgs; [
13
     cowsay
14
     lolcat
15 ];
16
17
    system.stateVersion = "24.05";
18 }
```

Creating a QEMU based virtual machine from a NixOS configuration

A NixOS virtual machine is created with the nix-build command:

```
$ nix-build '<nixpkgs/nixos>' -A vm -I nixpkgs=channel:nixos-24.05 -I nixos-config=
```

This command builds the attribute wm from the nixos-24.05 release of NixOS, using the NixOS configuration as specified in the relative path.

```
Detailed explanation
```

The complete configuration.nix file looks like this:

```
1 { config, pkgs, ... }:
 2 {
    boot.loader.systemd-boot.enable = true;
    boot.loader.efi.canTouchEfiVariables = true;
 5
 6
   services.xserver.enable = true;
 7
 8 services.xserver.displayManager.gdm.enable = true;
 9 services.xserver.desktopManager.gnome.enable = true;
10
users.users.alice = {
isNormalUser = true;
     extraGroups = [ "wheel" ];
13
14
    initialPassword = "test";
15
   };
16
17 system.stateVersion = "24.05";
18 }
```

To get graphical output, run the virtual machine without special options:

```
$ nix-build '<nixpkgs/nixos>' -A vm -I nixpkgs=channel:nixos-24.05 -I nixos-config=
$ ./result/bin/run-nixos-vm
```

Running Sway as Wayland compositor on a VM

To change to a Wayland compositor, disable services.xserver.desktopManager.gnome and enable programs.sway:

```
configuration.nix

- services.xserver.desktopManager.gnome.enable = true;
+ programs.sway.enable = true;
```



Running Wayland compositors in a virtual machine might lead to complications with the display drivers used by QEMU. You need to choose from the available drivers one that is compatible with Sway. See QEMU User Documentation for options. One possibility is the virtio-vga driver:

```
$ ./result/bin/run-nixos-vm -device virtio-vga
```

Arguments to QEMU can also be added to the configuration file:

```
1 { config, pkgs, ... }:
 2 {
    boot.loader.systemd-boot.enable = true;
   boot.loader.efi.canTouchEfiVariables = true;
   services.xserver.enable = true;
 7
 8 services.xserver.displayManager.gdm.enable = true;
    programs.sway.enable = true;
9
10
11
   imports = [ <nixpkgs/nixos/modules/virtualisation/qemu-vm.nix> ];
virtualisation.qemu.options = [
    "-device virtio-vga"
13
14
   ];
15
16 users.users.alice = {
isNormalUser = true;
    extraGroups = [ "wheel" ];
18
   initialPassword = "test";
19
20
   };
21
    system.stateVersion = "24.05";
22
23 }
```

The NixOS manual has chapters on X11 and Wayland listing alternative window managers.

References

- NixOS Manual: NixOS Configuration.
- NixOS Manual: Modules.
- NixOS Manual Options reference.
- NixOS Manual: Changing the configuration.

- NixOS source code: vm attribute in default.nix.
- Nix manual: nix-build.
- Nix manual: common command-line options.
- QEMU User Documentation for more runtime options
- NixOS option search: virtualisation.qemu for declarative virtual machine configuration

Next steps

- Module system deep dive
- Integration testing with NixOS virtual machines
- Building a bootable ISO image