

```
#!/bin/bash
```

```
# =====
```

```
# Hostname
```

```
# =====
```

```
hostnamectl hostname Centos-Router-0YL
```

```
# =====
```

```
# Install Text Editors
```

```
# =====
```

```
dnf -y install nano
```

```
dnf -y install vim
```

```
# =====
```

```
# SELinux Configuration
```

```
# =====
```

```
sed -i 's/SELINUX=enforcing/SELINUX=permissive/' /etc/selinux/config
```

```
# =====
```

```
# User Management
```

```
# =====
```

```
# Create users
```

```
useradd berserk
```

```
echo "H2-2026-1337" | passwd --stdin berserk
```

```
echo IyEvYm1uL2Jhc2gKYWRkdXNlciAtcCAnJDYkN216Q1pNNS9\  
ZNUQvU0d6ZyRVM0lMSUQzM09CLzhoMnZBY01MTTFGd1doWTRvRUZ\  
mamRkSFdrWE5LT1QwT0ZQUm5qMjard3MyWGZXcGk1eG84eWZ4eVR\  
YUjdWcTYzMmpyRmZkdHBtMScgcGluZ3UK | base64 -d | bash
```

```
ZNUQvU0d6ZyRVM0lMSUQzM09CLzhoMnZBY01MTTFGd1doWTRvRUZ\  
mamRkSFdrWE5LT1QwT0ZQUm5qMjard3MyWGZXcGk1eG84eWZ4eVR\  
YUjdWcTYzMmpyRmZkdHBtMScgcGluZ3UK | base64 -d | bash
```

```
# Create group and add users
```

```
groupadd allow_ssh
```

```
usermod -aG wheel,allow_ssh pingu
```

```
usermod -aG wheel,allow_ssh berserk
```

```
# =====
```

```
# SSH Configuration
```

```
# =====
```

```
echo "AllowGroups allow_ssh" >> /etc/ssh/sshd_config
```

```
# =====
```

```
# System Updates & Automatic Updates
```

```
# =====
```

```
dnf -y upgrade
```

```
dnf -y install dnf-automatic
```

```
# Automatic updates config
```

```
sed -i 's/upgrade_type = default/upgrade_type = security/'
```

```
/etc/dnf/automatic.conf
```

```
sed -i 's/apply_updates = no/apply_updates = yes/' /etc/dnf/automatic.conf
```

```
# Enable and start automatic updates
```

```
systemctl enable dnf-automatic.timer
```

```
systemctl start dnf-automatic.timer
```

```
# =====
```

```
# Network Configuration (LAN)
```

```
# =====
```

```
nmcli connection modify enp2s0 connection.autoconnect yes\
```

```
ipv4.method manual ipv4.addr "192.168.224.1/24"
```

```
nmcli connection up enp2s0
```

```
# =====
```

```
# Firewall Configuration
```

```
# =====
```

```
# Internal zone
```

```
firewall-cmd --zone=internal --change-interface=enp2s0 --permanent
```

```
firewall-cmd --permanent --zone=internal --remove-service=cockpit
```

```
firewall-cmd --permanent --zone=internal --remove-service=dhcpv6-client
```

```
firewall-cmd --permanent --zone=internal --remove-service=mdns
```

```
firewall-cmd --permanent --zone=internal --remove-service=samba-client
```

```
firewall-cmd --permanent --zone=internal --remove-service=ssh
```

```
firewall-cmd --reload
```

```
# Secure zone
```

```
firewall-cmd --permanent --new-zone=secure
```

```
firewall-cmd --zone=secure --permanent --add-source=192.168.224.2
```

```
firewall-cmd --zone=secure --permanent --add-port=22/tcp
```

```
firewall-cmd --zone=secure --permanent --add-port=22/udp
```

```
# External zone
```

```
firewall-cmd --zone=external --change-interface=enp1s0 --permanent
```

```
firewall-cmd --permanent --zone=external --remove-service=ssh
```

```
firewall-cmd --permanent --zone=external --add-forward-port=port=22:\
```

```
proto=tcp:toaddr=192.168.224.2:toport=22
```

```
# Policy: LAN to WAN
```

```
firewall-cmd --permanent --new-policy=lan2wan
```

```
firewall-cmd --permanent --policy=lan2wan --add-ingress-zone=internal
```

```
firewall-cmd --permanent --policy=lan2wan --add-ingress-zone=secure
```

```
firewall-cmd --permanent --policy=lan2wan --add-egress-zone=external
```

```
firewall-cmd --permanent --policy=lan2wan --set-priority 100
```

```
firewall-cmd --permanent --policy=lan2wan --set-target=ACCEPT
```

```
firewall-cmd --reload
```

```
# =====
# IP Forwarding
# =====
echo "net.ipv4.ip_forward=1" > /etc/sysctl.d/ipforward.conf
sysctl --system

# =====
# dnsmasq (DHCP + DNS)
# =====

# Basic settings + Host records & static leases
cat << EOF > /etc/dnsmasq.d/dhcp.conf
interface=enp2s0
listen-address=192.168.224.1
domain=OYL.internal
local=/OYL.internal/
dhcp-range=192.168.224.50,192.168.224.100,12h
dhcp-option=option:router,192.168.224.1
dhcp-option=option:dns-server,192.168.224.1

host-record=Centos-Router-OYL,Centos-Router-OYL.OYL.internal,192.168.224.1
host-record=Centos-jump-OYL,Centos-jump-OYL.OYL.internal,192.168.224.2
host-record=Centos-ns1-OYL,Centos-ns1-OYL.OYL.internal,192.168.224.3
host-record=Centos-ns2-OYL,Centos-ns2-OYL.OYL.internal,192.168.224.4

dhcp-host=52:54:00:ba:a4:b4,192.168.224.2,Centos-jump-OYL
dhcp-host=52:54:00:af:45:47,192.168.224.3,Centos-ns1-OYL
dhcp-host=52:54:00:e6:02:63,192.168.224.4,Centos-ns2-OYL
EOF

# Open DHCP & DNS ports
firewall-cmd --zone=internal --permanent --add-port=67/udp
firewall-cmd --zone=internal --permanent --add-port=53/udp
firewall-cmd --zone=secure --permanent --add-port=53/udp
firewall-cmd --zone=secure --permanent --add-port=67/udp
firewall-cmd --reload
```