


Ooonana OS



Ooonana OS 0.9.6 field guide

What it is

Ooonana OS is a scratch-built Linux project with its own rootfs, boot flow, installer experiments, WSL export, and custom ooonana package manager. Debian or Ubuntu are host build tools only. Alpine APKs are imported into Ooonana .pkg repos; the target OS installs Ooonana packages, not live Alpine APKs.

Editions

minimal: BusyBox-style rootfs, kernel, GRUB disk, installer ISO, WSL rootfs, command line AI.
full-i3: minimal plus i3, Xorg, Spotlight-style launcher, movable GTK apps, wallpaper, GUI installer, AI desktop app, and full WSL rootfs.

Package install

```
oonana update
oonana search nano
oonana show nano
oonana get nano --dry-run
oonana get nano
oonana files nano
oonana verify nano
oonana upgrade
oonana remove nano
oonana purge nano
oonana fix nano --reinstall
```

Cloud repo

Default cloud path is the GitLab Pages direct repository:
<https://oonana.gitlab.io/oonana-repo>
Run ooonana update && ooonana upgrade. Metadata syncs first; package archives download only when install or upgrade needs them.
GitHub Releases remains a backup tarball repository path.

Installer

Full-i3 live ISO boots i3. Installer requires explicit target and dry-run preview. Erase-disk mode offers optional swap; custom root, home, swap and EFI must share target disk.

USB live modes

Normal live mode mounts ISO and rootfs read-only. It uses a cleared temporary overlay on OONANA_PERSIST when available on the same boot USB, with RAM fallback.

Persistent live mode accepts only an ext4 OONANA_PERSIST partition on the same physical boot USB. Its full writable overlay saves files, settings, Wi-Fi, Bluetooth pairings, packages, and system changes.

Other disks may be probed read-only. Live mode writes only to matching boot USB persistence. Only the confirmed installer target can be partitioned or formatted.

First boot

oonana setup --first-boot --gui can create user, set password, write network config, choose theme, set zram and disk-swap policy, add cloud repo, and mark setup complete.

WSL

Import full-i3 with scripts/install-wsl-distro.sh --distro Ooonana --tarball /var/tmp/oonana-os/release/oonana-full-i3-wsl-rootfs.tar.gz --force

Launch desktop with: wsl.exe -d Ooonana -u ooonana --exec start-oonana-i3

WSL GUI needs WSLg and Xephyr, or an X server with DISPLAY set. Nested mode keeps i3 panel and dock together in one window.

Update an imported distro with: ooonana update && ooonana upgrade

AI

Ooonana AI runs as ooonana ai ... or ooonana-ai. It supports cloud providers, offline Intel OpenVINO, ask/chat, tools, tasks, audit, history, status, and a native GUI.

The full-i3 desktop includes a ChatGPT-style AI workspace, Settings, Wi-Fi, Bluetooth, Packages, and Spotlight-style application launcher.

Desktop and hardware

The i3 desktop uses solid graphite and orange styling, rounded controls, a top music/window bar, and a centered opaque dock with running dots, click-to-restore apps, and right-click window actions.

Core 0.9.6 adds matching native app icons, event-driven third-party titlebar controls and 10% larger cursor defaults (public 19px, personal 21px).

Ctrl+Shift+Esc opens native Task Manager with processes, performance, and available temperature and fan sensors. Unavailable hardware counters are labeled, not guessed.

Live USB starts compressed zram swap. OpenVINO setup requires persistent USB storage or an installed system; RAM-only live storage cannot hold its runtime and models.

Ooonana OpenVINO Chat 0.2.1 has a browser GUI through an authenticated loopback bridge. Windows-only computer-control tools are unavailable on Linux.

Wi-Fi supports personal and enterprise profiles. NetworkManager, BlueZ, D-Bus, Intel Wi-Fi/Bluetooth firmware, Chromium, Python 3, sudo, su, and doas are included in full-i3.

Installed password-login handoff passed diskless VM tests as UID 1000. Physical Xorg, wireless, audio, sensors and inference remain hardware checks; no sound was played.

OpenVINO Linux dependencies use exact wheel hashes and a pinned Ubuntu image/APT snapshot. Signing private key stays local; public CI signing is deferred.

Bootable PDF

docs/oonana.pdf now uses native RISC-V64 Linux 6.18.37 and BusyBox 1.37.0. TinyEMU boot, input and version checks passed; package-sync performance and Chromium viewer checks remain.

RV64 JavaScript emulator clock is scaled down 16x for CPU progress. Guest time is slower than real time. This terminal PDF is not the x86 i3 desktop.

Build proof markers

00ONANA_CLI_OK

00ONANA_BOOT_OK

00ONANA_INSTALL_OK

00ONANA_FULL_I3_OK

More detail lives in README.md, docs/oonana-ai.md, and docs/jarvis-agi-research.md.