AC VIEWER SDK TUTORIAL How build and get AC Viewer application

DOWNLOAD Augmented.City SDK (see <u>link</u>) and perform the following steps in order to get AC Viewer demo app.

https://github.com/OpenArCloud/oscp-unity-client.git

PRELIMINARY STEP: install Unity with all dependencies

1. Install Unity version 2019.2.11 or higher (see Fig.1) and add Modules (see Fig.2).

To install Unity, **get Unity Hub from the following link**: https://unity3d.com/get-unity/download/archive

The Unity Hub is a standalone application that allows easly to manage your Unity Projects and installations. In addition, you can manually manage the installation of multiple versions of the Editor and run two versions of Unity at the same time (see Fig.3). Note that to prevent local conflicts, you should only open a Project in one Editor instance at a time.




Fig.1: Example of the several installed versions of Unity.

NOTE: you can add modules click the three dots to the right of the version label, then select **Add Modules**. (**NOTE:** If you didn't install the Editor via the Hub, you will not see this option. To enable this option, install the Editor via the Hub.)

- 1. In the **Add Modules** dialog, locate the module to add and tick its checkbox.
- 2. When you have selected all the modules to add, select **Done**.




Fig.2: Example of the adding Modules in Unity Hub.




Fig.3: Example of the created projects using different versions of Unity.

NOTE: You can click the drop-down arrow next to the Unity Version to select a different version of the Editor. If you try to open a Project with an older version of the Editor than the one it was created in,

Unity warns you that downgrading the Project might result in data loss and asks you to confirm your selection.

You can visit the following link to see Unity documentation: https://docs.unity3d.com/Manual/UnityManual.html

Download and build SDK Unity project

1. Open the existing Unity project included into the downloaded SDK

Select the proper Unity version (version 2019.2.11 or higher) and click on ADD project (see Fig.4




Fig.4: Opening the existing Unity project using Unity Hub

2. Set project settings for Android/ios and ARcore (see Fig.5)

SDK uses ARFoundation systems, so you have to install the following packages (**Window** -> **Package manager**):

ARFoundation 2.1.4 ARCore XR Plugin 2.1.1 ARKit XR Plugin 2.1.2




Fig.5: Screenshot showing how to check the installed packages of AR Foundation system

3. Build for Android/IOS

You can build *AugCityDemo* Scene on Android/IOS and get an application that localizes and shows placeholders on scanned buildings.

To create a build for Android/iOS, go to Build Settings (menu: File > Build Settings). In the Platform list, select Android/iOS, then select the Switch Platform button (see Fig.7/Fig.8).

Set project settings for Android and ARcore / iOS and ARKit setting at true "Allow 'unsafe' Code" (see Fig. 9)

Android environment setup

To build and run for Android (see Fig.7), you must install the Unity Android Build Support platform module. You also need to install the Android Software Development Kit (SDK) and the Native Development Kit (NDK) to build and run any code on your Android device. By default, Unity installs a Java Development Kit based on OpenJDK.

Use the Unity Hub to install Android Build Support and the required dependencies: Android SDK & NDK tools, and OpenJDK (see <u>Fig.2</u>).

You can check the Android SDK & NDK Tools and OpenJDK installation going to **Preferences > External tools** (see Fig. 6).




Fig. 6: Check installed dependencies for Android platform: go to **Preferences > External tools**

Below some useful links:

- Unity gradle support:
 https://developers.google.com/ar/develop/unity/android-11-build#unity_20193_and_20
 194
- Download the Gradle version from the following link: https://gradle.org/releases/




Fig.7: Steps to build for Android.




Fig.8: Steps to build for IOS.




Fig. 9: Set project settings for iOS and ARKit: Allow 'unsafe' Code - true