Command Reference: SetWorkingDir()

Set working directory


The SetWorkingDir() command sets the working directory for following commands. The working directory is normally set in one of the following ways, with the current setting being defined by the most recent action that has occurred:

- 1. The startup directory for the TSTool program,
- 2. The directory containing the most recently opened or saved command file.
- 3. The directory specified by a SetWorkingDir () command,
- 4. The directory specified by *File...Set Working Directory*.

In most cases, a SetWorkingDir() command is not needed and should be avoided because it may complicate commands and troubleshooting. However, for complicated command files that process data in multiple directories, it may be useful to change the working directory during processing. Setting the working directory to an absolute path causes all relative paths for input and output files to be appended to the working directory. Relative paths that use "../" can be specified to move up and down a directory tree. The current working directory during processing is reset to the initial working directory (the location of the command file) each time that the commands are run.

In any case, it is recommended that paths used in command parameters be specified using relative paths (relative to the command file) so that command files and associated data files can be easily moved from one computer to another.

The following dialog is used to edit the command and illustrates the syntax of the command.



SetWorkingDir() Command Editor

SetWorkingDir

The command syntax is as follows:

SetWorkingDir(Parameter=Value,...)

Command Parameters

Parameter	Description	Default
WorkingDir	The working directory that should be	None – must be specified.
	used. Specify a relative path (e.g., "")	
	to adjust the current working directory.	
	Can be specified using \${Property}.	
RunMode	Indicate the run mode in which the	GUIAndBatch
	command should be applied, one of:	
	• GUIOnly - the command applies	
	only to interactive runs	
	• GUIAndBatch - the command	
	applies to interactive and batch runs	
	• BatchOnly – the command applies	
	to batch runs only	

A sample command file is as follows:

```
SetWorkingDir(WorkingDir="C:\temp")
```