
Command Reference: InsertTableColumn()

Insert a column into a table

Version 11.00.00, 2015-03-17

The InsertTableColumn() command inserts a column into a table. An initial value can be set or use the SetTableValues() command to set values after inserting the column.

The following dialog is used to edit the command and illustrates the syntax of the command



InsertTableColumn() Command Editor

InsertTableColumn

The command syntax is as follows:

InsertTableColumn(Parameter=Value,...)

Command Parameters

Parameter	Description	Default
TableID	The identifier for the table being modified.	None – must be
		specified.
InsertColumn	The column name to insert.	Required
InsertBeforeColumn	The name of the column to insert before.	Insert at the end of
		the table
ColumnType	The data type for the column, one of:	String
	• DateTime - date/time object	
	Double – double precision number	
	• Float – single precision number	
	• Integer - integer	
	• Long – long integer	
	• Short – short integer	
	• String — string	
InitialValue	The initial data value to set for the column. For a	null
	date/time column use the format YYYY-MM-DD	
	hh:mm or MM/DD/YYYY hh:mm.	
ColumnWidth	The column width in characters, if a String column	Dynamic sizing
	type.	
ColumnPrecision	The number of digits of precision to show, if a	6
	Double or Float column type.	