## Command Reference: ReadTableFromDelimitedFile()


Read a table from a delimited file

Version 10.03.00, 2012-01-09

The ReadTableFromDelimitedFile() command reads a table from a comma-delimited file. Tables are used by other commands when performing lookups of information or generating summary information from processing. Table files have the following characteristics:

- Comments indicated by lines starting with # are stripped during the read.
- Extraneous lines in the file can be skipped during the read using the SkipLines parameter.
- Column headings indicated by "quoted" values in the first non-comment line will be used to assign string names to the columns. If no quoted values are present, columns will not have headings.
- Data in columns are assumed to be of consistent type (i.e., all numerical data or all text), based on rows after the header. The data type for the column will be determined automatically.
- Missing values can be indicated by blanks. However, a line ending with the delimiter may cause warnings because blank is not assumed at the end of the line (this is a software limitation that may be addressed in the future) work around by adding an extra delimiter or ensure that the last column is not blank.
- Strings containing the delimiter should be surrounded by double quotes. This command currently does not deal with """text"" notation although support may be added in the future (see information about comma-separated-value [CSV] standards: http://en.wikipedia.org/wiki/Comma-separated\_values).

The following dialog is used to edit the command and illustrates the syntax for the command.



## ReadTableFromDelimitedFile() Command Editor

ReadTableFromDelimitedFile

The command syntax is as follows:

ReadTableFromDelimitedFile(Parameter=Value,...)

## **Command Parameters**

Parameter	Description	Default
TableID	Identifier to assign to the table that is read,	None – must be specified.
	which allows the table data to be used with	
	other commands.	
InputFile	The name of the file to read, as an absolute	None – must be specified.
	path or relative to the command file location.	
SkipLines	Indicates the number of lines in the file to	No lines are skipped.
	skip, which otherwise would interfere with	
	reading row data. Individual row numbers	
	and ranges can be specified, for example:	
	1,5-6,17	
HeaderLines	Indicate the rows that include header	If the first non-comment line
	information, which should be used for	contains quoted field names,
	column names. Currently this should only be	they are assumed to be
	one row, although a range may be fully	headers. Otherwise, no
	supported in the future.	headers are read.

The following example command file illustrates how to read a table from a delimited file:

```
ReadTableFromDelimitedFile(TableID="Table1",
InputFile="Sample.csv",SkipRows="2")
```

An excerpt from a simple delimited file is:

```
# A comment some junk to be skipped "Header1", "Header2", "Header3" 1,1.0,1.0 2,2.0,1.5 3,3.0,2.0
```

ReadTableFromDelimitedFile	(	) Command

TO		D		tatio	_
1.5	വവ	ואחרו	ımer	ntatioi	n

This page is intentionally blank.