Selection – choose the pages that are shown and printed

With a **selection** you decide which pages ODV shows and prints. You always start with all pages and remove the ones you do not want. It is handy when a session contains many documents but you only need a few pages.

This guide belongs with Getting started with OpenDocViewer. The pictures show a made-up test document, in the Swedish interface; the button names here are the English ones.
Download the guide as PDF.

Important: a selection hides pages in ODV and controls what is printed. The original documents in the archive are never affected.

1. Open the selection workspace | **2. Remove pages** | **3. Add pages back**


4. Change the order | **5. Take a closer look at a page** | **6. Save or leave**

7. How to tell that a selection is active | **8. Print the selection** | **9. Remove the selection**

---

1. Open the selection workspace

Click the **selection button** in the toolbar – the one with a list and a tick, directly to the right of the print button (tooltip: *Manage the pages shown and printed*). The *Manage selection* workspace opens over the whole window.



The selection workspace. On the left, *Available pages*: every page there is. On the right, *Selected pages*: the pages included in the selection. A tick on a page on the left means it is included.




The workspace toolbar. Mode (Documents or Pages), panel layout, thumbnail size, undo/redo, reset, *Save* and *Leave*.

▾ Two modes: Documents and Pages


- **Documents** is the default. Pages are kept together per document. You can remove and add pages and move them within their document.
- **Pages** drops the grouping. Pages from different documents can be mixed in any order you like – for example before printing in a particular order.

2. Remove pages

1. **Mark** the pages in the right panel that should not be included. Click one page at a time.
2. Click **Remove selected** – the arrow ‹ between the panels. The pages lose their tick in the left panel.
3. To remove everything and start from scratch: click **Remove all** (‹‹).




Marked pages get a grey frame.




After Remove selected. Document 1 now has one page left and the counter shows 21 selected. The Save button has turned green.

▾ **Faster ways to mark and remove**

- `Shift`+click marks every page between two clicks. `Ctrl`+click adds or removes a single page from the marking.
- Drag a **rectangle** over several pages to mark them all at once.
- **Double-click** a page in the left panel to add or remove it directly.
- You do not need to open the workspace at all for single pages: **right-click** a thumbnail or the page in the main view and choose *Hide this page* or *Hide document*. The `Delete` key hides the page you are looking at, `Ctrl`+`Delete` the whole document.



Right-clicking a thumbnail.



Right-clicking the page.

---

3. Add pages back

Changed your mind? Mark the pages in the **left** panel and click **Add selected** (›), or **Add all** (») to get everything back. The *Undo* and *Redo* buttons in the toolbar take back one step at a time.


---

4. Change the order

Drag a page in the right panel to a new place. In *Documents* mode you can move pages within their document; in *Pages* mode you can mix freely. The order in the selection becomes the order of the printout.

5. Take a closer look at a page

Hover over a page and click the **eye**. The page is shown large, with arrows to browse to the next one. A green edge means the page is included in the selection, and the button at the top adds or removes the page directly. `Esc` closes.




Preview. The page's place, document and metadata are shown at the top left.

6. Save or leave

The **Save** button turns green as soon as you have changed something. Click it when you are done, and then **Leave** to get back to the document. If you leave without saving, you get a question.




Unsaved changes. The green button saves, the orange button discards the changes.



Leaving without saving. Save, discard, or *Continue editing*.

7. How to tell that a selection is active


Back in the document, the **selection button is red**, the page counter only counts the selection's pages, and the thumbnail pane only shows the pages that are included. At the top of the pane there is a **red reset button**.



Active selection. The page counter shows 1 / 21, the selection button is red, the pane only shows the selection.

8. Print the selection

Open printing with the print button and choose **All pages**. When a selection is active, you can choose between **Current selection** – only the pages in the selection, preselected – and **Entire session**, which prints everything and ignores the selection.



All pages with a selection. *Current selection (21 pages)* is preselected.


The *Simple range* and *Custom pages* options are not available when a selection is active – the selection then decides what is printed. The rest of printing (reason, recipient, watermark) works as in the Getting started guide.

Good to know: printing a selection prints the pages as they are in the archive. If you have rotated a page or changed brightness and contrast, that is not included here – it only is with the *Active page* print method.

---

9. Remove the selection

Click the **red button at the top of the thumbnail pane**. All pages come back. You can also open the workspace, choose *Add all*, *Save* and *Leave*.



The reset button at the top right of the pane.

Short checklist

- ✓ A green Save button means you have unsaved changes.
- ✓ A red selection button in the toolbar means pages are hidden.
- ✓ *Current selection* prints what you chose, *Entire session* prints everything.

Back to Getting started with OpenDocViewer. This guide covers OpenDocViewer 2.8.

Updated 2026-09-26.