


***On the Host Machine (Your Main System)
Create Folder Named share in your home folder***



Then we need to add a virtiofs device.


Virtiofs needs shared memory to work. This can be enabled in the hardware configuration window. Navigate to *Hardware -> Memory* and select *Enable shared memory*.

After that, open virt-manager and navigate to the hardware settings of the virtual machine. Click on *Add Hardware*.



Virtual Machine Manager hardware configuration window.

A dialog box should pop up. In the pane on the left, click on *Filesystem*



The 'Add Hardware' dialog window

Enter the necessary settings.

Storage

Controller

Network

Input

Graphics

Sound

Serial

Parallel

Console

Channel

USB Host Device

PCI Host Device

MDEV Host Device

Video

Watchdog

Filesystem

Smartcard

USB Redirection

TPM

RNG

Panic Notifier

VirtIO VSOCK

Filesystem Passthrough

Details

XML

Driver:

virtiofs

Source path:

/mnt/vfs_share

Browse...

Target path:

share

☐ Export filesystem as readonly mount

Cancel

Finish

The settings are as follows:

For the *Driver*, we keep the default (virtiofs). The source path is the path on our host filesystem. The target path is a bit of a misnomer. It's not actually a path, just an identifier that we use as a mount point in our guest file system. This will become clear when we mount the file system in the guest later.

If you want a more detailed overview of these options and some alternatives, check out the libvirt knowledge base on [virtiofs](#)

Guest

Linux

After that, it's time to configure the guest. First we create a folder in our users home directory that we will mount the share into.

```
mkdir ~/share
```

[Copy](#)

After that, we can mount the share with:

```
sudo mount -t virtiofs share /home/foo/share
```

[Copy](#)

If we want to make this permanent, we can just add an entry to `/etc/fstab`

```
share    /home/foo/share    virtiofs    defaults    0    0
```

After rebooting, the share should be mounted! If your user on the host and the guest are the same, you don't even need to worry about any other permissions. Otherwise, change the folder with `chmod` to suit your needs.