

Bingo Boy

The Original Bingo Breaker · User Manual



For Bingo Boy 1.1 (build 13) · October 2026

Contents

1. Welcome to Bingo Boy 4
   - What cards it works with 4
   - Your data stays on your phone 4
   - Words used in this manual 4
2. Quick start 5
3. The home screen 6
4. Sessions (your bingo nights) 7
   - 4.1 The session screen 7
   - 4.2 Quit game: save it for later, or throw it away 8
   - 4.3 End the night and archive 8
   - 4.4 Starting a new session while one is open 8
   - 4.5 Resuming a saved night 9
5. Adding main books and photographing pages 10
   - 5.1 Taking the photo 10
   - 5.2 Cropping 10
   - 5.3 Reading the cards 11
   - 5.4 Checking the numbers (important) 11
   - 5.5 Entering numbers yourself, and randomizing 12
   - 5.6 Leaving before you save 13
6. Managing a book 14
7. Page counts must match 15
   - 7.1 The rule 15
   - 7.2 What you can change, game by game 15
   - 7.3 Adding a book in the middle of the night 16
8. Side books: slabs and tickets 18
   - 8.1 Single slab 18
   - 8.2 Number ticket (pull-tab) 18
   - 8.3 Switching side books on and off 19
9. Playing a game 20
   - 9.1 What the game is played for 20
   - 9.2 The game screen 21
   - 9.3 Calling numbers 21
   - 9.4 One number away 22

10. Bingo! and winners 23
10.1 When one of your cards wins 23
10.2 When the hall calls a winner 24
11. Moving between pages and going back 25
12. End of the main game, and side games 26
12.1 Main game over 26
12.2 Side games 26
13. Patterns 28
13.1 Built-in patterns 28
13.2 Making your own pattern 28
14. Sessions & stats 30
15. Settings, backup and restore 31
15.1 Appearance 31
15.2 Backup and restore 31
16. The sample game 33
17. Tips and help inside the app 34
18. Limits at a glance 35
19. Troubleshooting and common questions 36
20. Privacy and support 37

1. Welcome to Bingo Boy

Bingo Boy helps you play paper bingo with a lot of cards at once. You photograph each page of your bingo books before the games start. Bingo Boy reads every card. Then, as the caller announces each number, you tap it once and every card in every book marks itself. The moment any card wins, Bingo Boy tells you exactly which book, page and card it is. It also warns you when a card is one number away.

What cards it works with

- **75-ball bingo only.** Cards are 5 × 5 with the columns B-I-N-G-O and a free space in the middle.
- Each column uses its own numbers: **B 1–15, I 16–30, N 31–45, G 46–60, O 61–75.**
- A page can hold up to 6 cards across and 8 cards down (48 cards).

Your data stays on your phone

- No account is needed and nothing is uploaded. Card reading happens on your phone.
- The photo is used only to read the numbers. It is not kept after the page is saved.
- Everything saves automatically as you go. To keep a copy somewhere safe, or to move to a new phone, use **Settings → Backup and restore** (see section 15).

> **ALWAYS CHECK AGAINST THE PAPER**
> Bingo Boy is a helper, not the caller. Before you claim a prize, check the highlighted card against your paper card and the hall's rules for the game.

Words used in this manual


Word	Meaning
Session (or night)	One bingo night. It holds your books, side books, called numbers and wins. One session is open at a time.
Main book	A book with several pages. Game 1 plays page 1 of every main book, game 2 plays page 2, and so on.
Page	One sheet in a book, usually a different paper color for each game. It holds several cards.
Card	One 5 × 5 bingo grid.
Side book	Something played every game while it is switched on: a **single slab** (one sheet of cards with no pages) or a **number ticket** (a pull-tab with 1 to 10 numbers).
Pattern	What a game is played for, like a line, four corners or a full card.
Main game	Playing through every page of your main books. After the last page, you can carry on with **side games** that use only side books.

2. Quick start

1. Open Bingo Boy and tap **“Start new session”**.
2. Optionally type the hall or night in **“Hall or night (optional)”**, for example “Lucky 7 Bingo, Friday”.
3. Under **Main books**, tap **“Add”**. Photograph page 1 of your first book, check the numbers it read, and tap **“Save page and continue”**. Photograph the next page and repeat until the book is done, then tap **“Done with this book”**.
4. Add your other books the same way. **Every main book must have the same number of pages.**
5. Add any slabs or pull-tab tickets under **Side books**, and switch on the ones you're playing.
6. Tap **“Play game 1”**. Tick what the game is played for, then tap **“Play for these 2”** (or however many you picked).
7. Tap each number once as it's called. When Bingo Boy shows **Bingo**, check your paper card. When the hall calls a winner, tap **“Winner called”** and move on to the next page.
8. After the last page, choose **“Finalize and archive game”** or **“Continue playing with side boards”**.

> **TRY IT FIRST**
> Tap **“Try a sample game”** on the home screen to play a whole night with made-up cards. Sample games don't count in your stats unless you add them.

3. The home screen



First time: start a new session




A night in progress: Resume game

Button	What it does
“Resume game”	Shows only when a night is in progress. It lists the night's name, the number of main and side books, and which game you're on (for example “game 3 of 10”). Tap it to go back to the session.
“Start new session”	Starts a fresh night. If a night is already in progress, Bingo Boy first asks what to do with it (see 4.4).
“Sessions & stats”	Your past nights, bingos and winnings (see section 14).
“How to play”	Short guides on setting up, playing and winning.
“Settings”	Appearance, custom patterns, and backup and restore. **“View instruction manual”** at the top right opens this manual.
“Try a sample game”	A practice night with made-up books (see section 16).


4. Sessions (your bingo nights)

A session is one bingo night. It has its own main books, side books, games and wins. Your custom patterns, appearance and stats name belong to the whole app and are shared by every session.

4.1 The session screen



A new, empty session




A session with four books

From top to bottom, the session screen has:

- **"Quit game"** (top right).
- The name box **"Hall or night (optional)"**, up to 40 characters. With no name, the night is called "Night of" plus the date.
- **Main books**, with an **"Add"** button.
- **Side books**, with its own **"Add"** button.
- **"End the night and archive"**.
- The big button at the bottom: **"Play game N"**.

Tap **"How it works"** for a three-step reminder.

4.2 Quit game: save it for later, or throw it away



Quit game

- **"Save to Open sessions"** keeps everything. The night leaves the home screen, and you can resume it any time from **Sessions & stats → Open sessions**. A fresh empty session opens in its place.
- **"Quit without saving"** asks you to confirm, then deletes every book, called number and win from that night for good.
- **"Cancel, keep playing"** closes the box.

4.3 End the night and archive

At the bottom of the session screen, **"End the night and archive"** asks you to confirm, then archives the night and returns to the home screen.

An archived night keeps only its **name, date, bingos, winnings and number of games played**. The books, cards, called numbers and side books are deleted to free up space. You can still see archived nights in Sessions & stats.

You can also archive from the Main game over screen (section 12) or from a night's detail page in Sessions & stats.

4.4 Starting a new session while one is open

If you tap **"Start new session"** or **"Try a sample game"** while a night is in progress, Bingo Boy asks what should happen to the open one:

- **"Save it to Open sessions"**: everything is kept, and you can resume it later.
- **"Archive it"**: keeps only its results in your stats. This isn't offered for a sample game.


- **“Delete it and replace”**: asks you to confirm, then deletes it for good.
- **“Cancel”**.

4.5 Resuming a saved night


Open **Sessions & stats**, tap the night under **Open sessions**, then tap **“Resume this session”**. The night you had open is set aside under Open sessions, so nothing is lost. An empty night or a sample game is discarded instead.

5. Adding main books and photographing pages


Tap **“Add”** under Main books. A new book is named “Book 1”, “Book 2” and so on (you can rename it later), and the photograph screen opens for its first page.



Photograph a page



Fit the box around the cards



Reading the cards

5.1 Taking the photo

Lay the page flat and include every card. Use even light, avoid glare and keep every card in focus. **Pages stay in the order you photograph them**, so start with the top sheet (page 1).

- **“Take photo”** opens the camera.
- **“Choose a picture or scan”** picks a photo or file you already have. It accepts photos (JPEG, PNG, HEIC and so on), **PDF** and **TIFF** scans.
  - Each page of a PDF or TIFF becomes one book page, up to 100 pages per file.
  - Scans skip the crop step, and Bingo Boy goes straight from one scan page to the next as you save each one.
- **“Enter numbers myself”** skips the photo so you can type the numbers or randomize them (see 5.5).
- **“Done with this book”** goes to the book's page list. It shows once the book has at least one page.

The strip of colored squares near the top shows the paper color of each page you've already saved.

5.2 Cropping

The box starts as the whole photo.

- Drag its corners or edges in so it fits just the bingo cards; anything outside the box is ignored. Drag inside the box to move it.
- For fine control, open **“Adjust crop with sliders”**. There's one slider for each edge, plus **“Reset crop”**.
- Tap **“Read the cards in the box”**, or **“Use the whole photo”** to skip cropping. **“Retake”** goes back to the camera.


5.3 Reading the cards

Bingo Boy finds the cards, works out the layout and reads every number. Keep the screen open while it works; a status line shows its progress.

Reading uses the column rules: a number that doesn't belong in its column gets a second look. If Bingo Boy isn't sure about a number, it leaves the square blank rather than guess.

If reading is slow or stuck, tap **“Stop and enter numbers myself”**.

5.4 Checking the numbers (important)



Compare every card with the paper

Before a page is saved, you check what was read. A message at the top tells you how it went:

- “The reader found every number. Compare every card with the paper before saving; a confident reading can still be wrong.”
- “N squares didn't read; fill them in”.
- “N highlighted squares are worth a second look”.

Fixing a square

- Tap a square and type the right number on the keypad. The hint shows the column's range, for example “B is 1–15”.
- Two digits save straight away and jump to the next square. For a one-digit number, tap **“OK”**.
- **Highlighted squares** are numbers Bingo Boy was less sure of. If one looks right, tap it and tap **“OK”** to confirm it.
- **“Clear”** on the keypad empties a square. **“Clear”** above a card empties the whole card, after asking you to confirm.
- The FREE center square can't be edited.

Problems Bingo Boy flags

- **Empty** square (dashed outline).
- **Out of column**: a number outside its column's range (red).
- **Repeated**: the same number twice in one column of a card (red).

“Save page and continue” stays off until every problem is fixed.

Layout and paper color

- Make sure the layout matches your paper. The quick buttons are **2×3, 2×4, 3×3 and 4×3** (across × down). The **“Across”** (1–6) and **“Down”** (1–8) steppers set any other layout.
- If a smaller layout would remove cards that already have numbers, Bingo Boy asks first.
- The paper color is detected from the photo and given a name like “Blue” or “Pink”. Tap the color swatch to change it, and edit the name if you like. The color helps you match the screen to the paper on game night.

Confirm and save

Tick **“I checked every card against my paper, including highlighted numbers and the number of cards. They match.”** Then tap **“Save page and continue”**.

Any later edit unticks the box, so you confirm again. After saving, you're ready to photograph the next page.

5.5 Entering numbers yourself, and randomizing

“Enter numbers myself” opens an empty 3×3 page in gray. Set the layout and color, then copy every number from your paper cards.

To play digitally without paper, you can also randomize:

- **Randomize page** fills every card on the page with valid random cards (each column uses only its own numbers, with no repeats).
- The shuffle button on a card randomizes just that card.
- **Randomize book** asks how many pages the book should have (up to 30) and fills them all. It copies the colors and layout of your other books where it can. Once a game has started, it can only fill up to the other books' page count.


Randomized cards don't need the “I checked every card” box.

5.6 Leaving before you save

If you tap Back with unsaved edits, Bingo Boy asks **“Leave this page?”**. Choose **“Discard and leave”** or **“Keep editing”**. Pages you already saved are kept either way.

6. Managing a book

Tap a book on the session screen to open its page list.



A book's pages

- **Name**: type a new name (up to 60 characters). It saves as you type.
- Each page shows its color, card count and layout, with small previews of every card.
- **“Fix numbers”** reopens a page so you can correct a misread number. **This always works, even in the middle of a game.**
- The up and down arrows move a page earlier or later.
- **“Delete”** removes a page (it asks first). Later pages move up by one.
- The bottom button adds the next page: **“Photograph page N”** or **“Photograph the next page”**.
- **Move earlier / Move later** (under the pages) changes the book's position in the list.
- **“Delete this book”** deletes the book and all its pages after asking. This is always allowed.


> **ONCE A GAME STARTS**
> Adding, moving and deleting pages are limited after numbers are called. The next section explains exactly when.

7. Page counts must match


Game 1 plays page 1 of every main book, game 2 plays page 2, and so on. That only works if **every main book has the same number of pages**.

7.1 The rule

- The book (or books) with the **most pages** sets the count.
- Any book with fewer pages is marked in red with a line such as **“4 of 5 pages · page count must match”**.
- The play button reads **“Page counts must match to play”** and can't be tapped until every book matches.
- To fix it, add pages to the books marked in red, or delete pages from the longest books. Each red mark disappears as soon as that book matches.
- **Side books (slabs and tickets) are never part of this.**



Book 1 has 5 pages, so Books 2 and 3 are marked




A short book says how many pages to add


7.2 What you can change, game by game

When	What you can do
Before any number is called	Anything: add, delete and reorder pages, and add or delete books.

Still on page 1 (numbers called, but play hasn't moved to page 2)	You can still change books, but first Bingo Boy asks **"Clear page 1 and end the game?"**. • If you choose **"Clear and continue"**, page 1's called numbers, patterns and any bingos from it are cleared and you start again from page 1. Your books, cards and side books stay. • **"Keep editing"** changes nothing. • A book that's short of pages can add pages without clearing.
Past page 1 (play has moved on to page 2 or later)	Existing books are **set for the game**: no adding, deleting or reordering pages. The button reads **"Pages are set for this game"**. You can still: • fix a misread number, • delete a whole book, • **add a brand-new main book** (see 7.3).
After the main game is over	Main books are finished and grayed out. Only side books play on (see section 12).



On page 1: clear the game first




Past page 1: pages are set

7.3 Adding a book in the middle of the night

Bought another book after the games started? Tap **"Add"** under Main books.

- **The new book starts on the page being played.** If everyone is on page 3, the first photo you take is page 3.
- The pages already played are skipped. They show as "already played before this book was added" and are never shown in a game.

- Keep photographing until the new book matches the others. Bingo Boy returns to the book once it has enough pages, and it can't go past the others' count.



A book added on page 2 starts at page 2




Page 1 is marked as already played

8. Side books: slabs and tickets

Side books are played **every game while they're switched on**. Main books keep turning to the next page each game. Add side books from the session screen with **“Add”** under Side books.



Choose a slab or a ticket



Pick the numbers on a ticket

8.1 Single slab

- A slab is one sheet of cards with no pages.
- Give it a name (up to 30 characters, like “Early bird”) and tap **“Photograph the slab”**. You photograph and check it just like a book page.
- A slab is **switched on** when you add it. It wins with the same patterns as the main game.
- Tap a slab to rename it, use **“Fix numbers”**, photograph it again, or **“Delete slab”**.

8.2 Number ticket (pull-tab)

- Choose **“Individual numbers”** and give it a name (up to 30 characters).
- Set **“How many numbers”** (1 to 10), then tap those numbers on the board. **You must pick exactly that many**; the button reads **“Pick N more”** until you do. Tap a picked number to remove it.
- A ticket wins when every one of its numbers is called.
- **A new ticket starts switched off.** Switch it on to play it.
- Tickets have a trash button for deleting them, or use **“Delete ticket”** in the editor.

8.3 Switching side books on and off

Use the switch beside each side book on the session screen. During a game, the **“Side boards”** button at the top lets you switch them without leaving the game. A side book stays on, game after game, until you switch it off. Each new game starts it with no numbers marked.

You can play with side books only, and no main books at all.

9. Playing a game

9.1 What the game is played for



Tick the patterns for this game


When a game starts, Bingo Boy asks what it's played for. **Line** and **Diagonal** are ticked to start with.

- Tick or untick patterns, then tap **"Play for these N"** (or **"Play for this pattern"** for one).
- **"Not now"** plays for Line and Diagonal.
- **"Rearrange"** changes the order of the list for every game.
- **"Make a custom pattern"** draws a new one (see section 13).


Bingo Boy only calls bingos for the ticked patterns.

To change patterns mid-game, tap **"Patterns"** at the top. Numbers already called count, so a card that now wins shows straight away.

9.2 The game screen



Every card marks itself




Side boards, during a game


- **Top bar**: the game number, and a **Page N** bubble in the paper color you should be playing, so you can match your paper at a glance. Beside it are **“Side boards”** and **“Patterns”**.
- **Sheets**: each main book's page for this game, then tickets and slabs.
  - Called numbers are daubed in red, and a winning card is marked **Bingo**.
  - Tap a card to see it large.
  - Tap a group or book heading to hide or show it.
- **Number board** at the bottom: all 75 numbers in B-I-N-G-O columns.

9.3 Calling numbers

- **Tap a number once when the caller announces it.** Every card in every book and every side book that's switched on marks itself.
- **Tapped the wrong one? Tap it again to remove it**, even many calls later. A bingo that needed that number is taken back off too.
- The line above the board shows the last call. Tap **“N/75”** to see every call in this game, most recent first.



Call history




Cards one number away

9.4 One number away


When cards are one number from winning, a button such as **“5 cards one away · O 71, G 47…”** appears above the board. It lists every card that's close and the number it's waiting for. **Tap a card in the list to jump straight to it** in its book.

10. Bingo! and winners

10.1 When one of your cards wins



Bingo pops up with the winning card



Winner called

The moment a call finishes a card or ticket, Bingo Boy pops up **Bingo** and the phone buzzes. It shows exactly which book, page and card won, with the pattern highlighted.


- Type what you won in **"Won $"** (optional) to keep track of your winnings.
- **"View"** shows the winning card large. **"Jump to sheet"** takes you to it in its book.
- Then choose:
  - **"Move to next page"**: every book moves to the next page for the next game. On the last page this button says **"End main game"**.
  - **"Continue on current page"**: keep playing this page with the same numbers, usually for a new pattern. Bingo Boy asks what the next game is played for.
  - **"Hide for a moment"**: closes the pop-up. A red Bingo banner stays, so you can open it again.

> **BINGOS ARE SAVED WHEN YOU CHOOSE**
> A bingo and its amount go into your stats when you tap Move to next page (or End main game) or Continue on current page.

10.2 When the hall calls a winner

Someone else won, or you've claimed your prize? Tap **“Winner called”** beside the number board, then choose **“Move to next page”** (on the last page, **“End main game”**), **“Continue on current page”** or **“Cancel”**.

11. Moving between pages and going back



Looking back at an earlier page


- The **"‹ Page N"** button beside the Main books heading goes back one page. Tap it again to go back further, as far as page 1. Nothing is cleared.
- An earlier or finished game shows a red **Completed or previous game · read only** note, so you can't change it by accident.
- Tap **"Edit this page"** to change its calls. This is useful if a game was ended by mistake.
- Tap **"Back to page N"** to return to the game being played.

12. End of the main game, and side games


12.1 Main game over

When the last page's game ends, Bingo Boy shows **Main game over**: how many bingos you got tonight, the total won and a list of each bingo. You have two choices:

- **"Finalize and archive game"** archives the night straight away (see 4.3) and returns to the home screen.
- **"Continue playing with side boards"** keeps the night going with side books only.




The last page: End main game




Main game over

12.2 Side games

- The session screen grays out your main books, which can no longer be opened or added to. Switch side books on or off, or add new ones, then tap **"Play side game"**. If none are on, the button reads **"Turn on a side board to play"**.
- Side games are numbered **Side game 1**, **Side game 2** and so on.
- After a winner (yours or the hall's), choose:
  - **"Keep playing side boards"**: starts the next side game.
  - **"End the game and archive"**: archives the night straight away and returns to the home screen.
- You can keep playing side games for as long as you like.



Main books grayed out



A ticket wins a side game



Keep playing, or archive

ARCHIVE IS IMMEDIATE

The archive buttons on these screens don't ask “are you sure?”. Archiving deletes the night's books and calls and keeps only the results.

13. Patterns

13.1 Built-in patterns


The free space always counts as marked.

Pattern	How it wins
Line	Any full row or column. Diagonals are separate.
Diagonal	Either diagonal. The free space counts.
Four corners	The four outside corners of a card.
Postage stamp	A 2×2 block in any of the four corners.
Outside edge	Every square around the edge of the card.
Pyramid	The bottom row, the middle three above it, and the free space.
Arrow	A diagonal with an arrowhead, pointing to any corner.
Top, middle & bottom	The top, middle and bottom rows all full.
Full card	Every square on the card.

13.2 Making your own pattern



Drawing a custom pattern



Settings

Go to **Settings → Make a custom pattern**, or use the button at the bottom of the game's pattern list.

1. Name it (up to 40 characters), for example “Kite” or “Letter X”.
2. Tap the squares that make the pattern.
3. Switch on **“Mirror horizontal”** and/or **“Mirror vertical”** if the pattern also counts flipped. Light squares show the mirror image.
4. Tap **“Save pattern”**.


Custom patterns are saved on your phone for every night. Starting a new session keeps them. A pattern made from the game's list is ticked for that game straight away.

Editing a pattern that's already been used

If a pattern was used in a saved night, or won a bingo, editing it would change the rules of those old games. So:

- Your edits save as a **new pattern** (named “… (copy)” unless you rename it). Tap **“See which games”** to list the nights and games that used it.
- The original can't be deleted while it's in use. To remove it, delete those nights in Sessions & stats first.


14. Sessions & stats



Your totals



Every night you've played



One night's bingos

- **Your name on this page (optional)**: type a name and the page becomes “Name's stats”.
- **Totals**:
  - **Won** (and your best night).
  - **Bingos** (split into main, slab and ticket).
  - **Sessions**.
  - **Games**, with bingos per game.

  A game counts once a number has been called in it. Sample games aren't counted unless you add them.
- **Open sessions** and **Archived sessions** list every night, showing its date, games, bingos and winnings.
- **Tap a night** to see its bingos. You can:
  - change or add a **“Won $”** amount,
  - remove a bingo with the trash button,
  - resume, archive or delete the night.

  Deleting a night removes its bingos and winnings from your stats too.


15. Settings, backup and restore

Tap **“View instruction manual”** at the top right of Settings to open the latest copy of this manual. It opens in Safari, so you need an internet connection.

15.1 Appearance

Choose **“Match device”** (follows your phone's light or dark setting), **“Green felt”** or **“Black felt”**.

15.2 Backup and restore



Backup


Bingo Boy saves on your phone as you go. Deleting the app or changing phones can remove those saves, so keep a backup somewhere you can find it again, such as Files, iCloud Drive or an email to yourself.

- **“Save a backup”** makes one file named like **bingo-boy-backup-2026-10-16.zip**. It holds:
  - every session (open, saved and archived), with its books, card numbers, called numbers, patterns, side books, bingos and winnings,
  - your custom patterns,
  - your stats name.

  Photos aren't included, since they're never kept.
- **“Restore from a backup”** picks a backup file and asks you to confirm.
  - The night that was open in the backup opens on this phone.
  - Nights already on the phone are kept; the one that was open is set aside under Open sessions.
  - Custom patterns are merged.

    - If a backed-up night is already on the phone, it's added as “… (restored)”.
- Backups can be up to 16 MB. If yours is bigger, remove old nights you don't need.

16. The sample game



Set up a sample night

Try Bingo Boy with made-up books before you play for real. Choose how many:

- **Books**: 1–10.
- **Pages in each book**: 1–12.
- **Cards on each page**: 1, 2, 4, 6, 9 or 12.
- **Side books too**: a slab and a pull-tab ticket.

Then tap **“Deal the books”**. Every book is identical, like at a hall, and the cards are new each time.

A sample night isn't in your stats unless you tap **“Add this sample game to my stats”**. If you archive a sample without adding it, it's removed.

In the sample you don't need to tick the “I checked every card” box, and any card can be shuffled.

17. Tips and help inside the app



How to play

- When a game opens, a **Quick tips** bubble appears.
  - **“Got it”** closes it for now.
  - **“Don't show again”** hides it for good.
- **How to play** on the home screen has short guides on getting started, playing a game, winning, pages, slabs and tickets, and sessions and stats. Its last topic, **Full manual**, points you to this manual.
- **Settings → View instruction manual** opens this manual on your phone.
- If you hid the tips, **How to play** has a **“Show game tips again”** button.

18. Limits at a glance

Item	Limit
Card type	75-ball, 5 × 5, free center
Cards on a page	Up to 6 across × 8 down (48)
Photo or scan file size	30 MB
Pages in one PDF or TIFF scan	100
Image size	16,384 pixels on a side, 48 megapixels
Book name / night name / side book name	60 / 40 / 30 characters
Color name / pattern name / stats name	30 / 40 / 30 characters
Randomize book	Up to 30 pages
Numbers on a ticket	1 to 10, picked exactly
Sample game	1–10 books, 1–12 pages
Backup file	16 MB

19. Troubleshooting and common questions

A number was read wrong.
Open the book, tap **“Fix numbers”** on that page, tap the square and type the right number. This works at any time, even mid-game.

“Couldn't find the cards.”
Lay the page flat, fill the photo with the cards, use even light and try again. You can also tap **“Enter numbers myself”**.

The Save button won't turn on.
Fix every empty, out-of-column or repeated square, then tick “I checked every card against my paper…”.

I can't tap Play.
Your main books have different page counts. Fix the books marked in red (section 7).

I can't add a page to my book.
Play has moved past page 1, so the books are set for the game. You can still add a brand-new book, which starts on the current page.

I need to change my books, but I've only played page 1.
Make the change and choose **“Clear and continue”**. Page 1 starts over.

I tapped a number by mistake.
Tap it again on the number board to remove it.

I moved to the next page by mistake.
Tap **“‹ Page N”** to go back, then **“Edit this page”** if you need to keep calling there.

Bingo didn't pop up for a win the hall called.
Check which patterns are ticked for this game (tap **“Patterns”**). Bingo Boy only calls the ticked patterns.

“This phone couldn't save the latest change.”
Free up some storage space. Bingo Boy keeps trying to save on its own.

Moving to a new phone.
On the old phone, use **Settings → Backup and restore → Save a backup**. On the new phone, install Bingo Boy and use **“Restore from a backup”**.

20. Privacy and support

- Bingo Boy needs no account, and nothing is uploaded. Card reading happens on your phone, and photos aren't kept.
- Privacy policy: ppp12ag.github.io/Bingo-Boy/privacy.html
- Support and questions: bingoboyapp@gmail.com. If something went wrong, tell us your phone model and what you were doing.
- The latest version of this manual: ppp12ag.github.io/Bingo-Boy/manual.pdf

This manual describes Bingo Boy 1.1 (build 13). Screens may look slightly different on your phone.