Install and Configure OpenVPN

Step 1: Install OpenVPN and Easy-RSA

dnf install epel-release -y
rpm -qa | grep openvpn
dnf install openvpn easy-rsa -y

Step 2: Set up Easy-RSA for OpenVPN

cp -rv /usr/share/easy-rsa/3.1.6/* /etc/openvpn/
cd /etc/openvpn/
./easyrsa init-pki
./easyrsa build-ca nopass
./easyrsa gen-req server nopass
./easyrsa sign-req server server
./easyrsa gen-req client nopass
./easyrsa sign-req client client
./easyrsa gen-dh
openvpn --genkey secret ta.key

Step 3: Move Certificates and Keys

mv pki/ca.crt pki/dh.pem /etc/openvpn/ mv pki/issued/server.crt /etc/openvpn/ mv pki/private/server.key /etc/openvpn/

Step 4: Configure OpenVPN Server

cp -rv /usr/share/doc/openvpn/sample/sample-config-files/server.conf /etc/openvpn/server/
vi /etc/openvpn/server/server.conf # Customize server config if needed
vi /etc/sysctl.conf # Enable IP forwarding
net.ipv4.ip_forward = 1

sysctl -p

chmod 600 /etc/openvpn/server/server.conf /etc/openvpn/*.key /etc/openvpn/*.crt

Step 5: Configure Firewall and Start OpenVPN Service

firewall-cmd --add-service=openvpn --permanent

firewall-cmd --add-masquerade --permanent

firewall-cmd --reload

systemctl start openvpn-server@server.service

systemctl enable openvpn-server@server.service

systemctl status openvpn-server@server.service

Step 6: Set Up OpenVPN Client

dnf install openvpn -y

cd /etc/openvpn/

scp /etc/openvpn/ca.crt /etc/openvpn/ta.key /etc/openvpn/pki/issued/client.crt /etc/openvpn/pki/private/client.key root@192.168.100.178:/etc/openvpn/

cp /usr/share/doc/openvpn/sample/sample-config-files/client.conf /etc/openvpn/client/

vi /etc/openvpn/client/client.conf # Update server IP: 192.168.100.167

chmod 600 /etc/openvpn/*.key /etc/openvpn/*.crt /etc/openvpn/client/client.conf

openvpn --config /etc/openvpn/client/client.conf