FreeCoAP

Generated by Doxygen 1.8.11

Contents

1	Clas	s Index			1
	1.1	Class I	_ist		 1
2	File	Index			3
	2.1	File Lis	st		 3
3	Clas	s Docu	mentation		5
	3.1	coap_c	client_t Str	uct Reference	 5
		3.1.1	Detailed	Description	 5
		3.1.2	Member	Data Documentation	 5
			3.1.2.1	cred	 5
			3.1.2.2	num_retrans	 6
			3.1.2.3	priority	 6
			3.1.2.4	sd	 6
			3.1.2.5	server_host	 6
			3.1.2.6	server_port	 6
			3.1.2.7	server_sin	 6
			3.1.2.8	server_sin_len	 6
			3.1.2.9	session	 6
			3.1.2.10	timeout	 6
			3.1.2.11	timer_fd	 6
	3.2	coap_r	msg_op St	ruct Reference	 7
		3.2.1	Detailed	Description	 7
		322	Member	Data Documentation	7

iv CONTENTS

		3.2.2.1	len	 	7
		3.2.2.2	next	 	7
		3.2.2.3	num	 	7
		3.2.2.4	val	 	8
3.3	coap_ı	msg_op_lis	st_t Struct Reference	 	8
	3.3.1	Detailed	Description	 	8
	3.3.2	Member	Data Documentation	 	8
		3.3.2.1	first	 	8
		3.3.2.2	last	 	9
3.4	coap_i	msg_t Stru	uct Reference	 	9
	3.4.1	Detailed	Description	 	10
	3.4.2	Member	Data Documentation	 	10
		3.4.2.1	code_class	 	10
		3.4.2.2	code_detail	 	10
		3.4.2.3	msg_id	 	10
		3.4.2.4	op_list	 	10
		3.4.2.5	payload	 	10
		3.4.2.6	payload_len	 	10
		3.4.2.7	token	 	10
		3.4.2.8	token_len	 	10
		3.4.2.9	type	 	10
		3.4.2.10	ver	 	11
3.5	coap_s	server Stru	uct Reference	 	11
	3.5.1	Detailed	Description	 	12
	3.5.2	Member	Data Documentation	 	12
		3.5.2.1	cred	 	12
		3.5.2.2	dh_params	 	12
		3.5.2.3	handle	 	12
		3.5.2.4	msg_id	 	12
		3.5.2.5	priority	 	12

CONTENTS

		3.5.2.6	sd	. 12
		3.5.2.7	sep_list	. 12
		3.5.2.8	trans	. 12
3.6	coap_s	server_path	h Struct Reference	. 13
	3.6.1	Detailed I	Description	. 13
	3.6.2	Member I	Data Documentation	. 13
		3.6.2.1	next	. 13
		3.6.2.2	str	. 13
3.7	coap_s	server_path	h_list_t Struct Reference	. 14
	3.7.1	Detailed I	Description	. 14
	3.7.2	Member I	Data Documentation	. 14
		3.7.2.1	first	. 14
		3.7.2.2	last	. 14
3.8	coap_s	server_tran	ns Struct Reference	. 15
	3.8.1	Detailed I	Description	. 16
	3.8.2	Member I	Data Documentation	. 16
		3.8.2.1	active	. 16
		3.8.2.2	client_addr	. 16
		3.8.2.3	client_sin	. 16
		3.8.2.4	client_sin_len	. 16
		3.8.2.5	last_use	. 16
		3.8.2.6	num_retrans	. 16
		3.8.2.7	req	. 16
		3.8.2.8	resp	. 16
		3.8.2.9	server	. 16
		3.8.2.10	session	. 17
		3.8.2.11	timeout	. 17
		3.8.2.12	timer_fd	. 17

vi

4	File	Docum	entation		19
	4.1	lib/incl	ude/coap_	client.h File Reference	19
		4.1.1	Detailed	Description	20
		4.1.2	Macro D	efinition Documentation	20
			4.1.2.1	COAP_CLIENT_HOST_BUF_LEN	20
			4.1.2.2	COAP_CLIENT_PORT_BUF_LEN	20
		4.1.3	Function	Documentation	20
			4.1.3.1	coap_client_create(coap_client_t *client, const char *host, const char *port, const char *key_file_name, const char *cert_file_name, const char *trust_file_\circ name, const char *crl_file_name, const char *common_name)	20
			4.1.3.2	coap_client_destroy(coap_client_t *client)	21
			4.1.3.3	coap_client_exchange(coap_client_t *client, coap_msg_t *req, coap_msg_t *resp)	21
	4.2	lib/incl	ude/coap_	ipv.h File Reference	21
		4.2.1	Detailed	Description	22
	4.3	lib/incl	ude/coap_	log.h File Reference	23
		4.3.1	Detailed	Description	23
		4.3.2	Macro D	efinition Documentation	24
			4.3.2.1	COAP_LOG_DEF_LEVEL	24
		4.3.3	Enumera	ation Type Documentation	24
			4.3.3.1	coap_log_level_t	24
		4.3.4	Function	Documentation	24
			4.3.4.1	coap_log_debug(const char *msg,)	24
			4.3.4.2	coap_log_error(const char *msg,)	24
			4.3.4.3	coap_log_get_level(void)	24
			4.3.4.4	coap_log_info(const char *msg,)	25
			4.3.4.5	coap_log_notice(const char *msg,)	25
			4.3.4.6	coap_log_set_level(coap_log_level_t level)	25
			4.3.4.7	coap_log_warn(const char *msg,)	25
	4.4	lib/incl	ude/coap_	msg.h File Reference	26
		4.4.1	Detailed	Description	29
		4.4.2	Macro D	efinition Documentation	29

CONTENTS vii

4.4.2.1	coap_msg_get_code_class	29
4.4.2.2	coap_msg_get_code_detail	29
4.4.2.3	coap_msg_get_first_op	29
4.4.2.4	coap_msg_get_msg_id	29
4.4.2.5	coap_msg_get_payload	30
4.4.2.6	coap_msg_get_payload_len	30
4.4.2.7	coap_msg_get_token	30
4.4.2.8	coap_msg_get_token_len	30
4.4.2.9	coap_msg_get_type	30
4.4.2.10	coap_msg_get_ver	30
4.4.2.11	coap_msg_is_empty	30
4.4.2.12	COAP_MSG_MAX_BUF_LEN	30
4.4.2.13	COAP_MSG_MAX_CODE_CLASS	30
4.4.2.14	COAP_MSG_MAX_CODE_DETAIL	30
4.4.2.15	COAP_MSG_MAX_MSG_ID	31
4.4.2.16	COAP_MSG_MAX_TOKEN_LEN	31
4.4.2.17	coap_msg_op_get_len	31
4.4.2.18	coap_msg_op_get_next	31
4.4.2.19	coap_msg_op_get_num	31
4.4.2.20	coap_msg_op_get_val	31
4.4.2.21	COAP_MSG_OP_MAX_BLOCK_SIZE	31
4.4.2.22	COAP_MSG_OP_MAX_BLOCK_VAL_LEN	31
4.4.2.23	coap_msg_op_num_is_critical	31
4.4.2.24	coap_msg_op_num_is_unsafe	31
4.4.2.25	coap_msg_op_num_no_cache_key	32
4.4.2.26	coap_msg_op_set_len	32
4.4.2.27	coap_msg_op_set_next	32
4.4.2.28	coap_msg_op_set_num	32
4.4.2.29	coap_msg_op_set_val	32
4.4.2.30	COAP_MSG_OP_URI_PATH_MAX_LEN	32

viii CONTENTS

	4.4.2.31	COAP_MSG_VER	32
4.4.3	Enumera	tion Type Documentation	32
	4.4.3.1	coap_msg_class_t	32
	4.4.3.2	coap_msg_client_err_t	33
	4.4.3.3	coap_msg_method_t	33
	4.4.3.4	coap_msg_op_num_t	33
	4.4.3.5	coap_msg_server_err_t	34
	4.4.3.6	coap_msg_success_t	34
	4.4.3.7	coap_msg_type_t	34
4.4.4	Function	Documentation	34
	4.4.4.1	coap_msg_add_op(coap_msg_t *msg, unsigned num, unsigned len, const char *val)	34
	4.4.4.2	coap_msg_check_critical_ops(coap_msg_t *msg)	35
	4.4.4.3	coap_msg_check_unsafe_ops(coap_msg_t *msg)	35
	4.4.4.4	coap_msg_copy(coap_msg_t *dst, coap_msg_t *src)	36
	4.4.4.5	coap_msg_create(coap_msg_t *msg)	36
	4.4.4.6	coap_msg_destroy(coap_msg_t *msg)	36
	4.4.4.7	coap_msg_format(coap_msg_t *msg, char *buf, size_t len)	36
	4.4.4.8	coap_msg_gen_rand_str(char *buf, size_t len)	37
	4.4.4.9	coap_msg_op_format_block_val(char *val, unsigned len, unsigned num, unsigned more, unsigned size)	37
	4.4.4.10	coap_msg_op_num_is_recognized(unsigned num)	38
	4.4.4.11	coap_msg_op_parse_block_val(unsigned *num, unsigned *more, unsigned *size, const char *val, unsigned len)	38
	4.4.4.12	coap_msg_parse(coap_msg_t *msg, char *buf, size_t len)	38
	4.4.4.13	<pre>coap_msg_parse_type_msg_id(char *buf, size_t len, unsigned *type, unsigned *msg_id)</pre>	39
	4.4.4.14	coap_msg_reset(coap_msg_t *msg)	39
	4.4.4.15	coap_msg_set_code(coap_msg_t *msg, unsigned code_class, unsigned code _detail)	40
	4.4.4.16	coap_msg_set_msg_id(coap_msg_t *msg, unsigned msg_id)	40
	4.4.4.17	coap_msg_set_payload(coap_msg_t *msg, char *buf, size_t len)	40
	4.4.4.18	coap_msg_set_token(coap_msg_t *msg, char *buf, size_t len)	41

CONTENTS

		4.4.4.19	coap_msg_set_type(coap_msg_t *msg, unsigned type)	41
		4.4.4.20	coap_msg_uri_path_to_str(coap_msg_t *msg, char *buf, size_t len)	42
4.5	lib/incl	ude/coap_	server.h File Reference	42
	4.5.1	Detailed	Description	44
	4.5.2	Macro De	efinition Documentation	44
		4.5.2.1	COAP_SERVER_ADDR_BUF_LEN	44
		4.5.2.2	COAP_SERVER_DIAG_PAYLOAD_LEN	44
		4.5.2.3	COAP_SERVER_NUM_TRANS	44
	4.5.3	Enumera	tion Type Documentation	44
		4.5.3.1	coap_server_resp_t	44
	4.5.4	Function	Documentation	44
		4.5.4.1	coap_server_add_sep_resp_uri_path(coap_server_t *server, const char *str)	44
		4.5.4.2	coap_server_create(coap_server_t *server, int(*handle)(coap_server_t *, coap_msg_t *, coap_msg_t *), const char *host, const char *port, const char *key_file_name, const char *cert_file_name, const char *trust_file_name, const char *crl_file_name)	45
		4.5.4.3	coap_server_destroy(coap_server_t *server)	45
		4.5.4.4	coap_server_get_next_msg_id(coap_server_t *server)	46
		4.5.4.5	coap_server_run(coap_server_t *server)	46
4.6	lib/src/	coap_clien	nt.c File Reference	46
	4.6.1	Detailed	Description	47
	4.6.2	Macro De	efinition Documentation	48
		4.6.2.1	COAP_CLIENT_ACK_TIMEOUT_SEC	48
		4.6.2.2	COAP_CLIENT_DTLS_MTU	48
		4.6.2.3	COAP_CLIENT_DTLS_PRIORITIES	48
		4.6.2.4	COAP_CLIENT_DTLS_RETRANS_TIMEOUT	48
		4.6.2.5	COAP_CLIENT_DTLS_TOTAL_TIMEOUT	48
		4.6.2.6	COAP_CLIENT_MAX_RETRANSMIT	48
		4.6.2.7	COAP_CLIENT_RESP_TIMEOUT_SEC	48
	4.6.3	Function	Documentation	48
		4.6.3.1	coap_client_create(coap_client_t *client, const char *host, const char *port, const char *key_file_name, const char *cert_file_name, const char *trust_file_ const char *crl_file_name, const char *common_name)	48

CONTENTS

		4.6.3.2	coap_client_destroy(coap_client_t *client)	49
		4.6.3.3	coap_client_exchange(coap_client_t *client, coap_msg_t *req, coap_msg_t *resp) 49
4.7	lib/src/d	coap_log.c	File Reference	49
	4.7.1	Detailed	Description	50
	4.7.2	Function	Documentation	50
		4.7.2.1	coap_log_debug(const char *msg,)	50
		4.7.2.2	coap_log_error(const char *msg,)	51
		4.7.2.3	coap_log_get_level(void)	51
		4.7.2.4	coap_log_info(const char *msg,)	51
		4.7.2.5	coap_log_notice(const char *msg,)	51
		4.7.2.6	coap_log_set_level(coap_log_level_t level)	51
		4.7.2.7	coap_log_warn(const char *msg,)	52
4.8	lib/src/d	coap_msg	.c File Reference	52
	4.8.1	Detailed	Description	53
	4.8.2	Macro De	efinition Documentation	54
		4.8.2.1	coap_msg_op_list_get_first	54
		4.8.2.2	coap_msg_op_list_get_last	54
		4.8.2.3	coap_msg_op_list_is_empty	54
	4.8.3	Function	Documentation	54
		4.8.3.1	coap_msg_add_op(coap_msg_t *msg, unsigned num, unsigned len, const char *val)	54
		4.8.3.2	coap_msg_check_critical_ops(coap_msg_t *msg)	54
		4.8.3.3	coap_msg_check_unsafe_ops(coap_msg_t *msg)	55
		4.8.3.4	coap_msg_copy(coap_msg_t *dst, coap_msg_t *src)	55
		4.8.3.5	coap_msg_create(coap_msg_t *msg)	56
		4.8.3.6	coap_msg_destroy(coap_msg_t *msg)	56
		4.8.3.7	coap_msg_format(coap_msg_t *msg, char *buf, size_t len)	56
		4.8.3.8	coap_msg_gen_rand_str(char *buf, size_t len)	56
		4.8.3.9	coap_msg_op_format_block_val(char *val, unsigned len, unsigned num, unsigned more, unsigned size)	57
		4.8.3.10	coap_msg_op_num_is_recognized(unsigned num)	57

CONTENTS xi

dex				67
		4.9.3.5	coap_server_run(coap_server_t *server)	65
		4.9.3.4	coap_server_get_next_msg_id(coap_server_t *server)	65
		4.9.3.3	coap_server_destroy(coap_server_t *server)	64
		4.9.3.2	coap_server_create(coap_server_t *server, int(*handle)(coap_server_t *, coap_msg_t *, coap_msg_t *), const char *host, const char *port, const char *key_file_name, const char *cert_file_name, const char *trust_file_name, const char *crl_file_name)	64
		4.9.3.1	coap_server_add_sep_resp_uri_path(coap_server_t *server, const char *str)	63
	4.9.3	Function	Documentation	63
		4.9.2.7	COAP_SERVER_MAX_RETRANSMIT	63
		4.9.2.6	COAP_SERVER_DTLS_TOTAL_TIMEOUT	63
		4.9.2.5	COAP_SERVER_DTLS_RETRANS_TIMEOUT	63
		4.9.2.4	COAP_SERVER_DTLS_PRIORITIES	63
		4.9.2.3	COAP_SERVER_DTLS_NUM_DH_BITS	63
		4.9.2.2	COAP_SERVER_DTLS_MTU	63
		4.9.2.1	COAP_SERVER_ACK_TIMEOUT_SEC	63
	4.9.2	Macro De	efinition Documentation	63
	4.9.1	Detailed	Description	63
4.9	lib/src/	coap_serv	er.c File Reference	61
		4.8.3.20	coap_msg_uri_path_to_str(coap_msg_t *msg, char *buf, size_t len)	61
		4.8.3.19	coap_msg_set_type(coap_msg_t *msg, unsigned type)	61
		4.8.3.18	coap_msg_set_token(coap_msg_t *msg, char *buf, size_t len)	60
		4.8.3.17	coap_msg_set_payload(coap_msg_t *msg, char *buf, size_t len)	60
		4.8.3.16	coap_msg_set_msg_id(coap_msg_t *msg, unsigned msg_id)	59
		4.8.3.15	coap_msg_set_code(coap_msg_t *msg, unsigned code_class, unsigned code ← detail)	59
		4.8.3.14	coap_msg_reset(coap_msg_t *msg)	59
		4.8.3.13	coap_msg_parse_type_msg_id(char *buf, size_t len, unsigned *type, unsigned *msg_id)	58
		4.8.3.12	coap_msg_parse(coap_msg_t *msg, char *buf, size_t len)	58
		4.0.3.11	*size, const char *val, unsigned len)	57
		4.0.3.11	coap may up parse block val(unsigned *mum, unsigned *more, unsigned	

Index

Chapter 1

Class Index

1.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

pap_client_t	
Client structure	5
pap_msg_op	
Option structure	7
pap_msg_op_list_t	
Option linked-list structure	8
pap_msg_t	
Message structure	9
pap_server	
Server structure	11
pap_server_path	
URI path structure	13
pap_server_path_list_t	
URI path list structure	14
pap_server_trans	
Transaction structure	15

2 Class Index

Chapter 2

File Index

2.1 File List

Here is a list of all documented files with brief descriptions:

lib/include/coap_client.h Include file for the FreeCoAP client library	19
lib/include/coap ipv.h	10
Include file for the FreeCoAP IP Version (IPv4/IPv6) abstraction layer	21
lib/include/coap_log.h	
Include file for the FreeCoAP logging module	23
lib/include/coap msg.h	
Include file for the FreeCoAP message parser/formatter library	26
lib/include/coap_server.h	
Include file for the FreeCoAP server library	42
lib/src/coap_client.c	
Source file for the FreeCoAP client library	46
lib/src/coap_log.c	
Source file for the FreeCoAP logging module	49
lib/src/coap_msg.c	
Source file for the FreeCoAP message parser/formatter library	52
lib/src/coap_server.c	
Source file for the FreeCoAP server library	61

File Index

Chapter 3

Class Documentation

3.1 coap_client_t Struct Reference

Client structure.

```
#include <coap_client.h>
```

Public Attributes

- int sd
- · int timer fd
- struct timespec timeout
- unsigned num_retrans
- coap_ipv_sockaddr_in_t server_sin
- socklen_t server_sin_len
- char server_host [COAP_CLIENT_HOST_BUF_LEN]
- char server_port [COAP_CLIENT_PORT_BUF_LEN]
- gnutls_session_t session
- gnutls_certificate_credentials_t cred
- gnutls_priority_t priority

3.1.1 Detailed Description

Client structure.

3.1.2 Member Data Documentation

3.1.2.1 gnutls_certificate_credentials_t coap_client_t::cred

DTLS credentials

3.1.2.2 unsigned coap_client_t::num_retrans Current number of retransmissions 3.1.2.3 gnutls_priority_t coap_client_t::priority DTLS priorities 3.1.2.4 int coap_client_t::sd Socket descriptor 3.1.2.5 char coap_client_t::server_host[COAP_CLIENT_HOST_BUF_LEN] String to hold the server host address 3.1.2.6 char coap_client_t::server_port[COAP_CLIENT_PORT_BUF_LEN] String to hold the server port number 3.1.2.7 coap_ipv_sockaddr_in_t coap_client_t::server_sin Socket structture 3.1.2.8 socklen_t coap_client_t::server_sin_len Socket structure length 3.1.2.9 gnutls_session_t coap_client_t::session DTLS session 3.1.2.10 struct timespec coap_client_t::timeout Timeout value 3.1.2.11 int coap_client_t::timer_fd Timer file descriptor The documentation for this struct was generated from the following file:


• lib/include/coap_client.h

3.2 coap_msg_op Struct Reference

Option structure.

#include <coap_msg.h>

Collaboration diagram for coap_msg_op:



Public Attributes

- unsigned num
- unsigned len
- char * val
- struct coap_msg_op * next

3.2.1 Detailed Description

Option structure.

3.2.2 Member Data Documentation

3.2.2.1 unsigned coap_msg_op::len

Option length

3.2.2.2 struct coap_msg_op* coap_msg_op::next

Pointer to the next option structure in the list

3.2.2.3 unsigned coap_msg_op::num

Option number

3.2.2.4 char* coap_msg_op::val

Pointer to a buffer containing the option value

The documentation for this struct was generated from the following file:


• lib/include/coap_msg.h

3.3 coap_msg_op_list_t Struct Reference

Option linked-list structure.

```
#include <coap_msg.h>
```

Collaboration diagram for coap_msg_op_list_t:



Public Attributes

- coap_msg_op_t * first
- coap_msg_op_t * last

3.3.1 Detailed Description

Option linked-list structure.

3.3.2 Member Data Documentation

3.3.2.1 coap_msg_op_t* coap_msg_op_list_t::first

Pointer to the first option structure in the list

3.3.2.2 coap_msg_op_t* coap_msg_op_list_t::last

Pointer to the last option structure in the list

The documentation for this struct was generated from the following file:


• lib/include/coap_msg.h

3.4 coap_msg_t Struct Reference

Message structure.

```
#include <coap_msg.h>
```

Collaboration diagram for coap_msg_t:



Public Attributes

- · unsigned ver
- coap_msg_type_t type
- unsigned token_len
- unsigned code_class
- unsigned code_detail
- unsigned msg_id
- char token [COAP_MSG_MAX_TOKEN_LEN]
- coap_msg_op_list_t op_list
- char * payload
- size_t payload_len

3.4.1 Detailed Description

Message structure.

3.4.2 Member Data Documentation

3.4.2.1 unsigned coap_msg_t::code_class

Code class

3.4.2.2 unsigned coap_msg_t::code_detail

Code detail

3.4.2.3 unsigned coap_msg_t::msg_id

Message ID

3.4.2.4 coap_msg_op_list_t coap_msg_t::op_list

Option list

3.4.2.5 char* coap_msg_t::payload

Pointer to a buffer containing the payload

3.4.2.6 size_t coap_msg_t::payload_len

Length of the payload

3.4.2.7 char coap_msg_t::token[COAP_MSG_MAX_TOKEN_LEN]

Token value

3.4.2.8 unsigned coap_msg_t::token_len

Token length

3.4.2.9 coap_msg_type_t coap_msg_t::type

Message type

3.4.2.10 unsigned coap_msg_t::ver

CoAP version

The documentation for this struct was generated from the following file:


• lib/include/coap_msg.h

3.5 coap_server Struct Reference

Server structure.

#include <coap_server.h>

Collaboration diagram for coap_server:



Public Attributes

- int sd
- unsigned msg_id
- coap_server_path_list_t sep_list
- coap_server_trans_t trans [COAP_SERVER_NUM_TRANS]
- int(* handle)(struct coap_server *, coap_msg_t *, coap_msg_t *)
- · gnutls_certificate_credentials_t cred
- gnutls_priority_t priority
- gnutls_dh_params_t dh_params

3.5.1 Detailed Description

Server structure.

3.5.2 Member Data Documentation

3.5.2.1 gnutls_certificate_credentials_t coap_server::cred

DTLS credentials

3.5.2.2 gnutls_dh_params_t coap_server::dh_params

Diffie-Hellman parameters

3.5.2.3 int(* coap_server::handle) (struct coap_server *, coap_msg_t *, coap_msg_t *)

Call-back function to handle requests and generate responses

3.5.2.4 unsigned coap_server::msg_id

Last message ID value used in a response message

3.5.2.5 gnutls_priority_t coap_server::priority

DTLS priorities

3.5.2.6 int coap_server::sd

Socket descriptor

3.5.2.7 coap_server_path_list_t coap_server::sep_list

List of URI paths that require separate responses

3.5.2.8 coap_server_trans_t coap_server::trans[COAP_SERVER_NUM_TRANS]

Array of transaction structures

The documentation for this struct was generated from the following file:


• lib/include/coap_server.h

3.6 coap_server_path Struct Reference

URI path structure.

```
#include <coap_server.h>
```

Collaboration diagram for coap_server_path:



Public Attributes

- char * str
- struct coap_server_path * next

3.6.1 Detailed Description

URI path structure.

3.6.2 Member Data Documentation

3.6.2.1 struct coap_server_path* coap_server_path::next

Pointer to the next URI path structure in the list

3.6.2.2 char* coap_server_path::str

String containing a path

The documentation for this struct was generated from the following file:


lib/include/coap_server.h

3.7 coap_server_path_list_t Struct Reference

URI path list structure.

```
#include <coap_server.h>
```

Collaboration diagram for coap_server_path_list_t:



Public Attributes

- coap_server_path_t * first
- coap_server_path_t * last

3.7.1 Detailed Description

URI path list structure.

3.7.2 Member Data Documentation

3.7.2.1 coap_server_path_t* coap_server_path_list_t::first

Pointer to the first URI path structure in the list

3.7.2.2 coap_server_path_t* coap_server_path_list_t::last

Pointer to the last URI path structure in the list

The documentation for this struct was generated from the following file:


• lib/include/coap_server.h

3.8 coap_server_trans Struct Reference

Transaction structure.

#include <coap_server.h>

Collaboration diagram for coap_server_trans:



Public Attributes

- · int active
- time_t last_use
- int timer fd
- struct timespec timeout
- unsigned num_retrans
- coap_ipv_sockaddr_in_t client_sin
- socklen_t client_sin_len
- char client_addr [COAP_SERVER_ADDR_BUF_LEN]
- coap_msg_t req
- · coap_msg_t resp
- struct coap_server * server
- gnutls_session_t session

3.8.1 Detailed Description

Transaction structure.

3.8.2 Member Data Documentation

3.8.2.1 int coap_server_trans::active

Flag to indicate if this transaction structure contains valid data

3.8.2.2 char coap_server_trans::client_addr[COAP_SERVER_ADDR_BUF_LEN]

String to hold the client address

3.8.2.3 coap_ipv_sockaddr_in_t coap_server_trans::client_sin

Socket structure

3.8.2.4 socklen_t coap_server_trans::client_sin_len

Socket structure length

3.8.2.5 time_t coap_server_trans::last_use

The time that this transaction structure was last used

3.8.2.6 unsigned coap_server_trans::num_retrans

Current number of retransmissions

3.8.2.7 coap_msg_t coap_server_trans::req

Last request message received for this transaction

3.8.2.8 coap_msg_t coap_server_trans::resp

Last response message sent for this transaction

3.8.2.9 struct coap_server* coap_server_trans::server

Pointer to the containing server structure

3.8.2.10 gnutls_session_t coap_server_trans::session

DTLS session

3.8.2.11 struct timespec coap_server_trans::timeout

Timeout value

3.8.2.12 int coap_server_trans::timer_fd

Timer file descriptor

The documentation for this struct was generated from the following file:

• lib/include/coap_server.h

Chapter 4


File Documentation

4.1 lib/include/coap_client.h File Reference


Include file for the FreeCoAP client library.

```
#include <time.h>
#include <netinet/in.h>
#include <gnutls/gnutls.h>
#include <gnutls/dtls.h>
#include "coap_msg.h"
#include "coap_ipv.h"
```

Include dependency graph for coap_client.h:



This graph shows which files directly or indirectly include this file:



20 File Documentation

Classes

struct coap_client_t

Client structure.

Macros

- #define COAP_CLIENT_HOST_BUF_LEN 128
- #define COAP_CLIENT_PORT_BUF_LEN 8

Functions

int coap_client_create (coap_client_t *client, const char *host, const char *port, const char *key_file_name, const char *cert_file_name, const char *trust_file_name, const char *crl_file_name, const char *common
 __name)

Initialise a client structure.

void coap_client_destroy (coap_client_t *client)

Deinitialise a client structure.

int coap_client_exchange (coap_client_t *client, coap_msg_t *req, coap_msg_t *resp)

Send a request to the server and receive the response.

4.1.1 Detailed Description

Include file for the FreeCoAP client library.

4.1.2 Macro Definition Documentation

4.1.2.1 #define COAP_CLIENT_HOST_BUF_LEN 128

Buffer length for host addresses

4.1.2.2 #define COAP_CLIENT_PORT_BUF_LEN 8

Buffer length for port numbers

4.1.3 Function Documentation

4.1.3.1 int coap_client_create (coap_client_t * client, const char * host, const char * port, const char * key_file_name, const char * cert_file_name, const char * crl_file_name, const char * common_name)

Initialise a client structure.

Parameters

out	client	Pointer to a client structure	
in	host	Pointer to a string containing the host address of the server	
in	port	Port number of the server	Generated by Doxygen
in	key_file_name	String containing the DTLS key file name	
in	cert_file_name	String containing the DTLS certificate file name	
in	trust file name	String containing the DTLS trust file name	

Returns

Operation status

Return values

0	Success
<0	Error

4.1.3.2 void coap_client_destroy (coap_client_t * client)

Deinitialise a client structure.

Parameters

in,out	client	Pointer to a client structure
--------	--------	-------------------------------

4.1.3.3 int coap_client_exchange ($coap_client_t * client$, $coap_msg_t * req$, $coap_msg_t * resp$)

Send a request to the server and receive the response.

This function sets the message ID and token fields of the request message overriding any values set by the calling function.

Parameters

in,out	client	Pointer to a client structure
in	req	Pointer to the request message
out	resp	Pointer to the response message

Returns

Operation status

Return values


0	Success
<0	Error

4.2 lib/include/coap_ipv.h File Reference


Include file for the FreeCoAP IP Version (IPv4/IPv6) abstraction layer.

22 File Documentation

#include <netinet/in.h>
Include dependency graph for coap_ipv.h:



This graph shows which files directly or indirectly include this file:



Macros

- #define COAP_IPV_AF_INET AF_INET
- #define COAP_IPV_SIN_ADDR sin_addr
- #define COAP_IPV_SIN_PORT sin_port

Typedefs

• typedef struct sockaddr_in coap_ipv_sockaddr_in_t


4.2.1 Detailed Description

Include file for the FreeCoAP IP Version (IPv4/IPv6) abstraction layer.

4.3 lib/include/coap_log.h File Reference

Include file for the FreeCoAP logging module.

This graph shows which files directly or indirectly include this file:



Macros

#define COAP_LOG_DEF_LEVEL COAP_LOG_ERROR

Enumerations

```
    enum coap_log_level_t {
        COAP_LOG_ERROR = 0, COAP_LOG_WARN = 1, COAP_LOG_NOTICE = 2, COAP_LOG_INFO = 3,
        COAP_LOG_DEBUG = 4 }
        Log level.
```

Functions

```
    void coap_log_set_level (coap_log_level_t level)
```

Set the log level.

coap_log_level_t coap_log_get_level (void)

Get the log level.

void coap_log_error (const char *msg,...)

Log an error message.

• void coap_log_warn (const char *msg,...)

Log a warning message.

• void coap_log_notice (const char *msg,...)

Log an notice message.

• void coap_log_info (const char *msg,...)

Log an info message.

• void coap_log_debug (const char *msg,...)

Log a debug message.

4.3.1 Detailed Description

Include file for the FreeCoAP logging module.

24 File Documentation

4.3.2 Macro Definition Documentation

4.3.2.1 #define COAP_LOG_DEF_LEVEL COAP_LOG_ERROR

Default log level

4.3.3 Enumeration Type Documentation

4.3.3.1 enum coap_log_level_t

Log level.

Enumerator

COAP_LOG_ERROR Error log level
COAP_LOG_WARN Warning log level
COAP_LOG_NOTICE Notice log level
COAP_LOG_INFO Informational log level
COAP_LOG_DEBUG Debug log level

4.3.4 Function Documentation

4.3.4.1 void coap_log_debug (const char * msg, ...)

Log a debug message.

Parameters

in	msg	String containing format specifiers
in		arguments for the format specifiers

4.3.4.2 void coap_log_error (const char * msg, ...)

Log an error message.

Parameters

in	msg	String containing format specifiers
in		arguments for the format specifiers

4.3.4.3 coap_log_level_t coap_log_get_level (void)

Get the log level.

Returns

The current log level

4.3.4.4 void coap_log_info (const char * msg, ...)

Log an info message.

Parameters

in	msg	String containing format specifiers
in		arguments for the format specifiers

4.3.4.5 void coap_log_notice (const char * msg, ...)

Log an notice message.

Parameters

in	msg	String containing format specifiers
in		arguments for the format specifiers

4.3.4.6 void coap_log_set_level (coap_log_level_t level)

Set the log level.

Messages with a severity below this level will be filtered. Error messages cannot be filtered.

Parameters

in	level	The new log level
----	-------	-------------------

- < Warning log level
- < Notice warning level
- < Informational warning level
- < Debug warning level

4.3.4.7 void coap_log_warn (const char * msg, ...)

Log a warning message.


Parameters

in	msg	String containing format specifiers
in		arguments for the format specifiers


4.4 lib/include/coap_msg.h File Reference

Include file for the FreeCoAP message parser/formatter library.

```
#include <stddef.h>
#include <sys/types.h>
Include dependency graph for coap_msg.h:
```



This graph shows which files directly or indirectly include this file:



Classes

struct coap_msg_op

Option structure.

• struct coap_msg_op_list_t

Option linked-list structure.

struct coap_msg_t

Message structure.

Macros

```
#define COAP_MSG_VER 0x01
#define COAP_MSG_MAX_TOKEN_LEN 8
#define COAP_MSG_MAX_CODE_CLASS 7
#define COAP_MSG_MAX_CODE_DETAIL 31
#define COAP_MSG_MAX_MSG_ID ((1 << 16) - 1)</li>
```

- #define COAP_MSG_OP_URI_PATH_MAX_LEN 256
 #define COAP_MSG_OP_MAX_PLOCK_VAL_LEN 2
- #define COAP_MSG_OP_MAX_BLOCK_VAL_LEN 3
- #define COAP_MSG_OP_MAX_BLOCK_SIZE (1 << 10)
- #define COAP MSG MAX BUF LEN 1152
- #define coap_msg_op_num_is_critical(num) ((num) & 1)
- #define coap_msg_op_num_is_unsafe(num) ((num) & 2)
- #define coap msg op num no cache key(num) ((num & 0x1e) == 0x1c)
- #define coap_msg_op_get_num(op) ((op)->num)
- #define coap_msg_op_set_num(op, num) ((op)->num = (num))
- #define coap_msg_op_get_len(op) ((op)->len)
- #define coap msg op set len(op, len) ((op)->len = (len))
- #define coap_msg_op_get_val(op) ((op)->val)
- #define coap_msg_op_set_val(op, val) ((op)->val = (val))
- #define coap_msg_op_get_next(op) ((op)->next)
- #define coap_msg_op_set_next(op, next_op) ((op)->next = (next_op))
- #define coap_msg_get_ver(msg) ((msg)->ver)
- #define coap_msg_get_type(msg) ((msg)->type)
- #define coap_msg_get_token_len(msg) ((msg)->token_len)
- #define coap_msg_get_code_class(msg) ((msg)->code_class)
- #define coap msg get code detail(msg) ((msg)->code detail)
- #define coap_msg_get_msg_id(msg) ((msg)->msg_id)
- #define coap_msg_get_token(msg) ((msg)->token)
- #define coap_msg_get_first_op(msg) ((msg)->op_list.first)
- #define coap_msg_get_payload(msg) ((msg)->payload)
- #define coap_msg_get_payload_len(msg) ((msg)->payload_len)
- #define coap_msg_is_empty(msg) (((msg)->code_class == 0) && ((msg)->code_detail == 0))

Typedefs

typedef struct coap_msg_op coap_msg_op_t
 Option structure.

Enumerations

enum coap_msg_type_t { COAP_MSG_CON = 0x0, COAP_MSG_NON = 0x1, COAP_MSG_ACK = 0x2, COAP_MSG_RST = 0x3 }

Message type enumeration.

• enum coap_msg_class_t { COAP_MSG_REQ = 0, COAP_MSG_SUCCESS = 2, COAP_MSG_CLIENT_E ← RR = 4, COAP_MSG_SERVER_ERR = 5 }

Code class enumeration.

Request code detail enumeration.

```
 enum coap msg success t {

 COAP_MSG_CREATED = 1, COAP_MSG_DELETED = 2, COAP_MSG_VALID = 3, COAP_MSG_CHAN ←
 GED = 4
 COAP MSG CONTENT = 5, COAP MSG CONTINUE = 31 }
    Success response code detail enumeration.
• enum coap msg client err t {
 COAP MSG BAD REQ = 0, COAP MSG UNAUTHORIZED = 1, COAP MSG BAD OPTION = 2, COA ←
 P MSG FORBIDDEN = 3.
 COAP MSG NOT FOUND = 4, COAP MSG METHOD NOT ALLOWED = 5, COAP MSG NOT ACC
 EPTABLE = 6, COAP MSG INCOMPLETE = 8,
 COAP_MSG_PRECOND_FAILED = 12, COAP_MSG_REQ_ENT_TOO_LARGE = 13, COAP_MSG_UNS ←
 UP_CONT_FMT = 15 }
    Client error response code detail enumeration.

    enum coap msg server err t {

 COAP MSG INT SERVER ERR = 0, COAP MSG NOT IMPL = 1, COAP MSG BAD GATEWAY = 2,
 COAP MSG SERV UNAVAIL = 3,
 COAP_MSG_GATEWAY_TIMEOUT = 4, COAP_MSG_PROXY_NOT_SUP = 5 }
    Server error response code detail enumeration.

 enum coap msg op num t {

 COAP MSG IF MATCH = 1, COAP MSG URI HOST = 3, COAP MSG ETAG = 4, COAP MSG IF N←
 ONE MATCH = 5.
 COAP MSG URI PORT = 7, COAP MSG LOCATION PATH = 8, COAP MSG URI PATH = 11, COA↔
 P MSG CONTENT FORMAT = 12,
 COAP_MSG_MAX_AGE = 14, COAP_MSG_URI_QUERY = 15, COAP_MSG_ACCEPT = 17, COAP_MS↔
 G LOCATION QUERY = 20,
 COAP_MSG_BLOCK2 = 23, COAP_MSG_BLOCK1 = 27, COAP_MSG_SIZE2 = 28, COAP_MSG_PROX←
 Y URI = 35,
 COAP MSG PROXY SCHEME = 39, COAP MSG SIZE1 = 60 }
    Option number enumeration.
```

Functions

int coap msg op num is recognized (unsigned num)

Check if option is recognized.

• int coap_msg_op_parse_block_val (unsigned *num, unsigned *more, unsigned *size, const char *val, unsigned len)

Parse Block1 or Block2 option value.

- int coap_msg_op_format_block_val (char *val, unsigned len, unsigned num, unsigned more, unsigned size)

 Format Block1 or Block2 option value.
- void coap msg gen rand str (char *buf, size t len)

Generate a random string of bytes.

void coap_msg_create (coap_msg_t *msg)

Initialise a message structure.

void coap_msg_destroy (coap_msg_t *msg)

Deinitialise a message structure.

void coap_msg_reset (coap_msg_t *msg)

Deinitialise and initialise a message structure.

unsigned coap_msg_check_critical_ops (coap_msg_t *msg)

Check that all of the critical options in a message are recognized.

unsigned coap msg check unsafe ops (coap msg t *msg)

Check that all of the unsafe options in a message are recognized.

• int coap msg parse type msg id (char *buf, size t len, unsigned *type, unsigned *msg id)

Extract the type and message ID values from a message.

```
    ssize_t coap_msg_parse (coap_msg_t *msg, char *buf, size_t len)
    Parse a message.
```

int coap_msg_set_type (coap_msg_t *msg, unsigned type)

Set the type in a message.

int coap_msg_set_code (coap_msg_t *msg, unsigned code_class, unsigned code_detail)
 Set the code in a message.

int coap_msg_set_msg_id (coap_msg_t *msg, unsigned msg_id)

Set the message ID in a message.

• int coap_msg_set_token (coap_msg_t *msg, char *buf, size_t len)

Set the token in a message.

• int coap_msg_add_op (coap_msg_t *msg, unsigned num, unsigned len, const char *val)

Add a token to a message structure.

int coap_msg_set_payload (coap_msg_t *msg, char *buf, size_t len)

Set the payload in a message.

• ssize_t coap_msg_format (coap_msg_t *msg, char *buf, size_t len)

Format a message.

int coap_msg_copy (coap_msg_t *dst, coap_msg_t *src)

Copy a message.

• size_t coap_msg_uri_path_to_str (coap_msg_t *msg, char *buf, size_t len)

Convert the URI path in a message to a string representation.

4.4.1 Detailed Description

Include file for the FreeCoAP message parser/formatter library.

4.4.2 Macro Definition Documentation

```
4.4.2.1 #define coap_msg_get_code_class( msg ) ((msg)->code_class)
```

Get the code class from a message

4.4.2.2 #define coap_msg_get_code_detail(msg) ((msg)->code_detail)

Get the code detail from a message

4.4.2.3 #define coap_msg_get_first_op(msg) ((msg)->op_list.first)

Get the first option from a message

4.4.2.4 #define coap_msg_get_msg_id(msg) ((msg)->msg_id)

Get the message ID from message

```
4.4.2.5 #define coap_msg_get_payload( msg ) ((msg)->payload)
Get the payload from a message
4.4.2.6 #define coap_msg_get_payload_len( msg ) ((msg)->payload_len)
Get the payload length from a message
4.4.2.7 #define coap_msg_get_token( msg ) ((msg)->token)
Get the token from a message
4.4.2.8 #define coap_msg_get_token_len( msg ) ((msg)->token_len)
Get the token length from a message
4.4.2.9 #define coap_msg_get_type( msg ) ((msg)->type)
Get the type from a message
4.4.2.10 #define coap_msg_get_ver( msg ) ((msg)->ver)
Get the version from a message
4.4.2.11 #define coap_msg_is_empty( msg ) (((msg)->code_class == 0) && ((msg)->code_detail == 0))
Indicate if a message is empty
4.4.2.12 #define COAP_MSG_MAX_BUF_LEN 1152
Maximum buffer length for header and payload
4.4.2.13 #define COAP_MSG_MAX_CODE_CLASS 7
Maximum code class
4.4.2.14 #define COAP_MSG_MAX_CODE_DETAIL 31
```

Maximum code detail

4.4.2.15 #define COAP_MSG_MAX_MSG_ID ((1 << 16) - 1)

Maximum message ID

4.4.2.16 #define COAP_MSG_MAX_TOKEN_LEN 8

Maximum token length

4.4.2.17 #define coap_msg_op_get_len(op) ((op)->len)

Get the option length from an option

4.4.2.18 #define coap_msg_op_get_next(op) ((op)->next)

Get the next pointer from an option

4.4.2.19 #define coap_msg_op_get_num(op) ((op)->num)

Get the option number from an option

4.4.2.20 #define coap_msg_op_get_val(op) ((op)->val)

Get the option value from an option

4.4.2.21 #define COAP_MSG_OP_MAX_BLOCK_SIZE (1 << 10)

Maximum block size for a Block1 or Block2 option

4.4.2.22 #define COAP_MSG_OP_MAX_BLOCK_VAL_LEN 3

Maximum buffer length for a Block1 or Block2 option value

4.4.2.23 #define coap_msg_op_num_is_critical(num) ((num) & 1)

Indicate if an option is critical

4.4.2.24 #define coap_msg_op_num_is_unsafe(num) ((num) & 2)

Indicate if an option is unsafe to forward

```
4.4.2.25 #define coap_msg_op_num_no_cache_key( num ) ((num & 0x1e) == 0x1c)
Indicate if an option is not part of the cache key
4.4.2.26 #define coap_msg_op_set_len( op, len ) ((op)->len = (len))
Set the option length in an option
4.4.2.27 #define coap_msg_op_set_next( op, next_op ) ((op)->next = (next_op))
Set the next pointer in an option
4.4.2.28 #define coap_msg_op_set_num( op, num ) ((op)->num = (num))
Set the option number in an option
4.4.2.29 #define coap_msg_op_set_val( op, val ) ((op)->val = (val))
Set the option value in an option
4.4.2.30 \quad \hbox{\#define COAP\_MSG\_OP\_URI\_PATH\_MAX\_LEN 256}
Maximum buffer length for a reconstructed URI path
4.4.2.31 #define COAP_MSG_VER 0x01
CoAP version
4.4.3 Enumeration Type Documentation
4.4.3.1 enum coap_msg_class_t
Code class enumeration.
Enumerator
     COAP_MSG_REQ Request
     COAP_MSG_SUCCESS Success response
```

COAP_MSG_CLIENT_ERR Client error response
COAP_MSG_SERVER_ERR Server error response

4.4.3.2 enum coap_msg_client_err_t

Client error response code detail enumeration.

Enumerator

COAP_MSG_BAD_REQ Bad request client error

COAP_MSG_UNAUTHORIZED Unauthorized client error

COAP_MSG_BAD_OPTION Bad option client error

COAP_MSG_FORBIDDEN Forbidden client error

COAP_MSG_NOT_FOUND Not found client error

COAP_MSG_METHOD_NOT_ALLOWED Method not allowed client error

COAP_MSG_NOT_ACCEPTABLE Not acceptable client error

COAP_MSG_INCOMPLETE Request entity incomplete client error

COAP_MSG_PRECOND_FAILED Precondition failed client error

COAP_MSG_REQ_ENT_TOO_LARGE Request entity too large client error

COAP_MSG_UNSUP_CONT_FMT Unsupported content-format client error

4.4.3.3 enum coap_msg_method_t

Request code detail enumeration.

Enumerator

COAP_MSG_GET Get request method
COAP_MSG_POST Post request method
COAP_MSG_PUT Put request method
COAP_MSG_DELETE Delete request method

4.4.3.4 enum coap_msg_op_num_t

Option number enumeration.

Enumerator

COAP_MSG_IF_MATCH If-Match option number COAP_MSG_URI_HOST URI-Host option number COAP_MSG_ETAG Entity-Tag option number COAP_MSG_IF_NONE_MATCH If-None-Match option number COAP_MSG_URI_PORT URI-Port option number COAP_MSG_LOCATION_PATH Location-Path option number COAP_MSG_URI_PATH URI-Path option number COAP_MSG_CONTENT_FORMAT Content-Format option number COAP_MSG_MAX_AGE Max-Age option number COAP_MSG_URI_QUERY URI-Query option number COAP_MSG_ACCEPT Accept option number COAP_MSG_LOCATION_QUERY Location-Query option number COAP_MSG_BLOCK2 Block2 option number COAP_MSG_BLOCK1 Block1 option number COAP MSG SIZE2 Size2 option number COAP_MSG_PROXY_URI Proxy-URI option number COAP MSG PROXY SCHEME Proxy-Scheme option number COAP_MSG_SIZE1 Size1 option number

```
4.4.3.5 enum coap_msg_server_err_t
```

Server error response code detail enumeration.

Enumerator

```
COAP_MSG_INT_SERVER_ERR Internal server error
COAP_MSG_NOT_IMPL Not implemented server error
COAP_MSG_BAD_GATEWAY Bad gateway server error
COAP_MSG_SERV_UNAVAIL Service unavailable server error
COAP_MSG_GATEWAY_TIMEOUT Gateway timeout server error
COAP_MSG_PROXY_NOT_SUP Proxying not supported server error
```

```
4.4.3.6 enum coap_msg_success_t
```

Success response code detail enumeration.

Enumerator

```
COAP_MSG_CREATED Created success response
COAP_MSG_DELETED Deleted success response
COAP_MSG_VALID Valid success response
COAP_MSG_CHANGED Changed success response
COAP_MSG_CONTENT Content success response
COAP_MSG_CONTINUE Continue success response
```

```
4.4.3.7 enum coap_msg_type_t
```

Message type enumeration.

Enumerator

```
    COAP_MSG_CON Confirmable message
    COAP_MSG_NON Non-confirmable message
    COAP_MSG_ACK Acknowledgement message
    COAP_MSG_RST Reset message
```

4.4.4 Function Documentation

4.4.4.1 int coap_msg_add_op (coap_msg_t * msg, unsigned num, unsigned len, const char * val)

Add a token to a message structure.

Parameters

in,out	msg	Pointer to a message structure
in	num	Option number
in	len	Option length
in	val	Pointer to a buffer containing the option value

Returns

Operation status

Return values

0	Success
<0	Error

4.4.4.2 unsigned coap_msg_check_critical_ops (coap_msg_t * msg)

Check that all of the critical options in a message are recognized.

Parameters

in	msg	Pointer to message structure
----	-----	------------------------------

Returns

Operation status or bad option number

Return values

0	Success
>0	Bad option number

4.4.4.3 unsigned coap_msg_check_unsafe_ops (coap_msg_t * msg)

Check that all of the unsafe options in a message are recognized.

Parameters

in	msg	Pointer to message structure
----	-----	------------------------------

Returns

Operation status or bad option number

Return values

0	Success
>0	Bad option number

4.4.4.4 int coap_msg_copy ($coap_msg_t * dst$, $coap_msg_t * src$)

Copy a message.

Parameters

in,out	dst	Pointer to the destination message structure
in	src	Pointer to the source message structure

Returns

Operation status

Return values

0	Success
<0	Error

4.4.4.5 void coap_msg_create ($coap_msg_t * msg$)

Initialise a message structure.

Parameters

out	msg	Pointer to a message structure
-----	-----	--------------------------------

4.4.4.6 void coap_msg_destroy (coap_msg_t * msg)

Deinitialise a message structure.

Parameters

in,out	msg	Pointer to a message structure

4.4.4.7 ssize_t coap_msg_format ($coap_msg_t * msg$, char * buf, $size_t len$)

Format a message.

Parameters

in	msg	Pointer to a message structure
out	buf	Pointer to a buffer to contain the formatted message
in	len	Length of the buffer

Returns

Length of the formatted message or error code

Return values

>0	Length of the formatted message
<0	Error

4.4.4.8 void coap_msg_gen_rand_str (char * buf, size_t len)

Generate a random string of bytes.

Parameters

out	buf	Pointer to the buffer to store the random string
in	len	Length of the buffer

4.4.4.9 int coap_msg_op_format_block_val (char * val, unsigned len, unsigned num, unsigned more, unsigned size)

Format Block1 or Block2 option value.

Parameters

out	val	Pointer to option value
in	len	Length of option value
in	num	Block number
in	more	More value
in	size	Block size

Returns

Length of the formatted option value or error code

Return values

>0	Length of the formatted option value
<0	Error

4.4.4.10 int coap_msg_op_num_is_recognized (unsigned num)

Check if option is recognized.

Parameters

in <i>num</i>	Option number
---------------	---------------

Returns

Operation status

Return values

1	Option is recognized
0	Option is not recognized

4.4.4.11 int coap_msg_op_parse_block_val (unsigned * num, unsigned * more, unsigned * size, const char * val, unsigned len)

Parse Block1 or Block2 option value.

Parameters

out	num	Pointer to Block number
out	more	Pointer to More value
out	size	Pointer to Block size
in	val	Pointer to the option value
in	len	Option length

Returns

Operation status

Return values

0	Success
<0	Error

4.4.4.12 ssize_t coap_msg_parse ($coap_msg_t * msg$, char * buf, $size_t len$)

Parse a message.

in,out	msg	Pointer to a message structure

Parameters

in	buf	Pointer to a buffer containing the message
in	len	Length of the buffer

Returns

Operation status

Return values

0	Success
<0	Error

4.4.4.13 int coap_msg_parse_type_msg_id (char * buf, size_t len, unsigned * type, unsigned * msg_id)

Extract the type and message ID values from a message.

If a message contains a format error, this function will attempt to extract the type and message ID so that a reset message can be returned to the sender.

Parameters

in	buf	Pointer to a buffer containing the message
in	len	Length of the buffer
out	type	Pointer to field to store the type value
out	msg← _id	Pointer to a field to store the message ID value

Returns

Operation status

Return values

0	Success
<0	Error

4.4.4.14 void coap_msg_reset (coap_msg_t * msg)

Deinitialise and initialise a message structure.

in,out	msg	Pointer to a message structure
--------	-----	--------------------------------

4.4.4.15 int coap_msg_set_code (coap_msg_t * msg, unsigned code_class, unsigned code_detail)

Set the code in a message.

Parameters

out	msg	Pointer to a message structure
in	code_class	Code class
in	code_detail	Code detail

Returns

Operation status

Return values

0	Success
<0	Error

4.4.4.16 int coap_msg_set_msg_id (coap_msg_t * msg, unsigned msg_id)

Set the message ID in a message.

Parameters

out	msg	Pointer to a message structure
in	msg⇔	Message ID
	_id	

Returns

Operation status

Return values

0	Success
<0	Error

4.4.4.17 int coap_msg_set_payload ($coap_msg_t * msg$, char * buf, $size_t len$)

Set the payload in a message.

Free the buffer in the message structure containing the current payload if there is one, allocate a buffer to contain the new payload and copy the buffer argument into the new payload buffer.

Parameters

in,out	msg	Pointer to a message structure
in	buf	Pointer to a buffer containing the payload
in	len	Length of the buffer

Returns

Operation status

Return values

0	Success
<0	Error

4.4.4.18 int coap_msg_set_token ($coap_msg_t * msg$, char * buf, $size_t len$)

Set the token in a message.

Parameters

out	msg	Pointer to a message structure
in	buf	Pointer to a buffer containing the token
in	len	Length of the buffer

Returns

Operation status

Return values

0	Success
<0	Error

4.4.4.19 int coap_msg_set_type ($coap_msg_t * msg$, unsigned type)

Set the type in a message.

out	msg	Pointer to a message structure
in	type	Message type

Returns

Operation status

Return values

0	Success
<0	Error

4.4.4.20 size_t coap_msg_uri_path_to_str (coap_msg_t * msg, char * buf, size_t len)

Convert the URI path in a message to a string representation.

Parameters

in	msg	Pointer to a message structure
out	buf	Pointer to a buffer to hold the string
in	len	Length of the buffer

Returns


The number of bytes that would be written to the buffer it was large enough

4.5 lib/include/coap_server.h File Reference


Include file for the FreeCoAP server library.

```
#include <time.h>
#include <netinet/in.h>
#include <gnutls/gnutls.h>
#include <gnutls/dtls.h>
#include "coap_msg.h"
#include "coap_ipv.h"
```

Include dependency graph for coap_server.h:



This graph shows which files directly or indirectly include this file:



Classes

struct coap_server_path

URI path structure.

struct coap_server_path_list_t

URI path list structure.

· struct coap server trans

Transaction structure.

· struct coap_server

Server structure.

Macros

- #define COAP_SERVER_NUM_TRANS 8
- #define COAP_SERVER_ADDR_BUF_LEN 128
- #define COAP_SERVER_DIAG_PAYLOAD_LEN 128

Typedefs

- typedef struct coap_server_path coap_server_path_t
 URI path structure.
- typedef struct coap_server_trans coap_server_trans_t

Transaction structure.

typedef struct coap_server coap_server_t

Server structure.

Enumerations

enum coap_server_resp_t { COAP_SERVER_PIGGYBACKED = 0, COAP_SERVER_SEPARATE = 1 }
 Response type enumeration.

Functions

int coap_server_create (coap_server_t *server, int(*handle)(coap_server_t *, coap_msg_t *, coap_msg_t *), const char *host, const char *port, const char *key_file_name, const char *cert_file_name, const char *trust_file_name, const char *crl_file_name)

Initialise a server structure.

void coap_server_destroy (coap_server_t *server)

Deinitialise a server structure.

unsigned coap_server_get_next_msg_id (coap_server_t *server)

Get a new message ID value.

int coap_server_add_sep_resp_uri_path (coap_server_t *server, const char *str)

Register a URI path that requires a separate response.

int coap_server_run (coap_server_t *server)

Run the server.

4.5.1 Detailed Description

Include file for the FreeCoAP server library.

4.5.2 Macro Definition Documentation

4.5.2.1 #define COAP_SERVER_ADDR_BUF_LEN 128

Buffer length for host addresses

4.5.2.2 #define COAP_SERVER_DIAG_PAYLOAD_LEN 128

Buffer length for diagnostic payloads

4.5.2.3 #define COAP_SERVER_NUM_TRANS 8

Maximum number of active transactions per server

4.5.3 Enumeration Type Documentation

4.5.3.1 enum coap_server_resp_t

Response type enumeration.

Enumerator

COAP_SERVER_PIGGYBACKED Piggybacked response **COAP_SERVER_SEPARATE** Separate response

4.5.4 Function Documentation

4.5.4.1 int coap_server_add_sep_resp_uri_path (coap_server_t * server, const char * str)

Register a URI path that requires a separate response.

Parameters

in,out	server	Pointer to a server structure
in	str	String representation of a URI path

Returns

Operation status

Return values

0	Success
<0	Error

4.5.4.2 int coap_server_create (coap_server_t * server, int(*)(coap_server_t *, coap_msg_t *, coap_msg_t *)

handle, const char * host, const char * port, const char * key_file_name, const char * cert_file_name, const char *

trust_file_name, const char * crl_file_name)

Initialise a server structure.

Parameters

out	server	Pointer to a server structure
in	handle	Call-back function to handle client requests
in	host	Pointer to a string containing the host address of the server
in	port	Port number of the server
in	key_file_name	String containing the DTLS key file name
in	cert_file_name	String containing the DTLS certificate file name
in	trust_file_name	String containing the DTLS trust file name
in	crl_file_name	String containing the DTLS certificate revocation list file name

Returns

Operation status

Return values

0	Success
<0	Error

4.5.4.3 void coap_server_destroy (coap_server_t * server)

Deinitialise a server structure.

in, out server Pointer to a server structure
--

4.5.4.4 unsigned coap_server_get_next_msg_id (coap_server_t * server)

Get a new message ID value.

Parameters

in,out	server	Pointer to a server structure
--------	--------	-------------------------------

Returns

message ID value

4.5.4.5 int coap_server_run (coap_server_t * server)

Run the server.

Listen for incoming requests. For each request received, call the handle call-back function in the server structure and send the response to the client.

Parameters

in,out	server	Pointer to a server structure
--------	--------	-------------------------------

Returns

Operation status

Return values

0	Success
<0	Error

4.6 lib/src/coap_client.c File Reference

Source file for the FreeCoAP client library.

```
#include <stdlib.h>
#include <stdio.h>
#include <stdio.h>
#include <stdint.h>
#include <errno.h>
#include <unistd.h>
#include <fcntl.h>
#include <netdb.h>
#include <sys/socket.h>
#include <sys/timerfd.h>
#include <sys/select.h>
#include #include <sys/select.h>
#include #include #include #include <inux/types.h>
#include #include #include #include #include #include 
#include
```

Include dependency graph for coap_client.c:



Macros

- #define COAP CLIENT ACK TIMEOUT SEC 2
- #define COAP_CLIENT_MAX_RETRANSMIT 4
- #define COAP_CLIENT_RESP_TIMEOUT_SEC 30
- #define COAP_CLIENT_DTLS_MTU COAP_MSG_MAX_BUF_LEN
- #define COAP CLIENT DTLS RETRANS TIMEOUT 100
- #define COAP CLIENT DTLS TOTAL TIMEOUT 5000
- #define COAP_CLIENT_DTLS_PRIORITIES "PERFORMANCE:-VERS-TLS-ALL:+VERS-DTLS1.0:%SE↔ RVER PRECEDENCE"

Functions

int coap_client_create (coap_client_t *client, const char *host, const char *port, const char *key_file_name, const char *cert_file_name, const char *trust_file_name, const char *crl_file_name, const char *common
 __name)

Initialise a client structure.

void coap client destroy (coap client t *client)

Deinitialise a client structure.

• int coap_client_exchange (coap_client_t *client, coap_msg_t *req, coap_msg_t *resp)

Send a request to the server and receive the response.

4.6.1 Detailed Description

Source file for the FreeCoAP client library.

4.6.2 Macro Definition Documentation

4.6.2.1 #define COAP_CLIENT_ACK_TIMEOUT_SEC 2

Minimum delay to wait before retransmitting a confirmable message

4.6.2.2 #define COAP_CLIENT_DTLS_MTU COAP_MSG_MAX_BUF_LEN

Maximum transmission unit excluding the UDP and IPv6 headers

4.6.2.3 #define COAP_CLIENT_DTLS_PRIORITIES "PERFORMANCE:-VERS-TLS-ALL:+VERS-DTLS1.0:%SERVER_PRECEDEN ← CE"

DTLS priorities

4.6.2.4 #define COAP_CLIENT_DTLS_RETRANS_TIMEOUT 100

Retransmission timeout (msec) for the DTLS handshake

4.6.2.5 #define COAP_CLIENT_DTLS_TOTAL_TIMEOUT 5000

Total timeout (msec) for the DTLS handshake

4.6.2.6 #define COAP_CLIENT_MAX_RETRANSMIT 4

Maximum number of times a confirmable message can be retransmitted

4.6.2.7 #define COAP_CLIENT_RESP_TIMEOUT_SEC 30

Maximum amount of time to wait for a response

4.6.3 Function Documentation

4.6.3.1 int coap_client_create (coap_client_t * client, const char * host, const char * port, const char * key_file_name, const char * crl_file_name, const char * common_name)

Initialise a client structure.

Parameters

out	client	Pointer to a client structure
in	host	Pointer to a string containing the host address of the server
in	port	Port number of the server
in	key_file_name	String containing the DTLS key file name
in	cert_file_name	String containing the DTLS certificate file name
in	trust_file_name	String containing the DTLS trust file name
in	crls_file_name	String containing the DTLS certificate revocation list file name

Generated by Doxygen

Returns

Operation status

Return values

0	Success
<0	Error

4.6.3.2 void coap_client_destroy (coap_client_t * client)

Deinitialise a client structure.

Parameters

in, out <i>client</i>	Pointer to a client structure
-----------------------	-------------------------------

4.6.3.3 int coap_client_exchange ($coap_client_t * client$, $coap_msg_t * req$, $coap_msg_t * resp$)

Send a request to the server and receive the response.

This function sets the message ID and token fields of the request message overriding any values set by the calling function.

Parameters

in,out	client	Pointer to a client structure
in	req	Pointer to the request message
out	resp	Pointer to the response message

Returns

Operation status

Return values


0	Success
<0	Error

4.7 lib/src/coap_log.c File Reference

Source file for the FreeCoAP logging module.

```
#include <stdio.h>
#include <stdarg.h>
#include "coap_log.h"
```

Include dependency graph for coap_log.c:



Functions

- void coap_log_set_level (coap_log_level_t level)
 Set the log level.
- coap_log_level_t coap_log_get_level (void)

Get the log level.

void coap_log_error (const char *msg,...)

Log an error message.

void coap_log_warn (const char *msg,...)

Log a warning message.

• void coap_log_notice (const char *msg,...)

Log an notice message.

void coap_log_info (const char *msg,...)

Log an info message.

void coap_log_debug (const char *msg,...)

Log a debug message.

4.7.1 Detailed Description

Source file for the FreeCoAP logging module.

4.7.2 Function Documentation

4.7.2.1 void coap_log_debug (const char * msg, ...)

Log a debug message.

in	msg	String containing format specifiers
in		arguments for the format specifiers

4.7.2.2 void coap_log_error (const char * msg, ...)

Log an error message.

Parameters

in	msg	String containing format specifiers
in		arguments for the format specifiers

4.7.2.3 coap_log_level_t coap_log_get_level (void)

Get the log level.

Returns

The current log level

4.7.2.4 void coap_log_info (const char * msg, ...)

Log an info message.

Parameters

in	msg	String containing format specifiers
in		arguments for the format specifiers

4.7.2.5 void coap_log_notice (const char * msg, ...)

Log an notice message.

Parameters

in	msg	String containing format specifiers
in		arguments for the format specifiers

4.7.2.6 void coap_log_set_level (coap_log_level_t level)

Set the log level.

Messages with a severity below this level will be filtered. Error messages cannot be filtered.

in	level	The new log level

- < Warning log level
- < Notice warning level
- < Informational warning level
- < Debug warning level

```
4.7.2.7 void coap_log_warn ( const char * msg, ... )
```

Log a warning message.

Parameters


in	msg	String containing format specifiers
in		arguments for the format specifiers

4.8 lib/src/coap_msg.c File Reference

Source file for the FreeCoAP message parser/formatter library.

```
#include <stdlib.h>
#include <string.h>
#include <stdint.h>
#include <time.h>
#include <errno.h>
#include <arpa/inet.h>
#include "coap_msg.h"
```

Include dependency graph for coap_msg.c:



Macros

- #define coap_msg_op_list_get_first(list) ((list)->first)
- #define coap_msg_op_list_get_last(list) ((list)->last)
- #define coap_msg_op_list_is_empty(list) ((list)->first == NULL)

Functions

```
    void coap msg gen rand str (char *buf, size t len)
```

Generate a random string of bytes.

int coap_msg_op_num_is_recognized (unsigned num)

Check if option is recognized.

• int coap_msg_op_parse_block_val (unsigned *num, unsigned *more, unsigned *size, const char *val, unsigned len)

Parse Block1 or Block2 option value.

• int coap msg op format block val (char *val, unsigned len, unsigned num, unsigned more, unsigned size)

Format Block1 or Block2 option value.

void coap_msg_create (coap_msg_t *msg)

Initialise a message structure.

void coap_msg_destroy (coap_msg_t *msg)

Deinitialise a message structure.

void coap_msg_reset (coap_msg_t *msg)

Deinitialise and initialise a message structure.

unsigned coap_msg_check_critical_ops (coap_msg_t *msg)

Check that all of the critical options in a message are recognized.

unsigned coap_msg_check_unsafe_ops (coap_msg_t *msg)

Check that all of the unsafe options in a message are recognized.

• int coap_msg_parse_type_msg_id (char *buf, size_t len, unsigned *type, unsigned *msg_id)

Extract the type and message ID values from a message.

ssize_t coap_msg_parse (coap_msg_t *msg, char *buf, size_t len)

Parse a message.

• int coap_msg_set_type (coap_msg_t *msg, unsigned type)

Set the type in a message.

int coap_msg_set_code (coap_msg_t *msg, unsigned code_class, unsigned code_detail)

Set the code in a message.

int coap_msg_set_msg_id (coap_msg_t *msg, unsigned msg_id)

Set the message ID in a message.

• int coap_msg_set_token (coap_msg_t *msg, char *buf, size_t len)

Set the token in a message.

• int coap_msg_add_op (coap_msg_t *msg, unsigned num, unsigned len, const char *val)

Add a token to a message structure.

• int coap_msg_set_payload (coap_msg_t *msg, char *buf, size_t len)

Set the payload in a message.

• ssize_t coap_msg_format (coap_msg_t *msg, char *buf, size_t len)

Format a message.

int coap msg copy (coap msg t *dst, coap msg t *src)

Copy a message.

• size_t coap_msg_uri_path_to_str (coap_msg_t *msg, char *buf, size_t len)

Convert the URI path in a message to a string representation.

4.8.1 Detailed Description

Source file for the FreeCoAP message parser/formatter library.

4.8.2 Macro Definition Documentation

4.8.2.1 #define coap_msg_op_list_get_first(list) ((list)->first)

Get the first option from an option linked-list

4.8.2.2 #define coap_msg_op_list_get_last(list) ((list)->last)

Get the last option in an option linked-list

4.8.2.3 #define coap_msg_op_list_is_empty(list) ((list)->first == NULL)

Indicate whether or not an option linked-list is empty

4.8.3 Function Documentation

4.8.3.1 int coap_msg_add_op (coap_msg_t * msg, unsigned num, unsigned len, const char * val)

Add a token to a message structure.

Parameters

in,out	msg	Pointer to a message structure	
in	num	num Option number	
in	len	len Option length	
in	val	Pointer to a buffer containing the option value	

Returns

Operation status

Return values

0	Success
<0	Error

4.8.3.2 unsigned coap_msg_check_critical_ops (coap_msg_t * msg)

Check that all of the critical options in a message are recognized.

in	msg	Pointer to message structure
----	-----	------------------------------

Returns

Operation status or bad option number

Return values

0	Success
>0	Bad option number

4.8.3.3 unsigned coap_msg_check_unsafe_ops ($coap_msg_t * msg$)

Check that all of the unsafe options in a message are recognized.

Parameters

in	msg	Pointer to message structure
----	-----	------------------------------

Returns

Operation status or bad option number

Return values

0	Success
>0	Bad option number

4.8.3.4 int coap_msg_copy ($coap_msg_t * dst$, $coap_msg_t * src$)

Copy a message.

Parameters

in,out	dst	Pointer to the destination message structure
in	src	Pointer to the source message structure

Returns

Operation status

Return values

0	Success
< 0	Frror

4.8.3.5 void coap_msg_create (coap_msg_t * msg)

Initialise a message structure.

Parameters

out	msg	Pointer to a message structure
-----	-----	--------------------------------

4.8.3.6 void coap_msg_destroy (coap_msg_t * msg)

Deinitialise a message structure.

Parameters

in, out msg Pointer to a message	structure
--------------------------------------	-----------

4.8.3.7 ssize_t coap_msg_format ($coap_msg_t * msg$, char * buf, $size_t len$)

Format a message.

Parameters

in	msg	Pointer to a message structure
out	buf	Pointer to a buffer to contain the formatted message
in	len	Length of the buffer

Returns

Length of the formatted message or error code

Return values

>0	Length of the formatted message
<0	Error

4.8.3.8 void coap_msg_gen_rand_str (char * buf, size_t len)

Generate a random string of bytes.

out	buf	Pointer to the buffer to store the random string
in	len	Length of the buffer

4.8.3.9 int coap_msg_op_format_block_val (char * val, unsigned len, unsigned num, unsigned more, unsigned size)

Format Block1 or Block2 option value.

Parameters

out	val	Pointer to option value
in	len	Length of option value
in	num	Block number
in	more	More value
in	size	Block size

Returns

Length of the formatted option value or error code

Return values

>0	Length of the formatted option value
<0	Error

4.8.3.10 int coap_msg_op_num_is_recognized (unsigned num)

Check if option is recognized.

Parameters

in	num	Option number
----	-----	---------------

Returns

Operation status

Return values

1	Option is recognized
0	Option is not recognized

4.8.3.11 int coap_msg_op_parse_block_val (unsigned * num, unsigned * more, unsigned * size, const char * val, unsigned len)

Parse Block1 or Block2 option value.

out	num	Pointer to Block number

Parameters

out	more	Pointer to More value
out	size	Pointer to Block size
in	val	Pointer to the option value
in	len	Option length

Returns

Operation status

Return values

0	Success
<0	Error

4.8.3.12 ssize_t coap_msg_parse (coap_msg_t * msg, char * buf, size_t len)

Parse a message.

Parameters

in,out	msg	Pointer to a message structure
in	buf	Pointer to a buffer containing the message
in	len	Length of the buffer

Returns

Operation status

Return values

0	Success
<0	Error

4.8.3.13 int coap_msg_parse_type_msg_id (char * buf, size_t len, unsigned * type, unsigned * msg_id)

Extract the type and message ID values from a message.

If a message contains a format error, this function will attempt to extract the type and message ID so that a reset message can be returned to the sender.

in	buf	Pointer to a buffer containing the message
in	len	Length of the buffer

Parameters

out	type	Pointer to field to store the type value
out	msg⇔	Pointer to a field to store the message ID value
	_id	

Returns

Operation status

Return values

0	Success
<0	Error

4.8.3.14 void coap_msg_reset (coap_msg_t * msg)

Deinitialise and initialise a message structure.

Parameters

in,out <i>msg</i>	Pointer to a message structure
-------------------	--------------------------------

4.8.3.15 int coap_msg_set_code (coap_msg_t * msg, unsigned code_class, unsigned code_detail)

Set the code in a message.

Parameters

out	msg	Pointer to a message structure
in	code_class	Code class
in	code detail	Code detail

Returns

Operation status

Return values

0	Success
<0	Error

4.8.3.16 int coap_msg_set_msg_id ($coap_msg_t * msg$, unsigned msg_id)

Set the message ID in a message.

Parameters

out	msg	Pointer to a message structure
in	msg⇔	Message ID
	_id	

Returns

Operation status

Return values

0	Success
<0	Error

4.8.3.17 int coap_msg_set_payload ($coap_msg_t * msg$, char * buf, $size_t len$)

Set the payload in a message.

Free the buffer in the message structure containing the current payload if there is one, allocate a buffer to contain the new payload and copy the buffer argument into the new payload buffer.

Parameters

-	in,out	msg	Pointer to a message structure
-	in	buf	Pointer to a buffer containing the payload
	in	len	Length of the buffer

Returns

Operation status

Return values

0	Success
<0	Error

4.8.3.18 int coap_msg_set_token ($coap_msg_t * msg$, char * buf, $size_t len$)

Set the token in a message.

out	msg	Pointer to a message structure
in	buf	Pointer to a buffer containing the token
in	len	Length of the buffer

Returns

Operation status

Return values

0	Success
<0	Error

4.8.3.19 int coap_msg_set_type (coap_msg_t * msg, unsigned type)

Set the type in a message.

Parameters

out	msg	Pointer to a message structure
in	type	Message type

Returns

Operation status

Return values

0	Success
<0	Error

4.8.3.20 size_t coap_msg_uri_path_to_str ($coap_msg_t * msg$, char * buf, $size_t len$)

Convert the URI path in a message to a string representation.

Parameters

in	msg	Pointer to a message structure
out	buf	Pointer to a buffer to hold the string
in	len	Length of the buffer

Returns

The number of bytes that would be written to the buffer it was large enough


4.9 lib/src/coap_server.c File Reference

Source file for the FreeCoAP server library.

62 File Documentation

```
#include <stdlib.h>
#include <stdio.h>
#include <string.h>
#include <stdint.h>
#include <time.h>
#include <errno.h>
#include <unistd.h>
#include <fcntl.h>
#include <arpa/inet.h>
#include <netdb.h>
#include <sys/socket.h>
#include <sys/timerfd.h>
#include <sys/select.h>
#include <linux/types.h>
#include <gnutls/x509.h>
#include "coap_server.h"
#include "coap log.h"
```

Include dependency graph for coap server.c:



Macros

- #define COAP SERVER ACK TIMEOUT SEC 2
- #define COAP_SERVER_MAX_RETRANSMIT 4
- #define COAP_SERVER_DTLS_MTU COAP_MSG_MAX_BUF_LEN
- #define COAP_SERVER_DTLS_RETRANS_TIMEOUT 100
- #define COAP_SERVER_DTLS_TOTAL_TIMEOUT 5000
- #define COAP SERVER DTLS NUM DH BITS 1024
- #define COAP_SERVER_DTLS_PRIORITIES "PERFORMANCE:-VERS-TLS-ALL:+VERS-DTLS1.0:%SE
 — RVER_PRECEDENCE"

Functions

int coap_server_create (coap_server_t *server, int(*handle)(coap_server_t *, coap_msg_t *, coap_msg_t *), const char *host, const char *port, const char *key_file_name, const char *cert_file_name, const char *trust_file_name, const char *crl_file_name)

Initialise a server structure.

void coap server destroy (coap server t *server)

Deinitialise a server structure.

• unsigned coap_server_get_next_msg_id (coap_server_t *server)

Get a new message ID value.

int coap_server_add_sep_resp_uri_path (coap_server_t *server, const char *str)

Register a URI path that requires a separate response.

• int coap_server_run (coap_server_t *server)

Run the server.

4.9.1 Detailed Description

Source file for the FreeCoAP server library.

4.9.2 Macro Definition Documentation

4.9.2.1 #define COAP_SERVER_ACK_TIMEOUT_SEC 2

Minimum delay to wait before retransmitting a confirmable message

4.9.2.2 #define COAP_SERVER_DTLS_MTU COAP_MSG_MAX_BUF_LEN

Maximum transmission unit excluding the UDP and IPv6 headers

4.9.2.3 #define COAP_SERVER_DTLS_NUM_DH_BITS 1024

DTLS Diffie-Hellman key size

DTLS priorities

4.9.2.5 #define COAP_SERVER_DTLS_RETRANS_TIMEOUT 100

Retransmission timeout (msec) for the DTLS handshake

4.9.2.6 #define COAP_SERVER_DTLS_TOTAL_TIMEOUT 5000

Total timeout (msec) for the DTLS handshake

4.9.2.7 #define COAP_SERVER_MAX_RETRANSMIT 4

Maximum number of times a confirmable message can be retransmitted

4.9.3 Function Documentation

4.9.3.1 int coap_server_add_sep_resp_uri_path (coap_server_t * server, const char * str)

Register a URI path that requires a separate response.

File Documentation

Parameters

in,out	server	Pointer to a server structure
in	str	String representation of a URI path

Returns

Operation status

Return values

0	Success
<0	Error

4.9.3.2 int coap_server_create (coap_server_t * server, int(*)(coap_server_t *, coap_msg_t *, coap_msg_t *)

handle, const char * host, const char * port, const char * key_file_name, const char * cert_file_name, const char *

trust_file_name, const char * crl_file_name)

Initialise a server structure.

Parameters

out	server	Pointer to a server structure
in	handle	Call-back function to handle client requests
in	host	Pointer to a string containing the host address of the server
in	port	Port number of the server
in	key_file_name	String containing the DTLS key file name
in	cert_file_name	String containing the DTLS certificate file name
in	trust_file_name	String containing the DTLS trust file name
in	crl_file_name	String containing the DTLS certificate revocation list file name

Returns

Operation status

Return values

0	Success
<0	Error

4.9.3.3 void coap_server_destroy (coap_server_t * server)

Deinitialise a server structure.

Parameters

in,out server	Pointer to a server structure
---------------	-------------------------------

4.9.3.4 unsigned coap_server_get_next_msg_id (coap_server_t * server)

Get a new message ID value.

Parameters

in, out server	Pointer to a server structure
----------------	-------------------------------

Returns

message ID value

4.9.3.5 int coap_server_run (coap_server_t * server)

Run the server.

Listen for incoming requests. For each request received, call the handle call-back function in the server structure and send the response to the client.

Parameters

in, out server	Pointer to a server structure
----------------	-------------------------------

Returns

Operation status

Return values

0	Success
<0	Error

File Documentation

Index

active	coap_msg.h, 32
coap_server_trans, 16	COAP_MSG_CONTENT_FORMAT
	coap_msg.h, 33
COAP_CLIENT_ACK_TIMEOUT_SEC	COAP_MSG_CONTENT
coap_client.c, 48	coap_msg.h, 34
COAP_CLIENT_DTLS_MTU	COAP_MSG_CONTINUE
coap_client.c, 48	coap_msg.h, 34
COAP_CLIENT_DTLS_PRIORITIES	COAP_MSG_CON
coap_client.c, 48 COAP CLIENT DTLS RETRANS TIMEOUT	coap_msg.h, 34
coap_client.c, 48	COAP_MSG_CREATED
COAP CLIENT DTLS TOTAL TIMEOUT	coap_msg.h, 34
coap_client.c, 48	COAP_MSG_DELETED
COAP_CLIENT_HOST_BUF_LEN	coap_msg.h, 34
coap_client.h, 20	COAP_MSG_DELETE
COAP_CLIENT_MAX_RETRANSMIT	coap_msg.h, 33
coap client.c, 48	COAP_MSG_ETAG
COAP CLIENT PORT BUF LEN	coap_msg.h, 33
coap_client.h, 20	COAP_MSG_FORBIDDEN
COAP_CLIENT_RESP_TIMEOUT_SEC	coap_msg.h, 33
coap_client.c, 48	COAP_MSG_GATEWAY_TIMEOUT
COAP_LOG_DEBUG	coap_msg.h, 34
coap_log.h, 24	COAP_MSG_GET
COAP_LOG_DEF_LEVEL	coap_msg.h, 33
coap_log.h, 24	COAP_MSG_IF_MATCH
COAP_LOG_ERROR	coap_msg.h, 33 COAP_MSG_IF_NONE_MATCH
coap_log.h, 24	coap_msg.h, 33
COAP_LOG_INFO	COAP_MSG_INCOMPLETE
coap_log.h, 24	coap_msg.h, 33
COAP_LOG_NOTICE	COAP_MSG_INT_SERVER_ERR
coap_log.h, 24	coap_msg.h, 34
COAP_LOG_WARN	COAP_MSG_LOCATION_PATH
coap_log.h, 24	coap_msg.h, 33
COAP_MSG_ACCEPT	COAP_MSG_LOCATION_QUERY
coap_msg.h, 33 COAP_MSG_ACK	coap msg.h, 33
coap msg.h, 34	COAP MSG MAX AGE
COAP_MSG_BAD_GATEWAY	coap_msg.h, 33
coap_msg.h, 34	COAP_MSG_MAX_BUF_LEN
COAP_MSG_BAD_OPTION	coap_msg.h, 30
coap_msg.h, 33	COAP_MSG_MAX_CODE_CLASS
COAP MSG BAD REQ	coap_msg.h, 30
coap msg.h, 33	COAP MSG MAX CODE DETAIL
COAP_MSG_BLOCK1	coap_msg.h, 30
coap_msg.h, 33	COAP MSG MAX MSG ID
COAP_MSG_BLOCK2	coap_msg.h, 30
coap_msg.h, 33	COAP_MSG_MAX_TOKEN_LEN
COAP_MSG_CHANGED	coap_msg.h, 31
coap_msg.h, 34	COAP_MSG_METHOD_NOT_ALLOWED
COAP_MSG_CLIENT_ERR	coap_msg.h, 33

COAP_MSG_NOT_ACCEPTABLE	COAP_SERVER_ACK_TIMEOUT_SEC
coap_msg.h, 33	coap_server.c, 63
COAP_MSG_NOT_FOUND	COAP_SERVER_ADDR_BUF_LEN
coap_msg.h, 33	coap_server.h, 44
COAP_MSG_NOT_IMPL	COAP_SERVER_DIAG_PAYLOAD_LEN
coap_msg.h, 34	coap_server.h, 44
COAP_MSG_NON	COAP_SERVER_DTLS_MTU
coap_msg.h, 34	coap_server.c, 63
COAP_MSG_OP_MAX_BLOCK_SIZE	COAP_SERVER_DTLS_NUM_DH_BITS
coap_msg.h, 31	coap_server.c, 63
COAP_MSG_OP_MAX_BLOCK_VAL_LEN	COAP_SERVER_DTLS_PRIORITIES
coap_msg.h, 31	coap_server.c, 63
COAP_MSG_OP_URI_PATH_MAX_LEN	COAP_SERVER_DTLS_RETRANS_TIMEOUT
coap_msg.h, 32	coap_server.c, 63
COAP_MSG_POST	COAP_SERVER_DTLS_TOTAL_TIMEOUT
coap_msg.h, 33	coap_server.c, 63
COAP_MSG_PRECOND_FAILED	COAP SERVER MAX RETRANSMIT
coap msg.h, 33	coap_server.c, 63
COAP MSG PROXY NOT SUP	COAP SERVER NUM TRANS
coap_msg.h, 34	coap_server.h, 44
COAP_MSG_PROXY_SCHEME	COAP_SERVER_PIGGYBACKED
coap msg.h, 33	coap_server.h, 44
COAP_MSG_PROXY_URI	COAP_SERVER_SEPARATE
coap msg.h, 33	coap_server.h, 44
COAP_MSG_PUT	client_addr
coap_msg.h, 33	coap_server_trans, 16
COAP_MSG_REQ_ENT_TOO_LARGE	client_sin
coap_msg.h, 33	coap_server_trans, 16
COAP_MSG_REQ	client_sin_len
coap_msg.h, 32	coap_server_trans, 16
COAP_MSG_RST	coap_client.c
coap_msg.h, 34	COAP_CLIENT_ACK_TIMEOUT_SEC, 48
COAP_MSG_SERV_UNAVAIL	COAP_CLIENT_DTLS_MTU, 48
coap_msg.h, 34	COAP_CLIENT_DTLS_PRIORITIES, 48
	COAP_CLIENT_DTLS_FRIORITIES, 46 COAP_CLIENT_DTLS_RETRANS_TIMEOUT, 48
COAP_MSG_SERVER_ERR	COAP CLIENT DTLS TOTAL TIMEOUT, 48
coap_msg.h, 32	COAP CLIENT MAX RETRANSMIT, 48
COAP_MSG_SIZE1	:
coap_msg.h, 33	COAP_CLIENT_RESP_TIMEOUT_SEC, 48
COAP_MSG_SIZE2	coap_client_create, 48
coap_msg.h, 33	coap_client_destroy, 49
COAP_MSG_SUCCESS	coap_client_exchange, 49
coap_msg.h, 32	coap_client.h
COAP_MSG_UNAUTHORIZED	COAP_CLIENT_HOST_BUF_LEN, 20
coap_msg.h, 33	COAP_CLIENT_PORT_BUF_LEN, 20
COAP_MSG_UNSUP_CONT_FMT	coap_client_create, 20
coap_msg.h, 33	coap_client_destroy, 21
COAP_MSG_URI_HOST	coap_client_exchange, 21
coap_msg.h, 33	coap_client_create
COAP_MSG_URI_PATH	coap_client.c, 48
coap_msg.h, 33	coap_client.h, 20
COAP_MSG_URI_PORT	coap_client_destroy
coap_msg.h, 33	coap_client.c, 49
COAP_MSG_URI_QUERY	coap_client.h, 21
coap_msg.h, 33	coap_client_exchange
COAP_MSG_VALID	coap_client.c, 49
coap_msg.h, 34	coap_client.h, 21
COAP_MSG_VER	coap_client_t, 5
coap_msg.h, 32	cred, 5

num_retrans, 5	coap_msg_check_critical_ops, 54
priority, 6	coap_msg_check_unsafe_ops, 55
sd, 6	coap_msg_copy, 55
server_host, 6	coap_msg_create, 55
server port, 6	coap_msg_destroy, 56
server sin, 6	coap_msg_format, 56
server_sin_len, 6	coap_msg_gen_rand_str, 56
session, 6	coap_msg_op_format_block_val, 56
timeout, 6	coap_msg_op_list_get_first, 54
timer_fd, 6	coap_msg_op_list_get_last, 54
coap_log.c	coap_msg_op_list_is_empty, 54
coap log debug, 50	coap_msg_op_num_is_recognized, 57
coap_log_error, 50	coap_msg_op_parse_block_val, 57
coap_log_get_level, 51	coap_msg_parse, 58
coap_log_info, 51	coap_msg_parse_type_msg_id, 58
coap_log_notice, 51	coap_msg_reset, 59
coap_log_set_level, 51	coap_msg_set_code, 59
coap log warn, 52	coap_msg_set_msg_id, 59
coap log.h	coap_msg_set_payload, 60
COAP LOG DEBUG, 24	coap_msg_set_token, 60
COAP LOG DEF LEVEL, 24	coap_msg_set_type, 61
COAP LOG ERROR, 24	coap_msg_uri_path_to_str, 61
COAP LOG INFO, 24	coap msg.h
COAP LOG NOTICE, 24	COAP MSG ACCEPT, 33
COAP_LOG_WARN, 24	COAP_MSG_ACK, 34
coap_log_debug, 24	COAP_MSG_BAD_GATEWAY, 34
coap_log_error, 24	COAP MSG BAD OPTION, 33
coap_log_get_level, 24	COAP_MSG_BAD_REQ, 33
coap_log_info, 25	COAP_MSG_BLOCK1, 33
coap_log_level_t, 24	COAP_MSG_BLOCK2, 33
coap_log_notice, 25	COAP MSG CHANGED, 34
coap_log_set_level, 25	COAP_MSG_CLIENT_ERR, 32
coap log warn, 25	COAP_MSG_CONTENT_FORMAT, 33
coap_log_debug	COAP MSG CONTENT, 34
coap_log.c, 50	COAP MSG CONTINUE, 34
coap_log.b, 24	COAP_MSG_CON, 34
coap_log_error	COAP MSG CREATED, 34
• — •	COAP_MSG_DELETED, 34
coap_log.c, 50	
coap_log.h, 24	COAP_MSG_DELETE, 33
coap_log_get_level	COAP_MSG_ETAG, 33 COAP MSG FORBIDDEN, 33
coap_log.c, 51	COAP_MSG_FORBIDDEN, 33 COAP_MSG_GATEWAY_TIMEOUT, 34
coap_log.h, 24	
coap_log_info	COAP_MSG_GET, 33
coap_log.c, 51	COAP_MSG_IF_MATCH, 33
coap_log.h, 25	COAP_MSG_IF_NONE_MATCH, 33
coap_log_level_t	COAP_MSG_INCOMPLETE, 33
coap_log.h, 24	COAP_MSG_INT_SERVER_ERR, 34
coap_log_notice	COAP_MSG_LOCATION_PATH, 33
coap_log.c, 51	COAP_MSG_LOCATION_QUERY, 33
coap_log.h, 25	COAP_MSG_MAX_AGE, 33
coap_log_set_level	COAP_MSG_MAX_BUF_LEN, 30
coap_log.c, 51	COAP_MSG_MAX_CODE_CLASS, 30
coap_log.h, 25	COAP_MSG_MAX_CODE_DETAIL, 30
coap_log_warn	COAP_MSG_MAX_MSG_ID, 30
coap_log.c, 52	COAP_MSG_MAX_TOKEN_LEN, 31
coap_log.h, 25	COAP_MSG_METHOD_NOT_ALLOWED, 33
coap_msg.c	COAP_MSG_NOT_ACCEPTABLE, 33
coap_msg_add_op, 54	COAP_MSG_NOT_FOUND, 33

COAP_MSG_NOT_IMPL, 34	coap_msg_op_num_t, 33
COAP_MSG_NON, 34	coap_msg_op_parse_block_val, 38
COAP_MSG_OP_MAX_BLOCK_SIZE, 31	coap_msg_op_set_len, 32
COAP_MSG_OP_MAX_BLOCK_VAL_LEN, 31	coap_msg_op_set_next, 32
COAP_MSG_OP_URI_PATH_MAX_LEN, 32	coap_msg_op_set_num, 32
COAP_MSG_POST, 33	coap_msg_op_set_val, 32
COAP MSG PRECOND FAILED, 33	coap_msg_parse, 38
COAP MSG PROXY NOT SUP, 34	coap_msg_parse_type_msg_id, 39
COAP MSG PROXY SCHEME, 33	coap_msg_reset, 39
COAP MSG PROXY URI, 33	coap_msg_server_err_t, 33
COAP MSG PUT, 33	coap_msg_set_code, 39
COAP_MSG_REQ_ENT_TOO_LARGE, 33	coap_msg_set_msg_id, 40
COAP_MSG_REQ, 32	coap_msg_set_payload, 40
COAP MSG RST, 34	coap_msg_set_token, 41
COAP MSG SERV UNAVAIL, 34	coap_msg_set_type, 41
COAP_MSG_SERVER_ERR, 32	coap_msg_success_t, 34
COAP MSG SIZE1, 33	coap_msg_type_t, 34
COAP MSG SIZE2, 33	coap_msg_uri_path_to_str, 42
COAP MSG SUCCESS, 32	coap_msg_add_op
COAP MSG UNAUTHORIZED, 33	coap_msg.c, 54
COAP_MSG_UNSUP_CONT_FMT, 33	
	coap_msg.h, 34
COAP_MSG_URI_HOST, 33	coap_msg_check_critical_ops
COAP_MSG_URI_PATH, 33	coap_msg.c, 54
COAP_MSG_URI_PORT, 33	coap_msg.h, 35
COAP_MSG_URI_QUERY, 33	coap_msg_check_unsafe_ops
COAP_MSG_VALID, 34	coap_msg.c, 55
COAP_MSG_VER, 32	coap_msg.h, 35
coap_msg_add_op, 34	coap_msg_class_t
coap_msg_check_critical_ops, 35	coap_msg.h, 32
coap_msg_check_unsafe_ops, 35	coap_msg_client_err_t
coap_msg_class_t, 32	coap_msg.h, 32
coap_msg_client_err_t, 32	coap_msg_copy
coap_msg_copy, 36	coap_msg.c, 55
coap_msg_create, 36	coap_msg.h, <mark>36</mark>
coap_msg_destroy, 36	coap_msg_create
coap_msg_format, 36	coap_msg.c, 55
coap_msg_gen_rand_str, 37	coap_msg.h, 36
coap_msg_get_code_class, 29	coap_msg_destroy
coap_msg_get_code_detail, 29	coap_msg.c, 56
coap_msg_get_first_op, 29	coap_msg.h, 36
coap_msg_get_msg_id, 29	coap_msg_format
coap_msg_get_payload, 29	coap_msg.c, 56
coap_msg_get_payload_len, 30	coap_msg.h, 36
coap_msg_get_token, 30	coap_msg_gen_rand_str
coap_msg_get_token_len, 30	coap msg.c, 56
coap_msg_get_type, 30	coap msg.h, 37
coap_msg_get_ver, 30	coap_msg_get_code_class
coap_msg_is_empty, 30	coap_msg.h, 29
coap_msg_method_t, 33	coap_msg_get_code_detail
coap_msg_op_format_block_val, 37	coap_msg.h, 29
coap_msg_op_get_len, 31	coap_msg_get_first_op
coap_msg_op_get_next, 31	coap_msg.h, 29
coap_msg_op_get_num, 31	coap_msg_get_msg_id
	coap_msg.h, 29
coap_msg_op_get_val, 31	• — •
coap_msg_op_num_is_critical, 31	coap_msg_get_payload
coap_msg_op_num_is_recognized, 37	coap_msg.h, 29
coap_msg_op_num_is_unsafe, 31	coap_msg_get_payload_len
coap_msg_op_num_no_cache_key, 31	coap_msg.h, <mark>30</mark>

coap_msg_get_token	coap_msg.h, 32
coap_msg.h, 30	coap_msg_parse
coap_msg_get_token_len coap_msg.h, 30	coap_msg.c, 58 coap_msg.h, 38
coap_msg_get_type	coap_msg_parse_type_msg_id
coap_msg.h, 30	coap_msg.c, 58
coap_msg_get_ver	coap_msg.h, 39
coap_msg.h, 30	coap_msg_reset
coap_msg_is_empty	coap_msg.c, 59
coap_msg.h, 30	coap_msg.h, 39
coap_msg_method_t	coap_msg_server_err_t
coap_msg.h, 33	coap_msg.h, 33
coap_msg_op, 7	coap_msg_set_code
len, 7	coap_msg.c, 59
next, 7	coap_msg.h, 39
num, 7	coap_msg_set_msg_id
val, 7	coap_msg.c, 59
coap_msg_op_format_block_val	coap_msg.h, 40
coap_msg.c, 56	coap_msg_set_payload
coap_msg.h, 37	coap_msg.c, 60
coap_msg_op_get_len	coap_msg.h, 40
coap_msg.h, 31	coap_msg_set_token
coap_msg_op_get_next	coap_msg.c, 60
coap_msg.h, 31	coap_msg.h, 41
coap_msg_op_get_num	coap_msg_set_type
coap_msg.h, 31	coap_msg.c, 61
coap_msg_op_get_val	coap_msg.h, 41
coap_msg.h, 31	coap_msg_success_t
coap_msg_op_list_get_first	coap_msg.h, 34
coap_msg.c, 54	coap_msg_t, 9
coap_msg_op_list_get_last	code_class, 10
coap_msg.c, 54	code_detail, 10
coap_msg_op_list_is_empty	msg_id, 10
coap_msg.c, 54	op_list, 10
coap_msg_op_list_t, 8	payload, 10
first, 8	payload_len, 10
last, 8	token, 10
coap_msg_op_num_is_critical	token_len, 10
coap_msg.h, 31	type, 10
coap_msg_op_num_is_recognized coap_msg.c, 57	ver, 10
coap_msg.h, 37	coap_msg_type_t coap_msg.h, 34
coap_msg_op_num_is_unsafe	coap_msg_uri_path_to_str
coap msg.h, 31	coap_msg.c, 61
coap_msg_op_num_no_cache_key	coap_msg.h, 42
coap_msg.h, 31	coap_server, 11
coap_msg_op_num_t	cred, 12
coap_msg.h, 33	dh_params, 12
coap_msg_op_parse_block_val	handle, 12
coap_msg.c, 57	msg id, 12
coap_msg.h, 38	priority, 12
coap_msg_op_set_len	sd, 12
coap_msg.h, 32	sep_list, 12
coap_msg_op_set_next	trans, 12
coap_msg.h, 32	coap_server.c
coap_msg_op_set_num	COAP_SERVER_ACK_TIMEOUT_SEC, 63
coap_msg.h, 32	COAP_SERVER_DTLS_MTU, 63
coap_msg_op_set_val	COAP_SERVER_DTLS_NUM_DH_BITS, 63
	<i>_ ,</i>

	COAP_SERVER_DTLS_PRIORITIES, 63 COAP_SERVER_DTLS_RETRANS_TIMEOUT,	code_class coap_msg_t, 10
	63	code detail
	COAP_SERVER_DTLS_TOTAL_TIMEOUT, 63	coap_msg_t, 10
	COAP_SERVER_MAX_RETRANSMIT, 63	cred
	coap_server_add_sep_resp_uri_path, 63	coap_client_t, 5
	coap_server_create, 64	coap_server, 12
	coap_server_destroy, 64	
	coap_server_get_next_msg_id, 65	dh_params
	coap_server_run, 65	coap_server, 12
-	_server.h	first
	COAP_SERVER_ADDR_BUF_LEN, 44	coap_msg_op_list_t, 8
	COAP_SERVER_DIAG_PAYLOAD_LEN, 44	coap_server_path_list_t, 14
	COAP_SERVER_NUM_TRANS, 44	
	COAP_SERVER_PIGGYBACKED, 44	handle
	COAP_SERVER_SEPARATE, 44	coap_server, 12
	coap_server_add_sep_resp_uri_path, 44	
	coap_server_create, 45	last
	coap_server_destroy, 45	coap_msg_op_list_t, 8
	coap_server_get_next_msg_id, 46	coap_server_path_list_t, 14
	coap_server_resp_t, 44	last_use
	coap_server_run, 46	coap_server_trans, 16
	_server_add_sep_resp_uri_path	len
	coap_server.c, 63	coap_msg_op, 7
	coap_server.h, 44	lib/include/coap_client.h, 19
	_server_create	lib/include/coap_ipv.h, 21
	coap_server.c, 64	lib/include/coap_log.h, 23
	coap_server.h, 45	lib/include/coap_msg.h, 26
	_server_destroy	lib/include/coap_server.h, 42
	coap_server.c, 64	lib/src/coap_client.c, 46
	coap_server.h, 45	lib/src/coap_log.c, 49
	_server_get_next_msg_id coap_server.c, 65	lib/src/coap_msg.c, 52 lib/src/coap_server.c, 61
	coap_server.b, 46	iib/sic/coap_server.c, or
	_server_path, 13	msg id
	next, 13	coap_msg_t, 10
	str, 13	coap_server, 12
	_server_path_list_t, 14	
	first, 14	next
	last, 14	coap_msg_op, 7
	server resp t	coap_server_path, 13
	coap_server.h, 44	num
	server run	coap_msg_op, 7
	coap_server.c, 65	num_retrans
	coap server.h, 46	coap_client_t, 5
	_server_trans, 15	coap_server_trans, 16
	active, 16	on list
	client_addr, 16	op_list
	client_sin, 16	coap_msg_t, 10
	client_sin_len, 16	payload
	last_use, 16	coap msg t, 10
	num_retrans, 16	payload_len
	req, 16	coap_msg_t, 10
	resp, 16	priority
	server, 16	coap_client_t, 6
	session, 16	coap_server, 12
	timeout, 17	. — ,
	timer_fd, 17	req

```
coap_server_trans, 16
resp
    coap_server_trans, 16
sd
    coap_client_t, 6
    coap_server, 12
sep list
    coap_server, 12
server
    coap_server_trans, 16
server_host
    coap_client_t, 6
server_port
    coap_client_t, 6
server_sin
    coap_client_t, 6
server_sin_len
    coap_client_t, 6
session
    coap_client_t, 6
    coap_server_trans, 16
str
    coap_server_path, 13
timeout
    coap_client_t, 6
    coap_server_trans, 17
timer_fd
    coap_client_t, 6
    coap_server_trans, 17
token
    coap_msg_t, 10
token_len
    coap_msg_t, 10
trans
    coap_server, 12
type
    coap_msg_t, 10
val
    coap_msg_op, 7
ver
    coap_msg_t, 10
```