2.7 FunctionalGroup — Functional Group

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
Interchange — Interchange Structure	1 .. 1				
├ **FunctionalGroup** — Functional Group	1 .. *				

Properties

Identifier FunctionalGroup

Name Functional Group

Cardinality min: 1 max: *

Syntax Type Related

External Category Element

Notes

Tech. Info. 0 Choice : (FunctionalGroup) (maxOccurs : 1) (minOccurs : 1)

2.8 S_UNZ — S UNZ

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
Interchange — Interchange Structure	1 .. 1				
└ **S_UNZ** — S UNZ	1 .. 1				
├ **D_0036** — Interchange control count	1 .. 1	Decimal			
└ **D_0020** — Interchange control reference	1 .. 1	String		1 .. 14	

Properties

Identifier S_UNZ

Name S UNZ

Cardinality min: 1 max: 1

Syntax Type Related

External Category Element

Leaf Elements

Identifier/Name	Description/Notes/Code Values	Properties
D_0036 Interchange control count	The count either of the number of messages or, if used, of the number of functional groups in an interchange. One of these counts shall appear.	**Cardinality** min: 1 max: 1 **Primitive Type** Decimal **Length** min: 0 **Total Digits** 6 **External Category** Element **Data Type** xsd:decimal
D_0020 Interchange control reference	Unique reference assigned by the sender to an interchange. **Usage 1** Shall be identical in UNB and UNZ.	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 14 **External Category** Element **Data Type** xsd:string

3 OVERVIEW MESSAGE

General Information

Name	EDIFACT_IFTMBC
Direction	In
Status	Active
Message Type	Booking confirmation message
Type System	UNEDIFACT
Version	D.96A S3
External Category	Message Type

Documentation

Definition

0. Introduction
This specification provides the definition of the Booking confirmation message (IFTMBC) to be used in Electronic Data Interchange (EDI) between trading partners involved in administration, commerce and transport.

1 Scope
This paper provides the definition of the Booking Confirmation Message to be used in fulfilling the requirements of trading partners in the transport chain worldwide, in the interchange of cargo and transport related information using Electronic Data Interchange (EDI). This message is a single consignment-based message, being aligned with other single consignment-based messages such as the other two booking messages (IFTMBP and IFTMBF), the instruction messages (IFTMIN and IFTMCS) and the Arrival Notice Message (IFTMAN). The single consignment-based messages can be used by all modes of transport for the forwarding and transport of goods from any origin to any destination, regardless of route or prevailing commercial practice. These messages are suitable for the arrangement of the transport of goods between all parties to the movement of the consignment (including the consignor/shipper and consignee as well as the forwarders, brokers, and carriers involved) as well as providing the information necessary to perform that transport and delivery of the goods. They should be used in the same way by each mode of transport when the requirements are common even if functionally similar information is known by different names.

1.1 Functional Definition
A message from the party providing forwarding and/or transport services to the party booking those services giving the confirmation information to the booking of the consignment concerned. A confirmation might read that the booking of a consignment is accepted, pending, conditionally accepted or rejected. The conditions under which requested services take place may be given in this message. This message may be applied for both national and international trade. It is based on universal practice and is not dependent on the type of business or industry.

1.2 Principles
The message can be used whenever a confirmation of the booking of a consignment is deemed necessary as an answer to a booking provisional or booking firm message concerning a certain consignment. The use of a Booking Confirmation Message is not compulsory.
- A consignment may contain several goods items.
- Goods items may or may not be containerized.
- A goods item may be transported in one or more containers, and a single container may contain one or more goods items.
- One goods item may be related to one or more customs tariff codes.
- Goods items related to one customs tariff code may be carried in one or more containers.
- Goods items may reflect either the contractual or operational description of the goods.
- A party to the movement of the consignment may book or order transport for one or more goods items.
- A party to the movement of the consignment may book or issue instructions of transport to be arranged for several goods items by means of one or several of the following messages: IFTMBP, IFTMBF, IFTMBC, IFTMIN, IFTMCS, IFTMAN.
- Pre-carriage (advanced haulage) and/or on-carriage (destination haulage) of goods items or equipment within one booking or instruction may take place in different steps, each step specified with its own transport details group.
- Equipment may have other types of equipment attached to it, e.g. a temperature control unit attached to a container.
- Equipment and/or goods items may be attached to or transported on another load or transport device, which as such may be attached to or transported on yet another load or transport device, e.g. a container on a chassis on a rail-car.
- Transport devices, which have the ability of powered movement on their own, are specified in the transport details group. Other load or transport devices are specified as equipment.
- The expression of packaging for goods items can be expressed at up to three levels. A number of generic transport terms are used in this specification, to be described as:
* MODE OF TRANSPORT: The method of transport used for the conveyance of goods or persons, e.g. by rail, by road, by sea.

* MEANS OF TRANSPORT: The vehicle used for the transport of goods or persons, e.g. aircraft, truck, vessel.
* TYPE OF MEANS OF TRANSPORT: The type of vehicle used in the transport process, e.g. wide body, tank truck, passenger vessel.
* EQUIPMENT: Material resources necessary to facilitate the transport and handling of cargo. Transport equipment does under the given circumstances not have the ability to move by its own propulsion (e.g. sea container, trailer, unit load device, pallet).
* TYPE OF EQUIPMENT: The type of material used, e.g. 40 feet container, four any pallet, mafi trailer.

Examples: Annex A Example (Details of transport)
1. TDT+20+HL12345+1:MARITIME+:CONTAINER VESSEL+:::HAPAG LLOYD+++PHXXX:::FAITHFUL'
Notes: 20 indicates 'main transport' (d.e. 8051); HL12345 is assigned by the carrier (d.e. 8028; is the 'flight number' in the air mode); PHXXX is the radio call sign (d.e. 8213); 'FAITHFUL' is the name of the vessel
2. TDT+20+91/05/0021+3:ROAD++:::INT. TRUCKING CO.+++BB-10-XX::::NL'
Note: BB-10-XX represents the (Dutch) truck registration no. Source: Western European EDIFACT Board

Notes

Example 1

```
UNA:+.? '
UNB+UNOC:3+4399901117228:14+gln-111:14+20200529:1431+2000'
UNH+388400022+IFTMBC:D:96A:UN'
BGM+770+33333333++AP'
FTX+AAP+++EX SWANA'
RFF+ABO:QM7_910'
GID+0001'
RFF+AAQ:CT1233444'
GID+0002'
RFF+AAQ:CT1233444'
GID+0003'
RFF+AAQ:CT1233555'
GID+0004'
RFF+AAQ:CT1233666'
UNT+15+388400022'
UNZ+1+2000'
```

3.1 Structure

The following table shows the complete structure.

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTMBC — Booking confirmation message	1 .. 1				
├ **UNH** — MESSAGE HEADER	1 .. 1		0010		
│ ├ **0062** — Message reference number	1 .. 1	String	010	1 .. 14	
│ └ **S009** — MESSAGE IDENTIFIER	1 .. 1		020		
│ ├ **0065** — Message type identifier	1 .. 1	String	010	1 .. 6	0065
│ ├ **0052** — Message type version number	1 .. 1	String	020	1 .. 3	0052
│ ├ **0054** — Message type release number	1 .. 1	String	030	1 .. 3	0054
│ └ **0051** — Controlling agency	1 .. 1	String	040	1 .. 2	0051
├ **BGM** — Beginning of message	1 .. 1		0020		
│ ├ **1004** — Document/message number	0 .. 1	String	020	1 .. 35	
│ └ **4343** — Response type, coded	0 .. 1	String	040	1 .. 3	4343
├ **FTX** — Free text - Response (free text)	0 .. 1		0070		
│ ├ **4451** — Text subject qualifier	1 .. 1	String	010	1 .. 3	4451
│ └ **C108** — Text literal	0 .. 1		040		
│ └ **4440** — Free text	1 .. 1	String	010	1 .. 1023	
├ **SG2** — Segment Group 2: RFF-DTM	0 .. 1		0120		
│ └ **RFF** — Reference	1 .. 1		0130		
│ └ **C506** — Reference - Consignee's shipment reference number	1 .. 1		010		
│ ├ **1153** — Reference qualifier	1 .. 1	String	010	1 .. 3	1153
│ └ **1154** — Reference number	0 .. 1	String	020	1 .. 35	
├ **SG8** — Segment Group 8: GID-HAN-TMP-RNG-TMD-LOC-FTX-SG9-GDS-SG10-SG11-SG12-SG13-SG14	0 .. 999		0350		
│ ├ **GID** — Goods item details	1 .. 1		0360		
│ │ └ **1496** — Goods item number	0 .. 1	String	010	1 .. 100	
│ └ **SG12** — Segment Group 12: RFF-DTM	0 .. 1		0530		
│ └ **RFF** — Reference	1 .. 1		0540		
│ └ **C506** — Reference - Unit load device (e.g. container) identification number	1 .. 1		010		
│ ├ **1153** — Reference qualifier	1 .. 1	String	010	1 .. 3	1153
│ └ **1154** — Reference number	0 .. 1	String	020	1 .. 60	
└ **UNT** — MESSAGE TRAILER	1 .. 1		0770		
├ **0074** — Number of segments in a message	1 .. 1	Decimal	010	1 .. 6	
└ **0062** — Message reference number	1 .. 1	String	020	1 .. 14	

4 DETAILS MESSAGE

4.1 IFTMBC — Booking confirmation message

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTMBC — Booking confirmation message	1 .. 1				
├ **UNH** — MESSAGE HEADER	1 .. 1		0010		
├ **BGM** — Beginning of message	1 .. 1		0020		
├ **FTX** — Free text - Response (free text)	0 .. 1		0070		
├ **SG2** — Segment Group 2: RFF-DTM	0 .. 1		0120		
├ **SG8** — Segment Group 8: GID-HAN-TMP-RNG-TMD-LOC-FTX-SG9-GDS-SG10-SG11-SG12-SG13-SG14	0 .. 999		0350		
└ **UNT** — MESSAGE TRAILER	1 .. 1		0770		

Properties

Tag IFTMBC

Name Booking confirmation message

Cardinality min: 1 max: 1

4.2 UNH — MESSAGE HEADER

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTMBC — Booking confirmation message	1 .. 1				
├ **UNH** — MESSAGE HEADER	1 .. 1		0010		
│ ├ **0062** — Message reference number	1 .. 1	String	010	1 .. 14	
│ └ **S009** — MESSAGE IDENTIFIER	1 .. 1		020		

Documentation

Definition A service segment starting and uniquely identifying a message. The message type code for the Booking confirmation message is IFTMBC. Note: Booking confirmation messages conforming to this document must contain the following data in segment UNH, composite S009: Data element 0065 IFTMBC 0052 D 0054 96A 0051 UN

Properties

Tag UNH

Name MESSAGE HEADER

Cardinality min: 1 max: 1

Syntax Type Related

External Category Segment

Position 0010

Level 2

Leaf Elements

Tag/Name	Description/Notes/Code Values	Properties
0062 Message reference number	Unique message reference assigned by the sender.	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 14 **External Category** Data Element **Data Type** an **Position** 010

4.3 S009 — MESSAGE IDENTIFIER

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTMBC — Booking confirmation message	1 .. 1				
├ **UNH** — MESSAGE HEADER	1 .. 1		0010		
│ └ **S009** — MESSAGE IDENTIFIER	1 .. 1		020		
│ ├ **0065** — Message type identifier	1 .. 1	String	010	1 .. 6	0065
│ ├ **0052** — Message type version number	1 .. 1	String	020	1 .. 3	0052
│ ├ **0054** — Message type release number	1 .. 1	String	030	1 .. 3	0054
│ └ **0051** — Controlling agency	1 .. 1	String	040	1 .. 2	0051

Documentation

Definition Identification of the type, version etc. of the message being interchanged.

Properties

Tag S009

Name MESSAGE IDENTIFIER

Cardinality min: 1 max: 1

Syntax Type Related

External Category Composite Data Element

Position 020

Leaf Elements

Tag/Name	Description/Notes/Code Values	Properties
0065 Message type identifier	Code identifying a type of message and assigned by its controlling agency. **Selected Values** All Values in Codelist	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 6 **External Category** Data Element **Data Type** an **Position** 010 **Codelist Id** 0065 **Type System** UNEDIFACT **Version Mode** Current **Version** D.96A S3
0052 Message type version number	Version number of a message type. **Selected Values** All Values in Codelist	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 3 **External Category** Data Element **Data Type** an **Position** 020 **Codelist Id** 0052 **Type System** UNEDIFACT **Version Mode** Current **Version** D.96A S3
0054 Message type release number	Release number within the current message type version number (0052). **Selected Values** All Values in Codelist	**Cardinality** min: 1 max: 1 **Primitive Type** String **Length** min: 1 max: 3 **External Category** Data Element **Data Type** an **Position** 030 **Codelist Id** 0054 **Type System** UNEDIFACT **Version Mode** Current

		Version D.96A S3
0051 Controlling agency	Code identifying the agency controlling the specification, maintenance and publication of the message type. **Selected Values** All Values in Codelist	**Cardinality** **min:** 1 **max:** 1 **Primitive Type** String **Length** **min:** 1 **max:** 2 **External Category** Data Element **Data Type** an **Position** 040 **Codelist Id** 0051 **Type System** UNEDIFACT **Version Mode** Current **Version** D.96A S3

4.4 BGM — Beginning of message

Structure

Node	Card.	Prim.Type	Pos.	Length	Codelists
IFTMBC — Booking confirmation message	1 .. 1				
├ **BGM** — Beginning of message	1 .. 1		0020		
│ ├ **1004** — Document/message number	0 .. 1	String	020	1 .. 35	
│ └ **4343** — Response type, coded	0 .. 1	String	040	1 .. 3	4343

Documentation

Definition A segment to indicate the beginning of a message and to transmit identifying number and type of the message.

Properties

Tag BGM

Name Beginning of message

Cardinality min: 1 max: 1

Syntax Type Related

External Category Segment

Position 0020

Level 2

Leaf Elements

Tag/Name	Description/Notes/Code Values	Properties
1004 Document/message number	Reference number assigned to the document/message by the issuer.	**Cardinality** min: 0 max: 1 **Primitive Type** String **Length** min: 1 max: 35 **External Category** Data Element **Data Type** an **Position** 020
4343 Response type, coded	Code specifying the type of acknowledgement required or transmitted. **Selected Values** **Code** AP **Name** Accepted Indication that the referenced offer or transaction (e.g., cargo booking or quotation request) has been accepted. **Code** RE **Name** Rejected Indication that the referenced offer or transaction (e.g., cargo booking or quotation request) is not accepted.	**Cardinality** min: 0 max: 1 **Primitive Type** String **Length** min: 1 max: 3 **External Category** Data Element **Data Type** an **Position** 040 **Codelist Id** 4343 **Type System** UNEDIFACT **Version Mode** Current **Version** D.96A S3