## 2.7 FunctionalGroup — Functional Group

### Structure

| Node | Card. | Prim.Type | Pos. | Length | Codelists |
|---|---|---|---|---|---|
| **Interchange** — Interchange Structure | 1 .. 1 | | | | |
| ├ **FunctionalGroup** — Functional Group | 1 .. * | | | | |

### Properties

**Identifier** FunctionalGroup

**Name** Functional Group

**Cardinality** min: 1 max: *

### Syntax Type Related

**External Category** Element

### Notes

**Tech. Info. 0** Choice : (FunctionalGroup) (maxOccurs : 1) (minOccurs : 1)

## 2.8 S_UNZ — S UNZ

### Structure

| Node | Card. | Prim.Type | Pos. | Length | Codelists |
|---|---|---|---|---|---|
| **Interchange** — Interchange Structure | 1 .. 1 | | | | |
| └ **S_UNZ** — S UNZ | 1 .. 1 | | | | |
| ├ **D_0036** — Interchange control count | 1 .. 1 | Decimal | | | |
| └ **D_0020** — Interchange control reference | 1 .. 1 | String | | 1 .. 14 | |

### Properties

**Identifier** S_UNZ

**Name** S UNZ

**Cardinality** min: 1 max: 1

### Syntax Type Related

**External Category** Element

### Leaf Elements

| Identifier/Name | Description/Notes/Code Values | Properties |
|---|---|---|
| **D_0036**<br>Interchange control count | The count either of the number of messages or, if used, of the number of functional groups in an interchange. One of these counts shall appear. | **Cardinality** min: 1 max: 1<br>**Primitive Type** Decimal<br>**Length** min: 0<br>**Total Digits** 6<br>**External Category** Element<br>**Data Type** xsd:decimal |
| **D_0020**<br>Interchange control reference | Unique reference assigned by the sender to an interchange.<br><br>**Usage 1**<br>Shall be identical in UNB and UNZ. | **Cardinality** min: 1 max: 1<br>**Primitive Type** String<br>**Length** min: 1 max: 14<br>**External Category** Element<br>**Data Type** xsd:string |

# 3 OVERVIEW MESSAGE

## General Information

| | |
|---|---|
| **Name** | EDIFACT_IFTSTA |
| **Direction** | In |
| **Status** | Active |
| **Message Type** | International multimodal status report message |
| **Type System** | UNEDIFACT |
| **Version** | D.01C S3 |
| **External Category** | Message Type |

## Documentation

**Definition**

Date:
2022-01-27
This specification provides the definition of the International multimodal status report message (IFTSTA) to be used in Electronic Data Interchange (EDI) between trading partners involved in the SAP LBN environment.A message to report the transport status and/or a change in the transport status (i.e. event) between agreed parties.The International multimodal status report message may be used for both national and international applications. It is based on universal practice related to administration, commerce and transport, and is not dependent on the type of business or industry.
This message allows for the exchange of information regarding the status of the physical movement of consignments, goods or equipment at any point (in time or place) within the full transport chain.This message can relate to a status (or statuses) that has or have been reached in a transport chain.
Data requirements for tracking equipment where equipment is not associated with a consignment (such as repair container) are NOT addressed in this message.

## Notes

**Example 1**

```
UNA:+.? ‘
UNB+UNOC:3+GLNID:14+GLNID:14+211214:1442+6743’
UNH+1+IFTSTA:D:01C:UN’
BGM+7+0959186+9’
DTM+137:20211214:102’
NAD+MS+00000041++NoteToCustomer:CORPORATE IT+EXAMPLE-STREET 2+CITY++ZIP+DE’
NAD+MR+03009631++COMPANY LTD:LOGISTICCENTER+STREETNAME 47+CITY++ZIP+DE’
CNI+1+04465986868’
STS+11+21+108:::ZUGESTELLT’
RFF+ZZ1:SenderSystemId’
RFF+ZZ2:FreightOrderId’
RFF+ZZ3:LBN_PORT_HH’
RFF+ZZ4:LBN_CUS_DT’
RFF+ZZ5:LbnId’
RFF+ZZ7:1’
RFF+ZZ8:2’
DTM+9:202112141411:203’
NAD+CS+00000010+NOTE, EXAMPLE+NOTE SE:LOREM IPSUM+ACCEPTING
PERSON+NOTE++NOTE+DE’
NAD+AP++MR. DOW’
CNI+2+04465986859’
STS+11+21+108:::ZUGESTELLT’
RFF+ZZ1:SenderSystemId’
RFF+ZZ2:FreightOrderId’
RFF+ZZ3:LBN_PORT_HH’
RFF+ZZ4:LBN_CUS_DT’
RFF+ZZ5:LbnId’
RFF+ZZ7:1’
RFF+ZZ8:3’
DTM+9:202112141411:203’
NAD+CS+00000010+NOTE, EXAMPLE+NOTE SE:LOREM IPSUM+ACCEPTING
PERSON+NOTE++NOTE+DE’
NAD+AP++MR. DOW’
CNI+3+04465956417’
STS+11+21+108:::ZUGESTELLT’
RFF+ZZ1:SenderSystemId’
RFF+ZZ2:FreightOrderId’
RFF+ZZ3:LBN_PORT_HH’
```

RFF+ZZ4:LBN_CUS_DT’
RFF+ZZ5:LbnId’
DTM+9:202112141344:203’
NAD+MS+00000041++NoteToCustomer:CORPORATE IT+EXAMPLE-STREET 2+CITY++ZIP+DE’
NAD+MR+03009631++COMPANY LTD:LOGISTICCENTER+STREETNAME 47+CITY++ZIP+DE’
CNI+4+04465947892’
STS+11+21+108:::ZUGESTELLT’
RFF+ZZ1:SenderSystemId’
RFF+ZZ2:FreightOrderId’
RFF+ZZ3:LBN_PORT_HH’
RFF+ZZ4:LBN_CUS_DT’
RFF+ZZ5:LbnId’
RFF+ZZ7:2’
RFF+ZZ8:3’
DTM+9:202112141344:203’
NAD+MS+00000041++NoteToCustomer:CORPORATE IT+EXAMPLE-STREET 2+CITY++ZIP+DE’
NAD+MR+03009631++COMPANY LTD:LOGISTICCENTER+STREETNAME 47+CITY++ZIP+DE’
UNT+54+1’
UNZ+1+6743’

### 3.1 Structure

The following table shows the complete structure.

| Node | Card. | Prim.Type | Pos. | Length | Codelists |
|---|---|---|---|---|---|
| **IFTSTA** — International multimodal status report message | 1 .. 1 | | | | |
| ├ **UNH** — Message header | 1 .. 99 | | 0010 | | |
| │ ├ **0062** — Message reference number | 1 .. 1 | String | 010 | 1 .. 14 | |
| │ └ **S009** — Message identifier | 1 .. 1 | | 020 | | |
| │ ├ **0065** — Message type | 1 .. 1 | String | 010 | 1 .. 6 | 0065 |
| │ ├ **0052** — Message version number | 1 .. 1 | String | 020 | 1 .. 3 | 0052 |
| │ ├ **0054** — Message release number | 1 .. 1 | String | 030 | 1 .. 3 | 0054 |
| │ └ **0051** — Controlling agency | 1 .. 1 | String | 040 | 1 .. 2 | 0051 |
| ├ **BGM** — Beginning of message | 1 .. 1 | | 0020 | | |
| ├ **SG4** — Segment Group 4: CNI-LOC-CNT-SG5 | 0 .. 99999 | | 0160 | | |
| │ ├ **CNI** — Consignment information | 1 .. 1 | | 0170 | | |
| │ └ **SG5** — Segment Group 5: STS-RFF-DTM-DOC-FTX-SG6-LOC-PCI-SG8-SG10-SG14 | 1 .. 99 | | 0200 | | |
| │ ├ **STS** — Status | 1 .. 1 | | 0210 | | |
| │ │ └ **C555** — Status | 1 .. 1 | | 020 | | |
| │ │ └ **4405** — Status description code | 1 .. 1 | String | 010 | 1 .. 3 | Rec_24 |
| │ ├ **RFF** — Reference - originatorId | 1 .. 1 | | 0220 | | |
| │ │ └ **C506** — Reference | 1 .. 1 | | 010 | | |
| │ │ ├ **1153** — Reference code qualifier | 1 .. 1 | String | 010 | 1 .. 3 | 1 |
| │ │ └ **1154** — Reference identifier | 1 .. 1 | String | 020 | 1 .. 70 | |
| │ ├ **RFF** — Reference - orderingPartyLbnId | 1 .. 1 | | 0220 | | |
| │ │ └ **C506** — Reference | 1 .. 1 | | 010 | | |
| │ │ ├ **1153** — Reference code qualifier | 1 .. 1 | String | 010 | 1 .. 3 | 1 |
| │ │ └ **1154** — Reference identifier | 1 .. 1 | String | 020 | 1 .. 70 | |
| │ ├ **RFF** — Reference - freightOrderId | 1 .. 1 | | 0220 | | |
| │ │ └ **C506** — Reference | 1 .. 1 | | 010 | | |
| │ │ ├ **1153** — Reference code qualifier | 1 .. 1 | String | 010 | 1 .. 3 | 1 |
| │ │ └ **1154** — Reference identifier | 1 .. 1 | String | 020 | 1 .. 70 | |
| │ ├ **RFF** — Reference - loadingStopId | 1 .. 1 | | 0220 | | |
| │ │ └ **C506** — Reference | 1 .. 1 | | 010 | | |
| │ │ ├ **1153** — Reference code qualifier | 1 .. 1 | String | 010 | 1 .. 3 | 1 |
| │ │ └ **1154** — Reference identifier | 1 .. 1 | String | 020 | 1 .. 70 | |
| │ ├ **RFF** — Reference - unloadingStopId | 1 .. 1 | | 0220 | | |
| │ │ └ **C506** — Reference | 1 .. 1 | | 010 | | |
| │ │ ├ **1153** — Reference code qualifier | 1 .. 1 | String | 010 | 1 .. 3 | 1 |
| │ │ └ **1154** — Reference identifier | 1 .. 1 | String | 020 | 1 .. 70 | |
| │ └ **DTM** — Date/time/period | 1 .. 1 | | 0230 | | |
| │ └ **C507** — Date/time/period | 1 .. 1 | | 010 | | |
| │ ├ **2005** — Date or time or period function code qualifier | 1 .. 1 | String | 010 | 1 .. 3 | 2005 |
| │ ├ **2380** — Date or time or period value | 1 .. 1 | String | 020 | 1 .. 35 | |
| │ └ **2379** — Date or time or period format code | 1 .. 1 | String | 030 | 1 .. 3 | 2379 |
| └ **UNT** — Message trailer | 1 .. 1 | | 0720 | | |
| ├ **0074** — Number of segments in the message | 1 .. 1 | Decimal | 010 | 1 .. 6 | |
| └ **0062** — Message reference number | 1 .. 1 | String | 020 | 1 .. 14 | |

# 4 DETAILS MESSAGE

## 4.1 IFTSTA — International multimodal status report message

### Structure

| Node | Card. | Prim.Type | Pos. | Length | Codelists |
|---|---|---|---|---|---|
| **IFTSTA** — International multimodal status report message | 1 .. 1 | | | | |
| ├ **UNH** — Message header | 1 .. 99 | | 0010 | | |
| ├ **BGM** — Beginning of message | 1 .. 1 | | 0020 | | |
| ├ **SG4** — Segment Group 4: CNI-LOC-CNT-SG5 | 0 .. 99999 | | 0160 | | |
| └ **UNT** — Message trailer | 1 .. 1 | | 0720 | | |

### Properties

**Identifier** IFTSTA

**Name** International multimodal status report message

**Cardinality** min: 1 max: 1

## 4.2 UNH — Message header

### Structure

| Node | Card. | Prim.Type | Pos. | Length | Codelists |
|---|---|---|---|---|---|
| **IFTSTA** — International multimodal status report message | 1 .. 1 | | | | |
| ├ **UNH** — Message header | 1 .. 99 | | 0010 | | |
| │ ├ **0062** — Message reference number | 1 .. 1 | String | 010 | 1 .. 14 | |
| │ └ **S009** — Message identifier | 1 .. 1 | | 020 | | |

### Documentation

**Definition** A service segment starting and uniquely identifying a message. The message type code for the International multimodal status report message is IFTSTA. Example: UNH+1+IFTSTA:D:01C:UN'

### Properties

**Identifier** UNH

**Name** Message header

**Cardinality** min: 1 max: 99

### Syntax Type Related

**External Category** Segment

**Position** 0010

**Level** 2

### Notes

**Example 1** UNH+1+IFTSTA:D:01C:UN'

### Leaf Elements

| Identifier/Name | Description/Notes/Code Values | Properties |
|---|---|---|
| **0062**<br>Message reference number | Unique message reference assigned by the sender.<br><br>**Usage 1**<br>Shall be identical in UNH and UNT. | **Cardinality** min: 1 max: 1<br>**Primitive Type** String<br>**Length** min: 1 max: 14<br>**External Category** Data Element<br>**Data Type** an<br>**Position** 010 |

## 4.3 S009 — Message identifier

### Structure

| Node | Card. | Prim.Type | Pos. | Length | Codelists |
|---|---|---|---|---|---|
| **IFTSTA** — International multimodal status report message | 1 .. 1 | | | | |
| ├ **UNH** — Message header | 1 .. 99 | | 0010 | | |
| │ └ **S009** — Message identifier | 1 .. 1 | | 020 | | |
| │ ├ **0065** — Message type | 1 .. 1 | String | 010 | 1 .. 6 | 0065 |
| │ ├ **0052** — Message version number | 1 .. 1 | String | 020 | 1 .. 3 | 0052 |
| │ ├ **0054** — Message release number | 1 .. 1 | String | 030 | 1 .. 3 | 0054 |
| │ └ **0051** — Controlling agency | 1 .. 1 | String | 040 | 1 .. 2 | 0051 |

### Documentation

**Definition** Identification of the type, version etc. of the message being interchanged.

### Properties

**Identifier** S009

**Name** Message identifier

**Cardinality** min: 1 max: 1

### Syntax Type Related

**External Category** Composite Data Element

**Position** 020

### Leaf Elements

| Identifier/Name | Description/Notes/Code Values | Properties |
|---|---|---|
| **0065**<br>Message type | Code identifying a type of message and assigned by its controlling agency.<br><br>**Usage 1**<br>Type of message being transmitted.<br><br>**Selected Values**<br>**Code** IFTSTA | **Cardinality** min: 1 max: 1<br>**Primitive Type** String<br>**Length** min: 1 max: 6<br>**External Category** Data Element<br>**Data Type** an<br>**Position** 010<br><br>**Codelist Id** 0065<br>**Type System** UNEDIFACT<br>**Version Mode** Current<br>**Version** D.01C S3 |
| **0052**<br>Message version number | Version number of a message type.<br><br>**Usage 1**<br>If UNG/UNE is used, shall be identical in UNG and UNE. The representation of 0052 was specified as n..3 in version 1 of ISO 9735.<br><br>**Selected Values**<br>**Code** D | **Cardinality** min: 1 max: 1<br>**Primitive Type** String<br>**Length** min: 1 max: 3<br>**External Category** Data Element<br>**Data Type** an<br>**Position** 020<br><br>**Codelist Id** 0052<br>**Type System** UNEDIFACT<br>**Version Mode** Current<br>**Version** D.01C S3 |
| **0054**<br>Message release number | Release number within the current message type version number (0052).<br><br>**Usage 1**<br>The representation of 0054 was specified as n..3 in version 1 of ISO 9735. | **Cardinality** min: 1 max: 1<br>**Primitive Type** String<br>**Length** min: 1 max: 3<br>**External Category** Data Element<br>**Data Type** an<br>**Position** 030 |

| | | |
|---|---|---|
| | **Selected Values**<br>**Code** 01C<br>**Code** 96A | **Codelist Id** 0054<br>**Type System** UNEDIFACT<br>**Version Mode** Current<br>**Version** D.01C S3 |
| **0051**<br>Controlling agency | Code to identify the agency controlling the specification, maintenance and publication of the message type.<br><br>**Selected Values**<br>**Code** UN | **Cardinality** **min:** 1 **max:** 1<br>**Primitive Type** String<br>**Length** **min:** 1 **max:** 2<br>**External Category** Data Element<br>**Data Type** an<br>**Position** 040<br><br>**Codelist Id** 0051<br>**Type System** UNEDIFACT<br>**Version Mode** Current<br>**Version** D.01C S3 |

## 4.4 BGM — Beginning of message

### Structure

| Node | Card. | Prim.Type | Pos. | Length | Codelists |
|---|---|---|---|---|---|
| **IFTSTA** — International multimodal status report message | 1 .. 1 | | | | |
| ├ **BGM** — Beginning of message | 1 .. 1 | | 0020 | | |

### Documentation

**Definition** A segment indicating the beginning of a message and identifying the consignment for which status is being reported. Remark: None of the information in BGM is used in SAP LBN. Hence there is no validation of codes and identifiers transmitted in this segment

### Properties

**Identifier** BGM

**Name** Beginning of message

**Cardinality** min: 1 max: 1

### Syntax Type Related

**External Category** Segment

**Position** 0020

**Level** 2

### Notes

**Comment 1** None of the information in BGM is used in SAP LBN. Hence there is no validation of codes and identifiers transmitted in this segment.

**Example 1** BGM+7+7867541+9’