
Data Center	Integration Platform Host URL of SAP Business Network for Logistics
KSA	`https://api.logistics.sa30.business-network.cloud.sap/cxf/lbn/b2b/soap/v1`

5. Select the site information.
6. Choose the certificate and save the root and intermediate certificate to `*.cer` format.
7. From the `*.p7b` file (which you downloaded and saved in previous chapters), extract the root and intermediate `*.cer` files.

   In the example shown in the image below, these are the **DigiCert Globa Root G5** and **DigiCert Global CA G5** certificates. You can do this via the KeyStore Explorer tool (https://keystore-explorer.org/).



8. Add SAP Business Network for Logistics SSL certificates to the STRUST PSE.

For each of the certificates, perform the following steps:

1. Select your PSE.
2. Import the certificate.
3. Choose **Add to Certificate List**.
4. Choose **Save**.

Additional information is available in SAP Note 1473710 at: STRUST: How to Export/Import a PSE from/to STRUST.

Once you have added the certificates, you have to restart the Internet Communication Manager (ICM) services by performing the following steps:

1. Go to transaction SMICM.
2. Choose Administration.
3. Choose ICM.
4. Choose Exit Soft.
5. Choose Global.

Configuring Endpoints via SOA Manager

Launch the transaction SOAMANAGER and maintain the consumer service for these interfaces as follows:

Outbound interfaces from SAP S/4HANA to SAP Business Network for Logistics:

- LocationBulkReplicationRequest_Out

To do so, perform the following steps:

1. Go to the transaction SOAMANAGER.
2. Choose Web Service Configuration and search for the outbound interface. Select it and then enter edit mode.
3. On the Consumer Security tab, specify the authentication settings by selecting X.509 SSL Client Certificate and specifying the STRUST PSE.

   > **Note**
   >
   > You specify the SSL Client PSE from the setup in STRUST as outlined in the previous steps, which contains the private key for authentication in SAP Business Network for Logistics.

4. On the Messaging tab, specify the messaging settings according to the below sample setup:




5. On the Transport Settings tab, use the live SAP Business Network for Logistics URL based on your SAP Business Network for Logistics tenant's data center:

Host URLs by Data Center

Data Center	Integration Platform Host URL of SAP Business Network for Logistics

Data Center	Integration Platform Host URL of SAP Business Network for Logistics
EU	`https://api.logistics.eu.business-network.cloud.sap/cxf/lbn/b2b/soap/v1`
US	`https://api.logistics.us.business-network.cloud.sap/cxf/lbn/b2b/soap/v1`
KSA	`https://api.logistics.sa30.business-network.cloud.sap/cxf/lbn/b2b/soap/v1`



Creating a Connection

By creating a connection in the System Connections app, you can then specify the details required for authenticating inbound and outbound messages between SAP Business Network for Logistics and your SAP backend system. If you need to connect multiple backend systems, create a connection for each system.

Procedure

1. In the System Connections app, click Add in the Connections column.
2. In the New Connection dialog box, select a connection type from the list.

   The following connection types are available:

   - ABAP-based SAP system
   - Qualtrics
   - SAP Analytics Cloud
3. Enter the following information for the new connection.

   a. Connection ID: meaningful name of the connection

b. **System ID**: ID of the system you're connecting, for example, QW9.

> **Note**
>
> Specify the source system ID as it appears in your external system (such as SAP Transportation Management). The format must be specified exactly as it appears in the external system. For example, QM7_910.
>
> If you use another system ID or change the system ID afterwards, this can have severe consequences. Your processes might stop working.

> **Caution**
>
> If you use both the freight collaboration and global track and trace for tracking harmonization purposes, you must enter the system ID in the following format: *<System>_<Client ID>*. For example, QW9_170.

c. **Logical System ID**: logical system ID of the system you're connecting, for example, QW9CLNT170.

The **Logical System ID** field is only available to the ABAP-based SAP system connection type. This setting helps users using both the freight collaboration and global track and trace solutions avoid duplicated tracking records.

4. Click **Add**.

Related Information

Authenticating Inbound Messages to SAP Business Network for Logistics

Configuring Links to Business Documents in Source Systems

Context

If your business documents in the source systems are sent to SAP Business Network Global Track and Trace for tracking, you may need to switch between the two systems to view the information and perform necessary tasks. To facilitate the navigation, the in-app navigation is enabled so that you can go to the business document in the source systems directly from the fulfillment tracking apps with a single click. For this to work properly, you must configure document links first in the **System Connections** app.

Procedure

1. Launch the **System Connections** app and click **Add**.
2. In the **New Connection** dialog, enter the following data and click **Add**:
   - **Connection Type**: select "**ABAP-based SAP system or external systems**". You can create document links only for connections of the **ABAP-based SAP system or external systems** type.
   - **Connection ID**: enter any value.
   - **System ID**: enter any value.
   - **Logical System ID**: enter the logical system of the target tracked process, for example, "QW9CLNT170". You must guarantee the logical system is correct before you add document link information in later steps.

> **Note**
>
> To find the logical system, click the target tracked process type in the **Check Process and Events** app. Search for the target tracked process and get the information in the **Logical System** column.
>
> You can't create multiple connections with the same logical system ID. Doing so will cause navigation errors.

3. Select **Create Document Links** in the upper-right corner. This opens the **Configure Document Links** panel. Then select **Create**.

4. In the **Create Document Link** dialog box, enter the following data:

Field	Purpose	Example Value
Document Type	You can navigate to the following business documents in your source systems: • From the **Track Shipments** app, you can navigate to TM freight orders, TM freight bookings, TM freight units and Non-TM shipments. **Note** The freight orders and freight bookings in the TM, and the LE-TRA shipment are all processed and referred as "shipment" in the GTT system, so above business documents are all supported for navigation from the **Shipment Details** page of the **Track Shipments** app. • From the **Track PO Fulfillment** app, you can navigate to purchase orders. • From the **Track SO Fulfillment** app, you can navigate to sales orders. • From the **Monitor Inbound ASNs** app, you can navigate to inbound deliveries. • From the **Monitor Outbound**	• TM Freight Order • TM Freight Booking • TM Freight Unit • Non-TM Shipment • Purchase Order • Inbound Delivery • Outbound Delivery • Sales Order

Field	Purpose	Example Value
	Deliveries app, you can navigate to outbound deliveries.	
Base URL	Contains the protocol, host, domain, and port of the target system.	https://xxxx-xxxx.wdf.sap.corp
Path	Path to the app in the target system.	/sap/bc/ui5_ui5/ui2/ushell/shells/abap/FioriLaunchpad.html#FreightOrder-display For more about paths to different document types, see Recommended Path and Parameter Configurations.

5. Optional: Under **Parameters**, you can enter additional parameters and their related values. Multiple parameters can be added as a key-value pair. The key is always mandatory, but the value is not. This is meant for the dynamic parameters, such as the document ID, which will be determined in the runtime by the application. The parameters in the URL are used to pass information from SAP Business Network for Logistics to the sourcel system.

   ### ⚠ Caution

   It's flexible where to add parameters, but you must keep them all in one place. Either append all of them to the path or maintain them all in this section. If you append one parameter to the path, and add another parameter in this section, the link won't work. For more about parameter configurations of different document types, see Recommended Path and Parameter Configurations.

Example Parameter Name	Example Parameter Value
sap-language	EN
ID	{{trackingId}} **ℹ Note** This is a dynamic parameter and the value will be filled by the application in the runtime after you click the Navigate icon.

Results

If the model cache is turned on, it takes up to 15 minutes for document links to take effective after the configuration. Once they are effective, in the detail pages of the fullfimment tracking apps, you can click the Navigate icon on the top right corner to go to the corresponding source business documents in source systems.

Recommended Path and Parameter Configurations

Document links vary based on the type of document. As previously mentioned, you have the flexibility to add configuration parameters either by appending them to the path or maintaining them in the **Parameters** section.

To improve the efficiency and accuracy, we recommend the following path and parameter configurations for different document types. You can copy and paste these configurations as needed:

TM Freight Order

You can provide the path and parameters as follows:

- Path: /sap/bc/ui5_ui5/ui2/ushell/shells/abap/FioriLaunchpad.html#FreightOrder-display
- Parameters: You are recommended to maintain parameters in the Parameters section. For example:

Name	Value
ID	{{trackingId}}

TM Freight Booking

You can provide the path and parameters as follows:

- Path: /sap/bc/ui5_ui5/ui2/ushell/shells/abap/FioriLaunchpad.html#FreightBooking-display
- Parameters: You are recommended to maintain parameters in the Parameters section. For example:

Name	Value
ID	{{trackingId}}

TM Freight Unit

You can provide the path and parameters as follows:

- Path: /sap/bc/ui5_ui5/ui2/ushell/shells/abap/FioriLaunchpad.html#FreightUnit-display
- Parameters: You are recommended to maintain parameters in the Parameters section. For example:

Name	Value
ID	{{trackingId}}

Non-TM Shipment

For Non-TM shipments, we recommend you appending the parameters to the path. You can provide the path as follows:

- Path: /sap/bc/ui5_ui5/ui2/ushell/shells/abap/FioriLaunchpad.html#Shell-startGUI?sap-ui2-tcode=VT03N&sap-system=S4MENU&VTTK-TKNUM={{trackingId}}

Purchase Order

For purchase orders, we recommend you appending the parameters to the path. You can provide the path as follows:

- Path: /sap/bc/ui2/flp#PurchaseOrder-display?PurchaseOrder={{trackingId}}&uitype=advanced

Sales Order

For sales orders, we recommend you appending the parameters to the path. You can provide the path as follows:

- Path: /sap/bc/ui2/flp#SalesOrder-display?SalesOrder={{trackingId}}

Inbound Delivery

For inbound deliveries, we recommend you appending the parameters to the path. You can provide the path as follows:

- Path: /sap/bc/ui2/flp#InboundDelivery-displayInWebGUI?InboundDelivery={{trackingId}}

Outbound Delivery

For outbound deliveries, we recommend you appending the parameters to the path. You can provide the path as follows:

- Path: /sap/bc/ui2/flp#OutboundDelivery-displayInWebGUI?OutboundDelivery={{trackingId}}

Authenticating Inbound Messages to SAP Business Network for Logistics

To authenticate inbound messages to SAP Business Network for Logistics from your SAP backend system, complete the following steps in the System Connections app.

Prerequisites

> ⚠ **Caution**
> This configuration is only applicable to location replication, read service and write service.

You've acquired a client certificate that's signed by SAP or a third-party certification authority:

- You're recommended to use an SAP client certificate, which you can request from your Identity Authentication account on SAP BTP. The certificate is signed by SAP Passport Certification Authority. For more information, see Configuring a Certificate for API Authentication.
- Alternatively, you can use a client certificate that's signed by one of the following third-party certification authorities.

Third-party certification authorities

- AddTrust External CA Root
- Baltimore CyberTrust Root
- Certum CA
- DigiCert High Assurance EV Root CA
- DigiCert Global Root CA
- GeoTrust Global CA
- GeoTrust Primary Certification Authority - G3

- GlobalSign
- GlobalSign Root CA
- Go Daddy Class 2 Certification Authority
- Go Daddy Root Certificate Authority - G2
- Entrust Root Certification Authority
- Entrust.net Certification Authority (2048)
- Entrust Root Certification Authority - G2
- Equifax Secure Certificate Authority
- QuoVadis Root CA 2
- TC TrustCenter Class 2 CA II
- SwissSign Gold CA - G2
- SwissSign Platinum CA - G2
- SwissSign Silver CA - G2
- Thawte Primary Root CA
- Thawte Primary Root CA - G3
- VeriSign Class 1 Public Primary Certification Authority - G3
- VeriSign Class 3 Public Primary Certification Authority
- VeriSign Class 3 Public Primary Certification Authority - G5
- VeriSign Universal Root Certification Authority

Note

The System Connections app only supports CER format certificate files. If you have a certificate in a different format, you must convert it to a CER format file.

Context

When you have a client certificate, complete the following steps to authenticate inbound messages to SAP Business Network for Logistics.

Procedure

1. In the **System Connections** app, select the connection and on the **Inbound to Network** tab, click **Add**.
2. In the **Add Certificate** dialog, enter a meaningful name for the certificate details, and upload the client certificate.
    a. Note, you can use a certificate for only one connection.
    b. Make sure you upload the same client certificate to your SAP backend system. This step establishes trust between the systems.
3. When the certificate expires, you need to get a new one and repeat these steps to upload it.

To receive notifications about certificate expiration, subscribe to the system notification service. For more information, see Subscribing to System Notifications.

Activating the Connection

After configuring and authenticating both inbound and outbound communication, you can activate the connection.

Procedure

1. To activate the connection, select the connection in the **Connections** column and choose **Activate Connections**.

Inbound Status Information

Status	Description
New	You have created the connection but not yet added a certificate.
Active	You have activated the connection.
Inactive	The certificate has expired or you have deactivated the connection.

2. Select the relevant options and choose **Save**.

Related Information

System Connections (Solution Owner)

Deactivating the Connection

You can deactivate an active connection.

Context

To deactivate an active connection, proceed as follows:

Procedure

1. To deactivate an ABAP-based connection, select the connection and choose **Activate Connections**.
2. Select if you want to deactivate an inbound connection or an outbound connection.
3. Choose **Save**.
4. The connection is set to **Inactive**.

Deleting the Connection

You can delete a connection.

Context