To delete a connection, proceed as follows:

Procedure

1. Before you can delete an ABAP-based connection, you must first delete the certificates within the inbound connection manually. Then choose **Delete Connection**.

   SAP Business Network for Logistics will show a warning about the impact on existing documents. The connectivity will be permanently terminated once you delete an ABAP-based connection. There might be some existing documents in the network created using the connection. After deletion, this connection will be lost forever.

2. To delete a connection of type **Qualtrics**, first deactivate the connection, then choose **Delete Connection**.
3. To delete a connection of type **SAP Analytics Cloud** (SAC), choose **Delete**.

Manage Alternate IDs (Solution Owner)

You can maintain alternate identifiers of your other accounts in the network. These identifiers shall be used in specific integration scenarios or in specific transaction flows in the network.

Additionally, the LBN ID of your tenant can be seen above the **Manage Alternate IDs** table as a read-only field.

SAP Business Network for Logistics supports the following alternate identifiers (alternate IDs):

- DUNS ID (Data Universal Numbering System ID)
- SCAC (Standard Carrier Alpha Code)
- Registration Number
- USDOT (US Department of Transportation)
- MC Number (Motor Carrier Number)
- Others
- GLN (Global Location Number)
- Technical User

To create your own alternate IDs, proceed as follows:

1. Choose **Manage Alternate IDs**.
2. Select an alternate ID type from the dropdown menu and type in the required value.
3. Choose **OK**.

You can also delete or change existing entries.

Configure Partner Connections

You can use the **Configure Partner Connections** app to establish a B2B connection to the external systems of your business partners. Using this configuration, SAP Business Network for Logistics can directly send documents to your partner's external systems.

Prerequisites

SAP Business Network for Logistics must support the desired business partner for B2B connectivity. This means that your company must agree on B2B integration with your data contributor.

Then, you must invite your network partner to join SAP Business Network for Logistics using the **Invite Business Partners** app. Only then will the network partner be visible in the **Configure Partner Connections** app.

The process of using the **Configure Partner Connections** app to create a connection and to authenticate messages includes the following steps:

1. Manage Credential Details
2. Create Partner Connection

Manage Credential Details

Context

The **Manage Credential Details** view is a secure storage for you to maintain all the credentials that you receive from your business partner or network partner with whom you would like to enable B2B communication. A network partner can consist of a network of business partners (in this case of data contributors) that provides services like tracking.

SAP Business Network for Logistics supports the following credential types:

- Basic
- OAuth 2.0
- API Key
- project44

  For more information, see the Configuration and Application Guide for project44 add-ons.

Procedure

1. In the **Configure Partner Connections** app, choose **Manage Credential Details**.
2. Select the tab with the credential type that you want to use for maintaining the credential details.
3. Choose **Add** and complete the dialog.
4. (Optional): To change the credential details, select the row and choose **Edit**.

Create Partner Connection

Context

Using the **Configure Partner Connections** app, you now need to map the connection details with your business partners and establish a B2B connection.

Procedure

1. In the **Configure Partner Connections** app, choose **Create**.
2. Provide the following information:

Field	Explanation	Usage (as maintained in Manage Credential Details)
Business Partner ID Type*	ID type of your individual connected business partner or of all connected business partners. A business partner is an entity with which the LBN customer does business (freight contracting, and order execution). You can maintain the following ID types: • LBN ID • SCAC • P44_EU • Motor Carrier Number • US DOT • GLN • VAT • SAPBPID – SAP Business Partner Number	You can choose between general ID types (Any LBN ID or Any Alternate ID) and specific ID types (such as LBN ID, SCAC, or GLN) for a connection with your business partners. Any LBN ID applies this setting to all business partners that are onboarded in the network and connected to your tenant. You can configure alternate business partner ID types to initiate tracking for your shipments. Onboarding of these business partners to SAP Business Network for Logistics is not required.
Business Partner ID Value*	Unique identifier representing the business partner.	Based on the business partner ID type, you choose the business partner ID value: • If you choose LBN ID, the field name is Business Partner (LBN ID). • If you choose a different ID than LBN ID, the field name is Business Partner ID Value.
Network Partner (LBN ID)	LBN ID of your network partner. A network partner is an entity which does data transfer/integration to business partners. Network partners will have many business partners in their network and have built integrations to business partner systems.	You must provide this information if you receive the data via a network partner.
Service*	A service is defined based on the combination of the following information coming from a solution owner: • *Tracking type*: Specifies if the tracking is based on a device or vehicle (such as the vehicle's license plate) or based on a shipment indicator (such as a bill of lading) • *Transportation mode* (such as *Road*) • *Scenario* (such as tracking)	SAP Business Network for Logistics supports the transportation modes *Road* and *Ocean* with the following services: • Resource Road Tracking FTL (Removed) • Shipment Road Tracking LTL • Shipment Tracking All • Shipment Road Tracking FTL • Resource Road Tracking LTL (Removed) • Shipment Ocean Tracking FCL

Field	Explanation	Usage (as maintained in Manage Credential Details)
	• *Shipping type* (such as LTL - less than truck load, or FTL - full truck load)	• Resource Ocean Tracking FCL (Removed) • Shipment Ocean Tracking LCL • Resource Ocean Tracking LCL (Removed) • Resource Tracking All (Removed) • Shipment Air Tracking All • Shipment Tracking Parcel • Resource Tracking Parcel (Removed) • Shipment Rail Tracking All **⚠ Caution** Resource tracking related services have been removed on August 17th, 2024. You can use the shipment tracking related services instead. **ℹ Note** Only those services that are supported by your business partner will be shown in the dropdown box.
Business Partner Credential	Credential provided to you by your business partner, which is maintained in the Manage Credential Details view.	You must maintain this field if you communicate directly with your business partner's system.
Network Partner Credential	Credential provided to you by your network partner, which is maintained in the Manage Credential Details view.	You must provide this information if you are communicating with your business partner via a network partner.

* mandatory fields

You can either save or save and activate your changes.

3. (Optional): Provide the following information under Custom Headers:

Fields	Explanation	Usage (as maintained in Manage Credential Details)
Key Value	Additional information provided by you to your business partners or network partners as key value pairs. It will be sent as header parameters in a Consumer API. **ℹ Note** This feature is only available for SAP Business Network for Logistics standard	Depending on your scenario, you can agree with your business partners or network partners to provide additional information. In SAP Business Network Global Track and Trace, the LBN ID of your business partner is only mapped with one alternate ID, which is used when sending a tracking request via a Consumer API. If the business partner has

Fields	Explanation	Usage (as maintained in Manage Credential Details)
	APIs and not for custom API integrations.	multiple alternate IDs and requests to use another one, then you can provide the following key value pairs to update the alternate ID in a Consumer API: • Key: `LBN_CUSTOM_CARRIER_ALT_ID` • Value: target alternate ID. It is of the highest priority and will overwrite the current alternate ID used in the Consumer API.

4. Save your entries.

Use Tracking Services Through project44 Unified API

Context

You can use the following tracking services through the project44 unified API:

- ocean tracking
- air tracking
- parcel tracking
- road LTL tracking
- road FTL tracking.

Before you follow the procedures below, you should first choose **Project44, Inc. – Unified** as your business partner in the **Discover Business Partners** app and request a connection. After project44 confirms the connection, a project44 account is created and credentials are issued to you by email from project44.

Procedure

1. In the **Configure Partner Connections** app, choose **Manage Credential Details**.
2. Select the **OAuth 2.0** tab.
3. Choose **Add** and complete the dialog:
    - Name
    - Credential Type: **Network Partner Credential**
    - Grant Type: **Client Credentials**
    - Authentication URL, Client ID, Client Secret: Refer to your email from project44.
    - Client Authentication: **Send as Body Parameter**
    - Scope Included: No
4. Back to the **Partner Connections** worklist page, choose **Create**.

5. Complete the dialog:
    - Business Partner ID Type:
        - For ocean, parcel, road LTL and road LTL tracking, choose **SCAC** or **LBN ID**.

          > **Note**
          >
          > For road FTL tracking, you can also choose other Business Partner ID types listed in Create Partner Connection, depending on the requirements of your carrier or visibility providers.

        - For air tracking, choose **Any Alternate ID**.
    - Network Partner (LBN ID): **Project44, Inc. – Unified**
    - Service:
        - For ocean tracking, choose **Shipment Ocean Tracking FCL** or **Shipment Ocean Tracking LCL**.
        - For air tracking, choose **Shipment Air Tracking All**.
        - For parcel tracking, choose **Shipment Tracking Parcel**.
        - For road LTL tracking, choose **Shipment Road Tracking LTL**.
        - For road FTL tracking, choose **Shipment Road Tracking FTL**.
    - Business Partner Credential: Ignore this field.
    - Network Partner Credential: Choose the credential that you just configured.
    - Status: Active

Enable EDIFACT IFTSTA for Event Tracking

The message type EDIFACT IFTSTA supports both inquiries of shipment status and responses for consignment status, making it suitable for use in both inbound and outbound connections. This message type can be leveraged to track the following business events in the global track and trace solution:

Code	Code Description
DEPARTURE	Departure
UNLOAD_END	Unloading End
ARRIV_DEST	Arrival
OUT_FOR_DELIVERY	Out for Delivery
LOAD_END	Loading End
DELAYED	Delay

Configuration

The GLNID is crucial for identifying both parties in IFTSTA communication. To set up EDIFACT integration for the IFTSTA message type, this identifier for both parties must be consistently maintained in the following apps:

- Configure Partner Connections

- System Connections

Maintaining GLNIDs as Customer Headers in Configure Partner Connections

Solution owners must maintain their GLNID and that of their data contributors. Use customer headers in the **Configure Partner Connections** app for this purpose.

To maintain GLNIDs in **Configure Partner Connections**, follow these steps:

1. Open the partner connection in which you want to enable the EDIFACT IFTSTA message type.
2. Scroll down to the **Custom Headers** section and click the plus sign.
3. Enter `SHIPPER_GLNID` as the key and enter your GLNID as the value.
4. Enter `CARRIER_GLNID` as the key and enter the GLNID of the data contributor you work with as the value.
5. Save your changes.
6. Repeat these steps if you want to enable EDIFACT IFTSTA in other partner connections.

Maintaining GLNIDs as Alternative Identifiers in System Connections

Both solution owners and data contributors must maintain their GLNID in the **System Connections** app.

To maintain GLNIDs in **System Connections**, follow these steps:

1. Choose **Manage Alternate IDs**.
2. Select **GLN** from the dropdown menu and enter your GLNID.
3. Choose **OK**.

Limitations

- In an inbound connection, if RFF+ZZ8 (stopId) is not provided, the stopId is converted to an empty string, instead of NULL.
- If an EDI file contains more than one event types, multiple messages with the same message number are sent to the global track and trace solution.
- The address name field of a location is not supported in an IFTSTA message.
- UNLOCODE and IATACODE are not supported in an IFTSTA message.
- A delay event can only refer to an arrival or departure event, and no event reason code is available in the delay event.

More information

You can refer your data contributors to this implementation guide for B2B IFTSTA integration:

https://help.sap.com/doc/df3dd1c3edd44250b0c27c9c71159459/LBN/en-US/SAP_LBN_EDI_HowToGuide_GTT.pdf

For detailed information about the IFTSTA messages used in the global track and trace solution, see the following Message Implementation Guide:

https://help.sap.com/doc/9cc21c6fda37437eaee763d114d5bbfe/LBN/en-US/SAP_LBN_IFTSTA_D01C_GTT.pdf

Manage Notification Templates

The Manage Notification Templates app enables you to create and maintain email notification templates that you can use to notify your business partner on the occurrence of an event.

This app enables you to create a customized notification template and maintain language specific notification email texts for this template. You can also specify the recipients of these emails in these templates.

Creation of a Notification Template

To create a notification template, perform the following:

1. Choose **Create**.

   The **Create Notification Template** dialog box appears.

2. Enter a template ID and template description.

3. Select the **Global Track and Trace** application and choose **OK**.

   The system creates the template.

When you select this template, you can view and maintain the email templates in different languages. You can use the **Delete** button to delete one or more templates. Note that you must set one of the templates as default and the default template cannot be deleted.

To maintain email templates in different languages you must select the notification template, perform the following:

1. Choose **Add**.

   The **Add Language** dialog box appears.

2. Select a language from the drop-down menu.

3. Enter a value from the **Insert Placeholder** button.

   Note that when you choose this button, the system displays a list of placeholders. Choose the appropriate placeholder for the email contacts.

4. Choose **OK**.

   A new window appears.

5. Enter an email subject and email body in the respective fields.

   Note that you can also enter a value from the **Insert Placeholder** button. When you choose this button, the system displays a list of placeholders. Choose the appropriate placeholder.

6. Choose **Save**.

   The system saves the language specific email template text.

Similarly, you can add multiple language email template texts to a template.

Note that the system sets the first language template that you create as the default template. Once you create two or more language templates, you select a template and use the **Set As Default** button to choose a different default template.

Manage Locations

You can use the Manage Locations app to manage location master data either manually replicated from another system or created from scratch using the app. Location master data can then be consumed by other apps in SAP Business Network Global Track and Trace.

You can set up a location replication using the Data Replication Framework (DRF) in the SAP S4/HANA source system. For more information, see Configurations for Location Replication.

Location master data consists of not only the address information, but also the business purpose of a location. Additionally, the master data of a location can include one or more alternative IDs so that the location becomes cross-platform identifiable.

The main features of this app include:

- View a location
- Create a location
- Upload locations
- Edit a location

ℹ Note

- The Manage Locations app implements all security features and data protection-relevant functions documented in the "Security and Data Protection and Privacy" section of the *Administration Guide*.
- A location master data record enters the blocking period if it has not been accessed for three consecutive years. The blocking period lasts for another three years, during which only audit specialists can access the record. The record will then be automatically deleted when the end of the blocking period is reached.

Viewing a Location

To view a location, proceed as follows:

1. By default, you can use the following fields to filter locations:
    - External ID
    - Source System
    - Object Type
    - Description
    - Country/Region
    - City
    - Data Processing Status
    - Additional Information

    You can also adjust the filter bar by chooosing **Adapt Filters**.
2. Click the location from the filter results to open the details page.

The detail view of the location consists of a header and other sections.

Header

The Header section displays the address information.

General

This section displays the basic information of a location. This includes the business purposes, the longitude/latitude coordinates, and the revision history.

Geographical Coordinates and Map

This section displays the geographical coordinates of the location. It also identifies the location on the map.

Alternative Location IDs

This section displays a list of type-specific alternative IDs of the location.

Contact Information

This section displays the contact information related to the location.

Additional Information

This section displays the contact information related to the location.

More Information

You can do the following with the filter bar:

- Specify filters to narrow down the worklists and search for locations.
- Add or remove the filters displayed on the filter bar by choosing **Adapt Filters**.
- Save the current filter settings as a view and apply it later.

  After you specified filters (and pressed Enter) and/or adapted filter display, the current view name shown in the upper-left corner displays a * sign, indicating the view has been changed. Save the view by either of the following:

  - Click the view name to open the **My Views** box and choose **Save** or **Save As**.
  - In the **Adapt Filters** dialog box, choose **Save**.

  Next time when you want to apply the view, just select the view name in the **My Views** box.

  Note

  The default **Standard** view cannot be changed.

Creating a Location

To create a location, proceed as follows:

1. Click **Create** on the upper-right corner of the **Locations** table. The **Create New Location** page opens.