

Table of Contents

CCIE Routing & Switching

- ► Unit 1: Preparation
- **▼** Unit 2: Switching

Static MAC Address Table Entry

Cisco Switch Virtualization

Introduction to VLANs (Virtual LAN)

How to configure VLANs

802.1Q Encapsulation

How to configure a trunk between switches

Cisco DTP (Dynamic Trunking Protocol) Negotiation

802.1Q Tunneling (Q-in-Q)

Etherchannel over 802.1Q Tunneling

How to change the Native VLAN

VTP (VLAN Trunking Protocol)

VTP Version 3

Protected Port

Private VLANs (PVLAN)

Introduction to Spanning-Tree

Spanning-Tree Cost Calculation

PVST (Per VLAN Spanning Tree)

Spanning-Tree Port States

Spanning-Tree TCN (Topology Change Notification)

Spanning-Tree Portfast

Spanning-Tree UplinkFast

Spanning-Tree Backbone Fast

Rapid Spanning-Tree

Rapid Spanning-Tree Configuration

MST (Multiple Spanning-Tree)

Spanning-Tree BPDUGuard

Spanning-Tree BPDUFilter

Spanning-Tree RootGuard

Spanning-Tree LoopGuard and UDLD

FlexLinks

Introduction to Etherchannel

Layer 3 Etherchannel

Cisco IOS SPAN and RSPAN

- Unit 3: IP Routing
- ▶ Unit 4: RIP
- Unit 5: EIGRP
- Unit 6: OSPF
- ▶ Unit 7: BGP
- Unit 8: Multicast
- ▶ Unit 9: IPv6
- ▶ Unit 10: Quality of Service
- ► Unit 11: Security
- Unit 12: System Management
- Unit 13: Network Services
- ▶ Unit 14: MPLS

You are here: Home » Cisco » CCIE Routing & Switching

FlexLinks
















When you have a redundant switched topology, spanning-tree will block some of the interfactor create a loop-free topology. Another method to deal with redundant topologies is by using flexlinks. When you configure **FlexLinks** you'll have an **active** and **standby** interface. Here's an example:



In the topology above spanning-tree would normally block one of the interfaces to create that loop-free topology. This time however we are going to use flexlinks. What happens is that one interface will be the active link and the other one will be a backup link. The backup link is down and only comes up when the active link fails.

I can configure this on SwitchC:

- Fa0/14 will be the active interface.
- Fa0/16 will be the backup interface (this one is blocked!).

When you configure interfaces as FlexLinks they will **not send BPDUs**. There is no way to detect loops because **we don't run spanning-tree** on them. Whenever our active interface fails the backup interface will take over.

Let's look at the configuration...

Configuration

I will configure SwitchC so that interface Fa0/14 is the active interface and Fa0/16 becomes a backup:

```
SwitchC(config)#interface fa0/14
SwitchC(config-if)#switchport backup interface fa0/16
```

This is how we make interface fa0/16 a backup of interface fa0/14.

```
SwitchC#
%SPANTREE-6-PORTDEL_ALL_VLANS: FastEthernet0/14 deleted from all Vlans
%SPANTREE-6-PORTDEL_ALL_VLANS: FastEthernet0/16 deleted from all Vlans
```

You can see spanning-tree is being disabled for these interfaces.

```
SwitchC#show interfaces switchport backup

Switch Backup Interface Pairs:

Active Interface Backup Interface State

FastEthernet0/14 FastEthernet0/16 Active Up/Backup Standby
```

Verify our configuration with the show interfaces switchport backup command. That's all there is to it. It's an interesting solution because we don't need spanning-tree anymore. After all only one interface is active at any moment. Let's see what happens when I disable the active interface:

```
SwitchC(config)#interface f0/14
SwitchC(config-if)#shutdown
```



Take a look below:

```
SwitchC#show interfaces switchport backup
```

Switch Backup Interface Pairs:

Active Interface	Backup Interface	State
FastEthernet0/14	FastEthernet0/16	Active Down/Backup Up

You can see that Fa0/16 has taken over. That's all there is to it!

Rate this Lesson:









Home > Forums > FlexLinks

This topic contains 9 replies, has 6 voices, and was last updated by Jie C 2 weeks ago.

Viewing 9 posts - 1 through 9 (of 9 total)

- Author
 - Posts | Subscribe
- August 31, 2015 at 01:50 #11315 Reply



Thomas K Participant



Rene,

Hi. In a normal working state, what does the interface status look like if one were to say issue a "show interface status" or "show interface F0/16" in this case?

Many thanks.

Thomas

August 31, 2015 at 10:56 #11316 Reply



Rene Molenaar Keymaster Hi Thomas,

It should show something like "standby mode" line protocol down instead of up/up.

Rene

October 13, 2015 at 04:21 #18824 Reply



Frades
Participant
is there any reason to run flexlink rather than STP?

October 13, 2015 at 16:59 #18832 Reply



Rene Molenaar Keymaster I think the only advantage is the convergence time, flexlinks are faster than RSTP.

February 16, 2016 at 06:54 #22158 Reply



Ranjana G Participant Hi Rene,



Can you explain what if failed link get backup, will it automatically switch over to active link.?

February 17, 2016 at 14:59 #22182 Reply



Rene Molenaar Keymaster Hi Ranjana,

Yes it will switch back to the active link.

Rene

May 26, 2016 at 16:05 #24513 Reply



Mohammad Hasanuz Z Participant Hi Rene,

ANY Ethernet Frame will not send to Backup link if receive then discarded, right??

Flexlink can work with Many link ??

br// zaman

June 1, 2016 at 13:28 #24659 Reply



Rene Molenaar Keymaster Hi Zaman,

The backup link is not used at all...unless the primary link fails. One flexlink has 1 primary and 1 backup link, you can configure multiple flexlink pairs though...the maximum number deper on the platform.

Rene

June 7, 2016 at 16:51 #24733 Reply



Jie C Participant Hei Rene,

Cisco says something else:

If port 1 goes down, port 2 comes up and starts forwarding traffic to switch C. When port 1 comes back up, it goes into standby mode and does not forward traffic; port 2 continues forwarding traffic.

But I Strongly agree with you! because i have done it on ME3400 live with customer:

When it was nothing connected to Gig 0/2 on ME3400:

GigabitEthernet0/1 GigabitEthernet0/2 Active Up/Backup Down

When he connected the lan cabel to Gig 0/2:

GigabitEthernet0/1 GigabitEthernet0/2 Active Up/Backup Standby

when he took Gig 0/1 out:

GigabitEthernet0/1 GigabitEthernet0/2 Active Down/Backup Up

when he connected Gig 0/1 back, For 5 sec the main interface was in standby mode:
GigabitEthernet0/1 GigabitEthernet0/2 Active Standby/Backup Up

Gig 0/1 took control:

GigabitEthernet0/1 GigabitEthernet0/2 Active Up/Backup Standby

Regards,

Jie

Author

Posts

Viewing 9 posts - 1 through 9 (of 9 total) Reply To: FlexLinks





Please put code in between `backticks` or use the CODE button.

To place inline images, please use any image share service (such as TinyPic or Imgur) and use the IMG button!

■ Notify me of follow-up replies via email

Maximum file size allowed is 2048 KB.

Attachments:

Выберите файл Файл не выбран

Add another file

Submit

About NetworkLessons.com



Hello There! I'm René Molenaar (CCIE #41726), Your Personal Instructor of Networklessons.com. I'd like to teach you everything about Cisco, Wireless and Security. I am here to Help You Master Networking!

Read my story

Social Fans









Highest Rated Lessons

MPLS Layer 3 VPN Configuration



VRF Lite Configuration on Cisco IOS

☆ ☆ ☆ ☆ ☆ (23 votes)

Cisco Portfast Configuration



IPv6 Address Types



EIGRP Stub Explained



New Lessons

Introduction to Cisco IOS XE

ERSPAN Configuration on Cisco IOS XE

IGMP Filter

IGMP Snooping without Router

Cisco Group Management Protocol (CGMP)

Disclaimer

Privacy Policy

Support

FlexLinks written by Rene Molenaar average rating 5/5 - 6 user ratings

