

IceWall SSO

Version 10.0

Standard HTML Customization Guide of Domain Gateway Option for UNIX

August 2010

Printed in Japan

HP Part No. B1544-97015

Rev.111011 A

Notice

The information contained in this document is subject to change without notice.

Meticulous care has been taken in the preparation of this document, however, if a questionable or erroneous item, or an omission of content is found, please contact us.

Hewlett-Packard shall not be liable for errors contained herein or for incidental or consequential damage in connection with the furnishing, performance or use of this document.

The copyright of this document is assigned to Hewlett-Packard Development Company, L.P. No part of this document may be photocopied or reproduced without prior written consent by Hewlett-Packard.

This manual and media, such as the CD-ROM supplied as a part of the product's package, are only to be used with this product.

IceWall is a trademark of Hewlett-Packard.

Adobe is a trademark of Adobe Systems Incorporated in the United States and/or other countries.

Intel, the Intel logo, Intel. Leap ahead., Intel. Leap ahead. logo, Itanium and Itanium Inside are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

Microsoft and Windows are trademarks or registered trademarks of Microsoft Corporation in the United States and other countries.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

- Table of Contents -

T	int	roduction	1
	1.1	Version designations in the text	1
	1.2	List of HTML Files Provided by the Domain Gateway Option 10.0	1
	1.3	Notice	2
	1.4	Image files	3
	1.5	Integrated Windows Authentication (automatic login) JavaScript file 10.0	3
	1.	5.1 Configuring the Integrated Windows Authentication (automatic login) JavaScript file	8
	1.	5.2 Using the Integrated Windows Authentication (automatic login) JavaScript file	9
	1.	5.3 Notes on using the Integrated Windows Authentication (Automatic Login) JavaScript file	10
	1.6	Conversion of Special Keywords	10
2	Des	scription of HTML	12
	2.1	Login page (login.html) 10.0	12
	2.2	Ticket Authentication Login page (login_tkt.html) ①	15
	2.3	Forced Login page (login_force_tkt.html)	18
	2.4	Permission Error page at Authentication Execution (login_addr_error.html) 10.0	21
	2.5	User ID Error page (login_userid_error.html) (10.0)	
	2.6	Ticket Validation Error page (login_tkt_error.html) (10.0)	
	2.7	Initial Authentication Error page (login_cert_error.html) 10.0	
	2.8	Account Lock Error page (login_lock_error.html) 10.0	
	2.9	No Group Error page (login_group_error.html) 10.0	34
	2.10	Login Stop Error page (login_stop.html) 10.0	37
	2.11	Maximum Login Count Error page (login_limit_error.html)	40
	2.12	Logout page (logout.html) 10.0	42
	2.13	System Error page (system_error.html)	44
	2.14	Authentication Module Down Error page (system_certd_error.html)	46
	2.15	Authentication DB Down Error page (system_ldap_error.html)	48
	2.16	Authentication Module Receive Timeout Error page (system_timeout_certd.html)	50
	2.17	Database Connection Busy Error page (system_busy_database.html) 10.0	53
	2.18	User-Defined Error page 1 (usr_ext1.html)	55
	2.19	User-Defined Error page 2 (usr_ext2.html)	57
	2.20	User-Defined Error page 3 (usr_ext3.html)	59

1 Introduction

This guide provides information on the restrictions required for customizing HTML pages used by the IceWall SSO Domain Gateway Option for UNIX (hereinafter referred to as "Domain Gateway Option").

The HTML files described in this document are the standard HTML files provided with the Domain Gateway Option.

1.1 Version designations in the text

The table below gives the meanings of the version designations added to the description.

Designation	Meaning
10.0	An item added with the version enclosed in the square. In this case, the designation indicates the item was added with 10.0.
10.0	An item where the specification was changed or the function was enhanced with the version enclosed in the oval. In this case, the designation indicates a specification change or function enhancement with 10.0.

1.2 List of HTML Files Provided by the Domain Gateway Option 10.0

Page name	File name
Login page	login.html
Ticket Authentication Login page	login_tkt.html
Forced Login page	login_force_tkt.html
Authentication Execution Permission Error page	login_addr_error.html
User ID Error page	login_userid_error.html
Ticket Verification Error page	login_tkt_error.html
Initial Authentication Error page	login_cert_error.html
Account Lock Error page	login_lock_error.html
No Group Error page	login_group_error.html
Login Stop Error page	login_stop.html
Maximum Login Count Error page	login_limit_error.html
Logout page 10.0	logout.html
System Error page	system_error.html
Authentication Module Down Error page	system_certd_error.html
Authentication DB Down Error page	system_ldap_error.html
Authentication Module Receive Timeout Error page	system_timeout_certd.html
Database Connection Busy Error page 10.0	system_busy_database.html
User-Defined Error page 1	usr_ext1.html

Page name	File name
User-Defined Error page 2	usr_ext2.html
User-Defined Error page 3	usr_ext3.html

^{*} These files are stored in the /opt/icewall-sso/dfw/dghtml directory.

1.3 Notice

The following describes each of the HTML files provided by the Domain Gateway Option for the initial configuration screens.

Reference information for each HTML file consists of a screen image, the HTML source code, and a description.

The style sheet definition given below is included within the <HEAD> tags for each HTML file, but the definition is omitted from the source code sections of this document.

```
<style type="text/css">
<!--
BODY, TD {
  font-family: Verdana, Arial, Helvetica, Sans-serif;
  font-size: 12px;
a:hover {
  color: #ff3300;
  text-decoration: underline;
.title {
  font-size: 18px;
  font-family: Verdana, Arial, Helvetica, Sans-serif;
.sub-title {
  font-size: 16px;
  font-family: Verdana, Arial, Helvetica, Sans-serif;
  line-height: 18px;
.sub-title2 {
  font-size: 14px;
  font-family: Verdana, Arial, Helvetica, Sans-serif;
.footer {
  font-size: 11px;
  font-family: Verdana, Arial, Helvetica, Sans-serif;
</style>
```

1.4 Image files

Some image files are used in the standard HTML pages. The following image files are used

File name	Intended use
arrow.gif	The arrow symbol indicating a link to the relogin page
curve_b.gif	The rounded corner at the top left of a dialog box (blue) within a page
curve_r.gif	The rounded corner at the top left of a dialog box (red) within a page
error.gif	"ERROR" message displayed when an error occurs
footer.gif	The company name at the bottom of the page
header.gif	The product name at the top of the page
title_b.gif	The product name in a dialog box (blue) within a page
title_r.gif	The product name in a dialog box (red) within a page

^{*} These files are stored in the /opt/icewall-sso/dfw/dghtml/image directory.

1.5 Integrated Windows Authentication (automatic login) JavaScript file 10.0

The Integrated Windows Authentication (automatic login) function is added with this version to allow a user who has once logged into IceWall SSO via Integrated Windows Authentication to automatically log in without operating the Login screen from the next time.

This function is embedded as JavaScript in the Login page (login.html) and adds a "Integrated Windows Authentication (automatic login) cookie" to JavaScript when the user logs in via Integrated Windows Authentication.

From the next login, JavaScript checks whether or not the "Integrated Windows Authentication (automatic login) cookie" exists, and if the cookie exists, it allows the user to automatically log in without showing the Login page*. If the cookie does not exist, JavaScript shows the Login page.

The following JavaScript files are used for the Integrated Windows Authentication (automatic login).

File name	Intended use
script.js	For Integrated Windows Authentication (automatic login):

^{*} This file is stored in the /opt/icewall-sso/dfw/dghtml/js directory.

^{*} The Login page may be shown temporarily in some cases.

```
// $Workfile: script.js $ $Revision: 7 $ $Date: 09/04/02 13:06 $
// DGFW automatic login script
var AUTOLOGINCOOKIE DFW = "autologin fw";
var AUTOLOGINCOOKIE_DGFW = null;
var SETCOOKIEPATH_DFW = "/fw/";
var SETCOOKIEPATH_DGFW = "/nt/";
// Automatic login judgment function
// Performs automatic login when the cookie exists,
// and shows the normal Login screen when it does not exist.
function autoLoadLogin() {
  var cookie_fw = null;
  var cookie nt = null;
  // Obtains the automatic login cookie
  cookie_fw = getAutoLoginCookie_DFW();
  cookie_nt = getAutoLoginCookie_DGFW();
  if ( cookie_fw != null | | cookie_nt != null ) {
    // Click the link to DGFW when when the cookie exists.
    document.getElementById("winauth").click();\\
// Element search function
// Obtains the name specified by elementName and
// value specified by elementValue.
function\ find Element (element Name, element Value)
  var element = null;
  element = document.getElementById(elementName);
  if( element != null ){
    return element.getAttribute(elementValue);
  } else {
    return null;
  }}
// Check for Login page cookie
// Adds a cookie if the checkbox for
// adding it is checked.
function setCookieChk()
  var chk = null;
```

```
chk = findElement("autologinbox","checked");
  if( chk != null && chk == true ){
    setAutoLoginCookie();
// Cookie addition function
// Issues the automatic login cookie effective for 30 days.
function setAutoLoginCookie()
  var cookieName1 = null;
  var cookieName2 = null;
  var cookiePath1 = null;
  var cookiePath2 = null;
  var cookieValue = null;
  var exptime = null;
  var expire = null;
  cookieName1 = AUTOLOGINCOOKIE_DFW;
  cookieName2 = AUTOLOGINCOOKIE_DGFW;
  cookiePath1 = SETCOOKIEPATH_DFW;
  cookiePath2 = SETCOOKIEPATH DGFW;
  cookieValue = "on";
  exptime = new Date();
  exptime.setTime(exptime.getTime() + 30*24*60*60*1000);
  expire = exptime.toGMTString();
  if( cookieName1 != null && cookiePath1 != null ){
   document.cookie = cookieName1 + "=" + cookieValue + "; expires=" + expire + "; path="
+ cookiePath1 + ";";
  if( cookieName2 != null && cookiePath2 != null ){
   document.cookie = cookieName2 + "=" + cookieValue + "; expires=" + expire + "; path="
+ cookiePath2 + ";";
  }
// Cookie acquisition function
// Obtains the automatic login cookie.
function getAutoLoginCookie_DFW()
  var cookieIndex;
 var cookieName = null;
  var startpt;
  cookieName = AUTOLOGINCOOKIE_DFW;
```

```
if( cookieName != null ){
    cookieIndex = document.cookie + ";";
    cookieName = cookieName + "=";
    startpt = cookieIndex.indexOf(cookieName);
    if( startpt != -1 ){
       return cookieName;
    } else {
       return null;
  } else {
    return null;
// Cookie acquisition function
// Obtains the automatic login cookie.
function getAutoLoginCookie_DGFW()
  var cookieIndex;
  var cookieName = null;
  var startpt;
  coookieName = AUTOLOGINCOOKIE_DGFW;
  if( coookieName != null ){
    cookieIndex = document.cookie + ";";
    cookieName = coookieName + "=";
    startpt = cookieIndex.indexOf(cookieName);
    if( startpt != -1 ){
       return coookieName;
    } else {
      return null;
    }
  } else {
    return null;
// Cookie deletion function
// Deletes the cookie.
// Uses Expires to specify the year and month a year ago.
function deleteCookie() {
  var autoCookie1 = null;
  var autoCookie2 = null;
  var autoCookiePath1 = null;
```

```
var autoCookiePath2 = null;
  var cookieValue="on";
  var chk = null;
  autoCookiePath1 = SETCOOKIEPATH_DFW;
  autoCookiePath2 = SETCOOKIEPATH_DGFW;
  chk = findElement("autologinbox","checked");
  if( chk != null ){
    autoCookie1 = AUTOLOGINCOOKIE_DFW;
    autoCookie2 = AUTOLOGINCOOKIE_DGFW;
    if ((autoCookie1!= null | | autoCookie2!= null) && chk == true) {
       exptime = new Date();
       exptime.setYear(exptime.getYear() - 1); // Sets to a year ago.
       expire = exptime.toGMTString();
       document.cookie = autoCookie1 + "=" + cookieValue + "; expires=" + exp
ire + "; path=" + autoCookiePath1 + ";";
       document.cookie = autoCookie2 + "=" + cookieValue + "; expires=" + exp
ire + "; path=" + autoCookiePath2 + ";";
    }
  }
// Check for Logout/Error page cookie
// Deletes the cookie if the checkbox for
// deleting it is checked.
function chkLogoutbox() {
  var cookie1 = null;
  var cookie2 = null;
  cookie1 = getAutoLoginCookie_DFW();
  cookie2 = getAutoLoginCookie_DGFW();
  if ( cookie1 != null | | cookie2 != null ) {
    addElement();
// Logout/Error page checkbox addition function
function addElement() {
  var element = document.createElement('input');
```

```
element.id = "autologinbox";
element.setAttribute("type","checkbox");

var objBody = document.getElementById('appendNode1');
objBody.appendChild(element);

var objBody2 = document.getElementById('appendNode2');
objBody2.innerHTML = "Do not automatically log in from the next time";
}
```

1.5.1 Configuring the Integrated Windows Authentication (automatic login) JavaScript file

In order to use this function, you need to configure the JavaScript file as directed below.

- * The following assumes that the Domain Gateway Option and the Forwarder have already been installed.
- (1) Change the HTML configuration of the Forwarder as shown below. Forwarder HTML configuration file (html.conf)

```
LOGOUT=file:///opt/icewall-sso/dfw/dghtml/logout.html
```

(2) Add the following to the file on the server where the Domain Gateway Option and Forwarder are running.

Apache configuration file (httpd.conf)

```
Alias /jscript/ "/opt/icewall-sso/dfw/dghtml/js/"
```

Restart the Web server after changing the configuration.

- (3) Change the setting of the following variable in the Integrated Windows Authentication (automatic login) JavaScript file (script.js).
 - · AUTOLOGINCOOKIE DFW

Set the cookie name for Integrated Windows Authentication (automatic login).

```
Configuration example)
var AUTOLOGINCOOKIE_DFW = "autologin_fw";
```

\cdot SETCOOKIEPATH_DFW

Set the path for setting the cookie for Integrated Windows Authentication (automatic login).

Set the path for the Forwarder and Domain Gateway Option to operate.

Configuration example)

When the Forwarder and Domain Gateway Option are running under /fw/: var SETCOOKIEPATH_DFW = "/fw/";

(4) Set the expiration period for the Integrated Windows Authentication (automatic login) cookie.

Configure the JavaScript file for Integrated Windows Authentication (automatic login) as shown below.

Configuration example)

To set the expiration period for Integrated Windows Authentication (automatic login) to 10 days:

exptime.setTime(exptime.getTime() + 10*24*60*60*1000);

* By default, the Integrated Windows Authentication (automatic login) cookie is effective for 30 days.

1.5.2 Using the Integrated Windows Authentication (automatic login) JavaScript file

Use this function as directed below.

- · To use automatic login:
 - (1) Select the "Automatically log in from the next time" checkbox on the Login page.
 - (2) Click the "Integrated Windows Authentication" link on the Login page.
- To cease using automatic login after selecting the checkbox:

At logout:

- (1) Select the "Do not automatically log in from the next time" checkbox on the Logout page.
- (2) Click the "Logout" button on the Logout page.

When login fails:

- (1) When login fails and one of the following pages appears, select the "Do not automatically log in from the next time" checkbox on each page.
 - Ticket Authentication Login page (login_thk.html)
 - · Authentication Execution Permission Error page (login_addr_error.html)
 - · User ID Error page (login uerid error.html)
 - Ticket Verification Error page (login_thk_error.html)
 - Initial Authentication Error page (login_cert_error.html)
 - Account Lock Error page (login_lock_error.html)
 - · No Group Error page (login_group_error.html)
 - · Login Stop Error page (login_stop.html)

- * The checkbox is shown on each page only when the Integrated Windows Authentication (automatic login) cookie is saved in the browser.
- * If you have customized a page used by the Domain Gateway Option, you need to describe the HTML source shown below for the customized page. By doing so, the "Do not automatically log in from the next time" checkbox will be shown on the customized page.

```
<span id="appendNode1"></span>
<span id="appendNode2"></span>
```

(2) Click the "Relogin" link on the error page.

1.5.3 Notes on using the Integrated Windows Authentication (Automatic Login) JavaScript file

- While the Integrated Windows Authentication (automatic login) cookie is effective, the user cannot log in using a user ID and password. To enable login using the user ID and password, delete the cookie as directed in "To cease using automatic login after selecting the checkbox" above.
- · When login fails, you cannot delete the cookie unless you click "Relogin." Be sure to click "Relogin" when deleting the cookie.
- · Since this function uses JavaScript, be sure to enable execution of JavaScript on the browser.

1.6 Conversion of Special Keywords

The Domain Gateway Option converts the following keywords into effective values upon execution.


Special keyword	Converted into
\$USER_ID	Converted into the user ID obtained from the ticket.
	In the case of a ticket analysis error, the converted value is blank.
\$DGFW	Converted into the execution path of the Domain Gateway Option.
	Example: /fw/dgfw
\$REQUEST_URL	Converted into the request which accessed the Domain Gateway
	Option, including the argument (QueryString).
	Example: /fw/dgfw?LOGIN=ICEWALL_LOGIN&HIDEURL=/fw/
	dfw/BK
\$HIDEURL	Converted into the path to the contents of the Backend Web Server
	which was requested to the Forwarder.
	Example: When the request to the Domain Gateway Option is /fw/
	dgfw?LOGIN=ICEWALL_LOGIN&HIDEURL=/fw/dfw/,
	it is converted into /fw/dfw/BK.

Special keyword	Converted into
\$KEY_LOGIN	Converted into the value set in the POSTKEY_LOGIN parameter
	in the Forwarder configuration file (dfw.conf). If it is not defined,
	the keyword is converted into the default value
	(ICEWALL_LOGIN).
	Example: For POSTKEY_LOGIN=ICEWALL_LOGIN, it is
	converted into ICEWALL_LOGIN.
\$IWTID [10.0]	Replaced by the transaction ID of the user who accessed the
	system.
	It is converted only when the TRANSID parameter is set to ON.

2 Description of HTML

2.1 Login page (login.html) 10.0

This page is displayed during login by the Forwarder. (It is linked with the Domain Gateway Option.)




V 017	
<div class="sub-title">- Login -</div>	HQ 3H3
Enter the user ID and password, and click the	
<form <="" action="\$DF" method="POST" name="form" th=""><th></th></form>	
)">
* &nbs	an challan ID c/hac/tda
td nowrap> <tont color="#noooo"> <tont>entropy color= #noooo > <tont>entropy color= #nooo > <tont>ent</tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont></tont>	
-1	1 D 1 // // 1
* <input hidden"="" name="SUBMIT" submit"="" type="password" value="S</th><th>Send"/>	
<input type="reset" value="Cancel"/>	
<a <="" href="/fw/dgfw?LOGIN=\$KEY_LOGIN&HIDEU]</th><th>BI -¢DFW¢HIDFIIRI " th="">	
onClick="setCookieChk()" id="winauth">Integrated Windows	
a> a>	5 Travilonouson V
<input id="autologinbox" type="checkbox"/> Autom	natically login from the
next time	

Screen image	HTML source
	Hewlett-Packard

2.2 Ticket Authentication Login page (login_tkt.html) 10.0

This page is displayed when the Domain Gateway Option requests the browser for the ticket. It is not displayed when the browser is configured correctly.




Screen image	HTML source
	*<!--</th-->
	font>
	<pre><div class="sub-title">- Browser Error -</div> </pre>
	
	<pre><div class="sub-title2">Integrated Windows Authentication</div></pre>
	<pre> <br <="" th=""/></pre>
	<img border="0" height="15" src="/imgd/</p></th></tr><tr><th></th><th>arrow.gif" width="15"/> Relogin
	
	
	<pre> </pre>
	<pre>ctr> <!--/pre--></pre>
	td bgcolor = #55ccn >cling src= /inigariooter.gn width= 100 height= 15 >c/
	Value

Screen image	HTML source

2.3 Forced Login page (login_force_tkt.html)

This page is displayed to ask a user whether or not to log in discarding the login access privileges of any existing user who is already logged in. This page is displayed if the Authentication Module is configured to disallow duplicate logins and force exclusive logins. When the forced login link is removed from this source code, login becomes completely exclusive.




Screen image	HTML source
Screen image	<pre>*<!-- font--> </pre>
	height="15" border="0"> Relogin
	<pre> </pre>

Screen image	HTML source

2.4 Permission Error page at Authentication Execution (login_addr_error.html) 10.0

This page is displayed when the IP address of the IceWall (Domain Gateway Option) server is not set in the FEDERATION parameter for the Authentication Module.




Screen image	HTML source
	*<!--</th-->
	font>
	<pre></pre>
	<pre></pre>
	<pre> <div class="sub-title2">Permission Error at Authentication</div></pre>
	Execution
	<pre><pre><pre><img border="0" height="15" src="/imgd/</pre></th></tr><tr><th></th><th>arrow.gif" width="15"/> Relogin</pre></pre></pre>
	<pre>carrow.gir witati= 15 height= 15 border= 0 > cansop,nerogin vas </pre>
	<pre></pre>
	<pre></pre>
	 </th
	td>
	/tr>

Screen image	HTML source

2.5 User ID Error page (login_userid_error.html) 10.0


This page is displayed when the user ID in the Kerberos ticket is not registered in the authentication database.



Screen image	HTML source
	<pre><div class="sub-title">- User ID Error -</div> </pre>
	<pre></pre>
	<div class="sub-title2">User ID error</div>
	<img <="" p="" src="/imgd/"/>
	arrow.gif" width="15" height="15" border="0"> Relogin
	<pre></pre>
	
	<pre></pre>
	<pre><!--/pre--></pre>
	td>

2.6 Ticket Validation Error page (login_tkt_error.html) 10.0


This page is displayed when an error occurs during analysis of the Kerberos ticket received from the browser.



Screen image	HTML source
	<1114 100 1
	<pre> </pre>
	<pre><div class="sub-title">- Invalid Ticket -</div> div = sub-title">- Invalid Ticket -</pre>
	<pre> <div class="sub-title2">Ticket validation error</div></pre>
	<div class="sub-title2"> licket validation error/div><img border="0" height="15" src="/imgd/</p></th></tr><tr><th></th><th>arrow.gif" width="15"/> Relogin</div>
	arrow.gn width= 15 height= 15 border= 0 >&mosp,nelogin
	
	<pre></pre>
	 </th
	td>
	A. d.

2.7 Initial Authentication Error page (login_cert_error.html) 10.0

This page is displayed when a user authenticated with a client certificate attempts to log in by Domain Gateway Option authentication. You can configure the Authentication Module to allow or disallow user ID authentication for users with the certificate.




Screen image	HTML source
	*<!--</th-->
	font>
	<pre><div class="sub-title">- Must Login with a Client Certificate -</div></pre>
	div>
	<pre> <div class="sub-title2">Initial authentication already has been</div></pre>
	done.
	<img <="" p="" src="/imgd/"/>
	arrow.gif" width="15" height="15" border="0"> Relogin
	
	
	 </th
	td>

Screen image	HTML source

2.8 Account Lock Error page (login_lock_error.html) 10.0

This page is displayed when the number of times the user enters an incorrect password is more than the specified number of allowable times for incorrect password input while the IceWall SSO account lock function is enabled.




Screen image	HTML source
	*<!--</th-->
	font>
	<div class="sub-title">- Account Locked -</div>
	
	<div class="sub-title2">Account has been locked.</div>
	<img border="0" height="15" src="/imgd/</th></tr><tr><th></th><th>arrow.gif" width="15"/> Relogin
	
	
	 </th
	td>

Screen image	HTML source

2.9 No Group Error page (login_group_error.html) 10.0

This page is displayed when user information exists for a user in the Authentication DB connected with the Authentication Module, but the user is not defined by the group definition file (cert.grp) for the Authentication Module.




Screen image	HTML source
	*<!--</th-->
	font>
	<div class="sub-title">- No Group Error -</div>
	
	<div class="sub-title2">User's group Not Found.</div>
	<img border="0" height="15" src="/imgd/</p></th></tr><tr><th></th><th>arrow.gif" width="15"/> Relogin
	 <
	
	
	 </th
	td>

Screen image	HTML source

2.10 Login Stop Error page (login_stop.html) 10.0

The IceWall SSO Administrator can prevent particular users from logging in. This page is displayed when the user attempts to log in while his/her login account is suspended.




Screen image	HTML source
	*<!--</th-->
	font>
	<pre><div class="sub-title">- Account Disabled -</div> </pre>
	
	<div class="sub-title2">Login account disabled.</div>
	<img border="0" height="15" src="/imgd/</p></th></tr><tr><th></th><th>arrow.gif" width="15"/> Relogin
	
	
	 </th
	td>

Screen image	HTML source

2.11 Maximum Login Count Error page (login_limit_error.html)


This page is displayed when a user tries to log in while the number of users logged in to the Authentication Module has reached the maximum limit.



Screen image	HTML source
	<pre><div class="sub-title">- Login Limit Error -</div> </pre>
	<pre></pre>
	<div class="sub-title2">Maximum login count has been reached.</div>
	b>
	<img <="" p="" src="/imgd/arrow.gif" width="15"/>
	height="15" border="0"> Relogin
	<pre></pre>
	 </th
	td bgcolor= #55cm > <mig height="15" src="/migd/looter.gn" width="100"></mig>
	/tr>

2.12 Logout page (logout.html) 10.0


This page is displayed when a user accesses the alias for logout (set in the LOALIAS parameter in the Forwarder configuration file). You can set this alias in Forwarder. Logout function is enabled.



Screen image	HTML source
	<div class="sub-title">- Logout -</div>
	<div class="sub-title2">Logging out.</div>
	Be sure to log out before closing the browser.
	<pre><form action="\$DFW" method="POST"> </form></pre>
	<pre><input name="LOGOUT" type="hidden" value="\$KEY_LOGOUT"/></pre>
	<pre><input name="SUBMIT" onclick="deleteCookie()" type="submit" value="Logout"/></pre>
	onClick= deleteCookie()">
	
	Hewlett-Packard

2.13 System Error page (system_error.html)


This page is displayed when a system error occurs in IceWall SSO.



Screen image	HTML source
	<pre><div class="sub-title">- System Error -/div> </div></pre>
	<pre></pre>
	<div class="sub-title2">System error occurred.</div>
	Contact your system administrator.
	<img <="" p="" src="/imgd/arrow.gif" width="15"/>
	height="15" border="0"> Relogin
	<pre> </pre>
	<pre> </pre>
	bgcolor="#99ccff"> </th
	td bgcolor= #55ccii > <imig neight="15" src="/migd/looter.gii" width="100"></imig>

2.14 Authentication Module Down Error page (system_certd_error.html)


This page is displayed when the Domain Gateway Option cannot access the Authentication Module. The Authentication Module may be down or the Authentication Server may be inaccessible due to a network failure.



Screen image	HTML source
	<11111110<
	<pre> </pre>
	<pre><div class="sub-title">- Authentication Module Down -</div> </pre>
	<mig art="Errror." meight="50" src="/migwerror.gir" witth="100"> <div class="sub-title2">Cannot connect to the Authentication</div></mig>
	Server.
	Contact your system administrator.
	<img <="" p="" src="/imgd/arrow.gif" width="15"/>
	height="15" border="0"> Relogin
	<pre>bgcolor="#99ccff"><!--/pre--></pre>
	td>

2.15 Authentication DB Down Error page (system_ldap_error.html)


This page is displayed when the Authentication Module cannot connect to the Authentication DB. The Authentication DB may be down or inaccessible due to a network failure.



Screen image	HTML source
	**d b ===l== #cccccc b
	> ctr>
	<pre><du class="sub-title">- Database Down -</du>> </pre>
	<pre></pre>
	<div class="sub-title2">Cannot connect to the database.</div>
	Contact your system administrator.
	<img <="" p="" src="/imgd/arrow.gif" width="15"/>
	height="15" border="0"> Relogin
	<pre>bgcolor="#99ccff"><!--/pre--></pre>
	td>
	/tr>

2.16 Authentication Module Receive Timeout Error page (system_timeout_certd.html)

This page is displayed when a connection is established in communications between the Domain Gateway Option and the Authentication Module, but processing is not completed within the specified time period.




Screen image	HTML source
Screen image	### source ctd width="227" height="35" align="right"> * font> ctr> ctable> ctable border="0" width="420" cellpadding="0" cellspacing="0"> ctr> ctable border="0" width="420" cellpadding="3" cellspacing="1"> ctr> ctd bgcolor="#666666"> ctable border="0" width="420" cellpadding="3" cellspacing="1"> ctr> ctd height="180" bgcolor="#ffffff" align="center"> ctd height="180" bgcolor="#fffffff" align="center"> ctd height="180" bgcolor="#fffffff" align="center"> ctd height="180" bgcolor="#fffffff" align="center"> ctd height="180" bgcolor="#ffffffffffffffffffffffffffffffffffff

Screen image	HTML source

2.17 Database Connection Busy Error page (system_busy_database.html) 10.0


This page is displayed when the Authentication Module cannot process the request due to congestion of database accesses.



Screen image	HTML source
	*<!--</th-->
	font>
	111 114 114 00111 1 1 114 0000000 1 1 1 1
	<pre><div class="sub-title">- Database Busy Error -</div> </pre>
	<pre> <div class="sub-title2">Cannot connect to the database br>due to</div></pre>
	<pre></pre>
	Try accessing again later.
	<pre>Try accessing again rater.</pre>
	 </th
	td>
	<pre></pre>
	Vitelii/

2.18 User-Defined Error page 1 (usr_ext1.html)


This page is displayed when user-defined error 1 is specified in the UserExit routine of the Authentication Module.



<pre></pre>	Screen image	HTML source
<pre></pre>		
<pre> <ti bgcolor="#99cff"></ti></pre>		
<pre></pre>		
td>		
		Vocation >

2.19 User-Defined Error page 2 (usr_ext2.html)


This page is displayed when user-defined error 2 is specified in the UserExit routine of the Authentication Module.



Screen image	HTML source
	td height="180" bgcolor="#ffffff" align="center">
	<pre><div class="sub-title">- UserExit Page2 -</div></pre>
	<div class="sub-title2">External Interface page 2</div>
	 </td
	td>

2.20 User-Defined Error page 3 (usr_ext3.html)

This page is displayed when user-defined error 3 is specified in the UserExit routine of the Authentication Module.



Screen image	HTML source
	**d b ===d== #cccccc
	<
	td height="180" bgcolor="#ffffff" align="center">
	<pre><div class="sub-title">- UserExit Page3 -</div></pre>
	<div class="sub-title2">External Interface page 3</div>
	bgcolor="#99ccff"> /
	td bgcolor= #55ccii > <imig height="15" src="/migd/looter.gii" width="100"></imig>
	VIIIII