School Election: Kiosk Mode

Run a voting booth with iPads. Students vote one at a time on a locked screen, with a teacher nearby. No student accounts needed.

What you need

- One iPad (or tablet) for each booth. Your plan says how many kiosks you can pair.
- A teacher or volunteer at each booth, and your 6-digit **Teacher PIN** (you chose it when you set up the election).
- Wi-Fi, or a phone hotspot. Offline mode (below) covers short drops.

Set up (a few days before)

1. **Set up the election.** Go to **Schools**, then **Set up a school election**. Add the offices, candidates and your Teacher PIN.
2. **Add your students** under **Roster and turnout**. One per line: *Name, Student ID*. Each student gets a random 6-character code. Press **Download roster with codes** and print it for the booth teacher.
3. **Try it first.** Press **View kiosk** next to Edit. It shows the real booth screen with your offices and candidates. Type any code and name. Nothing is saved or counted.
4. **Open voting** when you are ready: press **Open voting** on the election page.
5. **Pair each iPad.** In the **Kiosks** section press **Pair an iPad**. A link appears once. Open it on the iPad in Safari. Do not post the link anywhere. Anyone who has it can open the booth screen. Lost it? Remove that kiosk and pair a new one.
6. **Lock the iPad.** Turn on Guided Access: Settings, Accessibility, Guided Access. Then triple-click the side button (or home button) on the booth page and choose Start. This stops students leaving the voting page.

Before the doors open

1. On each iPad, tap **Teacher** (small, bottom right), enter the PIN, and choose **Get ready for offline**. (The same screen has **Unlock kiosk** if a booth gets locked.) This stores the ballot on the iPad so students can still vote if the Wi-Fi drops.
2. Check each iPad shows your election name and the welcome screen.

Voting day at the booth

1. The teacher gives the student their code (from the printed list).
2. The student types the code and their first and last name on the iPad.
3. The student sees one office per screen. They tap a candidate (tap again to clear) and press **Next**. They may skip an office.

4. The student reviews the ballot and presses **Submit my ballot**. A thank-you screen appears and the iPad resets for the next student.
5. If a student walks away, the booth resets itself after about 90 seconds. The next student never sees their ballot.

If something goes wrong

- **“Code and name don't match.”** Check the spelling against the roster. The name must match the class list.
- **“Code already used.”** That student has already voted, at a booth or by link. Each student votes once per office.
- **Wi-Fi drops.** Keep going. Ballots are saved on the iPad and sent automatically when the connection returns. Keep the page open.
- **Too many wrong PINs** locks the teacher screen for a few minutes. Wait, then try again.
- **Candidate videos** that were pasted as links (YouTube, Vimeo) need internet. Uploaded videos play on the iPad.

When voting ends

1. Voting stops at the closing time, or press **Close voting now**.
2. Review turnout and results, tick the review box, then press **Certify the results**.
3. Press **Print the certificate** or **View winners graphic**.
4. Teachers: tap **Teacher** on each iPad, enter the PIN, press **Confirm teacher to exit**, then turn off Guided Access.

Good to know
• You can use kiosks and vote by link in the same election. A student only votes once per office either way.
• Run a practice election first with **Reset practice** to clear it.
• Need help? Email **Support@boutcasts.com**.