
- Feature Selection: Chooses a subset of the original features.



Intro to Principal Component Analysis (PCA):

- Is a technique for dimensionality reduction.

It aims to find a low-dimensional representation of high dimensional data.

- Uses and motivations of PCA:
- 1. Visualization: High-dim data are extremely hard to Visualize (I.e. To see how disjoint 2 diff categories of Feature vectors might be or to see how noisy some measurements are.) PCA provides a way to project high-dim data onto 2d or 3d for purposes of easy visualization.
- 2. Pre-processing: Learning regression and classification models from high-dim data is often very slow and prone to overfitting. This is called the curse of dimensionality.
- 3. Compression: One of PCA's earliest uses was data compression. If one can find a low-dim representation of a high-dim image, for example, then one can use such a representation to store and transmit data more efficiently.

PCA Intuition and Steps: - Assume each data point Ji has dimension p, so Y; ERP. The aim is to reduce the dimension. There are 2 ways to do so. Maximum Variance Formulation: - Find the orthogonal projection of the data into a lower dim linear space s.t. the variance of the projected data is maximised. - Consider the projection onto a 1-0 space. - The linear projection is UTS, U. ERP For convenience, we choose the unit vector. I.e. U, 'U, =1 Assume Si is standardized. by $y-\overline{y}$ ← The mean of y. 50(4) Then, the sample variance of the projected data is (0,7 4;)2 = 0,750, N where S = 12 = 4-4.T

- We want to max U, TSU, w.r.t U, given the constraint U, TU,=1.

- We have arg max (0, 750, +2, (1-0, 70, 1))

The soln is: $SU_1 = \lambda_1 U_1$ $\longrightarrow U_1^T SU_1 = \lambda_1$ (Hultiply both sides by U_1^T)

- The variance is max when $U_1 =$ the eigenvector having the largest eigenvalue χ_1 .

 Such $U_1^T Y_1$ is called the first principal component.
- We can extend this to k-Dim.

 Let $U = [U_i, U_i, ..., U_k] \rightarrow U \in \mathbb{R}^{p \times k}$ The k^{th} principal component for the i^{th} sample is $U_k^T Y_i$. We can find get this by ranking the eigenvalues.

The new (dimension reduced) data is:

	UITYI	
X; =	UzTY	= UTY; ERE
	1	
	UKTY;	

Principal components are uncorrelated: $E(U^{T}yy^{T}U) = U^{T}E(yy^{T})U$ $= U^{T}(UDU^{T}U)$ $= (U^{T}U)D(U^{T}U)$ $= D \leftarrow A \text{ diagonal matrix}$

	5
- Minimum Error Formulation:	
- Find a linear projection that min the error	
botus the data points and their projection	
y = Wx + b where W is a pxk matrix and	
X is a k-dim vector.	
X IS at page of the control.	
$\omega = [\omega_1,, \omega_k]$	
- One way to learn the model is to solve the	16
following problem:	
process	
arg min 2 114; - (WX; +6)112	
W, b, Exi3 i	
Subject to WTW = Ikxk	
Identity matrix of size	k.
This constraint requires that we obtain an	
orthonormal mapping W.	
I.e.	
$w_i^T w_j = \{1, i=j\}$	
0, i ≠ j	
Without this, the problem would be under con	strained.
Eig.	
Assume 270	
$y_i = \omega^+ x_i$	
$= (\lambda \omega^{+})(\dot{\lambda} \times i)$	
I can change W+ and Xi but still get	
the same error.	

Steps to solve the problem: 1. Let $B = \overline{\Sigma_i y_i}$

- 2. Compute the data co-variance matrix $C = \sum_{i} (y_i b)(y_i b)^T$
- 3. Let $VDV^T = C$ be the eigenvector decomposition of C. D is a diagonal matrix of eigenvalues (I.e. $D = diag(N_1, ..., N_d)$) and $V = [V_1, ..., V_d]$ contains the orthonormal eigenvectors. $V^TV = I_d$
 - 4. Assume the eigenvalues are sorted from largest to smallest. If this is not the case, sort them along with their corresponding eigenvectors.
 - 5. Let W be a matrix containing the first k eigenvectors.

 I.e. W = [V1, ..., Vk]
 - 6. Let X; = WT(Y; b) Vi

Representation and Reconstruction of New Data: - Suppose we have learned a PCA model and are given a new ynew value. To estimate its corresponding Xnew value, do: 1. Minimize 11 ynew - (W Xnew + b) 112 However, since w is orthonormal, the Solution simplifies to 2. Xnew = WT (Ynew -b) Properties of PCA: 1. Mean Zero Coefficients: The PCA coefficients/ latent coordinates, Exi3:=1, have a mean of o. Proof: Mean(X) = \ \frac{2}{2} \ Xi = E WT(Yi-b) = By Step 6 on pg 6 = WT (2 (4; b)) = WT ("N To Equals 0 N ("E y Nb) = 0 = By Step 1 on pg 6. We set b = Eiyi

ivis = du

- 2. Max Var Formulation and Min Error Formulation are equivalent.
- 3. Out of subspace error: The total variance in the data is given by the sum of the eigenvalues of the sample co-variance matrix. The variance captured by PCA is the sum of the first k eigenvalues. The total amount of variance lost is given by the sum of the remaining eigenvalues.

One can show that the least-squares error in the approx to the original data provided by the opt model params W*, {Xi*3, and b* is:

$$\frac{\sum ||y_{i} - (w^{*} X_{i}^{*} + b^{*})||^{2}}{\sum_{i=k+1}^{n} ||x_{i}^{*}||^{2}}$$

When learning a PCA model, it is common to use the ratio of the total LS error and total variance in the training data (I.e. The sum of all eigenvalues). One needs to choose a k large enough s.t. this ratio is small (often 0.1 or less).

4. Proportion of Variance:

$$\frac{P}{\sum_{j=1}^{p} \lambda_j = \sum_{j=1}^{p} \lambda_{ar}(x_j) = P}$$

PCA Final Comments:

1. Generally, it's critical to perform Standardization prior to PCA.

PCA is very sensitive to the variances of the inital variables.

I.e. If there are large diff blun the range of the initial variables, the variables with the larger ranges will dominate over those with small ranges.

2. Pros:

- Removes correlated features. Used a lot in the multi-collinearity issue.
- Can speed up algos with fewer features,
- Reduces over Fitting with Fewer Features.

3, Cons:

- Less interpretable since it transforms the original data.
- Data Standardization is a must.
- Into loss w/o proper number of components