
Amazon Elastic File System

User Guide



Amazon Elastic File System: User Guide

Copyright © 2022 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon. All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.

Table of Contents

What is Amazon Elastic File System?	1
Are you a first-time user of Amazon EFS?	2
How it works	3
Overview	3
How Amazon EFS works with Amazon EC2 and other supported compute instances	4
Amazon EFS with Standard storage classes	4
Amazon EFS with One Zone storage classes	5
How Amazon EFS works with AWS Direct Connect and AWS Managed VPN	6
How Amazon EFS works with AWS Backup	8
Implementation summary	8
Authentication and access control	9
Data consistency in Amazon EFS	9
File locking	9
Storage classes	10
EFS Lifecycle Management	10
EFS Intelligent-Tiering	10
EFS replication	11
Setting Up	12
Sign up for AWS	12
Create an IAM User	12
Getting started	14
Assumptions	14
Related topics	14
Step 1: Create your file system	15
Step 2: Create EC2 resources and launch an instance	17
Step 3: Transfer files using DataSync	18
Before you begin	18
Step 4: Clean up resources	19
Storage classes	20
EFS Standard and Standard-IA storage classes	20
EFS One Zone and One Zone-IA storage classes	20
Infrequent access performance	21
Compare storage classes	22
Storage class pricing	22
Viewing storage class size	23
Using Amazon EFS storage classes	24
Working with EFS resources	25
Resource IDs	26
Creating a file system	26
Requirements	26
Configuration options	27
Creating a file system using the console	28
Creating a file system using the AWS CLI	34
Deleting a file system	36
Using the console	37
Using the CLI	37
Mount targets and security groups	37
Creating security groups	43
Creating security groups using the AWS Management Console	44
Creating security groups using the AWS CLI	45
Creating file system policies	45
Creating and deleting access points	47
Deleting an access point	50
Tagging Amazon EFS resources	50

Tag basics	50
Tag your resources	51
Tag restrictions	51
Using tags for access control	52
Using file systems	53
Related topics	53
Using amazon-efs-utils	54
Overview	54
Supported distributions	55
Using AWS Systems Manager to install amazon-efs-utils	55
What the Amazon EFS client does during installation	56
Systems Manager Distributor supported operating systems	56
How to use AWS Systems Manager to automatically install or update amazon-efs-utils	56
Manually installing the Amazon EFS client	57
Installing the Amazon EFS client on Amazon Linux and Amazon Linux 2	58
Installing the Amazon EFS client on other Linux distributions	58
Installing the EFS client on EC2 macOS Big Sur and macOS Monterey instances	62
Installing botocore	63
Upgrading botocore	64
Upgrading stunnel	64
Disabling Certificate Hostname Checking	66
Enabling Online Certificate Status Protocol	66
Mounting file systems	68
Mounting with EFS mount helper	68
How it works	69
Getting support logs	70
Prerequisites	70
Mounting on EC2 Linux	71
Mounting on EC2 Mac	73
Mounting from a different region	74
Mounting One Zone file systems	75
Mounting with IAM authorization	78
Mounting with EFS access points	78
Mounting with on-premises clients	79
Mounting EFS automatically	79
Mounting multiple EC2 instances	85
Mounting from another account or VPC	85
Additional mounting considerations	88
Unmounting file systems	89
Troubleshooting AMI and kernel versions	89
Transferring data	90
Using AWS DataSync to transfer data in Amazon EFS	90
Using AWS Transfer Family with Amazon EFS	90
Prerequisites for using AWS Transfer Family with Amazon EFS	91
Configuring your Amazon EFS file system to work with AWS Transfer Family	91
Managing file systems	95
Managing mount targets	95
Creating or deleting mount targets in a VPC	97
Changing the VPC for your mount target	98
Updating the mount target configuration	98
Managing throughput	99
EFS lifecycle management	100
EFS intelligent tiering	101
Using lifecycle policies	101
File system operations for lifecycle management	102
Using EFS Lifecycle Management and EFS Intelligent Tiering	102
Managing access to encrypted file systems	104

Performing administrative actions on Amazon EFS KMS keys	105
Related topics	105
File system metering	106
Metering objects	106
Metered file system size	106
Metering provisioned throughput	107
Managing file system costs with AWS Budgets	108
Prerequisites	108
Creating a monthly cost budget for an EFS file system	108
File system status	109
Monitoring EFS	110
Monitoring tools	110
Automated tools	110
Manual monitoring tools	111
Monitoring with CloudWatch	111
Amazon CloudWatch metrics for Amazon EFS	112
How do I use Amazon EFS metrics?	115
Using metric math with Amazon EFS	116
Monitoring EFS file system mount status	119
Accessing CloudWatch metrics	120
Creating alarms	121
Logging Amazon EFS API Calls with AWS CloudTrail	122
Amazon EFS Information in CloudTrail	122
Understanding Amazon EFS Log File Entries	123
Amazon EFS Log File Entries for Encrypted-at-Rest File Systems	128
Performance	130
Performance summary	130
Storage classes and performance	131
Performance modes	131
Throughput modes	132
Understanding metered throughput	132
Bursting Throughput	133
Provisioned Throughput	134
Restrictions on switching throughput modes and changing provisioned amount	134
Performance tips	134
Average I/O size	134
Request model	135
NFS client mount settings	135
Optimizing small-file performance	135
Optimizing directory performance	136
Optimizing the NFS read_ahead_kb size	136
EFS backups	138
AWS Backup and EFS	138
Incremental backups	138
Backup consistency	139
Performance	139
Backup completion window	139
EFS storage classes	139
IAM permissions for creating and restoring backups	139
On-demand backups	140
Concurrent backups	140
Automatic backups	140
Manually configure backups	141
Restore a recovery point	141
Deleting backups	142
EFS replication	143
Replicating file systems	143

Storage classes	143
What's in a replication configuration	145
Permissions required	146
Costs	146
Performance	147
Mounting a destination file system	147
Failing over to a destination file system	147
Creating a replication configuration	147
View a replication	150
Delete a replication configuration	152
Monitoring replication status	153
Walkthroughs	155
Walkthrough: Create and mount a file system using the AWS CLI	155
Before you begin	156
Setting up the AWS CLI	156
Step 1: Create Amazon EC2 resources	157
Step 2: Create Amazon EFS resources	161
Step 3: Mount and test the file system	163
Step 4: Clean up	166
Walkthrough: Set up an Apache web server and serve files	167
Single EC2 instance serving files	167
Multiple EC2 instances serving files	169
Walkthrough: Create writable per-user subdirectories	172
Automatic remounting on reboot	173
Walkthrough: Mount EFS on an on-premises client	173
Before you begin	174
Step 1: Create your Amazon Elastic File System resources	174
Step 2: Install the NFS client	175
Step 3: Mount the Amazon EFS file system on your on-premises Client	176
Step 4: Clean up resources and protect your AWS account	177
Optional: Encrypting data in transit	177
Walkthrough: Mount a File System from a Different VPC	180
Before You Begin	180
Step 1: Determine the Availability Zone ID of the EFS Mount Target	180
Step 2: Determine the Mount Target IP Address	181
Step 3: Add a Host Entry for the Mount Target	182
Step 4: Mount Your File System Using the EFS Mount Helper	182
Step 5: Clean Up Resources and Protect Your AWS Account	183
Walkthrough: Enforcing Encryption on an Amazon EFS File System at Rest	184
Enforcing Encryption at Rest	184
Enable root squashing using IAM for NFS	186
Security	189
Data encryption in Amazon EFS	189
When to use encryption	190
Encrypting data at rest	190
Encrypting data in transit	194
Identity and access management	196
Authentication	196
Access control	197
Overview of managing access	197
Controlling API access	201
Controlling file system data access	206
Using IAM to enforce creating encrypted file systems	209
Blocking public access	212
Using tags with Amazon EFS	213
Using the EFS Service-Linked Role	215
Controlling network access	218

Using VPC security groups for Amazon EC2 instances and mount targets	218
Source ports	219
Security considerations for network access	219
Working with VPC Endpoints	220
NFS-Level users, groups, and permissions	221
File and directory permissions	222
Example Amazon EFS file system use cases and permissions	222
User and Group ID Permissions for Files and Directories Within a File System	223
No root squashing	224
Permissions caching	224
Changing file system object ownership	224
EFS access points	224
Working with access points	224
Creating an access point	225
Mounting with access points	225
Enforcing a user identity	225
Enforcing a root directory	226
Using access points in IAM policies	227
Logging and monitoring	228
AWS managed policies	228
AmazonElasticFileSystemFullAccess	229
AmazonElasticFileSystemReadOnlyAccess	230
AmazonElasticFileSystemClientReadWriteAccess	231
Policy updates	232
Compliance Validation	233
Resilience	233
Network Isolation	234
EFS quotas	235
Amazon EFS quotas that you can increase	235
Requesting a quota increase	236
Amazon EFS resource quotas that you cannot change	237
Quotas for NFS clients	237
Quotas for Amazon EFS file systems	237
Unsupported NFSv4.0 and 4.1 features	238
Additional considerations	239
Troubleshooting Amazon EFS	240
Troubleshooting General Issues	240
Unable to create an EFS file system	240
Errors when accessing the Amazon EFS console	241
Amazon EC2 instance hangs	241
Application writing large amounts of data hangs	241
Poor performance when opening many files in parallel	242
Custom NFS settings causing write delays	242
Creating backups with Oracle Recovery Manager is slow	243
Troubleshooting file operation errors	243
Command fails with "Disk quota exceeded" error	243
Command fails with "I/O error"	243
Command fails with "File name is too long" error	244
Command fails with "File not found" error	244
Command fails with "Too many links" error	244
Command fails with "File too large" error	244
Troubleshooting AMI and kernel issues	245
Unable to chown	245
File system keeps performing operations repeatedly due to client bug	245
Deadlocked client	245
Listing files in a large directory takes a long time	246
Troubleshooting mount issues	246

File system mount on Windows instance fails	246
Access denied by server	247
Automatic mounting fails and the instance is unresponsive	247
Mounting multiple Amazon EFS file systems in /etc/fstab fails	247
Mount command fails with "wrong fs type" error message	248
Mount command fails with "incorrect mount option" error message	248
Mounting with access point fails	249
File system mount fails immediately after file system creation	249
File system mount hangs and then fails with timeout error	249
File system mount with NFS using DNS name fails	250
File system mount fails with "nfs not responding"	250
mount target lifecycle state is stuck	251
Mount does not respond	251
Operations on newly mounted file system return "bad file handle" Error	251
Unmounting a file system fails	251
Troubleshooting encryption	252
Mounting with encryption of data in transit fails	252
Mounting with encryption of data in transit is interrupted	252
Encrypted-at-rest file system can't be created	253
Unusable encrypted file system	253
Amazon EFS API	254
API endpoint	254
API version	254
Related topics	255
Working with the query API request rate for Amazon EFS	255
Polling	255
Retries or batch processing	255
Calculating the sleep interval	255
Actions	255
CreateAccessPoint	257
CreateFileSystem	262
CreateMountTarget	272
CreateReplicationConfiguration	280
CreateTags	285
DeleteAccessPoint	287
DeleteFileSystem	289
DeleteFileSystemPolicy	292
DeleteMountTarget	294
DeleteReplicationConfiguration	297
DeleteTags	299
DescribeAccessPoints	301
DescribeAccountPreferences	304
DescribeBackupPolicy	306
DescribeFileSystemPolicy	308
DescribeFileSystems	311
DescribeLifecycleConfiguration	315
DescribeMountTargets	318
DescribeMountTargetSecurityGroups	322
DescribeReplicationConfigurations	325
DescribeTags	328
ListTagsForResource	331
ModifyMountTargetSecurityGroups	334
PutAccountPreferences	337
PutBackupPolicy	339
PutFileSystemPolicy	341
PutLifecycleConfiguration	345
TagResource	350

UntagResource	353
UpdateFileSystem	355
Data Types	360
AccessPointDescription	361
BackupPolicy	363
CreationInfo	364
Destination	366
DestinationToCreate	368
FileSystemDescription	370
FileSystemSize	374
LifecyclePolicy	375
MountTargetDescription	376
PosixUser	379
ReplicationConfigurationDescription	380
ResourceIdPreference	382
RootDirectory	383
Tag	384
Additional information	385
Back up with AWS Data Pipeline	385
Recommended Amazon EFS backup solutions	385
Legacy EFS backup solution using AWS Data Pipeline	385
Performance for Amazon EFS backups using AWS Data Pipeline	386
Considerations for Amazon EFS backup using AWS Data Pipeline	387
Assumptions for Amazon EFS backup with AWS Data Pipeline	387
How to back up an Amazon EFS file system with AWS Data Pipeline	388
Additional backup resources	393
Mounting file systems without the EFS mount helper	397
NFS support	398
Installing the NFS client	399
NFS mount options	400
Mounting on Amazon EC2 with a DNS name	401
Mounting with an IP address	403
Document History	405

What is Amazon Elastic File System?

Amazon Elastic File System (Amazon EFS) provides a simple, serverless, set-and-forget elastic file system for use with AWS Cloud services and on-premises resources. It is built to scale on demand to petabytes without disrupting applications, growing and shrinking automatically as you add and remove files, eliminating the need to provision and manage capacity to accommodate growth. Amazon EFS has a simple web services interface that allows you to create and configure file systems quickly and easily. The service manages all the file storage infrastructure for you, meaning that you can avoid the complexity of deploying, patching, and maintaining complex file system configurations.

Amazon EFS supports the Network File System version 4 (NFSv4.1 and NFSv4.0) protocol, so the applications and tools that you use today work seamlessly with Amazon EFS. Multiple compute instances, including Amazon EC2, Amazon ECS, and AWS Lambda, can access an Amazon EFS file system at the same time, providing a common data source for workloads and applications running on more than one compute instance or server.

With Amazon EFS, you pay only for the storage used by your file system and there is no minimum fee or setup cost. Amazon EFS offers a range of storage classes designed for different use cases. These include:

- **Standard storage classes** – EFS Standard and EFS Standard–Infrequent Access (Standard–IA), which offer multi-AZ resilience and the highest levels of durability and availability.
- **One Zone storage classes** – EFS One Zone and EFS One Zone–Infrequent Access (EFS One Zone–IA), which offer customers the choice of additional savings by choosing to save their data in a single Availability Zone.

For more information, see [EFS storage classes \(p. 20\)](#). Costs related to Provisioned Throughput are determined by the throughput values you specify. For more information, see [Amazon EFS Pricing](#).

Amazon EFS is designed to provide the throughput, IOPS, and low latency needed for a broad range of workloads. With Amazon EFS, you can choose from two performance modes and two throughput modes:

- The default *General Purpose performance mode* is ideal for latency-sensitive use cases, like web serving environments, content management systems, home directories, and general file serving.
- File systems in the *Max I/O mode* can scale to higher levels of aggregate throughput and operations per second with a tradeoff of higher latencies for file system operations. For more information, see [Performance modes \(p. 131\)](#).
- Using the default *Bursting Throughput mode*, throughput scales as your file system grows.
- Using *Provisioned Throughput mode*, you can specify the throughput of your file system independent of the amount of data stored. For more information, see [Throughput modes \(p. 132\)](#).

The service is designed to be highly scalable, highly available, and highly durable. Amazon EFS file systems using Standard storage classes store data and metadata across multiple Availability Zones in an AWS Region. EFS file systems can grow to petabyte scale, drive high levels of throughput, and allow massively parallel access from compute instances to your data.

Amazon EFS provides file system access semantics, such as strong data consistency and file locking. For more information, see [Data consistency in Amazon EFS \(p. 9\)](#). Amazon EFS also enables you to control access to your file systems through Portable Operating System Interface (POSIX) permissions. For more information, see [Security in Amazon EFS \(p. 189\)](#).

Amazon EFS supports authentication, authorization, and encryption capabilities to help you meet your security and compliance requirements. Amazon EFS supports two forms of encryption for file systems,

encryption in transit and encryption at rest. You can enable encryption at rest when creating an Amazon EFS file system. If you do, all your data and metadata is encrypted. You can enable encryption in transit when you mount the file system. NFS client access to EFS is controlled by both AWS Identity and Access Management (IAM) policies and network security policies like security groups. For more information, see [Data encryption in Amazon EFS \(p. 189\)](#), [Identity and access management for Amazon EFS \(p. 196\)](#), and [Controlling network access to Amazon EFS file systems for NFS clients \(p. 218\)](#).

Note

Using Amazon EFS with Microsoft Windows-based Amazon EC2 instances is not supported.

Are you a first-time user of Amazon EFS?

If you are a first-time user of Amazon EFS, we recommend that you read the following sections in order:

1. For an Amazon EFS product and pricing overview, see [Amazon EFS](#).
2. For an Amazon EFS technical overview, see [Amazon EFS: How it works \(p. 3\)](#).
3. Try the introductory exercises:
 - [Getting started \(p. 14\)](#)
 - [Walkthroughs \(p. 155\)](#)

If you want to learn more about Amazon EFS, the following topics discuss the service in greater detail:

- [Working with Amazon EFS resources \(p. 25\)](#)
- [Managing Amazon EFS file systems \(p. 95\)](#)
- [Amazon EFS API \(p. 254\)](#)

Amazon EFS: How it works

Following, you can find a description about how Amazon EFS works, its implementation details, and security considerations.

Topics

- [Overview \(p. 3\)](#)
- [How Amazon EFS works with Amazon EC2 and other supported compute instances \(p. 4\)](#)
- [How Amazon EFS works with AWS Direct Connect and AWS Managed VPN \(p. 6\)](#)
- [How Amazon EFS works with AWS Backup \(p. 8\)](#)
- [Implementation summary \(p. 8\)](#)
- [Authentication and access control \(p. 9\)](#)
- [Data consistency in Amazon EFS \(p. 9\)](#)
- [Storage classes \(p. 10\)](#)
- [EFS replication \(p. 11\)](#)

Overview

Amazon EFS provides a simple, serverless, set-and-forget elastic file system. With Amazon EFS, you can create a file system, mount the file system on an Amazon EC2 instance, and then read and write data to and from your file system. You can mount an Amazon EFS file system in your virtual private cloud (VPC), through the Network File System versions 4.0 and 4.1 (NFSv4) protocol. We recommend using a current generation Linux NFSv4.1 client, such as those found in the latest Amazon Linux, Amazon Linux 2, Red Hat, Ubuntu, and macOS Big Sur AMIs, in conjunction with the Amazon EFS mount helper. For instructions, see [Using the amazon-efs-utils Tools \(p. 54\)](#).

For a list of Amazon EC2 Linux and macOS Amazon Machine Images (AMIs) that support this protocol, see [NFS support \(p. 398\)](#). For some AMIs, you must install an NFS client to mount your file system on your Amazon EC2 instance. For instructions, see [Installing the NFS client \(p. 399\)](#).

You can access your Amazon EFS file system concurrently from multiple NFS clients, so applications that scale beyond a single connection can access a file system. Amazon EC2 and other AWS compute instances running in multiple Availability Zones within the same AWS Region can access the file system, so that many users can access and share a common data source.

For a list of AWS Regions where you can create an Amazon EFS file system, see the [Amazon Web Services General Reference](#).

To access your Amazon EFS file system in a VPC, you create one or more mount targets in the VPC.

- For file systems using Standard storage classes, you can create a mount target in each availability Zone in the AWS Region.
- For file systems using One Zone storage classes, you create only a single mount target that is in the same Availability Zone as the file system.

For more information, see [EFS storage classes \(p. 20\)](#).

A *mount target* provides an IP address for an NFSv4 endpoint at which you can mount an Amazon EFS file system. You mount your file system using its Domain Name Service (DNS) name, which resolves to the IP address of the EFS mount target in the same Availability Zone as your EC2 instance. You can create one mount target in each Availability Zone in an AWS Region. If there are multiple subnets in an Availability Zone in your VPC, you create a mount target in one of the subnets. Then all EC2 instances in that Availability Zone share that mount target.

Note

An Amazon EFS file system can only have mount targets in one VPC at a time.

Mount targets themselves are designed to be highly available. As you design for high availability and failover to other Availability Zones, keep in mind that while the IP addresses and DNS for your mount targets in each Availability Zone are static, they are redundant components backed by multiple resources.

After mounting the file system by using its DNS name, you use it like any other POSIX-compliant file system. For information about NFS-level permissions and related considerations, see [Working with users, groups, and permissions at the Network File System \(NFS\) Level \(p. 221\)](#).


You can mount your Amazon EFS file systems on your on-premises data center servers when connected to your Amazon VPC with AWS Direct Connect or AWS VPN. You can mount your EFS file systems on on-premises servers to migrate datasets to EFS, enable cloud bursting scenarios, or backup your on-premises data to Amazon EFS.

How Amazon EFS works with Amazon EC2 and other supported compute instances

This section explains how Amazon EFS file systems that use Standard and One Zone storage classes are mounted to EC2 instances in an Amazon VPC.

Amazon EFS with Standard storage classes

The following illustration shows multiple EC2 instances accessing an Amazon EFS file system that is configured with Standard storage classes from multiple Availability Zones in an AWS Region.




In this illustration, the Amazon Virtual Private Cloud (VPC) has three Availability Zones. Because the file system uses Standard storage classes, a mount target was created in each Availability Zone. We recommend that you access the file system from a mount target within the same Availability Zone for performance and cost reasons. One of the Availability Zones has two subnets. However, a mount target is created in only one of the subnets. Creating this setup works as follows:

1. Create your Amazon EC2 resources and launch your Amazon EC2 instance. For more information on Amazon EC2, see [Amazon EC2 - Virtual Server Hosting](#).
2. Choose **Regional** durability and availability when creating your Amazon EFS file system.
3. Connect to each of your Amazon EC2 instances, and mount the Amazon EFS file system.

For detailed steps, see [Getting started with Amazon Elastic File System \(p. 14\)](#).

Amazon EFS with One Zone storage classes

The following illustration shows multiple EC2 instances accessing an Amazon EFS file system using One Zone storage from different Availability Zones in an AWS Region.



In this illustration, the VPC has two Availability Zones, each with one subnet. The file system uses One Zone storage classes, so it can only have a single mount target. For better performance and cost, we recommend that you access the file system from a mount target in the same Availability Zone as the EC2 instance that you're mounting it on.

In this example, the EC2 instance in the us-west-2c Availability Zone will pay EC2 data access charges for accessing a mount target in a different Availability Zone. Creating this setup works as follows:

1. Create your Amazon EC2 resources and launch your Amazon EC2 instance. For more information about Amazon EC2, see [Amazon EC2](#).
2. Create your Amazon EFS file system with One Zone storage.
3. Connect to each of your Amazon EC2 instances, and mount the Amazon EFS file system using the same mount target for each instance.

How Amazon EFS works with AWS Direct Connect and AWS Managed VPN

By using an Amazon EFS file system mounted on an on-premises server, you can migrate on-premises data into the AWS Cloud hosted in an Amazon EFS file system. You can also take advantage of bursting. In other words, you can move data from your on-premises servers into Amazon EFS and analyze it on a fleet of Amazon EC2 instances in your Amazon VPC. You can then store the results permanently in your file system or move the results back to your on-premises server.


Keep the following considerations in mind when using Amazon EFS with an on-premises server:

- Your on-premises server must have a Linux-based operating system. We recommend Linux kernel version 4.0 or later.

- For the sake of simplicity, we recommend mounting an Amazon EFS file system on an on-premises server using a mount target IP address instead of a DNS name.

There is no additional cost for on-premises access to your Amazon EFS file systems. You are charged for the AWS Direct Connect connection to your Amazon VPC. For more information, see [AWS Direct Connect pricing](#).

The following illustration shows an example of how to access an Amazon EFS file system from on-premises (the on-premises servers have the file systems mounted).



You can use any mount target in your VPC if you can reach that mount target's subnet by using an AWS Direct Connect connection between your on-premises server and VPC. To access Amazon EFS from an on-premises server, add a rule to your mount target security group to allow inbound traffic to the NFS port (2049) from your on-premises server.

To create a setup like this, you do the following:

- Establish an AWS Direct Connect connection between your on-premises data center and your Amazon VPC. For more information on AWS Direct Connect, see [AWS Direct Connect](#).
- Create your Amazon EFS file system.
- Mount the Amazon EFS file system on your on-premises server.

For detailed steps, see [Walkthrough: Create and mount a file system on-premises with AWS Direct Connect and VPN \(p. 173\)](#).

How Amazon EFS works with AWS Backup

For a comprehensive backup implementation for your file systems, you can use Amazon EFS with AWS Backup. AWS Backup is a fully managed backup service that makes it easy to centralize and automate data backup across AWS services in the cloud and on-premises. Using AWS Backup, you can centrally configure backup policies and monitor backup activity for your AWS resources. Amazon EFS always prioritizes file system operations over backup operations. To learn more about backing up EFS file systems using AWS Backup, see [Using AWS Backup to back up and restore Amazon EFS file systems \(p. 138\)](#).

Implementation summary

In Amazon EFS, a file system is the primary resource. Each file system has properties such as ID, creation token, creation time, file system size in bytes, number of mount targets created for the file system, and the file system lifecycle state. For more information, see [CreateFileSystem \(p. 262\)](#).

Amazon EFS also supports other resources to configure the primary resource. These include mount targets and access points:

- **Mount target** – To access your file system, you must create mount targets in your VPC. Each mount target has the following properties: the mount target ID, the subnet ID in which it is created, the file system ID for which it is created, an IP address at which the file system may be mounted, VPC security groups, and the mount target state. You can use the IP address or the DNS name in your mount command.

Each file system has a DNS name of the following form.

`file-system-id.efs.aws-region.amazonaws.com`

You can specify this DNS name in your mount command to mount the Amazon EFS file system. Suppose you create an `efs-mount-point` subdirectory off of your home directory on your EC2 instance or on-premises server. Then, you can use the mount command to mount the file system. For example, on an Amazon Linux AMI, you can use the following mount command.

```
$ sudo mount -t nfs -o
  nfsvers=4.1,rsize=1048576,wsize=1048576,hard,timeo=600,retrans=2,noresvport file-system-DNS-name:/ ~/efs-mount-point
```

For more information, see [Creating and managing mount targets and security groups \(p. 37\)](#). First, you need to install the NFS client on your EC2 instance. The [Getting started \(p. 14\)](#) exercise provides step-by-step instructions.

- **Access Points** – An access point applies an operating system user, group, and file system path to any file system request made using the access point. The access point's operating system user and group override any identity information provided by the NFS client. The file system path is exposed to the client as the access point's root directory. This ensures that each application always uses the correct operating system identity and the correct directory when accessing shared file-based datasets. Applications using the access point can only access data in its own directory and below. For more information, see [Working with Amazon EFS access points \(p. 224\)](#).

Mount targets and tags are *subresources* that are associated with a file system. You can only create them within the context of an existing file system.

Amazon EFS provides API operations for you to create and manage these resources. In addition to the create and delete operations for each resource, Amazon EFS also supports a describe operation that

enables you to retrieve resource information. You have the following options for creating and managing these resources:

- Use the Amazon EFS console – For an example, see [Getting started \(p. 14\)](#).
- Use the Amazon EFS command line interface (CLI) – For an example, see [Walkthrough: Create an Amazon EFS file system and mount it on an Amazon EC2 instance using the AWS CLI \(p. 155\)](#).
- You can also manage these resources programmatically as follows:
 - Use the AWS SDKs – The AWS SDKs simplify your programming tasks by wrapping the underlying Amazon EFS API. The SDK clients also authenticate your requests by using access keys that you provide. For more information, see [Sample Code and Libraries](#).
 - Call the Amazon EFS API directly from your application – If you cannot use the SDKs for some reason, you can make the Amazon EFS API calls directly from your application. However, you need to write the necessary code to authenticate your requests if you use this option. For more information about the Amazon EFS API, see [Amazon EFS API \(p. 254\)](#).

Authentication and access control

You must have valid credentials to make Amazon EFS API requests, such as create a file system. In addition, you must also have permissions to create or access resources. By default, when you use the root account credentials of your AWS account you can create and access resources owned by that account. However, we don't recommend using root account credentials. In addition, any AWS Identity and Access Management (IAM) users and roles that you create in your account must be granted permissions to create or access resources. For more information about permissions, see [Identity and access management for Amazon EFS \(p. 196\)](#).

IAM authorization for NFS clients is an additional security option for Amazon EFS that uses IAM to simplify access management for Network File System (NFS) clients at scale. With IAM authorization for NFS clients, you can use IAM to manage access to an EFS file system in an inherently scalable way. IAM authorization for NFS clients is also optimized for cloud environments. For more information on using IAM authorization for NFS clients, see [Using IAM to control file system data access \(p. 206\)](#).

Data consistency in Amazon EFS

Amazon EFS provides the close-to-open consistency semantics that applications expect from NFS.

In Amazon EFS, write operations are durably stored across Availability Zones on file systems using Standard storage classes in these situations:

- An application performs a synchronous write operation (for example, using the open Linux command with the O_DIRECT flag, or the fsync Linux command).
- An application closes a file.

Depending on the access pattern, Amazon EFS can provide stronger consistency guarantees than close-to-open semantics. Applications that perform synchronous data access and perform non-appending writes have read-after-write consistency for data access.

File locking

NFS client applications can use NFS version 4 file locking (including byte-range locking) for read and write operations on Amazon EFS files.

Remember the following about how Amazon EFS locks files:

- Amazon EFS only supports advisory locking, so read/write operations don't check for conflicting locks before executing. For example, to avoid file synchronization issues with atomic operations, your application must be aware of NFS semantics (such as close-to-open consistency).
- Any one particular file can have up to 512 locks across all instances connected and users accessing the file.

Storage classes

With Amazon EFS, you can choose from a range of storage classes that are designed for different use cases:

- **EFS Standard** – A regional storage class for frequently accessed data. It offers the highest levels of availability and durability by storing file system data redundantly across multiple Availability Zones in an AWS Region.
- **EFS Standard-Infrequent Access (Standard-IA)** – A regional storage class for infrequently accessed data. It offers the highest levels of availability and durability by storing file system data redundantly across multiple Availability Zones in an AWS Region.
- **EFS One Zone** – For frequently accessed files stored redundantly within a single Availability Zone in an AWS Region.
- **EFS One Zone-IA (One Zone-IA)** – A lower-cost storage class for infrequently accessed files stored redundantly within a single Availability Zone in an AWS Region.

The EFS Standard storage classes are regional storage classes that store file system data and metadata redundantly across multiple geographically separated Availability Zones within an AWS Region. They offer the highest levels of availability and durability, providing continuous availability to data even when one or more Availability Zones in a Region are unavailable.

The EFS One Zone storage classes are lower cost, single Availability Zone storage classes. They store file system data and metadata redundantly in a single Availability Zone within an AWS Region.

Both of the IA storage classes reduce storage costs for files that aren't accessed every day. We recommend using IA storage if you need your full dataset to be readily accessible, and you want to automatically save on storage costs for files that are less frequently accessed. Examples include keeping files accessible to satisfy audit requirements, perform historical analysis, or perform backup and recovery. For more information about Amazon EFS storage classes, see [EFS storage classes \(p. 20\)](#).

EFS Lifecycle Management

Amazon EFS Lifecycle Management automatically manages cost-effective file storage for your file systems. When enabled, Lifecycle Management migrates files that haven't been accessed for a set period of time to an infrequent access storage class, Standard-IA or One Zone-IA. You define that period of time by using a *lifecycle policy*. For more information, see [Amazon EFS lifecycle management \(p. 100\)](#).

EFS Intelligent-Tiering

Amazon EFS Intelligent-Tiering uses lifecycle management to monitor the access patterns of your workload and automatically transitions files to and from your corresponding Infrequent Access (IA) storage class. With intelligent tiering, files in the standard storage class (EFS Standard or EFS One Zone) that are not accessed for a period of time, for example 30 days, are transitioned to the corresponding Infrequent Access (IA) storage class. Additionally, if access patterns change, EFS Intelligent-Tiering automatically moves files back to the EFS Standard or EFS One Zone storage classes. This helps to eliminate the risk of unbounded access charges, while providing consistent low latencies. For more information, see [Amazon EFS Intelligent-Tiering \(p. 101\)](#).

EFS replication

You can create a replica of your Amazon EFS file system in the AWS Region of your preference using Amazon EFS Replication. When enabled, Amazon EFS Replication automatically and transparently replicates the data and metadata on your EFS file system to a new destination EFS file system that is created in an AWS Region that you choose.

Amazon EFS automatically keeps the source and destination file systems synchronized. Amazon EFS replication is continual and designed to provide a recovery point objective (RPO) and a recovery time objective (RTO) of minutes. These features should assist you in meeting your compliance and business continuity goals. For more information, see [Amazon EFS replication \(p. 143\)](#).

Setting Up

Before you use Amazon EFS for the first time, complete the following tasks:

1. [Sign up for AWS \(p. 12\)](#)
2. [Create an IAM User \(p. 12\)](#)

Sign up for AWS

When you sign up for Amazon Web Services (AWS), your AWS account is automatically signed up for all services in AWS, including Amazon EFS. You are charged only for the services that you use.

With Amazon EFS, you pay only for the storage you use. For more information about Amazon EFS usage rates, see the [Amazon Elastic File System Pricing](#). If you are a new AWS customer, you can get started with Amazon EFS for free. For more information, see [AWS Free Usage Tier](#).

If you have an AWS account already, skip to the next task. If you don't have an AWS account, use the following procedure to create one.

To create an AWS account

1. Open <https://portal.aws.amazon.com/billing/signup>.
2. Follow the online instructions.

Part of the sign-up procedure involves receiving a phone call and entering a verification code on the phone keypad.

When you sign up for an AWS account, an *AWS account root user* is created. The root user has access to all AWS services and resources in the account. As a security best practice, [assign administrative access to an administrative user](#), and use only the root user to perform [tasks that require root user access](#).

Note your AWS account number, because you'll need it for the next task.

Create an IAM User

Services in AWS, such as Amazon EFS, require that you provide credentials when you access them, so that the service can determine whether you have permissions to access its resources. AWS recommends that you do not use the root credentials of your AWS account to make requests. Instead, create an IAM user, and grant that user full access. We refer to these users as administrator users. You can use the administrator user credentials, instead of root credentials of your account, to interact with AWS and perform tasks, such as create a bucket, create users, and grant them permissions. For more information, see [Root Account Credentials vs. IAM User Credentials](#) in the *AWS General Reference* and [IAM Best Practices](#) in the *IAM User Guide*.

If you signed up for AWS but have not created an IAM user for yourself, you can create one using the IAM console.

To create an administrator user, choose one of the following options.

Choose one way to manage your administration	To	By	You can also
In IAM Identity Center (Recommended)	Use short-term credentials to access AWS. This aligns with the security best practices. For information about best practices, see Security best practices in IAM in the <i>IAM User Guide</i> .	Following the instructions in Getting started in the AWS <i>IAM Identity Center (successor to AWS Single Sign-On) User Guide</i> .	Configure programmatic access by Configuring the AWS CLI to use AWS IAM Identity Center (successor to AWS Single Sign-On) in the <i>AWS Command Line Interface User Guide</i> .
In IAM (Not recommended)	Use long-term credentials to access AWS.	Following the instructions in Creating your first IAM admin user and user group in the <i>IAM User Guide</i> .	Configure programmatic access by Managing access keys for IAM users in the <i>IAM User Guide</i> .

To sign in as this new IAM user, sign out of the AWS Management Console, and then use the following URL, where *your_aws_account_id* is your AWS account number without the hyphens (for example, if your AWS account number is 1234-5678-9012, your AWS account ID is 123456789012):

[https://*your_aws_account_id*.signin.aws.amazon.com/console/](https://your_aws_account_id.signin.aws.amazon.com/console/)

Enter the IAM user name and password that you just created. When you're signed in, the navigation bar displays *your_user_name@your_aws_account_id*.

If you don't want the URL for your sign-in page to contain your AWS account ID, you can create an account alias. From the IAM dashboard, locate **IAM users sign-in link:** and choose **Customize**. Enter an alias, such as your company name. To sign in after you create an account alias, use the following URL:

[https://*your_account_alias*.signin.aws.amazon.com/console/](https://your_account_alias.signin.aws.amazon.com/console/)

To verify the sign-in link for IAM users for your account, open the IAM console and check under **AWS account Alias** on the dashboard.

Getting started with Amazon Elastic File System

In this Getting Started exercise, you can learn how to quickly create an Amazon Elastic File System (Amazon EFS) file system. As part of this process, you mount your file system on an Amazon Elastic Compute Cloud (Amazon EC2) instance in your virtual private cloud (VPC). You also test the end-to-end setup.

There are four steps that you need to perform to create and use your first Amazon EFS file system:

- Create your Amazon EFS file system.
- Create your Amazon EC2 resources, launch your instance, and mount the file system.
- Transfer files to your EFS file system using AWS DataSync.
- Clean up your resources and protect your AWS account.

Topics

- [Assumptions \(p. 14\)](#)
- [Related topics \(p. 14\)](#)
- [Step 1: Create your Amazon EFS file system \(p. 15\)](#)
- [Step 2: Create your EC2 resources and launch your EC2 instance \(p. 17\)](#)
- [Step 3: Transfer files to Amazon EFS using AWS DataSync \(p. 18\)](#)
- [Step 4: Clean up resources and protect your AWS account \(p. 19\)](#)

Assumptions

For this exercise, we assume the following:

- You're already familiar with using the Amazon EC2 console to launch instances.
- Your Amazon VPC, Amazon EC2, and Amazon EFS resources are all in the same AWS Region. This guide uses the US West (Oregon) Region (us-west-2).
- You have a default VPC in the AWS Region that you're using for this Getting Started exercise. If you don't have a default VPC, or if you want to mount your file system from a new VPC with new or existing security groups, you can still use this Getting Started exercise. To do so, configure [Using VPC security groups for Amazon EC2 instances and mount targets \(p. 218\)](#).
- You haven't changed the default inbound access rule for the default security group.

You can use your AWS account root user credentials to sign in to the console and try the Getting Started exercise. However, AWS Identity and Access Management (IAM) recommends that you do not use the account root user credentials. Instead, create an administrator user in your account and use those credentials to manage resources in your account. For more information, see [Setting Up \(p. 12\)](#).

Related topics

This guide also provides a walkthrough to perform a similar Getting Started exercise using AWS Command Line Interface (AWS CLI) commands to make the Amazon EFS API calls. For more information,

see [Walkthrough: Create an Amazon EFS file system and mount it on an Amazon EC2 instance using the AWS CLI \(p. 155\)](#).

Step 1: Create your Amazon EFS file system

In this step, you create your Amazon EFS file system that has the service recommended settings using the Amazon EFS console.

To create your Amazon EFS file system

1. Open the Amazon EFS Management Console at <https://console.aws.amazon.com/efs/>.
2. Choose **Create file system** to open the **Create file system** dialog box.

The screenshot shows the 'Create file system' dialog box. At the top, it says 'Create file system'. Below that, a note says 'Create an EFS file system with service recommended settings. [Learn more](#)'. The 'Name - optional' field contains 'MyFS'. The 'Virtual Private Cloud (VPC)' dropdown shows 'vpc-d8c88ab0' and 'default'. Under 'Availability and Durability', 'One Zone' is selected. Under 'Availability Zone', 'eu-west-2a' is chosen. At the bottom, there are 'Cancel', 'Customize', and a large orange 'Create' button.

3. (Optional) Enter a **Name** for your file system.
4. For **Virtual Private Cloud (VPC)**, choose your VPC, or keep it set to your default VPC.
5. For **Availability and Durability**, choose one of the following:
 - **Regional** to create a file system that uses [Standard storage classes \(p. 20\)](#). Standard storage classes store file system data and metadata redundantly across all Availability Zones within an AWS Region. **Regional** offers the highest levels of availability and durability.
 - **One Zone** to create a file system that uses [One Zone storage classes \(p. 20\)](#). One Zone storage classes store file system data and metadata redundantly within a single Availability Zone which makes it less expensive than Standard storage classes.

Because EFS One Zone storage classes store data in a single AWS Availability Zone, data stored in these storage classes may be lost in the event of a disaster or other fault that affects all copies of the data within the Availability Zone, or in the event of Availability Zone destruction resulting from disasters, such as earthquakes and floods.

If you choose One Zone, choose the **Availability Zone** that you want the file system created in, or leave the default setting.

Note

One Zone storage classes are not available in all Availability Zones in AWS Regions where Amazon EFS is available.

For more information, see [EFS storage classes \(p. 20\)](#).

6. Choose **Create** to create a file system that uses the following service recommended settings:

- Automatic backups turned on, for more information, see [Using AWS Backup to back up and restore Amazon EFS file systems \(p. 138\)](#).
- Mount targets – Amazon EFS creates mount targets with the following settings:
 - For file systems that use Standard storage classes, a mount target is created in each Availability Zone in the AWS Region in which the file system is created. For file systems that use One Zone storage classes, a single mount target is created in the Availability Zone you specified.
 - Located in the default subnets of the VPC you selected.
 - Using the VPC's default security group – You can manage security groups after the file system is created.

For more information, see [Managing file system network accessibility \(p. 95\)](#).


- General Purpose performance mode – For more information, see [Performance modes \(p. 131\)](#).
- Bursting throughput mode – For more information, see [Throughput modes \(p. 132\)](#).
- Encryption of data at rest enabled using your default key for Amazon EFS (aws/elasticfilesystem) – For more information, see [Encrypting data at rest \(p. 190\)](#).
- Lifecycle Management – Amazon EFS creates the file system with the following lifecycle policies:
 - **Transition into IA** set to **30 days since last access**
 - **Transition out of IA** set to **On first access**

For more information, see [Amazon EFS lifecycle management \(p. 100\)](#).

After you create the file system, you can customize the file system's settings with the exception of availability and durability, encryption, and performance mode.

If you want to create a file system with a customized configuration, choose **Customize**. For more information about creating a file system with customized settings, see [Creating a file system with custom settings using the Amazon EFS console \(p. 28\)](#).

7. The **File systems** page appears with a banner across the top showing the status of the file system you created. A link to access the file system details page appears in the banner when the file system becomes available.



For more information about file system status, see [File system status \(p. 109\)](#).

Step 2: Create your EC2 resources and launch your EC2 instance

Note

You can't use Amazon EFS with Microsoft Windows-based Amazon EC2 instances with Amazon EFS.

In this step you will create a new Amazon EC2 instance running Amazon Linux 2, and configure it to automatically mount the EFS file system you just created in [Step 1. \(p. 15\)](#)

Before you can launch and connect to an Amazon EC2 instance, you need to create a key pair, unless you already have one. You can create a key pair using the Amazon EC2 console, and then you can launch your EC2 instance.

To create a key pair

- Follow the steps in [Setting up with Amazon EC2](#) in the *Amazon EC2 User Guide for Linux Instances* to create a key pair. If you already have a key pair, you don't need to create a new one. You can use your existing key pair for this exercise.

To launch the EC2 instance and mount an EFS file system

- Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
- Choose **Launch Instance**.
- In **Step 1: Choose an Amazon Machine Image (AMI)**, find an Amazon Linux 2 AMI at the top of the list and choose **Select**.
- In **Step 2: Choose an Instance Type**, choose **Next: Configure Instance Details**.

5. In **Step 3: Configure Instance Details**, provide the following information:
 - Leave **Number of instances** at one.
 - Leave **Purchasing option** at the default setting.
 - For **Network**, choose the entry for the same VPC that you noted when you created your EFS file system in [Step 1: Create your Amazon EFS file system \(p. 15\)](#).
 - For **Subnet**, choose a default subnet in any Availability Zone.
 - For **File systems**, make sure that the EFS file system that you created in [Step 1: Create your Amazon EFS file system \(p. 15\)](#) is selected. The path shown next to the file system ID is the mount point that the EC2 instance will use, which you can change.
 - The **User data** automatically includes the commands for mounting your Amazon EFS file system.
6. Choose **Next: Add Storage**.
7. Choose **Next: Add Tags**.
8. Name your instance and choose **Next: Configure Security Group**.
9. In **Step 6: Configure Security Group**, set **Assign a security group** to **Select an existing security group**. Choose the default security group to make sure that it can access your EFS file system.
10. Choose **Review and Launch**.
11. Choose **Launch**.
12. Select the check box for the key pair that you created, and then choose **Launch Instances**.

Once the EC2 instance is created and becomes available, it will be mounted to your EFS file system. At this point, you will be able to transfer files to your EFS file system.

Step 3: Transfer files to Amazon EFS using AWS DataSync

Now that you have created a functioning Amazon EFS file system, you can use AWS DataSync to transfer files from an existing file system to Amazon EFS. AWS DataSync is a data transfer service that simplifies, automates, and accelerates moving and replicating data between on-premises storage systems and AWS storage services over the internet or AWS Direct Connect. AWS DataSync can transfer your file data, and also file system metadata such as ownership, timestamps, and access permissions.

Before you begin

In this step, we assume that you have the following:

- A source NFS file system that you can transfer files from. This source system needs to be accessible over NFS version 3, version 4, or 4.1. Example file systems include those located in an on-premises data center, self-managed in-cloud file systems, and Amazon EFS file systems.
- A destination Amazon EFS file system to transfer files to. If you don't have an Amazon EFS file system, create one. For more information, see [Getting started with Amazon Elastic File System \(p. 14\)](#).
- Your server and network meet the AWS DataSync requirements. To learn more, see the [AWS DataSync requirements](#).

To transfer files from a source location to a destination location using AWS DataSync, you do the following:

- Download and deploy an agent in your environment and activate it.
- Create and configure a source and destination location.

- Create and configure a task.
- Run the task to transfer files from the source to the destination.

To learn how to transfer files from an existing on-premises file system to your EFS file system, see [Getting Started with AWS DataSync](#) in the *AWS DataSync User Guide*. To learn how to transfer files from an existing in-cloud file system to your EFS file system, see [Deploying the AWS DataSync Agent as an Amazon EC2 Instance](#) in the *AWS DataSync User Guide*, and the [Amazon EFS AWS DataSync In-Cloud Transfer Quick Start and Scheduler](#).

Step 4: Clean up resources and protect your AWS account

This guide includes walkthroughs that you can use to further explore Amazon EFS. Before you perform this clean-up step, you can use the resources you've created and connected to in this Getting Started exercise in those walkthroughs. For more information, see [Walkthroughs \(p. 155\)](#). After you finish the walkthroughs, or if you don't want to explore the walkthroughs, take the following steps to clean up your resources and protect your AWS account.

To clean up resources and protect your account

1. Connect to your Amazon EC2 instance.
2. Unmount the Amazon EFS file system with the following command.

```
$ sudo umount efs
```

3. Open the Amazon EFS console at <https://console.aws.amazon.com/efs/>.
4. Choose the Amazon EFS file system that you want to delete from the list of file systems.
5. For **Actions**, choose **Delete file system**.
6. In the **Permanently delete file system** dialog box, type the file system ID for the Amazon EFS file system that you want to delete, and then choose **Delete File System**.
7. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
8. Choose the Amazon EC2 instance that you want to terminate from the list of instances.
9. For **Actions**, choose **Instance State** and then choose **Terminate**.
10. In **Terminate Instances**, choose **Yes, Terminate** to terminate the instance that you created for this Getting Started exercise.
11. In the navigation pane, choose **Security Groups**.
12. Select the name of the security group that you created for this Getting Started exercise in [Step 2: Create your EC2 resources and launch your EC2 instance \(p. 17\)](#) as a part of the Amazon EC2 instance Launch Wizard.

Warning

Don't delete the default security group for your VPC.

13. For **Actions**, choose **Delete Security Group**.
14. In **Delete Security Group**, choose **Yes, Delete** to delete the security group you created for this Getting Started exercise.

EFS storage classes

Amazon EFS offers a range of storage classes that are designed for different use cases. These include EFS Standard, EFS Standard-Infrequent Access (Standard-IA), EFS One Zone, and EFS One Zone-Infrequent Access (EFS One Zone-IA). The following sections provide details of these storage classes.


Amazon EFS Standard and Standard-IA storage classes

EFS Standard and Standard-IA storage classes are regional storage classes that are designed to provide continuous availability to data, even when one or more Availability Zones in an AWS Region are unavailable. They offer the highest levels of availability and durability by storing file system data and metadata redundantly across multiple geographically separated Availability Zones within a Region.

The EFS Standard storage class is used for frequently accessed files. It is the storage class to which customer data is initially written for Standard storage classes.

The Standard-IA storage class reduces storage costs for files that are not accessed every day. It does this without sacrificing the high availability, high durability, elasticity, and POSIX file system access that Amazon EFS provides. We recommend Standard-IA storage if you need your full dataset to be readily accessible and want to automatically save on storage costs for files that are less frequently accessed. Examples include keeping files accessible to satisfy audit requirements, performing historical analysis, or performing backup and recovery. Standard-IA storage is compatible with all Amazon EFS features, and is available in all AWS Regions where Amazon EFS is available.

The following diagram illustrates the features of EFS Standard storage class.



Amazon EFS One Zone and EFS One Zone-IA storage classes


EFS One Zone and One Zone-IA storage classes are designed to provide continuous availability to data within a single Availability Zone. The EFS One Zone storage classes store file system data and metadata

redundantly within a single Availability Zone in an AWS Region. Because they store data in a single AWS Availability Zone, data that is stored in these storage classes might be lost in the event of a disaster or other fault that affects all copies of the data within the Availability Zone, or in the event of Availability Zone destruction.

For added data protection, Amazon EFS automatically backs up file systems using One Zone storage classes with AWS Backup. You can restore file system backups to any operational Availability Zone within an AWS Region, or you can restore them to a different Region. Amazon EFS file system backups that are created and managed using AWS Backup are replicated to three Availability Zones and are designed for 11 9's durability. For more information, see [Resilience in AWS Backup](#).

EFS One Zone–Standard is used for frequently accessed files. It is the storage class to which customer data is initially written for One Zone storage classes.

The EFS One Zone–IA storage class reduces storage costs for files that are not accessed every day. We recommend EFS One Zone–IA storage if you need your full dataset to be readily accessible and want to automatically save on storage costs for files that are less frequently accessed. One Zone–IA storage is compatible with all Amazon EFS features, and is available in all AWS Regions where Amazon EFS is available. The following diagram illustrates the features of the EFS One Zone storage class.



Infrequent access performance

First-byte latency when reading from or writing to either of the infrequent access (IA) storage classes is higher than that for the EFS Standard or EFS One Zone storage classes.

You can move files from an IA storage class to a frequently accessed storage class by copying them to another location on your file system. If you want your files to remain in the frequently accessed storage

class, turn off Lifecycle Management on the file system, and then copy your files to a new location on the file system.

Comparing Amazon EFS storage classes

The following table compares the storage classes, including their availability, durability, minimum storage duration, and other considerations.

Storage class	Designed for	Durability (designed for)	Availability	Availability zones	Other considerations
EFS Standard	Frequently accessed data requiring the highest durability and availability.	99.999999999% (11 9's)	99.99%	>=3	None
EFS Standard-Infrequent Access (IA)	Long lived, infrequently accessed data requiring the highest durability and availability.	99.999999999% (11 9's)	99.99%	>=3	Per GB retrieval fees apply.
EFS One Zone	Frequently accessed data that doesn't require highest levels of durability and availability.	99.999999999% (11 9's)*	99.90%	1	Not resilient to the loss of the Availability Zone.
EFS One Zone-IA	Long lived, infrequently accessed data that doesn't require highest levels of durability and availability.	99.999999999% (11 9's)*	99.90%	1	Not resilient to the loss of the Availability Zone. Per GB retrieval fees apply.

*Because EFS One Zone storage classes store data in a single AWS Availability Zone, data stored in these storage classes may be lost in the event of a disaster or other fault that affects all copies of the data within the Availability Zone, or in the event of Availability Zone destruction.

Storage class pricing

You are billed for the amount of data in each storage class. You are also billed for data access when files in IA storage are read and when files are transitioned to IA storage from EFS Standard or One Zone storage. The AWS bill displays the capacity for each storage class and the metered access against the file system's IA storage class (Standard-IA or One Zone-IA). To learn more, see [Amazon EFS Pricing](#).

For file systems using Bursting Throughput, the allowed throughput is determined based on the amount of the data stored in the EFS Standard and EFS One Zone storage classes only. For file systems using Provisioned Throughput mode, you're billed for the throughput provisioned above what you are provided based on the amount of data that is in the EFS Standard and EFS One Zone storage classes. For more information on EFS performance, see [Throughput modes \(p. 132\)](#).

Note

You don't incur data access charges when using AWS Backup to back up lifecycle management-enabled EFS file systems. To learn more about AWS Backup and EFS lifecycle management, see [EFS storage classes \(p. 139\)](#).

Viewing storage class size

You can view how much data is stored in each storage class of your file system using the Amazon EFS console, the AWS CLI, or the EFS API.

Viewing storage data size in the Amazon EFS console

The **Metered size** tab on the **File system details** page displays the current metered size of the file system in binary multiples of bytes (kilobytes, mebibytes, gibibytes, and tebibytes). The metric is emitted every 15 minutes and lets you view your file system's metered size over time. **Metered size** displays the following information for the file system storage size:

- **Total size** is the size (in binary bytes) of data stored in the file system, including all storage classes.
- **Size in Standard / One Zone** is the size (in binary bytes) of data stored in the EFS Standard or EFS One Zone storage class.
- **Size in Standard-IA / One Zone-IA** is the size (in binary bytes) of data stored in the Standard-IA or One Zone-IA storage class, depending on whether your file system uses Standard or One Zone storage classes.

You can also view the **Storage bytes** metric on the **Monitoring** tab on the **File system details** page in the Amazon EFS console. For more information, see [Accessing CloudWatch metrics \(p. 120\)](#).

Viewing storage data size using the AWS CLI

You can view how much data is stored in each storage class of your file system using the AWS CLI or EFS API. View data storage details by calling the `describe-file-systems` CLI command (the corresponding API operation is [DescribeFileSystems \(p. 311\)](#)).

```
$ aws efs describe-file-systems \
--region us-west-2 \
--profile adminuser
```

In the response, `SizeInBytes>ValueInIA` displays the last metered size in bytes in the file system's IA storage class, either Standard-IA or One Zone-IA. `ValueInStandard` displays the last metered size in bytes in either the EFS Standard or EFS One Zone storage class, depending on the file system configuration. Added together, they equal the size of the entire file system, displayed by `Value`.

```
{
  "FileSystems": [
    {
      "OwnerId": "251839141158",
      "CreationToken": "MyFileSystem1",
      "FileSystemId": "fs-47a2c22e",
      "PerformanceMode": "generalPurpose",
      "CreationTime": 1403301078,
      "LifeCycleState": "created",
      "NumberOfMountTargets": 1,
      "SizeInBytes": {
        "Value": 29313417216,
        "ValueInIA": 675432,
```

```
        "ValueInStandard": 29312741784
    },
    "ThroughputMode": "bursting"
}
]
```

For additional ways to view and measure disk usage, see [Metering Amazon EFS file system objects \(p. 106\)](#).

Using Amazon EFS storage classes

To use the EFS Standard and Standard-IA storage classes, create a file system that stores data redundantly across multiple Availability Zones in an AWS Region. To do this when creating a file system using the AWS Management Console, choose **Availability and Durability**, and then choose **Regional**.

To use the Standard-IA storage class, you must enable the Amazon EFS lifecycle management feature. When enabled, lifecycle management automates moving files from Standard storage to IA storage. When you create a file system using the console, **Lifecycle management** is enabled by default with a setting of **30 days since last access**. For more information, see [Amazon EFS lifecycle management \(p. 100\)](#).

To use the EFS One Zone and One Zone-IA storage classes, you must create a file system that stores data redundantly within a single Availability Zone in an AWS Region. To do this when creating a file system using the console, choose **Availability and Durability**, and then choose **One Zone**.

To use the One Zone-IA storage class, you must enable the Amazon EFS lifecycle management feature. When enabled, lifecycle management automates moving files from Standard storage to IA storage. When you create a file system using the console, **Lifecycle management** is enabled by default with a setting of **30 days since last access**. For more information, see [Amazon EFS lifecycle management \(p. 100\)](#).

Working with Amazon EFS resources

Amazon EFS provides elastic, shared file storage that is POSIX-compliant. The file system you create supports concurrent read and write access from multiple Amazon EC2 instances and is accessible from all of the Availability Zones in the AWS Region where it is created.

You can mount an Amazon EFS file system on EC2 instances in your virtual private cloud (VPC) based on Amazon VPC using the Network File System versions 4.0 and 4.1 protocol (NFSv4). For more information, see [Amazon EFS: How it works \(p. 3\)](#).

As an example, suppose that you have one or more EC2 instances launched in your VPC. Now you want to create and use a file system on these instances. Following are the typical steps you need to perform to use Amazon EFS file systems in the VPC:

- **Create an Amazon EFS file system** – When creating a file system, we recommend that you consider using the **Name** tag because the **Name** tag value appears in the console and makes it easier to identify the file system. You can also add other optional tags to the file system.
- **Create mount targets for the file system** – To access the file system in your VPC and mount the file system to your Amazon EC2 instance, you must create mount targets in the VPC subnets.
- **Create security groups** – Both an Amazon EC2 instance and a mount target need to have associated security groups. These security groups act as a virtual firewall that controls the traffic between them. You can use the security group you associated with the mount target to control inbound traffic to your file system by adding an inbound rule to the mount target security group that allows access from a specific EC2 instance. Then, you can mount the file system only on that EC2 instance.

If you are new to Amazon EFS, we recommend that you try the following exercises that provide a first-hand, end-to-end experience of using an Amazon EFS file system:

- [Getting started \(p. 14\)](#) – The Getting Started exercise walks you through creating a file system with the service recommended settings using the Amazon EFS QuickCreate wizard, mounting it on an EC2 instance, and testing the setup. The console takes care of many things for you and helps you set up the end-to-end experience quickly.
- [Walkthrough: Create an Amazon EFS file system and mount it on an Amazon EC2 instance using the AWS CLI \(p. 155\)](#) – The walkthrough is similar to the Getting Started exercise, but it uses the AWS Command Line Interface (AWS CLI) to perform most of the tasks. Because the AWS CLI commands closely map to the Amazon EFS API, the walkthrough can help you familiarize yourself with the Amazon EFS API operations.

For more information about creating EFS resources and accessing a file system, see the following topics.

Topics

- [Resource IDs \(p. 26\)](#)
- [Creating Amazon EFS file systems \(p. 26\)](#)
- [Deleting an Amazon EFS file system \(p. 36\)](#)
- [Creating and managing mount targets and security groups \(p. 37\)](#)
- [Creating security groups \(p. 43\)](#)
- [Creating file system policies \(p. 45\)](#)

- [Creating and deleting access points \(p. 47\)](#)
- [Tagging Amazon EFS resources \(p. 50\)](#)

Resource IDs

Amazon EFS assigns unique resource identifiers (IDs) to all EFS resources when they are created. All EFS resource IDs consist of a resource identifier and a combination of digits 0-9 and lowercase letters a-f.

Prior to October 2021, the IDs assigned to newly created file system and mount target resources used 8 characters after the hyphen (for example, fs-12345678). From May 2021 to October 2021, we changed the IDs of these resource types to use 17 characters after the hyphen (for example, fs-1234567890abcdef0). Depending on when your account was created, you might have file system and mount target resources with short IDs, though any new resources of these types receive the longer IDs. The IDs of existing EFS resources never change.

Creating Amazon EFS file systems

Following, you can find an explanation about how to create an Amazon EFS file system using the AWS Management Console and the AWS CLI.

If you are new to Amazon EFS, we recommend you go through the Getting Started exercise, which provides console-based end-to-end instructions to create and access a file system in your VPC. For more information, see [Getting started \(p. 14\)](#).

Topics

- [Requirements \(p. 26\)](#)
- [Configuration options when creating a file system \(p. 27\)](#)
- [Creating a file system with custom settings using the Amazon EFS console \(p. 28\)](#)
- [Creating a file system using the AWS CLI \(p. 34\)](#)

Requirements

This section describes requirements and prerequisites for creating Amazon EFS file systems.

Creation token and idempotency

Idempotency ensures that an API request completes only once. With idempotent requests, if the original request completes successfully, subsequent requests have no additional effect. This is useful to prevent duplicate jobs from being created when you interact with the Amazon EFS API.

The Amazon EFS API supports idempotency with client request tokens. A *client request token* is a unique string that you specify when you make a create job request.

A client request token can be any string that includes up to 64 ASCII characters. If you reuse a client request token within one minute of a successful request, the API returns the job details of the original request.

If you use the console, it generates the token for you. If you use the **Custom Create** flow in the console, the creation token that is generated for you has the following format:

```
"CreationToken": "console-d215fa78-1f83-4651-b026-facaf8a7da7"
```

If you use QuickCreate to create a file system with the service recommended settings, the creation token has the following format:

```
"CreationToken": "quickCreated-d7f56c5f-e433-41ca-8307-9d9c0f8a77a2"
```

Permissions required

To create EFS resources such as a file system and access points, a user must have AWS Identity and Access Management (IAM) permissions for the corresponding API action and resource.

You can perform any Amazon EFS operations using your AWS account root user credentials, but using root user credentials is not recommended. We recommend that you create IAM users in your account, and grant them permissions for Amazon EFS actions with user policies. You can also use roles to grant cross-account permissions. Amazon Elastic File System also uses an AWS IAM service-linked role that includes permissions required to call other AWS services on your behalf. For more information about managing permissions for the API actions, see [Identity and access management for Amazon EFS \(p. 196\)](#).

Configuration options when creating a file system

You can create a file system using the Amazon EFS console or using the AWS Command Line Interface (AWS CLI). You can also create file systems programmatically using AWS SDKs or the Amazon EFS API directly.

When creating an Amazon EFS file system using the custom create flow or the AWS CLI, you can choose settings for the following file system features and configuration options.

Availability and durability

Availability and durability refer to the redundancy with which an Amazon EFS file system stores data within an AWS Region. You have the following choices for your file system's availability and durability:

- Choosing **Regional** creates a file system that uses [Standard storage classes \(p. 20\)](#) that store file system data and metadata redundantly across all Availability Zones within an AWS Region. You can also create mount targets in each Availability Zone in the AWS Region. **Regional** offers the highest levels of availability and durability.
- Choosing **One Zone** creates a file system that uses [One Zone storage classes \(p. 20\)](#) that store file system data and metadata redundantly within a single Availability Zone. File systems using One Zone storage classes can have only a single mount target which is located in the Availability Zone in which the file system is created.

Amazon EFS One Zone storage classes store data in a single AWS Availability Zone. Therefore, data stored in these storage classes may be lost in the event of a disaster or other fault that affects all copies of the data within the Availability Zone, or in the event of Availability Zone destruction.

If you choose One Zone, you can choose the Availability Zone in which the file system is created.

Automatic backups

Automatic backups are always enabled by default when you create a file system using the console. When you use the CLI or API to create a file system, automatic backups are enabled by default only when you are creating file systems using One Zone storage classes. For more information, see [Automatic backups \(p. 140\)](#).

EFS Lifecycle Management and EFS Intelligent-Tiering

EFS Intelligent-Tiering uses lifecycle management to automatically move files into and out of the lower-cost Infrequent Access (IA) storage class based on access patterns. When you create a file system using the AWS Management Console, the file system's lifecycle policy is configured with the following default settings:

- **Transition into IA** set to **30 days since last access**
- **Transition out of IA** set to **After first access**

When you create a file system using the AWS CLI, API or SDKs, you cannot set a lifecycle policy. You have to wait until the file system is created, and then use the [PutLifecycleConfiguration \(p. 345\)](#) API action to update the lifecycle configuration. For more information, see [Amazon EFS lifecycle management \(p. 100\)](#).

Performance modes

When creating a file system, you also choose a performance mode. There are two performance modes to choose from—*General Purpose* and *Max I/O*. For the majority of use cases, we recommend that you use the General Purpose performance mode for your file system. You cannot change a file system's performance mode after it is created. For more information, see [Performance modes \(p. 131\)](#).

Note

For file systems that use One Zone storage classes, only the General Purpose performance mode is available.

Throughput modes

There are two throughput modes to choose from—*Bursting Throughput* and *Provisioned Throughput*. The default Bursting Throughput mode is simple to work with and is suitable for a majority of applications and a wide range of performance requirements. Provisioned Throughput mode is for applications that require a greater ratio of throughput to storage capacity than allowed by Bursting Throughput mode. For more information, see [Throughput modes \(p. 132\)](#).

Note

Additional charges are associated with using Provisioned Throughput mode. For more information, see [Amazon EFS pricing](#).

Encryption

You can enable encryption at rest when creating a file system. If you enable encryption at rest for your file system, all data and metadata stored on it are encrypted. You can enable encryption in transit later, when you mount the file system. For more information about Amazon EFS encryption, see [Data encryption in Amazon EFS \(p. 189\)](#).

To create the file system mount targets in your VPC, you must specify VPC subnets. The console pre-populates the list of VPCs in your account that are in the selected AWS Region. First, you select your VPC, and then the console lists the Availability Zones in the VPC. For each Availability Zone, you can select a subnet from the list, or use the default subnet if it exists. After you select a subnet, you can either specify an available IP address in the subnet or let Amazon EFS choose an address automatically.

Creating a file system with custom settings using the Amazon EFS console

This section describes the process of using the Amazon EFS console to create an EFS file system with customized settings instead of using the service recommended settings. For more information about


creating a file system using the service recommended settings, see [Step 1: Create your Amazon EFS file system \(p. 15\)](#).

Creating an Amazon EFS file system using the console is a four-step process:

- Step 1 - Configure general file system settings, including availability and durability, lifecycle management, performance and throughput modes, and encryption of data at rest.
- Step 2 - Configure file system network settings, including the virtual private cloud (VPC) and mount targets. For each mount target, set the Availability Zone, subnet, IP address, and security groups.
- Step 3 - (Optional) Create a file system policy to control NFS client access to the file system.
- Step 4 - Review the file system settings, make any changes, and then create the file system.

Step 1: Configure file system settings

1. Sign in to the AWS Management Console and open the Amazon EFS console at <https://console.aws.amazon.com/efs/>.
2. Choose **Create file system** to open the **Create file system** dialog box.



3. Choose **Customize** to create a customized file system instead of creating a file system using the service recommended settings.

The **File system settings** page appears.

General

Name - *optional*
 Name your file system.

Optional. Apply a name to your file system

Name must not be longer than 256 characters, and must only contain letters, numbers, and these characters: + - = . _ : /

Availability and Durability
 Choose Regional (recommended) to create a file system using regional storage classes. Choose One Zone to create a file system using One Zone storage classes. [Learn more](#)

Regional
Stores data redundantly across multiple AZs

One Zone
Stores data redundantly within a single AZ

Automatic backups
 Automatically backup your file system data with AWS Backup using recommended settings. Additional pricing applies. [Learn more](#)

Enable automatic backups

Lifecycle management
 EFS Intelligent-Tiering uses Lifecycle Management to automatically achieves the right price and performance blend for your application by placing your files in the appropriate storage class. [Learn more](#)

Transition into IA
 Transition files from Standard to Standard-Infrequent Access.

30 days since last access ▾

Transition out of IA
 Transition files from Standard-Infrequent Access to Standard.

On first access ▾

Performance mode
 Set your file system's performance mode based on IOPS required. [Learn more](#)

General Purpose
Ideal for latency-sensitive use cases, like web serving environments and content management systems

Max I/O
Scale to higher levels of aggregate throughput and operations per second

Throughput mode
 Set how your file system's throughput limits are determined. [Learn more](#)

Bursting
Throughput scales with file system size

Provisioned
Throughput fixed at specified amount

Encryption
 Choose to enable encryption of your file system's data at rest. Uses the AWS KMS service key (aws/elasticfilesystem) by default. [Learn more](#)

Enable encryption of data at rest

▼ Customize encryption settings

KMS key
 Choose or input a KMS key ID or ARN to use instead of the AWS KMS service key. [Learn more](#)

Choose an AWS KMS key or enter an ARN

[Create an AWS KMS key](#)

4. For **General** settings, enter the following.
 - a. (Optional) Enter a **Name** for the file system.
 - b. For **Availability and Durability**, choose one of the following:

- Choose **Regional** to create a file system that uses Standard storage classes. Standard storage classes store file system data and metadata redundantly across all Availability Zones within an AWS Region. **Regional** offers the highest levels of availability and durability.
- Choose **One Zone** to create a file system that uses One Zone storage classes. One Zone storage classes store file system data and metadata redundantly within a single Availability Zone.

Amazon EFS One Zone storage classes store data in a single AWS Availability Zone. Therefore, data stored in these storage classes might be lost in the event of a disaster or other fault that affects all copies of the data within the Availability Zone, or in the event of Availability Zone destruction.

If you choose One Zone, choose the **Availability Zone** that you want the file system created in, or keep the default setting.

For more information, see [EFS storage classes \(p. 20\)](#).

- Automatic backups are turned on by default. You can turn off automatic backups by clearing the check box. For more information, see [Using AWS Backup to back up and restore Amazon EFS file systems \(p. 138\)](#).
- For **Lifecycle management**, the default policy sets **Transition into IA to 30 days after last access** and **Transition out of IA to After first access**. If you don't want to use intelligent tiering, choose **None** for each of these policy settings. For more information, see [Amazon EFS lifecycle management \(p. 100\)](#).
- Choose a **Performance mode**, either the default **General Purpose** mode or **Max I/O**. You can change the performance mode after the file system becomes available. For more information, see [Performance modes \(p. 131\)](#).

Note

Only the General Purpose mode is available for file systems that are configured for One Zone availability and durability.

- Choose a **Throughput mode**, either the default **Bursting** mode or **Provisioned** mode.

If you choose **Provisioned**, the **Provisioned Throughput (MiB/s)** section appears. Enter the amount of **Throughput** to provision for file system requests.

The amount of **Maximum Read Throughput** is displayed at three times the amount of the throughput you enter. EFS file systems meter read requests at one-third the rate of other requests. After you enter the throughput, an estimate of the monthly cost for the file system is displayed.

You can change the amount of write throughput anytime after the file system becomes available. For more information, see [Throughput modes \(p. 132\)](#).

- For **Encryption**, encryption of data at rest is enabled by default. It uses your AWS Key Management Service (AWS KMS) EFS service key (aws/elasticfilesystem) by default. To choose a different KMS key to use for encryption, expand **Customize encryption settings** and choose a key from the list. Or, enter a KMS key ID or Amazon Resource Name (ARN) for the KMS key you want to use.

If you need to create a new key, choose **Create an AWS KMS key** to launch the AWS KMS console and create a new key.

You can turn off encryption of data at rest by clearing the check box.

- (Optional) Add tag key-value pairs to your file system.
- Choose **Next** to continue to the **Network Access** step in the configuration process.

Step 2: Configure network access

In Step 2, you configure the file system's network settings, including the VPC and mount targets.

The screenshot shows the 'Network access' configuration step of the EFS creation wizard. It includes sections for 'Virtual Private Cloud (VPC)' and 'Mount targets'. Under 'Mount targets', there are six entries, one for each Availability Zone (us-east-1a through us-east-1f). Each entry has fields for 'Availability zone', 'Subnet ID', 'IP address' (set to 'Automatic'), and 'Security groups'. The 'Security groups' dropdown for each row shows 'sg-1004395a default'. Below the table is a note: 'You can only create one mount target per Availability Zone.'

1. Choose the **Virtual Private Cloud (VPC)** where you want EC2 instances to connect to your file system. For more information, see [Managing file system network accessibility \(p. 95\)](#).
2. For **Mount targets**, you create one or more mount targets for your file system. For each mount target, set the following properties:
 - **Availability zone** – By default, a mount target is configured in each Availability Zone in an AWS Region. If you don't want a mount target in a particular Availability Zone, choose **Remove** to delete the mount target for that zone. Create a mount target in every Availability Zone that you plan to access your file system from – there is no cost to do so.
 - **Subnet ID** – Choose from the available subnets in an Availability Zone. The default subnet is preselected.
 - **IP Address** – By default, Amazon EFS chooses the IP address automatically from the available addresses in the subnet. Or, you can enter a specific IP address that's in the subnet. Although mount targets have a single IP address, they are redundant, highly available network resources.

- **Security groups** – You can specify one or more security groups for the mount target. For more information, see [Using VPC security groups for Amazon EC2 instances and mount targets \(p. 218\)](#).

To add another security group, or to change the security group, choose **Choose security groups** and add another security group from the list. If you don't want to use the default security group, you can delete it. For more information, see [Creating security groups \(p. 43\)](#).

3. Choose **Add mount target** to create a mount target for an Availability Zone that doesn't have one. If a mount target is configured for each Availability Zone, this choice is not available.
4. Choose **Next** to continue. The **File system policy** page is displayed.

Step 3: Create a file system policy (optional)

Optionally, you can create a file system policy for your file system. An EFS file system policy is an IAM resource policy that you use to control NFS client access to the file system. For more information, see [Using IAM to control file system data access \(p. 206\)](#).

File system policy

Policy options

Select one or more of these common policy options, or create a more advanced policy using the editor. [Learn more](#)

Prevent root access by default*

Enforce read-only access by default*

Enforce in-transit encryption for all clients

* Identity-based policies can override these default permissions.

Policy editor

```

1  [
2   "Version": "2012-10-17",
3   "Id": "efs-policy-wizard-30808dfc-7d49-4696-b13d-952ff9ec93ba",
4   "Statement": [
5     {
6       "Sid": "efs-statement-c3fdfadc-56f2-4e47-99b6-cf474447d5ec",
7       "Effect": "Allow",
8       "Principal": {
9         "AWS": "*"
10      },
11      "Action": [
12        "elasticfilesystem:ClientMount"
13      ]
14    },
15    {
16      "Sid": "efs-statement-dd35422c-86c0-42aa-bb58-5fc3917011a5",
17      "Effect": "Deny",
18      "Principal": {
19        "AWS": "*"
20      },
21      "Action": "*",
22      "Condition": {
23        "Bool": {
24          "aws:SecureTransport": "false"
25        }
26      }
27    }
28  ]

```

Manual changes will prevent the use of checkboxes until the editor is cleared.

Cancel Save

1. In **Policy options**, you can choose any combination of the available preconfigured policies:
 - Prevent root access by default
 - Enforce read-only access by default
 - Enforce in-transit encryption for all clients
2. Use the **Policy editor** to customize a preconfigured policy or to create your own policy. When you choose one of the preconfigured policies, the JSON policy definition appears in the policy editor. You can edit the JSON to create a policy of your choice. To undo your changes, choose **Clear**.

The preconfigured policies become available once again in **Policy options**.


3. Choose **Next** to continue. The **Review and create** page appears.

Step 4: Review and create

1. Review each of the file system configuration groups. You can make changes to each group at this time by choosing **Edit**.
2. Choose **Create** to create your file system and return to the **File systems** page.

A banner across the top shows that the new file system is being created. A link to access the new file system details page appears in the banner when the file system becomes available.

3. The **File systems** page displays the file system and its configuration details, as shown following.



Creating a file system using the AWS CLI

When using the AWS CLI, you create these resources in order. First, you create a file system. Then, you can create mount targets and any additional optional tags for the file system using corresponding AWS CLI commands.

The following examples use the `adminuser` as the `profile` parameter values. You need to use an appropriate user profile to provide your credentials. For information about the AWS CLI, see [Installing the AWS CLI in the AWS Command Line Interface User Guide](#).

- To create an encrypted file system that uses Standard storage classes, with automatic backups enabled, use the Amazon EFS `create-file-system` CLI command (the corresponding operation is [CreateFileSystem \(p. 262\)](#)), as shown following.

```
aws efs create-file-system \
--creation-token creation-token \
--encrypted \
--backup \
--performance-mode generalPurpose \
--throughput-mode bursting \
```

```
--region aws-region \
--tags Key=key,Value=value Key=key1,Value=value1 \
--profile adminuser
```

For example, the following `create-file-system` command creates a file system in the `us-west-2` AWS Region. The command specifies `MyFirstFS` as the creation token. For a list of AWS Regions where you can create an Amazon EFS file system, see the [Amazon Web Services General Reference](#).

```
aws efs create-file-system \
--creation-token MyFirstFS \
--backup \
--encrypted \
--performance-mode generalPurpose \
--throughput-mode bursting \
--region us-west-2 \
--tags Key=Name,Value="Test File System" Key=developer,Value=rhoward \
--profile adminuser
```

After successfully creating the file system, Amazon EFS returns the file system description as JSON, as shown in the following example.

```
{
    "OwnerId": "123456789abcd",
    "CreationToken": "MyFirstFS",
    "Encrypted": true,
    "FileSystemId": "fs-c7a0456e",
    "CreationTime": 1422823614.0,
    "LifeCycleState": "creating",
    "Name": "Test File System",
    "NumberOfMountTargets": 0,
    "SizeInBytes": {
        "Value": 6144,
        "ValueInIA": 0,
        "ValueInStandard": 6144
    },
    "PerformanceMode": "generalPurpose",
    "ThroughputMode": "bursting",
    "Tags": [
        {
            "Key": "Name",
            "Value": "Test File System"
        }
    ]
}
```

- The following example creates a file system that uses One Zone storage classes in the `us-west-2a` Availability Zone using the `availability-zone-name` property.

```
aws efs create-file-system \
--creation-token MyFirstFS \
--availability-zone-name us-west-2a \
--backup \
--encrypted \
--performance-mode generalPurpose \
--throughput-mode bursting \
--region us-west-2 \
--tags Key=Name,Value="Test File System" Key=developer,Value=rhoward \
--profile adminuser
```

After successfully creating the file system, Amazon EFS returns the file system description as JSON, as shown in the following example.

```
{  
    "AvailabilityZoneId": "usw-az1",  
    "AvailabilityZoneName": "us-west-2a",  
    "OwnerId": "123456789abcd",  
    "CreationToken": "MyFirstFS",  
    "Encrypted": true,  
    "FileSystemId": "fs-c7a0456e",  
    "CreationTime": 1422823614.0,  
    "LifeCycleState": "creating",  
    "Name": "Test File System",  
    "NumberOfMountTargets": 0,  
    "SizeInBytes": {  
        "Value": 6144,  
        "ValueInIA": 0,  
        "ValueInStandard": 6144  
    },  
    "PerformanceMode": "generalPurpose",  
    "ThroughputMode": "bursting",  
    "Tags": [  
        {  
            "Key": "Name",  
            "Value": "Test File System"  
        }  
    ]  
}
```

Amazon EFS also provides the `describe-file-systems` CLI command (the corresponding API operation is [DescribeFileSystems \(p. 311\)](#)), which you can use to retrieve a list of file systems in your account, as shown following.

```
aws efs describe-file-systems \  
--region aws-region \  
--profile adminuser
```

Amazon EFS returns a list of the file systems in your AWS account created in the specified Region.

Deleting an Amazon EFS file system

File system deletion is a destructive action that you can't undo. You lose the file system and any data you have in it. Any data that you delete from a file system is gone, and you can't restore the data. When users delete data from a file system, that data is immediately rendered unusable. EFS force-overwrites the data in an eventual manner.

Note

You cannot delete a file system that is part of an EFS Replication configuration. You need to delete the replication configuration first. For more information, see [Deleting a replication configuration \(p. 152\)](#).


Important

You should always unmount a file system before you delete it.

Using the console

To delete a file system

1. Open the Amazon Elastic File System console at <https://console.aws.amazon.com/efs/>.
2. Select the file system that you want to delete in the **File systems** page.
3. Choose **Delete**.
4. In the **Delete file system** dialog box, enter the file system id shown, and choose **Confirm** to confirm the delete.



The console simplifies the file system deletion for you. First it deletes the associated mount targets, and then it deletes the file system.

Using the CLI


Before you can use the AWS CLI command to delete a file system, you must delete all of the mount targets and access points created for the file system.

For example AWS CLI commands, see [Step 4: Clean up \(p. 166\)](#).


Creating and managing mount targets and security groups

After you create an Amazon EFS file system, you can create mount targets. For Amazon EFS file systems that use Standard storage classes, you can create a mount target in each Availability Zone in an AWS Region. For EFS file systems that use One Zone storage classes, you can only create a single mount target in the same Availability Zone as the file system. Then you can mount the file system on compute instances, including Amazon EC2, Amazon ECS, and AWS Lambda in your virtual private cloud (VPC).

The following diagram shows an Amazon EFS file system that uses Standard storage classes, with mount targets created in all Availability Zones in the VPC.



The following diagram shows an Amazon EFS file system using One Zone storage classes, with a single mount target created in the same Availability Zone as the file system. Accessing the file system using the EC2 instance in the us-west-2c Availability Zone incurs data access charges because it is located in a different Availability Zone than the mount target.



The mount target security group acts as a virtual firewall that controls the traffic. For example, it determines which clients can access the file system. This section explains the following:

- Managing mount target security groups and enabling traffic.
- Mounting the file system on your clients.
- NFS-level permissions considerations.

Initially, only the root user on the Amazon EC2 instance has read-write-execute permissions on the file system. This topic discusses NFS-level permissions and provides examples that show you how to grant permissions in common scenarios. For more information, see [Working with users, groups, and permissions at the Network File System \(NFS\) Level \(p. 221\)](#).

You can create mount targets for a file system using the AWS Management Console, AWS CLI, or programmatically using the AWS SDKs. When using the console, you can create mount targets when you first create a file system or after the file system is created.


For instructions to create mount targets using the Amazon EFS console when creating a new file system, see [Step 2: Configure network access \(p. 32\)](#).

Managing mount targets using the Amazon EFS console

Use the following procedure to add or modify mount targets for an existing Amazon EFS file system.

To manage mount targets on an Amazon EFS file system (console)

1. Sign in to the AWS Management Console and open the Amazon EFS console at <https://console.aws.amazon.com/efs/>.
2. In the left navigation pane, choose **File systems**. The **File systems** page displays the EFS file systems in your account.
3. Choose the file system that you want to manage mount targets for by choosing its **Name** or the **File system ID** to display the file system details page.
4. Choose **Network** to display the list of existing mount targets.



The screenshot shows the 'Network' tab of the Amazon EFS console. At the top, there are tabs for Metered size, Monitoring, Tags, File system policy, Access points, and Network. The Network tab is selected. Below the tabs, there is a search bar and a 'Manage' button. A table lists six mount targets, each with columns for Availability zone, Mount target ID, Subnet ID, Mount target state, IP address, and Network interface ID. All mount targets are listed as 'Available'. The table includes a header row and a footer row with a total count of 6.

Metered size	Monitoring	Tags	File system policy	Access points	Network
Network					
Availability zone	Mount target ID	Subnet ID	Mount target state	IP address	Network interface ID
us-east-1a	fsmt-dd3be55d	subnet-01234567	Available	172.31.23.131	eni-0e7b50f58a307a926
us-east-1b	fsmt-df3be55f	subnet-01234568	Available	172.31.37.177	eni-0e88508e32ec15070
us-east-1c	fsmt-e03be560	subnet-01234569	Available	172.31.11.13	eni-06343f9498849fa58
us-east-1d	fsmt-e33be563	subnet-0123456a	Available	172.31.92.207	eni-0d54638d38e2a59ea
us-east-1e	fsmt-db3be55b	subnet-0123456b	Available	172.31.51.232	eni-0ff1865ac2f141a39
us-east-1f	fsmt-e53be565	subnet-0123456c	Available	172.31.68.84	eni-07d8cc978670bfe5a

5. Choose **Manage** to display the **Availability zone** page and make modifications.

Availability zone

Virtual Private Cloud (VPC)
Choose the VPC where you want EC2 instances to connect to your file system. [Learn more](#)

vpc-24b47d5e	default
--------------	---------

You must delete all existing mount targets in order to change the VPC of your file system.

Mount targets

A mount target provides an NFSv4 endpoint at which you can mount an Amazon EFS file system. We recommend creating one mount target per Availability Zone. [Learn more](#)

Availability zone	Subnet ID	IP address	Security groups
us-east-1a	subnet- 	172.31.21.124	Choose security gro... ▾ sg-1004395a X <small>default</small>
us-east-1b	subnet- 	172.31.38.206	Choose security gro... ▾ sg-1004395a X <small>default</small>
us-east-1c	subnet- 	172.31.6.202	Choose security gro... ▾ sg-1004395a X <small>default</small>
us-east-1d	subnet- 	172.31.88.219	Choose security gro... ▾ sg-1004395a X <small>default</small>
us-east-1e	subnet- 	172.31.61.113	Choose security gro... ▾ sg-1004395a X <small>default</small>
us-east-1f	subnet- 	172.31.72.83	Choose security gro... ▾ sg-1004395a X <small>default</small>

[Add mount target](#)

You can only create one mount target per Availability Zone.

[Cancel](#) [Save](#)

On this page, for existing mount targets, you can add and remove security groups, or delete the mount target. You can also create new mount targets.

Note

For file systems that use One Zone storage classes, you can only create a single mount target that is in the same Availability Zone as the file system.

- To remove a security group from a mount target, choose **X** next to the security group ID.
- To add a security group to a mount target, choose **Select security groups** to display a list of available security groups. Or, enter a security group ID in the search field at the top of the list.
- To queue a mount target for deletion, choose **Remove**.

Note

Before deleting a mount target, first unmount the file system.

- To add a mount target, choose **Add mount target**. This is available only for file systems that use Standard storage classes, and if mount targets do not already exist in each Availability Zone for the AWS Region.

6. Choose **Save** to save any changes.

To change the VPC for an Amazon EFS file system (console)

To change the VPC for a file system's network configuration, you must delete all of the file system's existing mount targets.

1. Open the Amazon Elastic File System console at <https://console.aws.amazon.com/efs/>.

2. In the left navigation pane, choose **File systems**. The **File systems** page shows the EFS file systems in your account.
3. For the file system that you want to change the VPC for, choose the **Name** or the **File system ID**. The file system details page is displayed.
4. Choose **Network** to display the list of existing mount targets.
5. Choose **Manage**. The **Availability zone** page appears.
6. Remove all mount targets displayed on the page.
7. Choose **Save** to save changes and delete the mount targets. The **Network** tab shows the mount targets status as **deleting**.
8. When all the mount targets statuses show as **deleted**, choose **Manage**. The **Availability zone** page appears.
9. Choose the new VPC from the **Virtual Private Cloud (VPC)** list.
10. Choose **Add mount target** to add a new mount target. For each mount target you add, enter the following:
 - An **Availability zone**
 - A **Subnet ID**
 - An **IP address**, or keep it set to **Automatic**
 - One or more **Security groups**
11. Choose **Save** to implement the VPC and mount target changes.

Managing mount targets using the AWS CLI

Note

For file systems that use One Zone storage classes, you can only create a single mount target that is in the same Availability Zone as the file system.

To create a mount target (CLI)

- To create a mount target, use the `create-mount-target` CLI command (corresponding operation is [CreateMountTarget \(p. 272\)](#)), as shown following.

```
$ aws efs create-mount-target \
--file-system-id file-system-id \
--subnet-id subnet-id \
--security-group ID-of-the-security-group-created-for-mount-target \
--region aws-region \
--profile adminuser
```

The following example shows the command with sample data.

```
$ aws efs create-mount-target \
--file-system-id fs-0123467 \
--subnet-id subnet-b3983dc4 \
--security-group sg-01234567 \
--region us-east-2 \
--profile adminuser
```

After successfully creating the mount target, Amazon EFS returns the mount target description as JSON as shown in the following example.

```
{  
    "MountTargetId": "fsmt-f9a14450",  
    "NetworkInterfaceId": "eni-3851ec4e",  
}
```

```
"FileSystemId": "fs-b6a0451f",
"LifeCycleState": "available",
"SubnetId": "subnet-b3983dc4",
"OwnerId": "23124example",
"IpAddress": "10.0.1.24"
}
```

To retrieve a list of mount targets for a file system (CLI)

- You can also retrieve a list of mount targets created for a file system using the [describe-mount-targets](#) CLI command (the corresponding operation is [DescribeMountTargets \(p. 318\)](#)), as shown following.

```
$ aws efs describe-mount-targets --file-system-id fs-a576a6dc
```

```
{
    "MountTargets": [
        {
            "OwnerId": "111122223333",
            "MountTargetId": "fsmt-48518531",
            "FileSystemId": "fs-a576a6dc",
            "SubnetId": "subnet-88556633",
            "LifeCycleState": "available",
            "IpAddress": "172.31.25.203",
            "NetworkInterfaceId": "eni-0123456789abcdef1",
            "AvailabilityZoneId": "use2-az2",
            "AvailabilityZoneName": "us-east-2b"
        },
        {
            "OwnerId": "111122223333",
            "MountTargetId": "fsmt-5651852f",
            "FileSystemId": "fs-a576a6dc",
            "SubnetId": "subnet-44223377",
            "LifeCycleState": "available",
            "IpAddress": "172.31.46.181",
            "NetworkInterfaceId": "eni-0123456789abcdefa",
            "AvailabilityZoneId": "use2-az3",
            "AvailabilityZoneName": "us-east-2c"
        },
        {
            "OwnerId": "111122223333",
            "MountTargetId": "fsmt-5751852e",
            "FileSystemId": "fs-a576a6dc",
            "SubnetId": "subnet-a3520bcb",
            "LifeCycleState": "available",
            "IpAddress": "172.31.12.219",
            "NetworkInterfaceId": "eni-0123456789abcdef0",
            "AvailabilityZoneId": "use2-az1",
            "AvailabilityZoneName": "us-east-2a"
        }
    ]
}
```

To delete an existing mount target (CLI)

- To delete an existing mount target, use the [delete-mount-target](#) AWS CLI command (corresponding operation is [DeleteMountTarget \(p. 294\)](#)), as shown following.

Note

Before deleting a mount target, first unmount the file system.

```
$ aws efs delete-mount-target \
--mount-target-id mount-target-ID-to-delete \
--region aws-region-where-mount-target-exists
```

The following is an example with sample data.

```
$ aws efs delete-mount-target \
--mount-target-id fsmt-5751852e \
--region us-east-2 \
```

To modify the security group of an existing mount target

- To modify security groups that are in effect for a mount target, use the `modify-mount-target-security-groups` AWS CLI command (the corresponding operation is [ModifyMountTargetSecurityGroups \(p. 334\)](#)) to replace any existing security groups, as shown following.

```
$ aws efs modify-mount-target-security-groups \
--mount-target-id mount-target-ID-whose-configuration-to-update \
--security-groups security-group-ids-separated-by-space \
--region aws-region-where-mount-target-exists \
--profile adminuser
```

The following is an example with sample data.

```
$ aws efs modify-mount-target-security-groups \
--mount-target-id fsmt-5751852e \
--security-groups sg-1004395a sg-1114433a \
--region us-east-2
```

For more information, see [Walkthrough: Create an Amazon EFS file system and mount it on an Amazon EC2 instance using the AWS CLI \(p. 155\)](#).

Creating security groups

Note

The following section is specific to Amazon EC2 and discusses how to create security groups so you can use Secure Shell (SSH) to connect to any instances that have mounted Amazon EFS file systems. If you're not using SSH to connect to your Amazon EC2 instances, you can skip this section.

Both an Amazon EC2 instance and a mount target have associated security groups. These security groups act as a virtual firewall that controls the traffic between them. If you don't provide a security group when creating a mount target, Amazon EFS associates the default security group of the VPC with it.

Regardless, to enable traffic between an EC2 instance and a mount target (and thus the file system), you must configure the following rules in these security groups:

- The security groups you associate with a mount target must allow inbound access for the TCP protocol on the NFS port from all EC2 instances on which you want to mount the file system.
- Each EC2 instance that mounts the file system must have a security group that allows outbound access to the mount target on the NFS port.

To change the security groups associated with your EFS file systems mount targets, see [Creating and managing mount targets and security groups \(p. 37\)](#).

For more information about security groups, see [Amazon EC2 Security Groups](#) in the *Amazon EC2 User Guide for Linux Instances*.

Creating security groups using the AWS Management Console

You can use the AWS Management Console to create security groups in your VPC. To connect your Amazon EFS file system to your Amazon EC2 instance, you must create two security groups: one for your Amazon EC2 instance and another for your Amazon EFS mount target.

1. Create two security groups in your VPC. For instructions, see [Creating a Security Group](#) in the *Amazon VPC User Guide*.
2. In the VPC console, verify the default rules for these security groups. Both security groups should have only an outbound rule that allows traffic to leave.
3. You need to authorize additional access to the security groups as follows:
 - a. Add a rule to the EC2 security group to allow SSH access to the instance on port 22 as shown following. This is useful if you're planning on using an SSH client like PuTTY to connect to and administer your EC2 instance through a terminal interface. Optionally, you can restrict the **Source** address.



For instructions, see [Adding, removing, and updating rules](#) in the *Amazon VPC User Guide*.

- b. Add a rule to the mount target security group to allow inbound access from the EC2 security group on TCP port 2049. The security group in the **Source** column is the security group associated with the EC2 instance.



To view the security groups associated with your file systems mount targets, in the EFS console, choose the **Network** tab in the File system details page. For more information, see [Creating and managing mount targets and security groups \(p. 37\)](#).

Note

You don't need to add an outbound rule because the default outbound rule allows all traffic to leave (otherwise, you will need to add an outbound rule to open TCP connection on the NFS port, identifying the mount target security group as the destination).

4. Verify that both security groups now authorize inbound and outbound access as described in this section.

Creating security groups using the AWS CLI

For an example that shows how to create security groups using the AWS CLI, see [Step 1: Create Amazon EC2 resources \(p. 157\)](#).

Creating file system policies

You can create a file system policy using the Amazon EFS console or using the AWS CLI. You can also create a file system policy programmatically using AWS SDKs or the Amazon EFS API directly. EFS file system policies have a 20,000 character limit. For more information about using an EFS file system policy and examples, see [Using IAM to control file system data access \(p. 206\)](#).

Note

Amazon EFS file system policy changes can take several minutes to take effect.

Creating a file system policy (console)

1. Open the Amazon Elastic File System console at <https://console.aws.amazon.com/efs/>.
2. Choose **File Systems**.
3. On the **File systems** page, choose the file system that you want to edit or create a file system policy for. The details page for that file system is displayed.
4. Choose **File system policy**, then choose **Edit**. The **File system policy** page appears.

The screenshot shows the 'File system policy' editor interface. On the left, the 'Policy options' pane lists several pre-configured policy options: Prevent root access by default*, Enforce read-only access by default*, Prevent anonymous access, and Enforce in-transit encryption for all clients. Below this is a 'Grant additional permissions' section and a 'Permissions' table where a Principal ARN is mapped to Read Access. On the right, the 'Policy editor (JSON)' pane displays the JSON code for the current policy:

```

1  {
2    "Version": "2012-10-17",
3    "Statement": [
4      {
5        "Sid": "efr-policy-wizard-5ab3f12-0036-457f-92fe-4047cb9f354",
6        "Effect": "Allow",
7        "Principal": "*",
8        "Action": "AWS::"
9      },
10     {
11       "Action": [
12         "elasticfilesystem:ClientRootAccess",
13         "elasticfilesystem:ClientWrite",
14         "elasticfilesystem:ClientMount"
15       ],
16       "Condition": {
17         "Bool": {
18           "elasticfilesystem:AccessedViaMountTarget": "true"
19         }
20       }
21     },
22     {
23       "Sid": "efr-policy-wizard-7371b922-c09e-46ce-a61f-44f90309c28a",
24       "Effect": "Allow",
25       "Principal": "*",
26       "Action": [
27         "elasticfilesystem:ClientMount"
28       ]
29     }
30   ]
31 }
32
33
34
35

```

Below the JSON code, a note states: 'Manual changes will prevent the use of the policy options on the left until the editor is cleared.'

5. In **Policy options**, you can choose any combination of the preconfigured file system policies:
 - Prevent root access by default - This option removes ClientRootAccess from the set of allowed EFS actions.
 - Enforce read-only access by default - This option removes ClientWriteAccess from the set of allowed EFS actions.
 - Prevent anonymous access - This option removes ClientMount from the set of allowed EFS actions.
 - Enforce in-transit encryption for all clients - This option denies access to unencrypted clients.

When you choose a preconfigured policy, the policy JSON object is displayed in the **Policy editor** pane.

6. Use **Grant additional permissions** to grant file system permissions to additional IAM principals, including another AWS account. Choose **Add**, and enter the principal ARN of the entity that you are granting permissions to. Then choose the **Permissions** that you want to grant. The additional permissions are shown in the **Policy editor**.
 7. You can use the **Policy editor** to customize a preconfigured policy or to create your own file system policy. When you use the editor, the preconfigured policy options become unavailable. To clear the current file system policy and start creating a new policy, choose **Clear**.
When you clear the editor, the preconfigured policies become available once again.
8. After you complete editing the policy, choose **Save**.

Creating a file system policy (CLI)

In the following example, the [put-file-system-policy](#) CLI command creates a file system policy that allows the specified AWS account read-only access to the EFS file system. The equivalent API command is [PutFileSystemPolicy \(p. 341\)](#).

```
aws efs put-file-system-policy --file-system-id fs-01234567 --policy '{  
    "Id": "1",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": [  
                "elasticfilesystem:ClientMount"  
            ],  
            "Principal": {  
                "AWS": "arn:aws:iam::111122223333:root"  
            }  
        }  
    ]  
}'
```

```
{  
    "FileSystemId": "fs-01234567",  
    "Policy": {"  
        "Version" : "2012-10-17",  
        "Id" : "1",  
        "Statement" : [  
            {  
                "Sid" : "efs-statement-7c8d8687-1c94-4fdc-98b7-555555555555",  
                "Effect" : "Allow",  
                "Principal" : {  
                    "AWS" : "arn:aws:iam::111122223333:root"  
                },  
                "Action" : [  
                    "elasticfilesystem:ClientMount"  
                ],  
                "Resource" : "arn:aws:elasticfilesystem:us-east-2:555555555555:file-system/  
fs-01234567"  
            }  
        ]  
    }  
}
```

Creating and deleting access points

You can create Amazon EFS access points using the AWS Management Console or the AWS CLI. You can also create access points programmatically using the AWS SDKs or the Amazon EFS API directly. You cannot modify an access point once it is created. A file system can have a maximum of 120 access points. For more information about EFS access points, see [Working with Amazon EFS access points \(p. 224\)](#).

The following procedures describe how to create an access point using the console and the AWS CLI.

Creating an access point (console)

You can create and delete Amazon EFS access points using the AWS Management Console, the AWS Command Line Interface (AWS CLI), and the Amazon EFS API and SDKs. You cannot modify an access point once it is created. A file system can have a maximum of 120 access points.

Note

If multiple requests to create access points on the same file system are sent in quick succession, and the file system is nearing the limit of 120 access points, you may experience a throttling response for these requests. This is to ensure that the file system does not exceed the stated access point quota.

1. Open the Amazon Elastic File System console at <https://console.aws.amazon.com/efs/>.
2. Choose **Access points** to open the **Access points** window.
3. Choose **Create access point** to display the **Create access point** page.

You can also open the **Create access point** page by choosing **File Systems**. Choose a file system **Name** or **File system ID** and then choose **Access points** and **Create access point** to create an access point for that file system.

Create access point

An access point is an application-specific entry point into an EFS file system that makes it easier to manage application access to shared datasets. [Learn more](#)

Details

File system

Choose the file system to which your access point is associated.

Enter a file system name or ID

Name - optional

EFS access point name

Maximum of 256 Unicode letters, whitespace, and numbers, plus + - = . _ : /

Root directory path - optional

Connections use the specified path as the file system's virtual root directory [Learn more](#)

Defaults to /

Example: "/foo/bar"

POSIX user - optional

The full POSIX identity on the access point that is used for all file operations by NFS clients. [Learn more](#)

User ID

POSIX user ID used for all file system operations using this access point.

POSIX UID

Accepts values from 0 to 4294967295

Group ID

POSIX group ID used for all file system operations using this access point.

POSIX GID

Accepts values from 0 to 4294967295

Secondary group IDs

Secondary POSIX group IDs used for all file system operations using this access point.

Example: "123,456,789"

A comma-separated list of valid POSIX group IDs

Root directory creation permissions - optional

EFS will automatically create the specified root directory with these permissions if the directory does not already exist. [Learn more](#)

Owner user ID

Owner user ID for the access point's root directory, if the directory does not already exist.

POSIX user ID to apply to path

Accepts values from 0 to 4294967295

Owner group ID

Owner group ID for the access point's root directory, if the directory does not already exist.

POSIX group ID to apply to path

Accepts values from 0 to 4294967295

Permissions

POSIX permissions to apply to the root directory path

Example: "0755"

An octal number representing the file's mode bits.

- a. Enter the following information in the **Details** panel:

- **File system** – Enter a file system name or ID and choose the matching file system, or just choose from the list that appears when you choose the input field.
- **(Optional) Name** – Enter a name for the access point.

- (Optional) **Root directory path** – You can specify a root directory for the access point; the default access point root is /. To enter a root directory path, use the format /foo/bar. For more information, see [Enforcing a root directory with an access point \(p. 226\)](#).
- b. (Optional) In the **POSIX user** panel, you can specify the full POSIX identity to use to enforce user and group information for all file operations by NFS clients using the access point. For more information, see [Enforcing a user identity using an access point \(p. 225\)](#).
 - **User ID** – Enter a numeric POSIX user ID for the user.
 - **Group ID** – Enter a numeric POSIX group ID for the user.
 - **Secondary group IDs** – Enter an optional comma-separated list of secondary group IDs.
- c. (Optional) For **Root directory creation permissions** you can specify the permissions to use when Amazon EFS creates the root directory path, if specified and the root directory doesn't already exist. For more information, see [Enforcing a root directory with an access point \(p. 226\)](#).

Note

If you don't specify any root directory ownership and permissions, and the root directory does not already exist, EFS will not create the root directory. Any attempts to mount the file system using the access point will fail.

- **Owner user ID** – enter the numeric POSIX user ID to use as the root directory owner.
- **Owner group ID** – enter the numeric POSIX group ID to use as the root directory owner group.
- **Permissions** – enter the Unix mode of the directory. A common configuration is 755. Ensure that the execute bit is set for the access point user so they are able to mount.

4. Choose **Create access point** to create the access point using this configuration.

Creating an access point (CLI)

In the following example, the `create-access-point` CLI command creates an access point for an EFS file system. The equivalent API command is [CreateAccessPoint \(p. 257\)](#).

```
aws efs create-access-point --file-system-id fs-abcdef0123456789a --client-token
  010102020-3 \
--root-directory Path=/efs/mobileapp/
east/,CreationInfo={OwnerUid=0,OwnerGid=11,Permissions=775} \
--posix-user Uid=22,Gid=4 \
--tags key=Name,value=east-users
```

If the request is successful, the CLI responds with the access point description.

```
{
  "ClientToken": "010102020-3",
  "Name": "east-users",
  "AccessPointId": "fsap-abcd1234ef5678901",
  "AccessPointArn": "arn:aws:elasticfilesystem:us-east-2:111122223333:access-point/fsap-
abcd1234ef5678901",
  "FileSystemId": "fs-01234567",
  "LifeCycleState": "creating",
  "OwnerId": "111122223333",
  "PosixUser": {
    "Gid": 4,
    "Uid": 22
  },
  "RootDirectory": {
    "CreationInfo": {
      "OwnerGid": 0,
```

```
        "OwnerUid": 11,
        "Permissions": "775"
    },
    "Path": "/efs/mobileapp/east",
},
"Tags": []
}
```

Note

If multiple requests to create access points on the same file system are sent in quick succession, and the file system is nearing the limit of 120 access points, you may experience a throttling response for these requests. This is to ensure that the file system does not exceed the stated access point quota.

Deleting an access point

When you delete an access point, any clients using the access point lose access to the Amazon EFS file system that it's configured for.

Deleting an access point (console)

1. Open the Amazon Elastic File System console at <https://console.aws.amazon.com/efs/>.
2. In the left navigation pane, choose **Access points** to open the **Access points** page.
3. Select the access point to delete.
4. Choose **Delete**.
5. Choose **Confirm** to confirm the action and delete the access point.

Deleting an access point (CLI)

In the following example, the `delete-access-point` CLI command deletes the specified access point. The equivalent API command is [DeleteAccessPoint \(p. 287\)](#). If the command is successful, the service returns an HTTP 204 response with an empty HTTP body.

```
aws efs delete-access-point --access-point-id fsap-092e9f80b3fb5e6f3 --client-token
010102020-3
```

Tagging Amazon EFS resources

To help you manage your Amazon EFS resources, you can assign your own metadata to each resource in the form of *tags*. Tags enable you to categorize your AWS resources in different ways, for example, by purpose, owner, or environment. This is useful when you have many resources of the same type—you can quickly identify a specific resource based on the tags that you've assigned to it. This topic describes tags and shows you how to create them.

Tag basics

A tag is a label that you assign to an AWS resource. Each tag consists of a key and an optional value, both of which you define.

Tags enable you to categorize your AWS resources in different ways, for example, by purpose, owner, or environment. For example, you could define a set of tags for your account's Amazon EFS file systems that helps you track each file system's owner.

We recommend that you devise a set of tag keys that meets your needs for each resource type. Using a consistent set of tag keys makes it easier for you to manage your resources. You can search and filter the resources based on the tags you add.

Tags don't have any semantic meaning to Amazon EFS and are interpreted strictly as a string of characters. Also, tags are not automatically assigned to your resources. You can edit tag keys and values, and you can remove tags from a resource at any time. You can set the value of a tag to an empty string, but you can't set the value of a tag to null. If you add a tag that has the same key as an existing tag on that resource, the new value overwrites the old value. If you delete a resource, any tags for the resource are also deleted.

Tag your resources

You can tag Amazon EFS file system and access point resources that already exist in your account.

You can use the Amazon EFS console to apply tags to existing resources by using the **Tags** tab on the resource details screen. The Amazon EFS console enables you to specify tags for a resource when you create the resource; for example, a tag with a key of Name and a value that you specify. In most cases, the console applies the tags immediately after the resource is created (rather than during resource creation). The console may organize resources according to the Name tag, but this tag doesn't have any semantic meaning to the Amazon EFS service.

If you're using the Amazon EFS API, the AWS CLI, or an AWS SDK, you can use the `TagResource` EFS API action to apply tags to existing resources. Additionally, some resource-creating actions enable you to specify tags for a resource when the resource is created.

The AWS CLI commands for managing tags, and the equivalent Amazon EFS API actions, are listed in the following table.

CLI command	Description	Equivalent API operation
<code>tag-resource</code>	Add new tags or update existing tags	TagResource (p. 350)
<code>list-tags-for-resource</code>	Retrieve existing tags	ListTagsForResource (p. 331)
<code>untag-resource</code>	Delete existing tags	UntagResource (p. 353)

Tag restrictions

The following basic restrictions apply to tags:

- Maximum number of tags per resource – 50
- For each resource, each tag key must be unique, and each tag key can have only one value.
- Maximum key length – 128 Unicode characters in UTF-8
- Maximum value length – 256 Unicode characters in UTF-8
- Although Amazon EFS allows for any character in its tags, other services are more restrictive. The allowed characters across services are: letters, numbers, and spaces representable in UTF-8, and the following characters: + - = . _ : / @.
- Tag keys and values are case-sensitive.
- The `aws :` prefix is reserved for AWS use. If a tag has a tag key with this prefix, then you can't edit or delete the tag's key or value. Tags with the `aws :` prefix do not count against your tags per resource limit.

You can't update or delete a resource based solely on its tags; you must specify the resource identifier. For example, to delete file systems that you tagged with a tag key called DeleteMe, you must use the `DeleteFileSystem` action with the resource identifiers of the file system, such as `fs-1234567890abcdef0`.

When you tag public or shared resources, the tags you assign are available only to your AWS account; no other AWS account will have access to those tags. For tag-based access control to shared resources, each AWS account must assign its own set of tags to control access to the resource.

You can tag Amazon EFS file system and access point resources.

Using tags for access control

You can use tags to control access to Amazon EFS resources and to implement attribute-based access control (ABAC). For more information, see [Using tags with Amazon EFS \(p. 213\)](#).

Note

EFS replication does not support using tags for attribute-based access control (ABAC).

Using file systems in Amazon EFS

Amazon Elastic File System presents a standard file-system interface that supports full file-system access semantics. Using Network File System (NFS) version 4.1 (NFSv4.1), you can mount your Amazon EFS file system on any Amazon Elastic Compute Cloud (Amazon EC2) Linux-based instance. After your system is mounted, you can work with the files and directories just as you do with a local file system. For more information on mounting, see [Mounting EFS file systems \(p. 68\)](#).

After you create a file system and mount it on your EC2 instance, to use your file system effectively you need to know about managing NFS-level permissions for users, groups, and related resources. When you first create your file system, there is only one root directory at /. By default, only the root user (UID 0) has read-write-execute permissions. For other users to modify the file system, the root user must explicitly grant them access. You use EFS access points to provision directories that are writable from a specific application. For more information, see [Working with users, groups, and permissions at the Network File System \(NFS\) Level \(p. 221\)](#) and [Working with Amazon EFS access points \(p. 224\)](#).

Related topics

[Amazon EFS: How it works \(p. 3\)](#)

[Getting started \(p. 14\)](#)

[Walkthroughs \(p. 155\)](#)

Using the amazon-efs-utils Tools

The `amazon-efs-utils` package is an open-source collection of Amazon EFS tools that is also referred to as the Amazon EFS client. Following, you can find a description of the Amazon EFS client. The Amazon EFS client includes the EFS mount helper, which makes it easier to mount EFS file systems. Using the EFS client enables the ability to use Amazon CloudWatch to monitor an EFS file system's mount status. You need to install the Amazon EFS client on an Amazon EC2 instance prior to mounting an EFS file system.

Topics

- [Overview \(p. 54\)](#)
- [Using AWS Systems Manager to automatically install or update Amazon EFS clients \(p. 55\)](#)
- [Manually installing the Amazon EFS client \(p. 57\)](#)
- [Installing botocore \(p. 63\)](#)
- [Upgrading stunnel \(p. 64\)](#)

Overview

The Amazon EFS client (`amazon-efs-utils`) is an open-source collection of Amazon EFS tools. There's no additional cost to use the Amazon EFS client, which you can download from GitHub here: <https://github.com/aws/efs-utils>. The `amazon-efs-utils` package is available in the Amazon Linux package repositories, and you can build and install the package on other Linux distributions. You can also use AWS Systems Manager to automatically install or update the package. For more information, see [Using AWS Systems Manager to automatically install or update Amazon EFS clients \(p. 55\)](#).

Note

The `amazon-efs-utils` package comes pre-installed on Amazon Linux and Amazon Linux 2 Amazon Machine Images (AMIs).

The Amazon EFS client includes a mount helper and tooling that makes it easier to perform encryption of data in transit for Amazon EFS file systems. A *mount helper* is a program that you use when you mount a specific type of file system. We recommend that you use the mount helper included with the Amazon EFS client to mount your Amazon EFS file systems. Using the Amazon EFS client simplifies mounting EFS file systems, and can provide improved file system performance. For more information about using the EFS client and mount helper, see [Mounting EFS file systems \(p. 68\)](#).

The following dependencies exist for `amazon-efs-utils` and are installed when you install the `amazon-efs-utils` package:

- NFS client
 - `nfs-utils` for RHEL, CentOS, Amazon Linux, and Fedora distributions
 - `nfs-common` for Debian and Ubuntu distributions
- Network relay (`stunnel` package, version 4.56 or later)
- Python (version 3.4 or later)
- OpenSSL 1.0.2 or newer

Note

By default, when using the Amazon EFS mount helper with Transport Layer Security (TLS), the mount helper enforces certificate hostname checking. The Amazon EFS mount helper uses the `stunnel` program for its TLS functionality. Some versions of Linux don't include a version of `stunnel` that supports these TLS features by default. When using one of those Linux versions, mounting an Amazon EFS file system using TLS fails.

When you've installed the `amazon-efs-utils` package, to upgrade your system's version of stunnel, see [Upgrading stunnel \(p. 64\)](#).

You can use AWS Systems Manager to manage Amazon EFS clients and automate the tasks required to install or update the `amazon-efs-utils` package on your EC2 instances. For more information, see [Using AWS Systems Manager to automatically install or update Amazon EFS clients \(p. 55\)](#).

For issues with encryption, see [Troubleshooting encryption \(p. 252\)](#).

Supported distributions

The Amazon EFS client has been verified against the following Linux and Mac distributions:

Distribution	Package type	init system
Amazon Linux 2017.09	rpm	upstart
Amazon Linux 2	rpm	systemd
CentOS 7, 8	rpm	systemd
Debian 9, 10	deb	systemd
Fedora 28 - 32	rpm	systemd
macOS Big Sur		launchd
macOS Monterey		launchd
OpenSUSE Leap, Tumbleweed	rpm	systemd
Red Hat Enterprise Linux (RHEL) 7, 8	rpm	systemd
SUSE Linux Enterprise Server (SLES) 12, 15	rpm	systemd
Ubuntu 16.04 LTS, 18.04 LTS, 20.04 LTS	deb	systemd

For a complete list of supported distributions that the package has been verified against, see the `amazon-efs-utils` [README](#) on Github.

In the following sections, you can learn how to install the Amazon EFS client on your EC2 Linux and Mac instances.

Using AWS Systems Manager to automatically install or update Amazon EFS clients

You can use AWS Systems Manager to simplify the management of the Amazon EFS client (`amazon-efs-utils`). AWS Systems Manager is an AWS service that you can use to view and control your infrastructure on AWS. With AWS Systems Manager you can automate the tasks required to install or update the `amazon-efs-utils` package on your EC2 instances. The Systems Manager capabilities like Distributor and State Manager enable you to automate the following processes:

- Maintaining version control over the Amazon EFS client.
- Centrally storing and systematically distributing the Amazon EFS client to your Amazon EC2 instances.
- Automate the process of keeping your Amazon EC2 instances in a defined state.

For more information, see [AWS Systems Manager User Guide](#).

What the Amazon EFS client does during installation

You use the Amazon EFS client to automate monitoring Amazon CloudWatch logs for file system mount status and upgrade stunnel to the latest version for selected Linux distributions. When you install the Amazon EFS client on your Amazon EC2 instances using Systems Manager, it takes the following actions:

- Installs the botocore package using the same steps described in [Installing botocore \(p. 63\)](#). The Amazon EFS client uses botocore to monitor the EFS file system mount status.
- Enables the monitoring of EFS file system mount status in CloudWatch logs by updating `efs-utils.conf`. For more information, see [Monitoring EFS file system mount status \(p. 119\)](#).
- For EC2 instances running RHEL7 or CentOS7, the Amazon EFS client automatically upgrades stunnel as described in [Upgrading stunnel \(p. 64\)](#). Upgrading stunnel is required in order to successfully mount an EFS file system using TLS, and the stunnel version shipped with RHEL7 and CentOS7 does not support the Amazon EFS client (`amazon-efs-utils`).

Systems Manager Distributor supported operating systems

Your EC2 instances must be running one of the following operating systems in order to be used with AWS Systems Manager to automatically update or install the Amazon EFS client.

Platform	Platform version	Architecture
Amazon Linux	2017.09, 2018.03	x86_64
Amazon Linux 2	2.0	x86_64, arm64 (Amazon Linux 2, A1 instance types)
CentOS	7, 8	x86_64
Red Hat Enterprise Linux (RHEL)	7, 8	x86_64, arm64 (RHEL 7.6 and later, A1 instance types)
SUSE Linux Enterprise Server (SLES)	12, 15	x86_64
Ubuntu Server	16.04, 18.04, 20.04	x86_64, arm64 (Ubuntu Server 16 and later, A1 instance types)

How to use AWS Systems Manager to automatically install or update amazon-efs-utils

There are two one-time configurations required to setup Systems Manager to automatically install or update the `amazon-efs-utils` package.

1. Configure an AWS Identity and Access Management (IAM) instance profile with the required permissions.
2. Configure an Association (including the schedule) used for installation or updates by the State Manager

Step 1: Configure an IAM instance profile with the required permissions

By default, AWS Systems Manager doesn't have permission to manage your Amazon EFS clients and install or update the amazon-efs-utils package. You must grant access to Systems Manager by using an AWS Identity and Access Management (IAM) instance profile. An instance profile is a container that passes IAM role information to an Amazon EC2 instance at launch.

Use the `AmazonElasticFileSystemsUtils` AWS managed permission policy to assign the appropriate permissions to roles. You can create a new role for your instance profile or add the `AmazonElasticFileSystemsUtils` permission policy to an existing role. You must then use this instance profile to launch your Amazon EC2 instances. For more information, see [Step 4: Create an IAM instance profile for Systems Manager](#).

Step 2: Configure an Association used by State Manager for installing or updating the Amazon EFS client

The `amazon-efs-utils` package is included with Distributor and is ready for you to deploy to managed EC2 instances. To view the latest version of `amazon-efs-utils` that is available for installation, you can use the AWS Systems Manager console or your preferred AWS command line tool. To access Distributor, open the <https://console.aws.amazon.com/systems-manager/> and choose **Distributor** in the left navigation pane. Locate **AmazonEFSUtils** in the **Owned by Amazon** section. Choose **AmazonEFSUtils** to see the package details. For more information, see [View packages](#).

Using State Manager, you can install or update the `amazon-efs-utils` package on your managed EC2 instances immediately or on a schedule. Additionally, you can ensure that `amazon-efs-utils` is automatically installed on new EC2 instances. For more information about installation or updating packages using Distributor and State Manager, see [Working with Distributor](#).

To automatically install or update the `amazon-efs-utils` package on instances using the Systems Manager console, see [Scheduling a package installation or update \(console\)](#). This will prompt you to create an association for State Manager, which defines the state you want to apply to a set of instances. Use the following inputs when you create your association:

- For **Parameters** choose **Action > Install** and **Installation Type > In-place update**.
- For **Targets** the recommended setting is **Choose all instances** to register all new and existing EC2 instances as targets to automatically install or update **AmazonEFSUtils**. Alternatively, you can specify instance tags, select instances manually, or choose a resource group to apply the association to a subset of instances. If you specify instance tags, you must launch your EC2 instances with the tags to allow AWS Systems Manager to automatically install or update the Amazon EFS client.
- For **Specify schedule** the recommended setting for **AmazonEFSUtils** is every 30 days. You can use controls to create a cron or rate schedule for the association.

To use AWS Systems Manager to mount multiple an Amazon EFS file system to multiple EC2 instances, see [Mounting EFS to multiple EC2 instances using AWS Systems Manager \(p. 85\)](#).

Manually installing the Amazon EFS client

You can manually install the Amazon EFS client on your Amazon EC2 Linux instances running Amazon Linux and Amazon Linux 2, and EC2 Mac instances running macOS Big Sur, and other supported Linux distributions. The installation procedures are described in the following sections.

Topics

- [Installing the Amazon EFS client on Amazon Linux and Amazon Linux 2 \(p. 58\)](#)
- [Installing the Amazon EFS client on other Linux distributions \(p. 58\)](#)
- [Installing the Amazon EFS client on EC2 running macOS Big Sur and macOS Monterey \(p. 62\)](#)

Installing the Amazon EFS client on Amazon Linux and Amazon Linux 2

The `amazon-efs-utils` package is available in the Amazon Linux and Amazon Linux AMI package repositories, and can be installed on EC2 instances running these AMIs. To install the Amazon EFS client on other Linux distributions, see [Installing the Amazon EFS client on other Linux distributions \(p. 58\)](#).

Note

If you're using AWS Direct Connect, you can find installation instructions in [Walkthrough: Create and mount a file system on-premises with AWS Direct Connect and VPN \(p. 173\)](#).

To install the `amazon-efs-utils` package on Amazon Linux 2 and Amazon Linux

1. Make sure that you've created an Amazon Linux or Amazon Linux 2 EC2 instance. For information on how to do this, see [Step 1: Launch an Instance](#) in the *Amazon EC2 User Guide for Linux Instances*.
2. Access the terminal for your instance through Secure Shell (SSH), and log in with the appropriate user name. For more information on how to do this, see [Connecting to your Linux instance using SSH](#) in the *Amazon EC2 User Guide for Linux Instances*.
3. Run the following command to install the `amazon-efs-utils` package.

```
sudo yum install -y amazon-efs-utils
```

Next steps

After installing `amazon-efs-utils` on your EC2 instance, proceed to the next steps for mounting your file system:

- [Install botocore \(p. 63\)](#) so that you can use Amazon CloudWatch to monitor your file system's mount status.
- [Upgrade to the latest version of stunnel \(p. 64\)](#) to enable encryption of data in transit.
- [Mount your file system \(p. 68\)](#) using the EFS mount helper.

Installing the Amazon EFS client on other Linux distributions

If you don't want to get the `amazon-efs-utils` package from Amazon Linux or Amazon Linux 2 AMIs, the `amazon-efs-utils` package is also available on GitHub.

After you clone the package, you can build and install `amazon-efs-utils` using one of the following methods, depending on the package type supported by your Linux distribution:

- **RPM** – This package type is supported by Amazon Linux, Red Hat Linux, CentOS, and similar.
- **DEB** – This package type is supported by Ubuntu, Debian, and similar.

To build and install amazon-efs-utils as an RPM package (for distributions other than OpenSUSE or SLES)

To clone amazon-efs-utils from Github

1. Connect to the EC2 instance using Secure Shell (SSH), and log in with the appropriate user name. For more information, see [Connecting to Your Linux Instance Using SSH](#) in the *Amazon EC2 User Guide for Linux Instances*.
2. Install git using the following command:

```
sudo yum -y install git
```

3. Install the rpm-build package if it's not already installed using the following command:

```
sudo yum -y install rpm-build
```

4. Clone amazon-efs-utils from GitHub using the following command.

```
git clone https://github.com/aws/efs-utils
```

To build and install the amazon-efs-utils RPM package

1. Open a terminal on your client and navigate to the directory that contains the amazon-efs-utils package.

```
cd /path/efs-utils
```

2. Install the bash make command if your operating system doesn't already have it as follows.

```
sudo yum -y install make
```

3. Install the rpm-build package if it's not already installed using the following command:

```
sudo yum -y install rpm-build
```

4. Build the amazon-efs-utils package using the following command:

```
sudo make rpm
```

5. Install the amazon-efs-utils package with the following command.

```
sudo yum -y install ./build/amazon-efs-utils*rpm
```

Next steps

After installing amazon-efs-utils on your EC2 instance, proceed to the next steps for mounting your file system:

- [Install botocore \(p. 63\)](#) so that you can use Amazon CloudWatch to monitor your file system's mount status.
- [Upgrade to the latest version of stunnel \(p. 64\)](#) to enable encryption of data in transit.
- [Mount your file system \(p. 68\)](#) using the EFS mount helper.

To build and install amazon-efs-utils as an RPM package for OpenSUSE and SLES

To clone amazon-efs-utils from GitHub

1. Connect to the EC2 instance using Secure Shell (SSH), and log in with the appropriate user name. For more information, see [Connecting to Your Linux Instance Using SSH](#) in the *Amazon EC2 User Guide for Linux Instances*.
2. Install zypper using the following command:

```
sudo zypper refresh
```

3. Install the rpm-build package and the bash **make** command if either are not already installed using the following command:

```
sudo zypper install -y git rpm-build make
```

- a. For OpenSUSE, if you get an error similar to the following:

```
File './suse/noarch/bash-completion-2.11-2.1.noarch.rpm' not found on medium  
'http://download.opensuse.org/tumbleweed/repo/oss/'
```

Run the following command to re-add the repo OSS and NON-OSS.

```
sudo zypper ar -f -n OSS http://download.opensuse.org/tumbleweed/repo/oss/ OSS  
sudo zypper ar -f -n NON-OSS http://download.opensuse.org/tumbleweed/repo/non-oss/ NON-OSS  
sudo zypper refresh
```

- b. Re-run the git install script again:

```
sudo zypper install -y git rpm-build make
```

4. Clone amazon-efs-utils from GitHub using the following command.

```
git clone https://github.com/aws/efs-utils
```

To build and install the amazon-efs-utils RPM package

1. Open a terminal on your client and navigate to the directory that contains the amazon-efs-utils package.

```
cd /path/efs-utils
```

2. Build the amazon-efs-utils package using the following command:

```
make rpm
```

3. Install the amazon-efs-utils package with the following command.

```
sudo zypper --no-gpg-checks install -y build/amazon-efs-utils*rpm
```

Next steps

After installing `amazon-efs-utils` on your EC2 instance, proceed to the next steps for mounting your file system:

- [Install botocore \(p. 63\)](#) so that you can use Amazon CloudWatch to monitor your file system's mount status.
- [Upgrade to the latest version of stunnel \(p. 64\)](#) to enable encryption of data in transit.
- [Mount your file system \(p. 68\)](#) using the EFS mount helper.

To build and install `amazon-efs-utils` as a Debian package for Ubuntu and Debian

To clone `amazon-efs-utils` from GitHub

1. Connect to the EC2 instance using Secure Shell (SSH), and log in with the appropriate user name. For more information, see [Connecting to Your Linux Instance Using SSH](#) in the *Amazon EC2 User Guide for Linux Instances*.
2. (Optional) Apply updates before installing the package with the following command:

```
sudo apt-get update
```

Install updates as needed.

3. Install `git` and `binutils`, using the following command. `binutils` is required for building DEB packages,

```
sudo apt-get -y install git binutils
```

4. Clone `amazon-efs-utils` from GitHub using the following command.

```
git clone https://github.com/aws/efs-utils
```

To build and install the `amazon-efs-utils` DEB package

1. Navigate to the directory that contains the `amazon-efs-utils` package.

```
cd /path/efs-utils
```

2. Build `amazon-efs-utils` using the following command:

```
./build-deb.sh
```

3. Install the package with the following command.

```
sudo apt-get -y install ./build/amazon-efs-utils*deb
```

Next steps

After installing `amazon-efs-utils` on your EC2 instance, proceed to the next steps for mounting your file system:

- [Install botocore \(p. 63\)](#) so that you can use Amazon CloudWatch to monitor your file system's mount status.
- [Upgrade to the latest version of stunnel \(p. 64\)](#) to enable encryption of data in transit.
- [Mount your file system \(p. 68\)](#) using the EFS mount helper.

Installing the Amazon EFS client on EC2 running macOS Big Sur and macOS Monterey

The `amazon-efs-utils` package is available for installation on EC2 Mac instances running macOS Big Sur and macOS Monterey.

To install the `amazon-efs-utils` package

1. Make sure that you've created an EC2 Mac instance running macOS Big Sur or macOS Monterey. For information on how to do this, see [Step 1: Launch an Instance](#) in the *Amazon EC2 User Guide for Mac Instances*.
2. Access the terminal for your instance through Secure Shell (SSH), and log in with the appropriate user name. For more information on how to do this, see [Connecting to your instance using SSH](#) in the *Amazon EC2 User Guide for Mac Instances*.
3. Run the following command to install `amazon-efs-utils`.

```
brew install amazon-efs-utils
```

The system responds with instructions to follow to complete the installation.

```
Perform below actions to start using efs:  
    sudo mkdir -p /Library/Filesystems/efs.fs/Contents/Resources  
    sudo ln -s /usr/local/bin/mount.efs /Library/Filesystems/efs.fs/Contents/  
Resources/mount_efs  
  
To enable watchdog for using TLS mounts:  
    sudo cp /usr/local/Cellar/amazon-efs-utils/<version>/libexec/amazon-efs-mount-  
watchdog.plist /Library/LaunchAgents  
    sudo launchctl load /Library/LaunchAgents/amazon-efs-mount-watchdog.plist
```

4. In order to mount an EFS file system, you need to ensure that the EFS mount helper in `amazon-efs-utils` is accessible by the `mount` command. To do so, run following commands:

```
sudo mkdir -p /Library/Filesystems/efs.fs/Contents/Resources  
sudo ln -s /usr/local/bin/mount.efs /Library/Filesystems/efs.fs/Contents/Resources/  
mount_efs
```

5. Run the following commands to enable the watchdog process (`amazon-efs-mount-watchdog`) that monitors the health of TLS mounts on your EFS file system.

```
sudo cp /usr/local/Cellar/amazon-efs-utils/<version>/libexec/amazon-efs-mount-  
watchdog.plist /Library/LaunchAgents  
sudo launchctl load /Library/LaunchAgents/amazon-efs-mount-watchdog.plist
```

Next steps

After installing `amazon-efs-utils` on your EC2 instance, proceed to the next steps for mounting your file system:

- [Install botocore \(p. 63\)](#) so that you can use Amazon CloudWatch to monitor your file system's mount status.
- [Upgrade to the latest version of stunnel \(p. 64\)](#) to enable encryption of data in transit.
- [Mount your file system \(p. 73\)](#) using the EFS mount helper.

Installing botocore

The Amazon EFS client uses botocore to send a file system's mount status to Amazon CloudWatch Logs. For more information, see [Monitoring EFS file system mount status \(p. 119\)](#). This section describes how install and upgrade botocore on an Amazon EC2 instance.

To install botocore as an RPM package

1. Run the following command to install wget.

```
sudo yum -y install wget
```

2. Use the following script to install the appropriate version of the pip package manager.

```
if [[ "$(python3 -V 2>&1)" =~ ^(Python 3.6.* ) ]]; then
    sudo wget https://bootstrap.pypa.io/pip/3.6/get-pip.py -O /tmp/get-pip.py
elif [[ "$(python3 -V 2>&1)" =~ ^(Python 3.5.* ) ]]; then
    sudo wget https://bootstrap.pypa.io/pip/3.5/get-pip.py -O /tmp/get-pip.py
elif [[ "$(python3 -V 2>&1)" =~ ^(Python 3.4.* ) ]]; then
    sudo wget https://bootstrap.pypa.io/pip/3.4/get-pip.py -O /tmp/get-pip.py
else
    sudo wget https://bootstrap.pypa.io/get-pip.py -O /tmp/get-pip.py
fi
```

3. Run the following commands to install botocore.

```
sudo python3 /tmp/get-pip.py
sudo pip3 install botocore
```

Or

```
sudo /usr/local/bin/pip3 install botocore
```

To install botocore as an DEB package

1. Run the following commands to install wget.

```
sudo apt-get update
sudo apt-get -y install wget
```

2. Use the following script to install the appropriate version of the pip package manager.

```
if echo $(python3 -V 2>&1) | grep -e "Python 3.6"; then
    sudo wget https://bootstrap.pypa.io/pip/3.6/get-pip.py -O /tmp/get-pip.py
elif echo $(python3 -V 2>&1) | grep -e "Python 3.5"; then
    sudo wget https://bootstrap.pypa.io/pip/3.5/get-pip.py -O /tmp/get-pip.py
elif echo $(python3 -V 2>&1) | grep -e "Python 3.4"; then
```

```
    sudo wget https://bootstrap.pypa.io/pip/3.4/get-pip.py -O /tmp/get-pip.py
else
    sudo apt-get -y install python3-distutils
    sudo wget https://bootstrap.pypa.io/get-pip.py -O /tmp/get-pip.py
fi
```

- Run the following commands to install botocore.

```
sudo python3 /tmp/get-pip.py
sudo pip3 install botocore
```

Or

```
sudo /usr/local/bin/pip3 install botocore
```

If you are installing botocore on Debian10 or Ubuntu20, use the following commands to install botocore in the specified target folder.

- For Debian10:

```
sudo python3 /tmp/get-pip.py
sudo pip3 install --target /usr/lib/python3/dist-packages botocore
```

- For Ubuntu20:

```
sudo /usr/local/bin/pip3 install --target /usr/lib/python3/dist-packages botocore
```

To install botocore on a Mac instance

- Run the following command to install botocore on your Mac instance.

```
sudo pip3 install botocore
```

Upgrading botocore

To upgrade to the latest compatible version of botocore, use the `--upgrade` option. For example:

```
sudo pip3 install botocore --upgrade
```

Upgrading stunnel

Encryption of data in transit with the Amazon EFS mount helper requires OpenSSL version 1.0.2 or newer, and a version of `stunnel` that supports both Online Certificate Status Protocol (OCSP) and certificate hostname checking. The Amazon EFS mount helper uses the `stunnel` program for its TLS functionality. Note that some versions of Linux don't include a version of `stunnel` that supports these TLS features by default. When using one of those Linux distributions, mounting an Amazon EFS file system using TLS fails.

After installing the Amazon EFS mount helper, you can upgrade your system's version of `stunnel` with the following instructions.

To upgrade stunnel on Amazon Linux, Amazon Linux 2, and other supported Linux distributions (except for SLES 12 (p. 66))

1. In a web browser, go to the stunnel downloads page <https://stunnel.org/downloads.html>.
2. Locate the latest stunnel version that is available in tar.gz format. Note the name of the file as you will need it in the following steps.
3. Open a terminal on your Linux client, and run the following commands in the order presented.

- a. For RPM:

```
sudo yum install -y gcc openssl-devel tcp_wrappers-devel
```

For DEB:

```
sudo apt-get install build-essential libwrap0-dev libssl-dev
```

- b. Replace *latest-stunnel-version* with the name of the file you noted previously in Step 2.

```
sudo curl -o latest-stunnel-version.tar.gz https://www.stunnel.org/downloads/latest-stunnel-version.tar.gz
```

- c. sudo tar xvfz *latest-stunnel-version*.tar.gz

- d. cd *latest-stunnel-version/*

- e. sudo ./configure

- f. sudo make

- g. The current stunnel package is installed in bin/stunnel. So that the new version can be installed, remove that directory with the following command.

```
sudo rm /bin/stunnel
```

- h. Install the latest version:

```
sudo make install
```

- i. **Note**

The default CentOS shell is csh, which has different syntax than the bash shell. The following code first invokes bash, then moves /bin/stunnel to /root.

```
bash
```

```
if [[ -f /bin/stunnel ]]; then
  sudo mv /bin/stunnel /root
fi
```

- j. Create a symlink:

```
sudo ln -s /usr/local/bin/stunnel /bin/stunnel
```

To upgrade stunnel on macOS Big Sur

- Open a terminal on your EC2 Mac instance, and run the following command to upgrade to the latest version of stunnel.

```
brew upgrade stunnel
```

Upgrading stunnel for SLES 12

- Run the following commands and follow the zypper package manager instructions to upgrade stunnel on your compute instance running SLES12.

```
sudo zypper addrepo https://download.opensuse.org/repositories/security:Stunnel/SLE_12_SP5/security:Stunnel.repo
sudo zypper refresh
sudo zypper install -y stunnel
```

After you've installed a version of stunnel with the required features, you can mount your file system using TLS with the Amazon EFS recommended settings.

Disabling Certificate Hostname Checking

If you are unable to install the required dependencies, you can optionally disable certificate hostname checking inside the Amazon EFS mount helper configuration. We do not recommend that you disable this feature in production environments. To disable certificate host name checking, do the following:

1. Using your text editor of choice, open the /etc/amazon/efs/efs-utils.conf file.
2. Set the stunnel_check_cert_hostname value to false.
3. Save the changes to the file and close it.

For more information on using encryption of data in transit, see [Mounting EFS file systems \(p. 68\)](#).

Enabling Online Certificate Status Protocol

In order to maximize file system availability in the event that the CA is not reachable from your VPC, the Online Certificate Status Protocol (OCSP) is not enabled by default when you choose to encrypt data in transit. Amazon EFS uses an [Amazon certificate authority](#) (CA) to issue and sign its TLS certificates, and the CA instructs the client to use OCSP to check for revoked certificates. The OCSP endpoint must be accessible over the Internet from your Virtual Private Cloud in order to check a certificate's status. Within the service, EFS continuously monitors certificate status, and issues new certificates to replace any revoked certificates it detects.

In order to provide the strongest security possible, you can enable OCSP so that your Linux clients can check for revoked certificates. OCSP protects against malicious use of revoked certificates, which is unlikely to occur within your VPC. In the event that an EFS TLS certificate is revoked, Amazon will publish a security bulletin and release a new version of EFS mount helper that rejects the revoked certificate.

To enable OCSP on your Linux client for all future TLS connections to EFS

1. Open a terminal on your Linux client.
2. Using your text editor of choice, open the /etc/amazon/efs/efs-utils.conf file.
3. Set the stunnel_check_cert_validity value to true.

4. Save the changes to the file and close it.

To enable OCSP as part of the `mount` command

- Use the following `mount` command to enable OCSP when mounting the file system.

```
$ sudo mount -t efs -o tls,ocsp fs-12345678:/ /mnt/efs
```

Mounting EFS file systems

In the following sections you can learn how to mount your Amazon EFS file system using the Amazon EFS mount helper. In addition, learn how to automatically remount your file system after any system restarts using the file `fstab` file. Using the EFS mount helper, you have the following options for mounting your Amazon EFS file system:

- Mounting on supported EC2 instances
- Mounting with IAM authorization
- Mounting with Amazon EFS access points
- Mounting with an on-premise Linux client
- Auto-mounting EFS file systems when an EC2 instance reboots
- Mounting a file system when creating a new EC2 instance

Note

Amazon EFS does not support mounting from Amazon EC2 Windows instances.

The EFS mount helper is part of the `amazon-efs-utils` package. The `amazon-efs-utils` package is an open-source collection of Amazon EFS tools. For more information, see [Manually installing the Amazon EFS client \(p. 57\)](#).

Before the Amazon EFS mount helper was available, we recommended mounting your Amazon EFS file systems using the standard Linux NFS client. For more information, see [Mounting file systems without the EFS mount helper \(p. 397\)](#).

Topics

- [Using EFS mount helper to mount EFS file systems \(p. 68\)](#)
- [Additional mounting considerations \(p. 88\)](#)
- [Troubleshooting AMI and kernel versions \(p. 89\)](#)

Using EFS mount helper to mount EFS file systems

The EFS mount helper helps you mount your EFS file systems on your EC2 Linux and Mac instances running the supported distributions listed in [Overview \(p. 54\)](#).

The Amazon EFS mount helper simplifies mounting your file systems. It includes the Amazon EFS recommended mount options by default. Additionally, the mount helper has built-in logging for troubleshooting purposes. If you encounter an issue with your Amazon EFS file system, you can share these logs with AWS Support. For more information about mounting your file system, see [Mounting EFS file systems \(p. 68\)](#).

Note

Amazon EFS does not support mounting from Amazon EC2 Windows instances.

Topics

- [How it works \(p. 69\)](#)
- [Getting support logs \(p. 70\)](#)
- [Prerequisites for using the EFS mount helper \(p. 70\)](#)
- [Mounting on Amazon EC2 Linux instances using the EFS mount helper \(p. 71\)](#)
- [Mounting on Amazon EC2 Mac instances using the EFS mount helper \(p. 73\)](#)

- [Mounting Amazon EFS file systems from a different AWS Region \(p. 74\)](#)
- [Mounting file systems with One Zone storage classes \(p. 75\)](#)
- [Mounting with IAM authorization \(p. 78\)](#)
- [Mounting with EFS access points \(p. 78\)](#)
- [Mounting on your on-premises Linux client with the EFS mount helper over AWS Direct Connect and VPN \(p. 79\)](#)
- [Mounting your Amazon EFS file system automatically \(p. 79\)](#)
- [Mounting EFS to multiple EC2 instances using AWS Systems Manager \(p. 85\)](#)
- [Mounting EFS file systems from another AWS account or VPC \(p. 85\)](#)

How it works

The mount helper defines a new network file system type, called `efs`, which is fully compatible with the standard `mount` command in Linux. The mount helper also supports mounting an Amazon EFS file system at instance boot time automatically by using entries in the `/etc/fstab` configuration file on EC2 Linux instances.

Warning

Use the `_netdev` option, used to identify network file systems, when mounting your file system automatically. If `_netdev` is missing, your EC2 instance might stop responding. This result is because network file systems need to be initialized after the compute instance starts its networking. For more information, see [Automatic mounting fails and the instance is unresponsive \(p. 247\)](#).

You can mount a file system by specifying one of the following properties:

- **File system DNS name** – If you use the file system DNS name, and the mount helper cannot resolve it, for example when you are mounting a file system in a different VPC, it will fall back to using the mount target IP address. For more information, see [Mounting EFS file systems from another AWS account or VPC \(p. 85\)](#).
- **File system ID** – If you use the file system ID, the mount helper resolves it to the local IP address of the mount target elastic network interface (ENI) without calling external resources.
- **Mount target IP address** – You can use the IP address of one of the file systems mount targets.

You can find the value for all of these properties in the Amazon EFS console. The file system DNS name is found in the **Attach** screen.

When encryption of data in transit is declared as a mount option for your Amazon EFS file system, the mount helper initializes a client `stunnel` process, and a supervisor process called `amazon-efs-mount-watchdog`. The `amazon-efs-mount-watchdog` process monitors the health of TLS mounts, and is started automatically the first time an EFS file system is mounted over TLS. This process is managed by either `upstart` or `systemd` depending on your Linux distribution, and by `launchd` on the macOS Big Sur distribution.

`Stunnel` is an open-source multipurpose network relay. The client `stunnel` process listens on a local port for inbound traffic, and the mount helper redirects NFS client traffic to this local port.

The mount helper uses TLS version 1.2 to communicate with your file system. Using TLS requires certificates, and these certificates are signed by a trusted Amazon Certificate Authority. For more information on how encryption works, see [Data encryption in Amazon EFS \(p. 189\)](#).

Mount options used by Amazon EFS client

The Amazon EFS client uses the following mount options that are optimized for Amazon EFS:

- `nfsvers=4.1` – used when mounting on EC2 Linux instances
- `nfsvers=4.0` – used when mounting on an EC2 Mac instance running MacOS Big Sur
- `rsize=1048576`
- `wsize=1048576`
- `hard`
- `timeo=600`
- `retrans=2`
- `noresvport`
- `mountport=2049` – only used when mounting on EC2 Mac instances running macOS Big Sur

Getting support logs

The mount helper has built-in logging for your Amazon EFS file system. You can share these logs with AWS Support for troubleshooting purposes.

You can find the logs stored in `/var/log/amazon/efs` for systems with the mount helper installed. These logs are for the mount helper, the stunnel process itself, and for the `amazon-efs-mount-watchdog` process that monitors the stunnel process.

Note

The watchdog process ensures that each mount's stunnel process is running, and stops the stunnel when the Amazon EFS file system is unmounted. If for some reason a stunnel process is terminated unexpectedly, the watchdog process restarts it.

You can change the configuration of your logs in `/etc/amazon/efs/efs-utils.conf`. However, doing so requires unmounting and then remounting the file system with the mount helper for the changes to take effect. Log capacity for the mount helper and watchdog logs is limited to 20 MiB. Logs for the stunnel process are disabled by default.

Important

You can enable logging for the stunnel process logs. However, enabling the stunnel logs can use up a nontrivial amount of space on your file system.

Prerequisites for using the EFS mount helper

You can mount an Amazon EFS file system on an Amazon EC2 instance using the Amazon EFS mount helper. To use the mount helper, you need the following:

- **File system ID of the file system to mount** – The EFS mount helper resolves the file system ID to the local IP address of the mount target elastic network interface (ENI) without calling external resources.
- **An Amazon EFS mount target** – You create mount targets in your virtual private cloud (VPC). If you create your file system in the console using the service recommended settings, a mount target is created in each availability zone in the AWS Region that the file system is in. For instructions to create mount targets, see [Creating and managing mount targets and security groups \(p. 37\)](#).

Note

We recommend that you wait 90 seconds after creating a mount target before you mount your file system. This wait lets the DNS records propagate fully in the AWS Region where the file system is.

If you use a mount target in an Availability Zone different from that of your Amazon EC2 instance, you incur standard EC2 charges for data sent across Availability Zones. You also might see increased latencies for file system operations.

- For mounting file systems with **One Zone storage classes** from a different Availability Zone:
 - **The name of the file system's Availability Zone** – If you are mounting an EFS file system using One Zone storage classes that is located in a different Availability Zone than the EC2 instance.
 - **Mount target DNS name** – Alternatively, you can specify the mount target's DNS name instead of the Availability Zone.
 - **An Amazon EC2 instance running one of the supported Linux or macOS distributions** – The supported distributions for mounting your file system with the mount helper are the following:
 - Amazon Linux 2
 - Amazon Linux 2017.09 and newer
 - macOS Big Sur
 - Red Hat Enterprise Linux (and derivatives such as CentOS) version 7 and newer
 - Ubuntu 16.04 LTS and newer
- Note**
EC2 Mac instances running macOS Big Sur support NFS 4.0 only.
- **The Amazon EFS mount helper is installed on the EC2 instance** – The mount helper is a tool in the amazon-efs-utils package of utilities. For information about installing amazon-efs-utils, see [Using AWS Systems Manager to install amazon-efs-utils \(p. 55\)](#) and [Manually installing amazon-efs-utils \(p. 57\)](#).
 - **The EC2 instance is in a VPC** – The connecting EC2 instance must be in a virtual private cloud (VPC) based on the Amazon VPC service. It also must be configured to use the DNS server provided by AWS. For information about the Amazon DNS server, see [DHCP Options Sets](#) in the [Amazon VPC User Guide](#).
 - **VPC has DNS hostnames enabled** – The VPC of the connecting EC2 instance must have DNS hostnames enabled. For more information, see [Viewing DNS Hostnames for Your EC2 Instance](#) in the [Amazon VPC User Guide](#).
 - **For EC2 instances and file systems in different AWS Regions** – If the EC2 instance and the file system you are mounting are located in different AWS Regions, you will need to edit the `region` property in the `efs-utils.conf` file. For more information, see [Mounting Amazon EFS file systems from a different AWS Region \(p. 74\)](#).

Mounting on Amazon EC2 Linux instances using the EFS mount helper

This procedure requires the following:

- You have installed the `amazon-efs-utils` package on the EC2 instance. For more information, see [Manually installing the Amazon EFS client \(p. 57\)](#).
- You have created mount targets for the file system. For more information, see [Creating and managing mount targets and security groups \(p. 37\)](#).

To mount your Amazon EFS file system using the mount helper on EC2 Linux instances

1. Open a terminal window on your EC2 instance through Secure Shell (SSH), and log in with the appropriate user name. For more information, see [Connect to your Linux instance using SSH](#) for Linux instances.
2. Create a directory `efs` that you will use as the file system mount point using the following command:

```
sudo mkdir efs
```

3. Run one of the following commands to mount your file system.

Note

If the EC2 instance and the file system you are mounting are located in different AWS Regions, see [Mounting Amazon EFS file systems from a different AWS Region \(p. 74\)](#) to edit the `region` property in the `efs-utils.conf` file.

- To mount using the file system id:

```
sudo mount -t efs file-system-id efs-mount-point/
```

Use the ID of the file system you are mounting in place `file-system-id` and `efs` in place of `efs-mount-point`.

```
sudo mount -t efs fs-abcd123456789ef0 efs/
```

Alternatively, if you want to use encryption of data in transit, you can mount your file system with the following command.

```
sudo mount -t efs -o tls fs-abcd123456789ef0 efs/
```

- To mount using the file system DNS name:

```
sudo mount -t efs -o tls file-system-dns-name efs-mount-point/
```

```
sudo mount -t efs -o tls fs-abcd123456789ef0.efs.us-east-2.amazonaws.com efs/
```


- To mount using the mount target IP address:

```
sudo mount -t efs -o tls,mounttargetip=mount-target-ip file-system-id efs-mount-point/
```

```
sudo mount -t efs -o tls,mounttargetip=192.0.2.0 fs-abcd123456789ef0 efs/
```

You can view and copy the exact commands to mount your file system in the **Attach** dialog box.

- In the Amazon EFS console, choose the file system that you want to mount to display its details page.
- To display the mount commands to use for this file system, choose **Attach** in the upper right.



The **Attach** screen displays the exact commands to use for mounting the file system in the following ways:

- (**Mount via DNS**) Using the file system's DNS name with the EFS mount helper or an NFS client.
- (**Mount via IP**) Using the mount target IP address in the selected Availability Zone with an NFS client.

Mounting on Amazon EC2 Mac instances using the EFS mount helper

This procedure requires the following:

- You have installed the `amazon-efs-utils` package on the EC2 Mac instance. For more information, see [Installing the Amazon EFS client on EC2 running macOS Big Sur and macOS Monterey \(p. 62\)](#).
- You have created mount targets for the file system. You can create mount targets at file system creation and add them to existing file systems. For more information, see [Creating and managing mount targets and security groups \(p. 37\)](#).
- You are mounting the file system on an EC2 Mac instance running macOS Big Sur or Monterey. Other macOS versions are not supported.

Note

Only EC2 Mac instances running macOS Big Sur or Monterey are supported. Other macOS versions are not supported for use with Amazon EFS.

To mount your Amazon EFS file system using the EFS mount helper on EC2 Mac instances running macOS Big Sur or Monterey

1. Open a terminal window on your EC2 Mac instance through Secure Shell (SSH), and log in with the appropriate user name. For more information, see [Connect to your instance using SSH for Mac instances](#), in the *Amazon EC2 User Guide for Linux Instances*.
2. Create a directory to use as the file system mount point using the following command:

```
sudo mkdir efs
```

3. Run the following command to mount your file system.

Note

By default, the EFS mount helper uses encryption in transit when mounting on EC2 Mac instances, whether or not you use the `tls` option in the mount command.

```
sudo mount -t efs file-system-id efs-mount-point/
```

```
sudo mount -t efs fs-abcd123456789ef0 efs/
```

You can also use the `tls` option when mounting.


```
sudo mount -t efs -o tls fs-abcd123456789ef0:/ efs
```

To mount a file system on an EC2 Mac instance without using encryption in transit, use the `notls` option, as shown in the following command.

```
sudo mount -t efs -o notls file-system-id efs-mount-point/
```

You can view and copy the exact commands to mount your file system in the management console's **Attach** dialog box, described as follows.

- a. In the Amazon EFS console, choose the file system that you want to mount to display its details page.
- b. To display the mount commands to use for this file system, choose **Attach** in the upper right.



The **Attach** screen displays the exact commands to use for mounting the file system in the following ways:

- (**Mount via DNS**) Using the file system's DNS name with the EFS mount helper or an NFS client.
- (**Mount via IP**) Using the mount target IP address in the selected Availability Zone with an NFS client.

Mounting Amazon EFS file systems from a different AWS Region

If you are mounting your EFS file system from an Amazon EC2 instance that is in a different AWS Region than the file system, you will need to edit the `region` property value in the `efs-utils.conf` file.

To edit the `region` property in `efs-utils.conf`

1. Access the terminal for your EC2 instance through Secure Shell (SSH), and log in with the appropriate user name. For more information on how to do this, see [Connecting to your Linux instance using SSH](#) in the *Amazon EC2 User Guide for Linux Instances*.
2. Locate the `efs-utils.conf` file, and open it using your preferred editor.
3. Locate the following line:

```
#region = us-east-1
```

- a. Uncomment the line.
- b. If the file system is not located in the `us-east-1` region, replace `us-east-1` with the ID of the region in which the file system is located.

- c. Save the changes.
4. Mount the file system using the EFS mount helper for [Linux \(p. 71\)](#) or [Mac \(p. 73\)](#) instances.

Mounting file systems with One Zone storage classes

Amazon EFS file systems that use One Zone storage classes support only a single mount target which is located in the same Availability Zone as the file system. You cannot add additional mount targets. This section describes things to consider when mounting Amazon EFS file systems that use One Zone storage classes.

You can avoid data transfer charges between Availability Zones and achieve better performance by accessing an EFS file system using an Amazon EC2 compute instance that is located in the same Availability Zone as that of the file system's mount target. This applies to file systems using EFS Standard or One Zone storage classes.

The procedures in this section require the following:

- You have installed the `amazon-efs-utils` package on the EC2 instance. For more information, see [Manually installing the Amazon EFS client \(p. 57\)](#).
- You have created a mount target for the file system. For more information, see [Creating and managing mount targets and security groups \(p. 37\)](#).

Mounting file systems that use One Zone storage on EC2 in a different Availability Zone

If you are mounting an EFS file system using One Zone storage classes on an EC2 instance that is located in a different Availability Zone, you have to specify the file system's Availability Zone name or the DNS name of the file system's mount target in the mount helper `mount` command.

Create a directory called `efs` to use as the file system mount point using the following command:

```
sudo mkdir efs
```

Use the following command to mount the file system using the EFS mount helper. The command specifies the file system's availability zone name.

```
sudo mount -t efs -o az=availability-zone-name,tls file-system-id mount-point/
```

This is the command with sample values:

```
sudo mount -t efs -o az=us-east-1a,tls fs-abcd1234567890ef efs/
```

The following command mounts the file system, specifying the DNS name of the file system's mount target.

```
sudo mount -t efs -o tls mount-target-dns-name mount-point/
```

This is the command with an example mount target DNS name.

```
sudo mount -t efs -o tls us-east-1a.fs-abcd1234567890ef9.efs.us-east-1.amazonaws.com efs/
```

Mounting One Zone file systems in a different Availability Zone automatically with EFS mount helper

If you are using `/etc/fstab` to mount an EFS file system using One Zone storage on an EC2 instance that is located in a different Availability Zone, you have to specify the file system's Availability Zone name or the DNS name of the file system's mount target in the `/etc/fstab` entry.

```
availability-zone-name.file-system-id.efs.aws-region.amazonaws.com:/ efs-mount-point efs
defaults,_netdev,noresvport,tls 0 0
```

```
us-east-1a.fs-abc123def456a7890.efs.us-east-1.amazonaws.com:/ efs-one-zone efs
defaults,_netdev,noresvport,tls 0 0
```

Mounting One Zone file systems automatically with NFS

If you are using `/etc/fstab` to mount an EFS file system using One Zone storage on an EC2 instance that is located in a different Availability Zone, you have to specify the file system's Availability Zone name with the file system's DNS name in the `/etc/fstab` entry.


```
availability-zone-name.file-system-id.efs.aws-region.amazonaws.com:/ efs-mount-point nfs4
nfsvers=4.1,rsize=1048576,wsize=1048576,hard,timeo=600,retrans=2,noresvport,_netdev 0 0
```

```
us-east-1a.fs-abc123def456a7890.efs.us-east-1.amazonaws.com:/ efs-one-zone nfs4
nfsvers=4.1,rsize=1048576,wsize=1048576,hard,timeo=600,retrans=2,noresvport,_netdev 0 0
```

For more information about how to edit the `/etc/fstab` file, and the values used in this command, see [Using NFS to automatically mount EFS file systems \(p. 83\)](#).

Mounting file systems with One Zone storage on other AWS compute instances

When you use an Amazon EFS file system with One Zone storage classes with Amazon Elastic Container Service, Amazon Elastic Kubernetes Service, or AWS Lambda, you need to configure the service to use the same Availability Zone that the EFS file system is located in, illustrated as follows, and described in the following sections.



Connecting from Amazon Elastic Container Service

You can use Amazon EFS file systems with Amazon ECS to share file system data across your fleet of container instances so your tasks have access to the same persistent storage, no matter the instance on which they land. To use Amazon EFS One Zone storage classes with Amazon ECS you should choose only subnets that are in the same Availability Zone as your file system when launching your task. For more information, see [Amazon EFS volumes](#) in the *Amazon Elastic Container Service Developer Guide*.

Connecting from Amazon Elastic Kubernetes Service

When mounting an Amazon EFS file system that uses One Zone storage classes from Amazon EKS, you can use the Amazon EFS [Container Storage Interface \(CSI\)](#) driver, which supports Amazon EFS access points, to share a file system between multiple pods in an Amazon EKS or self-managed Kubernetes cluster. The Amazon EFS CSI driver is installed in the Fargate stack. When using the Amazon EFS CSI driver with Amazon EFS One Zone storage classes, you can use the `nodeSelector` option when launching your pod to ensure it gets scheduled within the same availability zone as your file system.

Connecting from AWS Lambda

You can use Amazon EFS with AWS Lambda to share data across function invocations, read large reference data files, and write function output to a persistent and shared store. Lambda securely connects the function instances to the Amazon EFS mount targets that are in the same Availability Zone and subnet. When you use Lambda with Amazon EFS file systems using EFS One Zone storage, configure your function to only launch invocations into subnets that are in the same Availability Zone as your file system.

Mounting with IAM authorization

To mount your Amazon EFS file system on Linux instances using AWS Identity and Access Management (IAM) authorization, you use the EFS mount helper. For more information about IAM authorization for NFS clients, see [Using IAM to control file system data access \(p. 206\)](#).

You will need to create a directory to use as the file system mount point in the following sections. You can use the following command to create a mount point directory `efs`:

```
sudo mkdir efs
```

You can then replace instances of `efs-mount-point` with `efs`.

Mounting with IAM using an EC2 instance profile

If you are mounting with IAM authorization to an Amazon EC2 instance with an instance profile, use the `tls` and `iam` mount options, shown following.

```
$ sudo mount -t efs -o tls,iam file-system-id efs-mount-point/
```

To automatically mount with IAM authorization to an Amazon EC2 instance that has an instance profile, add the following line to the `/etc/fstab` file on the EC2 instance.

```
file-system-id:/efs-mount-point efs _netdev,tls,iam 0 0
```

Mounting with IAM using a named profile

You can mount with IAM authorization using the IAM credentials located in the AWS CLI credentials file `~/.aws/credentials`, or the AWS CLI config file `~/.aws/config`. If "awsprofile" is not specified, the "default" profile is used.

To mount with IAM authorization to a Linux instance using a credentials file, use the `tls`, `awsprofile`, and `iam` mount options, shown following.

```
$ sudo mount -t efs -o tls,iam,awsprofile=namedprofile file-system-id efs-mount-point/
```

To automatically mount with IAM authorization to a Linux instance using a credentials file, add the following line to the `/etc/fstab` file on the EC2 instance.

```
file-system-id:/efs-mount-point efs _netdev,tls,iam,awsprofile=namedprofile 0 0
```

Mounting with EFS access points

You can mount an EFS file system using an EFS access point only by using the EFS mount helper.

Note

You must configure one or more mount targets for your file system when mounting a file system using EFS access points.

When you mount a file system using an access point, the mount command includes the `access-point-id` and the `tls` mount option in addition to the regular mount options. An example is shown following.

```
$ sudo mount -t efs -o tls,accesspoint=access-point-id file-system-id efs-mount-point
```

To automatically mount a file system using an access point, add the following line to the `/etc/fstab` file on the EC2 instance.

```
file-system-id efs-mount-point efs _netdev,tls,accesspoint=access-point-id 0 0
```

For more information about EFS access points, see [Working with Amazon EFS access points \(p. 224\)](#).

Mounting on your on-premises Linux client with the EFS mount helper over AWS Direct Connect and VPN

You can mount your Amazon EFS file systems on your on-premises data center servers when connected to your Amazon VPC with AWS Direct Connect or VPN. Mounting your Amazon EFS file systems with `amazon-efs-utils` also makes mounting simpler with the mount helper and allows you to enable encryption of data in transit.

For more information about how to use `amazon-efs-utils` with AWS Direct Connect and VPN to mount Amazon EFS file systems onto on-premises Linux clients, see [Walkthrough: Create and mount a file system on-premises with AWS Direct Connect and VPN \(p. 173\)](#).

Mounting your Amazon EFS file system automatically

You can configure an Amazon EC2 instance to automatically mount an EFS file system when it reboots using the EFS mount helper or NFS.

- Using the EFS mount helper:
 - Attach an EFS file system when you create a new EC2 Linux instance using the EC2 Launch Instance Wizard.
 - Update the EC2 `/etc/fstab` file with an entry for the EFS file system.
- Using [NFS without the EFS mount helper \(p. 83\)](#) to update the EC2 `/etc/fstab` file, for support EC2 Linux and Mac instances.

Note

The EFS mount helper does not support automatic mounting on Amazon EC2 Mac instances running macOS Big Sur or Monterey. Instead, you can use [NFS to configure the `/etc/fstab` file on an EC2 Mac instance \(p. 83\)](#) to automatically mount an EFS file system.

Topics

- [Using the EFS mount helper to automatically re-mount EFS file systems \(p. 79\)](#)
- [Using NFS to automatically mount EFS file systems \(p. 83\)](#)

Using the EFS mount helper to automatically re-mount EFS file systems

Use the EFS mount helper to configure the `/etc/fstab` on EC2 Linux instances to automatically remount your EFS file systems when the instance re-starts.

Topics

- [Attach an EFS file system when creating an EC2 instance to enable automatic mounting on reboot \(p. 80\)](#)
- [Using `/etc/fstab` with EFS mount helper to automatically remount EFS file systems \(p. 81\)](#)

Attach an EFS file system when creating an EC2 instance to enable automatic mounting on reboot

This method uses the EFS mount helper to mount the file system update the /etc/fstab file on the EC2 instance. The mount helper is part of the [amazon-efs-utils \(p. 54\)](#) set of tools.

When you create a new Amazon EC2 Linux instance using the EC2 Launch Instance Wizard, you can configure it to mount your Amazon EFS file system automatically. The EC2 instance mounts the file system automatically the instance first launched and also whenever it restarts.

Note

Amazon EFS file systems do not support mounting on Amazon EC2 Mac instances running macOS Big Sur or Monterey at instance launch.

Before you perform this procedure, make sure that you have created your Amazon EFS file system. For more information, see [Step 1: Create your Amazon EFS file system \(p. 15\)](#) in the Amazon EFS Getting Started exercise.

Note

You can't use Amazon EFS with Microsoft Windows-based Amazon EC2 instances.

Before you can launch and connect to an Amazon EC2 instance, you need to create a key pair, unless you already have one. Follow the steps in [Setting Up with Amazon EC2](#) in the *Amazon EC2 User Guide for Linux Instances* to create a key pair. If you already have a key pair, you can use it for this exercise.

To configure your EC2 instance to mount an EFS file system automatically at launch

1. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
2. Choose **Launch Instance**.
3. In **Step 1: Choose an Amazon Machine Image (AMI)**, find an Amazon Linux AMI at the top of the list and choose **Select**.
4. In **Step 2: Choose an Instance Type**, choose **Next: Configure Instance Details**.
5. In **Step 3: Configure Instance Details**, provide the following information:
 - For **Network**, choose the entry for the same VPC that the EFS file system you're mounting is in.
 - For **Subnet**, choose a default subnet in any Availability Zone.
 - For **File systems**, choose the EFS file system that you want to mount. The path shown next the file system ID is the mount point that the EC2 instance will use, which you can change.
 - Under **Advanced Details**, the **User data** is automatically generated, and includes the commands needed to mount the EFS file systems you specified under **File systems**.
6. Choose **Next: Add Storage**.
7. Choose **Next: Add Tags**.
8. Name your instance and choose **Next: Configure Security Group**.
9. In **Step 6: Configure Security Group**, set **Assign a security group** to **Select an existing security group**. Choose the default security group to make sure that it can access your EFS file system.

You can't access your EC2 instance by Secure Shell (SSH) using this security group. For access by SSH, later you can edit the default security and add a rule to allow SSH or a new security group that allows SSH. You can use the following settings:

- **Type:** SSH
 - **Protocol:** TCP
 - **Port Range:** 22
 - **Source:** Anywhere 0.0.0.0/0
10. Choose **Review and Launch**.
 11. Choose **Launch**.

12. Select the check box for the key pair that you created, and then choose **Launch Instances**.

Your EC2 instance is now configured to mount the EFS file system at launch and whenever it's rebooted.

Using /etc/fstab with EFS mount helper to automatically remount EFS file systems

The /etc/fstab file contains information about file systems. The command `mount -a`, which runs during instance start-up, mounts all the file systems listed in /etc/fstab. In this procedure, you will manually update the /etc/fstab on an EC2 Linux instance so that the instance uses the EFS mount helper to automatically remount an EFS file system when the instance restarts.

Note

Amazon EFS file systems do not support automatic mounting using /etc/fstab with the EFS mount helper on Amazon EC2 Mac instances running macOS Big Sur or Monterey. Instead, you can use [NFS with /etc/fstab \(p. 83\)](#) to automatically mount your file system on EC2 Mac instances running macOS Big Sur and Monterey.

This method uses the EFS mount helper to mount the file system. The mount helper is part of the `amazon-efs-utils` set of tools.

The `amazon-efs-utils` tools are available for installation on Amazon Linux and Amazon Linux 2 Amazon Machine Images (AMIs). For more information about `amazon-efs-utils`, see [Using the amazon-efs-utils Tools \(p. 54\)](#). If you are using another Linux distribution, such as Red Hat Enterprise Linux (RHEL), manually build and install `amazon-efs-utils`. For more information, see [Installing the Amazon EFS client on other Linux distributions \(p. 58\)](#).

Prerequisites

The following requirements need to be in place before you can successfully implement this procedure:

- You have already created the Amazon EFS file system that you want to be automatically remounted. For more information, see [Step 1: Create your Amazon EFS file system \(p. 15\)](#).
- You have already created the EC2 Linux instance that you want to configure to automatically remount an EFS file system.
- The EFS mount helper is installed on the EC2 Linux instance. For more information, see [Using the amazon-efs-utils Tools \(p. 54\)](#).

To update the /etc/fstab file on your EC2 instance

1. Connect to your EC2 instance:
 - To connect to your instance from a computer running macOS or Linux, specify the .pem file for your SSH command. To do this, use the `-i` option and the path to your private key.
 - To connect to your instance from a computer running Windows, you can use either MindTerm or PuTTY. To use PuTTY, install it and convert the .pem file to a .ppk file.

For more information, see the following topics in the *Amazon EC2 User Guide for Linux Instances*:

- [Connecting to your Linux instance from Windows using PuTTY](#)
 - [Connecting to your Linux instance using SSH](#)
2. Open the /etc/fstab file in an editor.
 3. For automatic mounting using either IAM authorization or an EFS access point:
 - To automatically mount with IAM authorization to an Amazon EC2 instance that has an instance profile, add the following line to the /etc/fstab file.

```
file-system-id:/ efs-mount-point efs _netdev,noresvport,tls,iam 0 0
```

- To automatically mount with IAM authorization to a Linux instance using a credentials file, add the following line to the /etc/fstab file.

```
file-system-id:/ efs-mount-point efs  
_netdev,noresvport,tls,iam,awsprofile=namedprofile 0 0
```

- To automatically mount a file system using an EFS access point, add the following line to the /etc/fstab file.

```
file-system-id:/ efs-mount-point efs _netdev,noresvport,tls,iam,accesspoint=access-  
point-id 0 0
```

Warning

Use the _netdev option, used to identify network file systems, when mounting your file system automatically. If _netdev is missing, your EC2 instance might stop responding. This result is because network file systems need to be initialized after the compute instance starts its networking. For more information, see [Automatic mounting fails and the instance is unresponsive \(p. 247\)](#).

For more information, see [Mounting with IAM authorization \(p. 78\)](#) and [Mounting with EFS access points \(p. 78\)](#).

4. Save the changes to the file.
5. Test the fstab entry by using the mount command with the 'fake' option along with the 'all' and 'verbose' options.

```
$ sudo mount -fav  
home/ec2-user/efs : successfully mounted
```

Your EC2 instance is now configured to mount the EFS file system whenever it restarts.

Note

In some cases, your Amazon EC2 instance might need to start regardless of the status of your mounted Amazon EFS file system. In such cases, add the nofail option to your file system's entry in your /etc/fstab file.

The line of code you added to the /etc/fstab file does the following.

Field	Description
file-system-id:/	The ID for your Amazon EFS file system. You can get this ID from the console or programmatically from the CLI or an AWS SDK.
efs-mount-point	The mount point for the EFS file system on your EC2 instance.
efs	The type of file system. When you're using the mount helper, this type is always efs.
mount options	Mount options for the file system. This is a comma-separated list of the following options: <ul style="list-style-type: none">• _netdev – This option tells the operating system that the file system resides on a device that requires network access. This option prevents

Field	Description
	<p>the instance from mounting the file system until the network has been enabled on the client.</p> <ul style="list-style-type: none"> • <code>noresvport</code> – Tells the NFS client to use a new Transmission Control Protocol (TCP) source port when a network connection is reestablished. Doing this helps make sure that the EFS file system has uninterrupted availability after a network recovery event. • <code>tls</code> – Enables encryption of data in transit. • <code>iam</code> – Use this option to mount with IAM authorization to an Amazon EC2 that has an instance profile. Using the <code>iam</code> mount option requires also using the <code>tls</code> option. For more information, see Using IAM to control file system data access (p. 206). • <code>awsprofile=namedprofile</code> – Use this option with the <code>iam</code> and <code>tls</code> options to mount with IAM authorization to a Linux instance using a credentials file. For more information about EFS access points, see Using IAM to control file system data access (p. 206). • <code>accesspoint=access-point-id</code> – Use this option with the <code>tls</code> option to mount using an EFS access point. For more information about EFS access points, see Working with Amazon EFS access points (p. 224).
0	A nonzero value indicates that the file system should be backed up by <code>dump</code> . For EFS, this value should be 0.
0	The order in which <code>fsck</code> checks file systems at boot. For EFS file systems, this value should be 0 to indicate that <code>fsck</code> should not run at start-up.

Using NFS to automatically mount EFS file systems

To update the `/etc/fstab` file on your EC2 instance

1. Connect to your EC2 instance:

- To connect to your instance from a computer running macOS or Linux, specify the `.pem` file for your SSH command. To do this, use the `-i` option and the path to your private key.
- To connect to your instance from a computer running Windows, you can use either MindTerm or PuTTY. To use PuTTY, install it and convert the `.pem` file to a `.ppk` file.

For more information, see the following topics in the *Amazon EC2 User Guide for Linux Instances*:

- [Connecting to your Linux instance from Windows using PuTTY](#)
- [Connecting to your Linux instance using SSH](#)

2. Open the `/etc/fstab` file in an editor.

3. To automatically mount a file system using NFS instead of the EFS mount helper, add the following line to the `/etc/fstab` file.
- Replace `file_system_id` with the ID of the file system you are mounting.
 - Replace `aws-region` with the AWS Region that the file system is in, such as `us-east-1`.
 - Replace `mount_point` with the file system's mount point.

```
file_system_id.efs.aws-region.amazonaws.com:/ mount_point nfs4
nfsvers=4.1,rsize=1048576,wszie=1048576,hard,timeo=600,retrans=2,noresvport,_netdev 0
0
```

The line of code you added to the `/etc/fstab` file does the following.

Field	Description
<i>file-system-id</i> :/	The ID for your Amazon EFS file system. You can get this ID from the console or programmatically from the CLI or an AWS SDK.
<i>efs-mount-point</i>	The mount point for the EFS file system on your EC2 instance.
nfs4	Specifies the file system type.
mount options	<p>The comma-separated list of mount options for the file system:</p> <ul style="list-style-type: none"> • <code>nfsvers=4.1</code> – specifies using NFS v4.1. • <code>rszie=1048576</code> – For improved performance, sets the maximum number of bytes of data that the NFS client can receive for each network READ request when reading data from a file on an EFS file system. 1048576 is the largest size possible. • <code>wszie=1048576</code> – For improved performance, sets the maximum number of bytes of data that the NFS client can send for each network WRITE request when writing data to a file on an EFS file system. 1048576 is the largest size possible. • <code>hard</code> – Sets the recovery behavior of the NFS client after an NFS request times out, so that NFS requests are retried indefinitely until the server replies. We recommend that you use the hard mount option (<code>hard</code>) to ensure data integrity. If you use a soft mount, set the <code>timeo</code> parameter to at least 150 deciseconds (15 seconds). Doing so helps minimize the risk of data corruption that is inherent with soft mounts. • <code>timeo=600</code> – Sets the timeout value that the NFS client uses to wait for a response before it retries a request to 600 deciseconds (60 seconds). If you must change the timeout parameter (<code>timeo</code>), we recommend that you use a value of at least 150, which is equivalent to 15 seconds. Doing so helps avoid diminished performance. • <code>retrans=2</code> – Sets to 2 the number of times the NFS client retries a request before it attempts further recovery action. • <code>noresvport</code> – Tells the NFS client to use a new Transmission Control Protocol (TCP) source port when a network connection is reestablished. Doing this helps make sure that the EFS file system has uninterrupted availability after a network recovery event. • <code>_netdev</code> – Prevents the client from attempting to mount the EFS file system until the network has been enabled.
0	Specifies the dump value; 0 tells the <code>dump</code> utility to not back up the file system.
0	Tells the <code>fsck</code> utility to not run at start-up.

Mounting EFS to multiple EC2 instances using AWS Systems Manager

You can mount EFS file systems to multiple Amazon EC2 instances remotely and securely without having to log in to the instances by using the AWS Systems Manager **Run Command**. For more information about AWS Systems Manager Run Command, see [AWS Systems Manager run command](#) in the *AWS Systems Manager User Guide*. The following prerequisites are required before mounting EFS file systems using this method:

1. The EC2 instances are launched with an instance profile that includes the `AmazonElasticFileSystemsUtils` permissions policy. For more information, see [Step 1: Configure an IAM instance profile with the required permissions \(p. 57\)](#).
2. Version 1.28.1 or later of the Amazon EFS client (`amazon-efs-utils` package) is installed on the EC2 instances. You can use AWS Systems Manager to automatically install the package on your instances. For more information, see [Step 2: Configure an Association used by State Manager for installing or updating the Amazon EFS client \(p. 57\)](#).

To mount multiple EFS file systems to multiple EC2 instances using the console

1. Open the AWS Systems Manager console at <https://console.aws.amazon.com/systems-manager/>.
2. In the navigation pane, choose **Run Command**.
3. Choose **Run a command**.
4. Enter **AWS-RunShellScript** in the **Commands** search field.
5. Select **AWS-RunShellScript**.
6. In **Command parameters** enter the mount command to use for each EFS file system that you want to mount. For example:

```
sudo mount -t efs -o tls fs-12345678:/ /mnt/efs
sudo mount -t efs -o tls,accesspoint=fsap-12345678 fs-01233210 /mnt/efs
```

For more information about EFS mount commands using the Amazon EFS client, see [Mounting on Amazon EC2 Linux instances using the EFS mount helper \(p. 71\)](#) or [Mounting on Amazon EC2 Mac instances using the EFS mount helper \(p. 73\)](#).

7. Select the target AWS Systems Manager managed EC2 instances that you want the command to run on.
8. Make any other additional settings you would like. Then choose **Run** to run the command and mount the EFS file systems specified in the command.

Once you run the command, you can see its status in the command history.

Mounting EFS file systems from another AWS account or VPC

You can mount your Amazon EFS file system using IAM authorization for NFS clients and EFS Access Points using the EFS mount helper. By default, the EFS mount helper uses domain name service (DNS) to resolve the IP address of your EFS mount target. If you are mounting the file system from a different account or virtual private cloud (VPC), you need to resolve the EFS mount target manually.

Following, you can find instructions for determining the correct EFS mount target IP address to use for your NFS client. You can also find instructions for configuring the client to mount the EFS file system using that IP address.

Mounting using IAM or access points from another VPC

When you use a VPC peering connection or transit gateway to connect VPCs, Amazon EC2 instances that are in one VPC can access EFS file systems in another VPC, even if the VPCs belong to different accounts.

Prerequisites

Before using the following the procedure, take these steps:

- Install the Amazon EFS client, part of the `amazon-efs-utils` set of utilities on the compute instance you're mounting the EFS file system on. You use the EFS mount helper, which is included in `amazon-efs-utils`, to mount the file system. For instructions on installing `amazon-efs-utils`, see [Using the `amazon-efs-utils` Tools \(p. 54\)](#).
- Allow the `ec2:DescribeAvailabilityZones` action in the IAM policy for the IAM role you attached to the instance. We recommend that you attach the AWS managed policy `AmazonElasticFileSystemsUtils` to an IAM entity to provide the necessary permissions for the entity.
- When mounting from another AWS account, update the file system resource policy to allow the `elasticfilesystem:DescribeMountTargets` action for the principal ARN of other AWS account. For example:

```
{  
    "Id": "access-point-example03",  
    "Statement": [  
        {  
            "Sid": "access-point-statement-example03",  
            "Effect": "Allow",  
            "Principal": {"AWS": "arn:aws:iam::555555555555"},  
            "Action": "elasticfilesystem:DescribeMountTargets",  
            "Resource": "arn:aws:elasticfilesystem:us-east-2:111122223333:file-system/  
fs-12345678",  
        }  
    ]  
}
```

For more information about EFS file system resource policies, see [Resource-based policies \(p. 199\)](#).

- Install botocore. The EFS client uses botocore to retrieve the mount target IP address when the file system DNS name cannot be resolved when mounting a file system in another VPC. For more information, see [Install botocore](#) in the `amazon-efs-utils` README file.
- Set up either a VPC peering connection or a VPC transit gateway.

You connect the client's VPC and your EFS file system's VPC using either a VPC peering connection or a VPC transit gateway. When you use a VPC peering connection or transit gateway to connect VPCs, Amazon EC2 instances that are in one VPC can access EFS file systems in another VPC, even if the VPCs belong to different accounts.

A *transit gateway* is a network transit hub that you can use to interconnect your VPCs and on-premises networks. For more information about using VPC transit gateways, see [Getting Started with transit gateways](#) in the *Amazon VPC Transit Gateways Guide*.

A *VPC peering connection* is a networking connection between two VPCs. This type of connection enables you to route traffic between them using private Internet Protocol version 4 (IPv4) or Internet Protocol version 6 (IPv6) addresses. You can use VPC peering to connect VPCs within the same AWS Region or between AWS Regions. For more information on VPC peering, see [What is VPC Peering?](#) in the *Amazon VPC Peering Guide*.

To ensure high availability of your file system, we recommend that you always use an EFS mount target IP address that is in the same availability zone as your NFS client. If you're mounting an EFS file system that is in another account, ensure that the NFS client and EFS mount target are in the same availability zone ID. This requirement applies because AZ names can differ from one account to another.

To mount an EFS file system in another VPC using IAM or an access point

1. Connect to your EC2 instance:

- To connect to your instance from a computer running macOS or Linux, specify the .pem file for your SSH command. To do this, use the `-i` option and the path to your private key.
- To connect to your instance from a computer running Windows, you can use either MindTerm or PuTTY. To use PuTTY, install it and convert the .pem file to a .ppk file.

For more information, see the following topics in the *Amazon EC2 User Guide for Linux Instances*:

- [Connecting to Your Linux Instance from Windows Using PuTTY](#)
- [Connecting to Your Linux Instance Using SSH](#)

2. Create a directory for mounting the file system using the following command:

```
$ sudo mkdir /mnt/efs
```

3. To mount the file system using IAM authorization, use the following command:

```
$ sudo mount -t efs -o tls,iam file-system-dns-name /mnt/efs/
```

For more information about using IAM authorization with EFS, see [Using IAM to control file system data access \(p. 206\)](#).

To mount the file system using an EFS access point, use the following command:

```
$ sudo mount -t efs -o tls,accesspoint=access-point-id file-system-dns-name /mnt/efs/
```

For more information about EFS access points, see [Working with Amazon EFS access points \(p. 224\)](#).

Mounting Amazon EFS file systems from a different AWS Region

If you are mounting your EFS file system from another VPC that is in a different AWS Region than the file system, you will need to edit the `efs-utils.conf` file. In `/dist/efs-utils.conf`, locate the following lines:

```
#region = us-east-1
```

Uncomment the line, and replace the value for the ID of the region in which the file system is located, if it is not in `us-east-1`.

Mounting from another AWS account in the same VPC

Using shared VPCs, you can mount an Amazon EFS file system that is owned by one AWS account from Amazon EC2 instances that are owned by a different AWS account. For more information about setting up a shared VPC, see [Working with shared VPCs](#) in the *Amazon VPC Peering Guide*.

After you set up VPC sharing, the EC2 instances can mount the EFS file system using Domain Name System (DNS) name resolution or the EFS mount helper. We recommend using the EFS mount helper to mount your EFS file systems.

Additional mounting considerations

We recommend the following default values for mount options on Linux:

- `rsize=1048576` – Sets the maximum number of bytes of data that the NFS client can receive for each network READ request. This value applies when reading data from a file on an EFS file system. We recommend that you use the largest size possible (up to 1048576) to avoid diminished performance.
- `wsize=1048576` – Sets the maximum number of bytes of data that the NFS client can send for each network WRITE request. This value applies when writing data to a file on an EFS file system. We recommend that you use the largest size possible (up to 1048576) to avoid diminished performance.
- `hard` – Sets the recovery behavior of the NFS client after an NFS request times out, so that NFS requests are retried indefinitely until the server replies. We recommend that you use the hard mount option (`hard`) to ensure data integrity. If you use a soft mount, set the `timeo` parameter to at least 150 deciseconds (15 seconds). Doing so helps minimize the risk of data corruption that is inherent with soft mounts.
- `timeo=600` – Sets the timeout value that the NFS client uses to wait for a response before it retries an NFS request to 600 deciseconds (60 seconds). If you must change the timeout parameter (`timeo`), we recommend that you use a value of at least 150, which is equivalent to 15 seconds. Doing so helps avoid diminished performance.
- `retrans=2` – Sets to 2 the number of times the NFS client retries a request before it attempts further recovery action.
- `noresvport` – Tells the NFS client to use a new Transmission Control Protocol (TCP) source port when a network connection is reestablished. Doing this helps make sure that the EFS file system has uninterrupted availability after a network recovery event.
- `_netdev` – When present in `/etc/fstab`, prevents the client from attempting to mount the EFS file system until the network has been enabled.

In general, avoid setting any other mount options that are different from the defaults, which can cause reduced performance and other issues. If you don't use the preceding defaults, be aware of the following:

- Changing read or write buffer sizes or disabling attribute caching can result in reduced performance.
- Amazon EFS ignores source ports. If you change Amazon EFS source ports, it doesn't have any effect.
- Amazon EFS doesn't support any of the Kerberos security variants. For example, the following mount command fails.

```
$ mount -t nfs4 -o krb5p <DNS_NAME>:/ /efs/
```

- We recommend that you mount your file system using its DNS name. Amazon EFS resolves this name to the IP address of the Amazon EFS mount target in the same Availability Zone as your Amazon EC2 instance without calling external resources. If you use a mount target in an Availability Zone different from that of your Amazon EC2 instance, you incur standard EC2 charges for data sent across Availability Zones. You also might see increased latencies for file system operations.
- For more mount options, and detailed explanations of the defaults, see the [man fstab](#) and [man nfs](#) pages in the Linux documentation.

Note

If your EC2 instance needs to start regardless of the status of your mounted EFS file system, add the `nofail` option to your file system's entry in your `/etc/fstab` file.

Unmounting file systems

Before you delete a file system, we recommend that you unmount it from every Amazon EC2 instance that it's connected to. You can unmount a file system on your Amazon EC2 instance by running the `umount` command on the instance itself. You can't unmount an Amazon EFS file system through the AWS CLI, the AWS Management Console, or through any of the AWS SDKs. To unmount an Amazon EFS file system connected to an Amazon EC2 instance running Linux, use the `umount` command as follows:

```
umount /mnt/efs
```

We recommend that you do not specify any other `umount` options. Avoid setting any other `umount` options that are different from the defaults.

You can verify that your Amazon EFS file system has been unmounted by running the `df` command. This command displays the disk usage statistics for the file systems currently mounted on your Linux-based Amazon EC2 instance. If the Amazon EFS file system that you want to unmount isn't listed in the `df` command output, this means that the file system is unmounted.

Example Example: Identify the mount status of an Amazon EFS file system and unmount it

```
$ df -T
Filesystem Type 1K-blocks Used Available Use% Mounted on
/dev/sda1 ext4 8123812 1138920 6884644 15% /
availability-zone.file-system-id.efs.aws-region.amazonaws.com :/ nfs4 9007199254740992 0
9007199254740992 0% /mnt/efs
```

```
$ umount /mnt/efs
```

```
$ df -T
```

```
Filesystem Type 1K-blocks Used Available Use% Mounted on
/dev/sda1 ext4 8123812 1138920 6884644 15% /
```

Troubleshooting AMI and kernel versions

To troubleshoot issues related to certain Amazon Machine Image (AMI) or kernel versions when using Amazon EFS from an Amazon EC2 instance, see [Troubleshooting AMI and kernel issues \(p. 245\)](#).

Note

Amazon EFS does not support mounting from Amazon EC2 Windows instances.

Transferring data into and out of Amazon EFS

You can use AWS Transfer Family and AWS DataSync to transfer data into and out of your Amazon EFS file systems. AWS DataSync is an online data transfer service that can copy data between Network File System (NFS), Server Message Block (SMB) file servers, self-managed object storage, and also between AWS services. For more information about using DataSync with Amazon EFS, see [Using AWS DataSync to transfer data in Amazon EFS \(p. 90\)](#).

AWS Transfer Family is a fully managed AWS service that you can use to transfer files into and out of Amazon EFS file systems over the Secure File Transfer Protocol (SFTP), File Transfer Protocol (FTP), and FTP over Secure Sockets Layer (FTPS) protocol. Using Transfer Family, you can provide your business partners access to files stored in your Amazon EFS file systems for use cases such as data distribution, supply chain, content management, and web serving applications. For more information about using Transfer Family with Amazon EFS, see [Using AWS Transfer Family to access files in your Amazon EFS file system \(p. 90\)](#).

Topics

- [Using AWS DataSync to transfer data in Amazon EFS \(p. 90\)](#)
- [Using AWS Transfer Family to access files in your Amazon EFS file system \(p. 90\)](#)

Using AWS DataSync to transfer data in Amazon EFS

AWS DataSync is an online data transfer service that simplifies, automates, and accelerates moving and replicating data between on-premises storage systems, and also between AWS storage services. DataSync can copy data between Network File System (NFS), Server Message Block (SMB) file servers, self-managed object storage, AWS Snowcone, Amazon S3 buckets, Amazon EFS file systems, and FSx for Windows File Server file systems.

You can also use DataSync to transfer files between two EFS file systems, including file systems in different AWS Regions and file systems owned by different AWS accounts. Using DataSync to copy data between EFS file systems, you can perform one-time data migrations, periodic data ingestion for distributed workloads, and automate replication for data protection and recovery.

To simplify transfer files between two EFS file systems using DataSync, you can use the [AWS DataSync In-Cloud QuickStart and Scheduler](#).

For more information, see [Getting started with Amazon Elastic File System \(p. 14\)](#) and the [AWS DataSync User Guide](#).

Using AWS Transfer Family to access files in your Amazon EFS file system

AWS Transfer Family is a fully managed AWS service that you can use to transfer files into and out of Amazon EFS file systems over the following protocols:

- Secure Shell (SSH) File Transfer Protocol (SFTP) (AWS Transfer for SFTP)
- File Transfer Protocol Secure (FTPS) (AWS Transfer for FTPS)
- File Transfer Protocol (FTP) (AWS Transfer for FTP)

Using Transfer Family, you can securely enable third parties such as your vendors, partners, or customers access to your files over the supported protocols at scale globally, without needing to manage any infrastructure. Additionally, you can now easily access your EFS file systems from Windows, macOS, and Linux environments using SFTP, FTPS, and FTP clients. This helps expand the accessibility of your data beyond NFS clients and access points, to users across multiple environments.

Using Transfer Family to transfer data in Amazon EFS file systems is accounted for in the same manner as other client usage. For more information, see [Throughput modes \(p. 132\)](#) and [Amazon EFS quotas and limits \(p. 235\)](#).

To learn more about AWS Transfer Family, see the [AWS Transfer Family User Guide](#).

Note

Using Transfer Family with Amazon EFS is disabled by default for AWS accounts that have Amazon EFS file systems with policies that allow public access that were created before January 6, 2021. To enable using Transfer Family to access your file system, contact AWS Support.

Topics

- [Prerequisites for using AWS Transfer Family with Amazon EFS \(p. 91\)](#)
- [Configuring your Amazon EFS file system to work with AWS Transfer Family \(p. 91\)](#)

Prerequisites for using AWS Transfer Family with Amazon EFS

To use Transfer Family to access files in your Amazon EFS file system, your configuration must meet the following conditions:

- The Transfer Family server and your Amazon EFS file system are located in the same AWS Region.
- IAM policies are configured to enable access to the IAM role used by Transfer Family. For more information, see [Create an IAM role and policy](#) in the *AWS Transfer Family User Guide*.
- (Optional) If the Transfer Family server is owned by a different account, enable cross-account access.
 - Ensure that your file system policy does not allow public access. For more information, see [Blocking public access \(p. 212\)](#).
 - Modify the file system policy to enable cross-account access. For more information, see [Configuring cross-account access for Transfer Family \(p. 93\)](#).

Configuring your Amazon EFS file system to work with AWS Transfer Family

Configuring an Amazon EFS file system to work with Transfer Family requires the following steps:

- **Step 1.** Get the list of POSIX IDs that are allocated to the Transfer Family users.
- **Step 2.** Ensure that your file system's directories are accessible to the Transfer Family users by using the POSIX IDs allocated to the Transfer Family users.
- **Step 3.** Configure IAM to enable access to the IAM role used by Transfer Family.

Setting file and directory permissions for Transfer Family users

Make sure that the Transfer Family users have access to the necessary file and directories on your EFS file system. Assign access permissions to the directory using the list of POSIX IDs allocated to the Transfer Family users. In this example, a user creates a directory named `transferFam` under the EFS mount point. Creating a directory is optional, depending on your use case. If needed, you can choose its name and location on the EFS file system.

To assign file and directory permissions to POSIX users for Transfer Family

1. Connect to your Amazon EC2 instance. Amazon EFS only supports mounting by Linux-based EC2 instances.
2. Mount your EFS file system if it is not already mounted on the EC2 instance. For more information, see [Mounting EFS file systems \(p. 68\)](#).
3. The following example creates the directory on the EFS file system, and changes its group to the POSIX group ID for the Transfer Family users, which is 1101 in this example.
 - a. Create the directory `efs/transferFam` using the following commands. In practice, you can use a name and location on the file system of your choosing.

```
[ec2-user@ip-192-0-2-0 ~]$ ls
efs  efs-mount-point  efs-mount-point2
[ec2-user@ip-192-0-2-0 ~]$ ls efs
[ec2-user@ip-192-0-2-0 ~]$ sudo mkdir efs/transferFam
[ec2-user@ip-192-0-2-0 ~]$ ls -l efs
total 0
drwxr-xr-x 2 root root 6 Jan  6 15:58 transferFam
```

- b. Use the following command to change the group of `efs/transferFam` to the POSIX GID assigned to the Transfer Family users.

```
[ec2-user@ip-192-0-2-0 ~]$ sudo chown :1101 efs/transferFam/
```

- c. Confirm the change.

```
[ec2-user@ip-192-0-2-0 ~]$ ls -l efs
total 0
drwxr-xr-x 2 root 1101 6 Jan  6 15:58 transferFam
```

Enable access to the IAM role used by Transfer Family

In Transfer Family, you create a resource-based IAM policy and an IAM role that define user access to the EFS file system. For more information, see [Create an IAM role and policy](#) in the *AWS Transfer Family User Guide*. You must grant that Transfer Family IAM role access to your EFS file system using either an IAM identity policy or a file system policy.

The following is an example file system policy that grants `ClientMount` (read) and `ClientWrite` access to the IAM role `EFS-role-for-transfer`.

```
{
    "Version": "2012-10-17",
    "Id": "efs-policy-wizard-8698b356-4212-4d30-901e-ad2030b57762",
    "Statement": [
        {
            "Sid": "Grant-transfer-role-access",
            "Effect": "Allow",
            "Principal": {
```

```
        "AWS": "arn:aws:iam::111122223333:role/EFS-role-for-transfer"
    },
    "Action": [
        "elasticfilesystem:ClientWrite",
        "elasticfilesystem:ClientMount"
    ]
}
}
```

For more information about creating a file system policy, see [Creating file system policies \(p. 45\)](#). For more information about using identity-based IAM policies to manage access to EFS resources, see [Managing access to resources \(p. 198\)](#).

Configuring cross-account access for Transfer Family

If the Transfer Family server used to access your file system belongs to a different AWS account, you must grant that account access to your file system. Also, your file system policy has to be non-public. For more information about blocking public access to your file system, see [Blocking public access \(p. 212\)](#).

You can grant a different AWS account access to your file system in the file system policy. In the Amazon EFS console, use the **Grant additional permissions** section of the **File system policy editor** to specify the AWS account and the level of file system access you are granting. For more information about creating or editing a file system policy, see [Creating file system policies \(p. 45\)](#).

You can specify the account using the account ID or the account Amazon Resource Name (ARN). For more information about ARNs, see [IAM ARNs](#) in the *IAM User Guide*.

The following example is a non-public file system policy that grants cross-account access to the file system. It has the following two statements:

1. The first statement, `NFS-client-read-write-via-fsmt`, grants read, write, and root privileges to NFS clients accessing the file system using a file system mount target.
2. The second statement, `Grant-cross-account-access`, grants only read and write privileges to the AWS account `111122223333`, which is the account that owns the Transfer Family server that needs access to this EFS file system in your account.

```
{
    "Statement": [
        {
            "Sid": "NFS-client-read-write-via-fsmt",
            "Effect": "Allow",
            "Principal": {
                "AWS": "*"
            },
            "Action": [
                "elasticfilesystem:ClientRootAccess",
                "elasticfilesystem:ClientWrite",
                "elasticfilesystem:ClientMount"
            ],
            "Condition": {
                "Bool": {
                    "elasticfilesystem:AccessedViaMountTarget": "true"
                }
            }
        },
        {
            "Sid": "Grant-cross-account-access",
            "Effect": "Allow",
            "Principal": {
                "AWS": "111122223333"
            }
        }
    ]
}
```

```
        "AWS": "arn:aws:iam::111122223333:root"
    },
    "Action": [
        "elasticfilesystem:ClientWrite",
        "elasticfilesystem:ClientMount"
    ]
}
}
```

The following file system policy adds a statement granting access to the IAM role used by Transfer Family.

```
{
    "Statement": [
        {
            "Sid": "NFS-client-read-write-via-fsmt",
            "Effect": "Allow",
            "Principal": {
                "AWS": "*"
            },
            "Action": [
                "elasticfilesystem:ClientRootAccess",
                "elasticfilesystem:ClientWrite",
                "elasticfilesystem:ClientMount"
            ],
            "Condition": {
                "Bool": {
                    "elasticfilesystem:AccessedViaMountTarget": "true"
                }
            }
        },
        {
            "Sid": "Grant-cross-account-access",
            "Effect": "Allow",
            "Principal": {
                "AWS": "arn:aws:iam::111122223333:root"
            },
            "Action": [
                "elasticfilesystem:ClientWrite",
                "elasticfilesystem:ClientMount"
            ]
        },
        {
            "Sid": "Grant-transfer-role-access",
            "Effect": "Allow",
            "Principal": {
                "AWS": "arn:aws:iam::111122223333:role/EFS-role-for-transfer"
            },
            "Action": [
                "elasticfilesystem:ClientWrite",
                "elasticfilesystem:ClientMount"
            ]
        }
    ]
}
```

Managing Amazon EFS file systems

File system management tasks refer to creating and deleting file systems and managing tags, file system backups, access, and network accessibility with mount targets of existing file systems.

You can perform these file system management tasks using the AWS Management Console, or programmatically using the AWS Command Line Interface (AWS CLI) or API, as discussed in the following sections.

Topics

- [Managing file system network accessibility \(p. 95\)](#)
- [Managing file system throughput \(p. 99\)](#)
- [Amazon EFS lifecycle management \(p. 100\)](#)
- [Managing access to encrypted file systems \(p. 104\)](#)
- [Metering: How Amazon EFS reports file system and object sizes \(p. 106\)](#)
- [Managing Amazon EFS file system costs using AWS Budgets \(p. 108\)](#)
- [File system status \(p. 109\)](#)


If you are new to Amazon EFS, we recommend that you try the following exercises that provide you with first-hand end-to-end experience using an Amazon EFS file system:

- [Getting started \(p. 14\)](#) – This exercise provides a console-based, end-to-end setup in which you create a file system, mount it on an Amazon EC2 instance, and test the setup. The console takes care of many things for you and thus helps you quickly set up the end-to-end experience.
- [Walkthrough: Create an Amazon EFS file system and mount it on an Amazon EC2 instance using the AWS CLI \(p. 155\)](#) – This walkthrough is similar to the Getting Started exercise, but it uses the AWS CLI to perform most of the tasks. Because the CLI commands closely map to the Amazon EFS API, the walkthrough can help you familiarize yourself with the Amazon EFS API.

Managing file system network accessibility

You mount your file system on Amazon EC2 or other AWS compute instance in your virtual private cloud (VPC) using a mount target that you create for the file system. Managing file system network accessibility refers to managing a file system's mount targets.

The following illustration shows how EC2 instances in a VPC access an Amazon EFS file system using a mount target.



The illustration shows three EC2 instances launched in different VPC subnets accessing an Amazon EFS file system. The illustration also shows one mount target in each of the Availability Zones (regardless of the number of subnets in each Availability Zone).

You can create only one mount target per Availability Zone. If an Availability Zone has multiple subnets, as shown in one of the zones in the illustration, you create a mount target in only one of the subnets. As long as you have one mount target in an Availability Zone, the EC2 instances launched in any of its subnets can share the same mount target.

Managing mount targets refers to these activities:

- **Creating and deleting mount targets in a VPC** – At a minimum, you should create a mount target in each Availability Zone from which you want to access the file system.

Note

We recommend that you create mount targets in all the Availability Zones. If you do, you can easily mount the file system on EC2 instances that you might launch in any of the Availability Zones.

If you delete a mount target, the operation forcibly breaks any mounts of the file system, which might disrupt instances or applications using those mounts. To avoid application disruption, stop applications and unmount the file system before deleting the mount target.

You can use a file system only in one VPC at a time. That is, you can create mount targets for the file system in one VPC at a time. If you want to access the file system from another VPC, first delete the mount targets from the current VPC. Then create new mount targets in another VPC.

- **Updating the mount target configuration** – When you create a mount target, you associate security groups with the mount target. A security group acts as a virtual firewall that controls the traffic to and from the mount target. You can add inbound rules to control access to the mount target, and thus the

file system. After creating a mount target, you might want to modify the security groups assigned to them.

Each mount target also has an IP address. When you create a mount target, you can choose an IP address from the subnet where you are placing the mount target. If you omit a value, Amazon EFS selects an unused IP address from that subnet.

There is no Amazon EFS operation to change the IP address after creating a mount target. Thus, you can't change the IP address programmatically or by using the AWS CLI. But the console enables you to change the IP address. Behind the scenes, the console deletes the mount target and creates the mount target again.

Warning

If you change the IP address of a mount target, you break any existing file system mounts and you need to remount the file system.

None of the configuration changes to file system network accessibility affects the file system itself. Your file system and data remain unchanged.

The following sections provide information about managing network accessibility of your file system.

Topics

- [Creating or deleting mount targets in a VPC \(p. 97\)](#)
- [Changing the VPC for your mount target \(p. 98\)](#)
- [Updating the mount target configuration \(p. 98\)](#)

Creating or deleting mount targets in a VPC

To access an Amazon EFS file system in a VPC, you need mount targets. For an Amazon EFS file system, the following is true:

- You can create one mount target in each Availability Zone.
- If the VPC has multiple subnets in an Availability Zone, you can create a mount target in only one of those subnets. All EC2 instances in the Availability Zone can share the single mount target.

Note

We recommend that you create a mount target in each of the Availability Zones. There are cost considerations for mounting a file system on an EC2 instance in an Availability Zone through a mount target created in another Availability Zone. For more information, see [Amazon EFS](#). In addition, by always using a mount target local to the instance's Availability Zone, you eliminate a partial failure scenario. If the mount target's zone goes down, you can't access your file system through that mount target.

You can delete mount targets. A mount target deletion forcibly breaks any mounts of the file system using that mount target, which might disrupt instances or applications using those mounts. For more information, see [Creating and managing mount targets and security groups \(p. 37\)](#).

Note

Before deleting a mount target, first unmount the file system. For more information, see [Unmounting file systems \(p. 89\)](#).

Using the AWS Management Console, the AWS CLI, and the API, you can create and manage mount targets on file systems. For existing mount targets, you can add and remove security groups, or delete the mount target. For more information, see [Creating and managing mount targets and security groups \(p. 37\)](#).

Changing the VPC for your mount target

You can use an Amazon EFS file system in one VPC based on the Amazon VPC service at a time. That is, you create mount targets in a VPC for your file system, and use those mount targets to provide access to the file system.

You can mount the Amazon EFS file system from these targets:

- Amazon EC2 instances in the same VPC
- EC2 instances in a VPC connected by VPC peering
- On-premises servers by using AWS Direct Connect
- On-premises servers over an AWS virtual private network (VPN) by using Amazon VPC

A *VPC peering connection* is a networking connection between two VPCs that enables you to route traffic between them. The connection can use private Internet Protocol version 4 (IPv4) or Internet Protocol version 6 (IPv6) addresses. For more information on how Amazon EFS works with VPC peering, see [Mounting EFS file systems from another AWS account or VPC \(p. 85\)](#).

To access the file system from EC2 instances in another VPC, you have to:

- Delete the current mount targets.
- Change the VPC.
- Create new mount targets.

For more information on performing these steps in the AWS Management Console, see [To change the VPC for an Amazon EFS file system \(console\) \(p. 40\)](#).

Using the CLI

To use a file system in another VPC, first delete any mount targets that you previously created in a VPC. Then create new mount targets in another VPC. For example AWS CLI commands, see [Managing mount targets using the AWS CLI \(p. 41\)](#).

Updating the mount target configuration

After you create a mount target for your file system, you might want to update the security groups that are in effect. You can't change the IP address of an existing mount target. To change an IP address, delete the mount target and create a new one with the new address. Deleting a mount target breaks any existing file system mounts.

Note

Before deleting a mount target, first unmount the file system.

Modifying a security group

Security groups define inbound and outbound access. When you change security groups associated with a mount target, make sure that you authorize necessary inbound and outbound access. Doing so enables your EC2 instance to communicate with the file system.

For more information about security groups, see [Amazon EC2 Security Groups](#) in the *Amazon EC2 User Guide for Linux Instances*.

To modify a mount target's security group using the AWS Management Console, see [Managing mount targets using the Amazon EFS console \(p. 39\)](#).

To modify a mount target's security group using the AWS CLI, see [Managing mount targets using the AWS CLI \(p. 41\)](#).

Managing file system throughput

You can modify the file system throughput mode after you create it. There are two throughput modes to choose from for your file system, *Bursting Throughput* and *Provisioned Throughput*. With *Bursting Throughput* mode, throughput scales as the size of your file system in the standard storage class grows. For more information about EFS storage classes, see [EFS storage classes \(p. 20\)](#). With *Provisioned Throughput* mode, you can instantly provision the throughput of your file system (in MiB/s) independent of the amount of data stored. For more information about Amazon EFS throughput modes, see [Throughput modes \(p. 132\)](#).

Note

You can decrease your file system throughput in *Provisioned Throughput* mode as long as it's been more than 24 hours since the last decrease. Additionally, you can change between *Provisioned Throughput* mode and the default *Bursting Throughput* mode as long as it's been more than 24 hours since the last throughput mode change.

You can manage the file system throughput mode using the Amazon EFS console, the CLI, and API.

To manage file system throughput (console)

1. Open the Amazon Elastic File System console at <https://console.aws.amazon.com/efs/>.
2. Choose **File systems** to display the list of EFS file systems in your account.
3. Choose the file system on which you want to modify lifecycle policies.
4. On the file system details page, in the **General** panel, choose **Edit**. The **Edit >> General** settings page displays.

Edit

General

Automatic backups
Automatically backup your file system data with Backup using recommended settings. Additional pricing applies.

Enable automatic backups

Lifecycle management
EFS Intelligent-Tiering uses Lifecycle Management to automatically achieve the right price and performance blend for your application by moving your files between the Standard and Standard-Infrequent Access storage classes. [Learn more](#)

Transition into IA
Transition files from Standard to Standard-Infrequent Access.
▼

Transition out of IA
Transition files from Standard-Infrequent Access to Standard.
▼

Throughput mode
Set how your file system's throughput limits are determined. [Learn more](#)

Bursting
Throughput scales with file system size

Provisioned
Throughput fixed at specified amount

Provisioned Throughput (MiB/s)

Valid range is 1-1024 MiB/s
Throughput bill can be up to \$180.00/month.

Maximum Read Throughput (MiB/s)

[Cancel](#) [Save changes](#)

5. Modify the **Throughput mode** setting. If you are changing to Provisioned throughput mode, or changing the amount of Provisioned throughput, enter the new value in MiBps. You can see the estimated cost of the new throughput value, along with the read throughput for the setting.
6. Choose **Save changes** to implement your changes.

To manage file system throughput (CLI)

- Use the [update-file-system](#) CLI command, or the [UpdateFileSystem \(p. 355\)](#) API action to make changes to a file system's throughput mode.

Amazon EFS lifecycle management

Amazon EFS lifecycle management automatically manages cost-effective file storage for your file systems. When enabled, lifecycle management migrates files that have not been accessed for a set period of time to the EFS Standard-Infrequent Access (Standard-IA) or One Zone-Infrequent Access (One Zone-IA) storage class, depending on your file system. You define that period of time by using the [Transition into IA lifecycle policy](#).

Amazon EFS lifecycle management uses an internal timer to track when a file was last accessed, and not the POSIX file system attributes that are publicly viewable. Whenever a file in Standard or One Zone storage is accessed, the lifecycle management timer is reset. After lifecycle management moves a file into one of the IA storage classes, the file remains there indefinitely if Amazon EFS Intelligent-Tiering is not enabled.

Metadata operations, such as listing the contents of a directory, don't count as file access. During the process of transitioning a file's content to one of the IA storage classes, the file is stored in the Standard or One Zone storage class and billed at that storage rate.

Lifecycle management applies to all files in the file system.

Amazon EFS Intelligent-Tiering

Amazon EFS Intelligent-Tiering uses lifecycle management to monitor the access patterns of your workload and is designed to automatically transition files to and from the file system's Infrequent Access (IA) storage class. With intelligent tiering, files in the standard storage class (EFS Standard or EFS One Zone) that are not accessed for the duration of the **Transition into IA** lifecycle policy setting, for example 30 days, are transitioned to the corresponding Infrequent Access (IA) storage class. Additionally, if access patterns change, EFS Intelligent-Tiering automatically moves files back to the EFS Standard or EFS One Zone storage classes when the **Transition out of IA** lifecycle policy is set to **On first access**. This helps to eliminate the risk of unbounded access charges, while providing consistent low latencies.

Using lifecycle policies

Amazon EFS supports two lifecycle policies. **Transition into IA** instructs lifecycle management when to transition files into the file system's Infrequent Access storage class. **Transition out of IA** instructs intelligent tiering when to transition files out of IA storage. Lifecycle policies apply to the entire Amazon EFS file system.

The **Transition into IA** lifecycle policy has the following values:

- **None**
- **7 days since last access**
- **14 days since last access**
- **30 days since last access**
- **60 days since last access**
- **90 days since last access**

The **Transition out of IA** lifecycle policy can have the following values

- **None**
- **On first access**

You can combine the two EFS lifecycle policies to achieve a variety of storage patterns, shown in the following table.

Transition into IA	Transition out of IA	Effect
7-90 days		
On	Off	Classic lifecycle management policy Files stay in IA storage
On	On	EFS Intelligent-Tiering Files move into and out of IA storage

Transition into IA	Transition out of IA	Effect
7-90 days		
Off	On	All files in IA are moved into standard, eventually
Off	Off	Only standard storage class is used

For more information about setting lifecycle policies, see [Using EFS Lifecycle Management and EFS Intelligent Tiering \(p. 102\)](#).

File system operations for lifecycle management

File system operations for lifecycle management and intelligent tiering, have a lower priority than operations for EFS file system workloads. The time required to transition files into or out of IA storage varies depending on the file size and file system workload.

File metadata, including file names, ownership information, and file system directory structure, is always stored in standard storage (Standard or One Zone) to ensure consistent metadata performance. All write operations to files in the file system's IA storage class (Standard-IA or One Zone-IA) are first written to standard storage, then transitioned to the applicable infrequent access storage class. Files smaller than 128 KB aren't eligible for lifecycle management and are always stored in the file system's standard storage class.

Using EFS Lifecycle Management and EFS Intelligent Tiering

When you create an Amazon EFS file system that uses the service recommended settings using the AWS Management Console, the file system's lifecycle policies use the following default settings:

- **Transition into IA** is set to **30 days since last access**
- **Transition out of IA** is set to **On first access**

For more information about creating a file system with the service recommended settings, see [Step 1: Create your Amazon EFS file system \(p. 15\)](#).

When you create a new file system with customized settings, you can set the lifecycle policies as needed. For more information, see [Creating a file system with custom settings using the Amazon EFS console \(p. 28\)](#).

You can configure lifecycle policies using the AWS Management Console and the AWS CLI, as described in the following procedures.

Manage lifecycle policies on an existing file system (console)

You can use the AWS Management Console to set the lifecycle policies for an existing file system.

1. Sign in to the AWS Management Console and open the Amazon EFS console at <https://console.aws.amazon.com/efs/>.
2. Choose **File systems** to display the list of file systems in your account.

Choose the file system on which you want to modify lifecycle policies.

3. On the file system details page, in the **General** panel, choose **Edit**. The **Edit >> General** settings page displays.

The screenshot shows the 'General' settings page for an EFS file system. It includes sections for 'Automatic backups', 'Lifecycle management', 'Throughput mode', and configuration dropdowns for 'Transition into IA' and 'Transition out of IA'.

Automatic backups: Automatically backup your file system data with AWS Backup using recommended settings. Additional pricing applies. [Learn more](#)

Enable automatic backups

Lifecycle management: Automatically save money as access patterns change by moving files into the EFS Infrequent Access (IA) storage class. File access charges are based on the policy selected. [Learn more](#)

Transition into IA: Transition files into the EFS Infrequent Access storage class.

Transition out of IA: Transition files from EFS Infrequent Access to the EFS Standard storage class.

Throughput mode: Set how your file system's throughput limits are determined. [Learn more](#)

Bursting Throughput scales with file system size

Provisioned Throughput fixed at specified amount

4. For Lifecycle management, you can change the following lifecycle policies:

- Set **Transition into IA** to one of the available settings. To stop moving files into IA storage, choose **None**.
- Set **Transition out of IA** to **On first access** to move files that are in IA storage to standard storage when they're accessed for non-metadata operations.

To stop moving files from IA to standard storage on first access, set to **None**.

5. Choose **Save changes** to save your changes.

Manage lifecycle policies on an existing file system (CLI)

You can use the AWS CLI to set or modify a file system's lifecycle policies:

- Run the [put-lifecycle-configuration](#) AWS CLI command or the [PutLifecycleConfiguration \(p. 345\)](#) API command, specifying the file system ID of the file system for which you are managing lifecycle management.

```
$ aws efs put-lifecycle-configuration \
--file-system-id File-System-ID \
--lifecycle-policies "[{\\"TransitionToIA\\": \"AFTER_60_DAYS\"}, \
{\\"TransitionToPrimaryStorageClass\\": \"AFTER_1_ACCESS\"}]" \
--region us-west-2 \
--profile adminuser
```

You get the following response.

```
{ "LifecyclePolicies": [ { "TransitionToIA": "AFTER_60_DAYS" }, { "TransitionToPrimaryStorageClass": "AFTER_1_ACCESS" } ] }
```

```
    ]  
}
```

To stop lifecycle management for an existing file system (CLI)

- Run the `put-lifecycle-configuration` command specifying the file system ID of the file system for which you are stopping lifecycle management. Keep the `--lifecycle-policies` property empty.

```
$ aws efs put-lifecycle-configuration \  
--file-system-id File-System-ID \  
--lifecycle-policies \  
--region us-west-2 \  
--profile adminuser
```

You get the following response.

```
{  
    "LifecyclePolicies": []  
}
```

Managing access to encrypted file systems

Using Amazon EFS, you can create encrypted file systems. Amazon EFS supports two forms of encryption for file systems, encryption in transit and encryption at rest. Any key management you need to perform is only related to encryption at rest. Amazon EFS automatically manages the keys for encryption in transit.

If you create a file system that uses encryption at rest, data and metadata are encrypted at rest. Amazon EFS uses AWS Key Management Service (AWS KMS) for key management. When you create a file system using encryption at rest, you specify an AWS KMS key . The KMS key can be `aws/elasticfilesystem` (the AWS managed key for Amazon EFS), or it can be a customer managed key that you manage.

File data—the contents of your files—is encrypted at rest using the KMS key that you specified when you created your file system. Metadata—file names, directory names, and directory contents—is encrypted using a key that Amazon EFS manages.

The EFS AWS managed key for your file system is used as the KMS key for encrypting the metadata in your file system, for example file names, directory names, and directory contents. You own the customer managed key used to encrypt file data (the contents of your files) at rest.

You manage who has access to your KMS keys and the contents of your encrypted file systems. This access is controlled by both AWS Identity and Access Management (IAM) policies and AWS KMS. IAM policies control a user's access to Amazon EFS API actions. AWS KMS key policies control a user's access to the KMS key you specified when the file system was created. For more information, see the following:

- [IAM Users in the *IAM User Guide*](#)
- [Using key policies in AWS KMS in the *AWS Key Management Service Developer Guide*](#)
- [Using grants in the *AWS Key Management Service Developer Guide*.](#)

As a key administrator, you can import external keys. You can also modify keys by enabling them, disabling them, or deleting them. The state of the KMS key that you specified (when you created the file

system with encryption at rest) affects access to its contents. The KMS key must be in the enabled state for users to have access to the contents of an encrypted-at-rest file system that is encrypted using that key.

Performing administrative actions on Amazon EFS KMS keys

Following, you can find how to enable, disable, or delete the KMS keys associated with your Amazon EFS file system. You can also learn about the behavior to expect from your file system when you perform these actions.

Disabling, deleting, or revoking access to the KMS key for a file system

You can disable or delete your customer managed KMS keys, or you can revoke Amazon EFS access to your KMS keys. Disabling and revoking access for Amazon EFS to your keys are reversible actions. Exercise significant caution when deleting KMS keys. Deleting a KMS key is an irreversible action.

If you disable or delete the KMS key used for your mounted file system, the following is true:

- That KMS key can't be used as the key for new encrypted-at-rest file systems.
- Existing encrypted-at-rest file systems that use that KMS key stop working after a period of time.

If you revoke Amazon EFS access to a grant for any existing mounted file system, the behavior is the same as if you disabled or deleted the associated KMS key. In other words, the encrypted-at-rest file system continues to function, but stops working after a period of time.

You can prevent access to a mounted encrypted-at-rest file system that has a KMS key that you disabled, deleted, or revoked Amazon EFS access to. To do this, unmount the file system and delete your Amazon EFS mount targets.

You can't immediately delete an AWS KMS key, but you can schedule it for deletion in 7-30 days. While a KMS key is scheduled for deletion, you can't use it for cryptographic operations. You can also cancel a KMS key's scheduled deletion.

To learn how to disable and re-enable customer managed KMS keys, see [Enabling and disabling keys](#) in the AWS Key Management Service Developer Guide. To learn how to schedule deletion of customer managed KMS keys, see [Deleting KMS keys](#) in the AWS Key Management Service Developer Guide.

Related topics

- For more information on encrypted data and metadata at rest in Amazon EFS, see [Data encryption in Amazon EFS \(p. 189\)](#).
- For example key policies, see [Amazon EFS key policies for AWS KMS \(p. 193\)](#).
- For a list of AWS CloudTrail log entries associated with an encrypted file system, see [Amazon EFS Log File Entries for Encrypted-at-Rest File Systems \(p. 128\)](#).
- For more information on determining what accounts and services have access to your KMS keys, see [Determining access to an AWS KMS key](#) in the *AWS Key Management Service Developer Guide*.

Metering: How Amazon EFS reports file system and object sizes

In the following section, find how Amazon EFS reports file system sizes and sizes of objects within a file system.

Metering Amazon EFS file system objects

Objects that you can view in an Amazon EFS system include regular files, directories, symbolic links, and special files (FIFOs and sockets). Each of these objects is metered for 2 kibibytes (KiB) of metadata (for its inode) and one or more increments of 4 KiB of data. The following list explains the metered data size for different types of file system objects:

- **Regular files** – The metered data size of a regular file is the logical size of the file rounded to the next 4-KiB increment, except that it might be less for sparse files.

A *sparse file* is a file to which data is not written to all positions of the file before its logical size is reached. For a sparse file, in some cases the actual storage used is less than the logical size rounded to the next 4-KiB increment. In these cases, Amazon EFS reports actual storage used as the metered data size.

- **Directories** – The metered data size of a directory is the actual storage used for the directory entries and the data structure that holds them, rounded to the next 4-KiB increment. The metered data size doesn't include the actual storage used by the file data.
- **Symbolic links and special files** – The metered data size for these objects is always 4 KiB.

When Amazon EFS reports the space used for an object, through the NFSv4.1 `space_used` attribute, it includes the object's current metered data size but not its metadata size. You can use two utilities for measuring the disk usage of a file, the `du` and `stat` utilities. Following is an example of how to use the `du` utility on an empty file, with the `-k` option to return the output in kilobytes.

```
$ du -k file
4      file
```

Following is an example of how to use the `stat` utility on an empty file to return the file's disk usage.

```
$ /usr/bin/stat --format="%b*%B" file | bc
4096
```

To measure the size of a directory, use the `stat` utility. Find the `Blocks` value, and then multiply that value by the block size. Following is an example of how to use the `stat` utility on an empty directory:

```
$ /usr/bin/stat --format="%b*%B" . | bc
4096
```

Metered size of an Amazon EFS file system

The metered size of an Amazon EFS file system includes the sum of the sizes of all current objects in the Standard and IA storage classes. The size of each object is calculated from a representative sampling of the size of the object during the metered hour, for example from 8 AM to 9 AM.

An empty file contributes 6 KiB (2 KiB metadata + 4 KiB data) to the metered size of a file system. Upon creation, a file system has a single empty root directory and therefore has a metered size of 6 KiB.

The metered sizes of a particular file system define the usage for which the owner account is billed for that file system for that hour.

Note

The computed metered size doesn't represent a consistent snapshot of the file system at any particular time during that hour. Instead, it represents the sizes of the objects that existed in the file system at varying times within each hour, or possibly the hour before it. These sizes are summed to determine the file system's metered size for the hour. The metered size of a file system is thus eventually consistent with the metered sizes of the objects stored when there are no writes to the file system.

You can see this metered size for an Amazon EFS file system in the following ways:

- Using the [describe-file-systems](#) AWS CLI command and the [DescribeFileSystems \(p. 311\)](#) API operation, the response includes the following:

```
"SizeInBytes":{  
    "Timestamp": 1403301078,  
    "Value": 29313417216,  
    "ValueInIA": 675432,  
    "ValueInStandard": 29312741784  
}
```

Where

The metered size of ValueInStandard is also used to determine your I/O throughput baseline and burst rates for file systems using the [Bursting Throughput \(p. 132\)](#) mode.

- View the **Size in Standard / One Zone** column in the **File systems** table, for each file system listed in the EFS management console.
- Run the df command in Linux at the terminal prompt of an EC2 instance.

Use the df command and not the du command. Don't use the du command on the root of the file system for storage metering purposes. The results don't provide full data.

Note

The metered size of ValueInStandard is also used to determine your I/O throughput baseline and burst rates. For more information, see [Bursting Throughput mode \(p. 133\)](#).

Metering infrequent access

Infrequent Access (IA) storage is metered in 4 KiB increments. IA file metadata (2 KiB per file) is always stored and metered in the Standard storage class. Data access for IA storage is metered in 1 MiB increments.

Metering provisioned throughput

Customers only pay for the amount of time that Provisioned Throughput is enabled. Provisioned Throughput is metered once every hour. For metering when Provision Throughput is set for less than one hour, Amazon EFS calculates the time-average using millisecond precision.

Amazon EFS file systems meter the throughput for read requests at one-third the rate of the other file system I/O operations. For example, if you are driving 30 MB/s of both read throughput and write throughput, the read portion counts as 10 MB/s of effective throughput, the write portion counts as 30 MB/s, and the combined metered throughput is 40 MB/s. This combined throughput adjusted for consumption rates is reflected in the MeteredIOBytes CloudWatch metric.

Managing Amazon EFS file system costs using AWS Budgets

You can plan and manage your Amazon EFS file system costs by using AWS Budgets.

You can work with AWS Budgets from the AWS Billing and Cost Management console. To use AWS Budgets, you create a monthly cost budget for your EFS file systems. You can set up your budget to notify you if your costs are forecast to exceed your budgeted amount, and then make adjustments to maintain your budget as needed.

There are costs associated with using AWS Budgets. For regular AWS accounts, your first two budgets are free. For more information about AWS Budgets, including costs, see [Managing Your Costs with Budgets](#) in the *AWS Billing User Guide*.

You can set custom budgets for your Amazon EFS costs and usage at the account, AWS Region, service, or tag level by using budget parameters. In the following section, you can find a high-level description of how to set up a cost budget on an EFS file system with AWS Budgets. You do so by using cost allocation tags.

Prerequisites

To perform the procedures referenced in the following sections, make sure that you have the following:

- An EFS file system
- An AWS Identity and Access Management (IAM) policy with the following permissions:
 - Access to the AWS Billing and Cost Management console.
 - Ability to perform the `elasticfilesystem:CreateTags` and `elasticfilesystem:DescribeTags` actions.

Creating a monthly cost budget for an EFS file system

Creating a monthly cost budget for your Amazon EFS file system using tags is a three-step process.

To create a monthly cost budget for your EFS file system using tags

1. Create a tag to use to identify the file system that you want to track costs for. To learn how, see [Tagging Amazon EFS resources \(p. 50\)](#).
2. In the Billing and Cost Management console, activate the tag as a cost allocation tag. For a detailed procedure, see [Activating user-defined cost allocation tags](#) in the *AWS Billing User Guide*.
3. In the Billing and Cost Management console, under **Budgets**, create a monthly cost budget in AWS Budgets. For a detailed procedure, see [Creating a cost budget](#) in the *AWS Billing User Guide*.

After you create your EFS monthly cost budget, you can view it in the **Budgets** dashboard, which displays the following budget data:

- Your current costs and usage incurred for a budget during the budget period.
- Your budgeted costs for the budget period.
- Your forecast costs for the budget period.
- A percentage that shows your costs compared to your budgeted amount.

- A percentage that shows your forecast costs compared to your budgeted amount.

For more information about viewing your EFS cost budget, see [Viewing your budgets](#) in the *AWS Billing User Guide*.

File system status

You can view the status of Amazon EFS file systems using the Amazon EFS console or the AWS CLI. An Amazon EFS file system can have one of the status values described in the following table.

File system state	Description
AVAILABLE	The file system is in a healthy state, and is reachable and available for use.
CREATING	Amazon EFS is in the process of creating the new file system.
DELETING	Amazon EFS is deleting the file system in response to a user-initiated delete request. For more information, see Deleting an Amazon EFS file system (p. 36) .
DELETED	Amazon EFS has deleted the file system in response to a user-initiated delete request. For more information, see Deleting an Amazon EFS file system (p. 36) .
UPDATING	The file system is undergoing an update in response to a user-initiated update request.
ERROR	Applicable for file systems using One Zone storage classes, including file systems in a replication configuration. The file system is in a failed state and is unrecoverable. To access the file system data, restore a backup of this file system to a new file system. For more information, see: <ul style="list-style-type: none">• Restore a recovery point (p. 141).• EFS storage classes (p. 20)• Amazon EFS replication (p. 143)

Monitoring Amazon EFS

Monitoring is an important part of maintaining the reliability, availability, and performance of Amazon EFS and your AWS solutions. We recommend that you collect monitoring data from all of the parts of your AWS solution so that you can more easily debug a multi-point failure if one occurs. Before you start monitoring Amazon EFS, however, create a monitoring plan that includes answers to the following questions:

- What are your monitoring goals?
- What resources will you monitor?
- How often will you monitor these resources?
- What monitoring tools will you use?
- Who will perform the monitoring tasks?
- Who should be notified when something goes wrong?

The next step is to establish a baseline for normal Amazon EFS performance in your environment, by measuring performance at various times and under different load conditions. As you monitor Amazon EFS, consider storing historical monitoring data. This stored data will give you a baseline to compare against with current performance data, identify normal performance patterns and performance anomalies, and devise methods to address issues.

For example, with Amazon EFS, you can monitor network throughput, I/O for read, write, and metadata operations, client connections, and burst credit balances for your file systems. If performance falls outside your established baseline, you might need to change the size of your file system or the number of connected clients to optimize the file system for your workload.

To establish a baseline, you should, at a minimum, monitor the following items:

- Your file system's network throughput.
- The number of client connections to a file system.
- The number of bytes for each file system operation, including data read, data write, and metadata operations.

Monitoring tools

AWS provides various tools that you can use to monitor Amazon EFS. You can configure some of these tools to do the monitoring for you, but some of the tools require manual intervention. We recommend that you automate monitoring tasks as much as possible.

Automated monitoring tools

You can use the following automated monitoring tools to watch Amazon EFS and report when something is wrong:

- **Amazon CloudWatch Alarms** – Watch a single metric over a time period that you specify, and perform one or more actions based on the value of the metric relative to a given threshold over a number of time periods. The action is a notification sent to an Amazon Simple Notification Service (Amazon SNS) topic or Amazon EC2 Auto Scaling policy. CloudWatch alarms do not invoke actions only because they

are in a particular state; the state must have changed and been maintained for a specified number of periods. For more information, see [Monitoring Amazon EFS with Amazon CloudWatch \(p. 111\)](#).

- **Amazon CloudWatch Logs** – Monitor, store, and access your log files from AWS CloudTrail or other sources. For more information, see [Monitoring Log Files](#) in the *Amazon CloudWatch User Guide*.
- **Amazon CloudWatch Events** – Match events and route them to one or more target functions or streams to make changes, capture state information, and take corrective action. For more information, see [What is Amazon CloudWatch Events](#) in the *Amazon CloudWatch User Guide*.
- **AWS CloudTrail Log Monitoring** – Share log files between accounts, monitor CloudTrail log files in real time by sending them to CloudWatch Logs, write log processing applications in Java, and validate that your log files have not changed after delivery by CloudTrail. For more information, see [Working with CloudTrail Log Files](#) in the *AWS CloudTrail User Guide*.

Manual monitoring tools

Another important part of monitoring Amazon EFS involves manually monitoring those items that the Amazon CloudWatch alarms don't cover. The Amazon EFS, CloudWatch, and other AWS Management Console dashboards provide an at-a-glance view of the state of your AWS environment. We recommend that you also check the log files on file system.

- From the Amazon EFS console, you can find the following items for your file systems:
 - The current metered size
 - The number of mount targets
 - The lifecycle state
- CloudWatch home page shows:
 - Current alarms and status
 - Graphs of alarms and resources
 - Service health status

In addition, you can use CloudWatch to do the following:

- Create [customized dashboards](#) to monitor the services that you use.
- Graph metric data to troubleshoot issues and discover trends.
- Search and browse all your AWS resource metrics.
- Create and edit alarms to be notified of problems.

Monitoring Amazon EFS with Amazon CloudWatch

You can monitor file systems using Amazon CloudWatch, which collects and processes raw data from Amazon EFS into readable, near real-time metrics. These statistics are recorded for a period of 15 months, so that you can gain a better perspective on how your web application or service is performing.

By default, Amazon EFS metric data is automatically sent to CloudWatch at 1-minute periods, unless noted for some individual metrics. The Amazon EFS console displays a series of graphs based on the raw data from Amazon CloudWatch. Depending on your needs, you might prefer to get data for your file systems from CloudWatch instead of the graphs in the console.

For more information about Amazon CloudWatch, see the [Amazon CloudWatch User Guide](#).

Topics

- [Amazon CloudWatch metrics for Amazon EFS \(p. 112\)](#)
- [How do I use Amazon EFS metrics? \(p. 115\)](#)
- [Using metric math with Amazon EFS \(p. 116\)](#)

- [Monitoring EFS file system mount status \(p. 119\)](#)
- [Accessing CloudWatch metrics \(p. 120\)](#)
- [Creating CloudWatch alarms to monitor Amazon EFS \(p. 121\)](#)

Amazon CloudWatch metrics for Amazon EFS

Amazon EFS metrics use the EFS namespace and provide metrics for a single dimension, `FileSystemId`. A file system's ID can be found in the Amazon EFS console, and it takes the form of `fs-abcdef0123456789a`.

The AWS/EFS namespace includes the following metrics.

TimeSinceLastSync

Shows the amount of time that has passed since the last successful sync to the destination file system in a replication configuration. Any changes to data on the source file system that occurred before the `TimeSinceLastSync` value have been successfully replicated. Any changes on the source that occurred after `TimeSinceLastSync` might not be fully replicated. For more information, see [Amazon EFS replication \(p. 143\)](#).

Units: Seconds

PercentIOLimit

Shows how close a file system is to reaching the I/O limit of the General Purpose performance mode. If this metric is at 100 percent more often than not, consider moving your application to a file system using the Max I/O performance mode.

Note

This metric is only submitted for file systems using the General Purpose performance mode.

Units: Percent

BurstCreditBalance

The number of burst credits that a file system has. Burst credits allow a file system to burst to throughput levels above a file system's baseline level for periods of time. For more information, see [Bursting Throughput mode \(p. 133\)](#).

The `Minimum` statistic is the smallest burst credit balance for any minute during the period. The `Maximum` statistic is the largest burst credit balance for any minute during the period. The `Average` statistic is the average burst credit balance during the period.

Units: Bytes

Valid statistics: `Minimum`, `Maximum`, `Average`

PermittedThroughput

The maximum amount of throughput that a file system can drive. For file systems in the Provisioned Throughput mode, if the amount of data stored in the EFS Standard storage class allows your file system to drive a higher throughput than you provisioned, this metric reflects the higher throughput instead of the provisioned amount. For file systems in Bursting Throughput mode, this value is a function of the file system size and `BurstCreditBalance`. For more information, see [Amazon EFS performance \(p. 130\)](#).

The `Minimum` statistic is the smallest throughput permitted for any minute during the period. The `Maximum` statistic is the highest throughput permitted for any minute during the period. The `Average` statistic is the average throughput permitted during the period.

Note

Read operations are metered at one-third the rate of other operations.

Units: Bytes per second

Valid statistics: Minimum, Maximum, Average

MeteredIOBytes

The number of metered bytes for each file system operation, including data read, data write, and metadata operations, with read operations metered at one-third the rate of other operations.

You can create a [CloudWatch metric math expression \(p. 117\)](#) that compares MeteredIOBytes to PermittedThroughput. If these values are equal, then you are consuming the entire amount of throughput allocated to your file system. In this situation, you might consider changing the file system's throughput mode to Provisioned Throughput to get higher throughput.

The Sum statistic is the total number of metered bytes associated with all file system operations. The Minimum statistic is the size of the smallest operation during the period. The Maximum statistic is the size of the largest operation during the period. The Average statistic is the average size of an operation during the period. The SampleCount statistic provides a count of all operations.

Units:

- Bytes for Minimum, Maximum, Average, and Sum statistics.
- Count for SampleCount.

Valid statistics: Minimum, Maximum, Average, Sum, SampleCount

TotalIOBytes

The actual number of bytes for each file system operation, including data read, data write, and metadata operations. This is the actual amount that your application is driving, and not the throughput the file system is being metered at. It might be higher than the numbers shown in PermittedThroughput.

The Sum statistic is the total number of bytes associated with all file system operations. The Minimum statistic is the size of the smallest operation during the period. The Maximum statistic is the size of the largest operation during the period. The Average statistic is the average size of an operation during the period. The SampleCount statistic provides a count of all operations.

Note

To calculate the average operations per second for a period, divide the SampleCount statistic by the number of seconds in the period. To calculate the average throughput (bytes per second) for a period, divide the Sum statistic by the number of seconds in the period.

Units:

- Bytes for Minimum, Maximum, Average, and Sum statistics.
- Count for SampleCount.

Valid statistics: Minimum, Maximum, Average, Sum, SampleCount

DataReadIOBytes

The number of bytes for each file system read operation.

The Sum statistic is the total number of bytes associated with read operations. The Minimum statistic is the size of the smallest read operation during the period. The Maximum statistic is the size of the largest read operation during the period. The Average statistic is the average size of read operations during the period. The SampleCount statistic provides a count of read operations.

Units:

- Bytes for Minimum, Maximum, Average, and Sum.
- Count for SampleCount.

Valid statistics: Minimum, Maximum, Average, Sum, SampleCount

DataWriteI0Bytes

The number of bytes for each file system write operation.

The Sum statistic is the total number of bytes associated with write operations. The Minimum statistic is the size of the smallest write operation during the period. The Maximum statistic is the size of the largest write operation during the period. The Average statistic is the average size of write operations during the period. The SampleCount statistic provides a count of write operations.

Units:

- Bytes are the units for the Minimum, Maximum, Average, and Sum statistics.
- Count for SampleCount.

Valid statistics: Minimum, Maximum, Average, Sum, SampleCount

MetadataI0Bytes

The number of bytes for each metadata operation.

The Sum statistic is the total number of bytes associated with metadata operations. The Minimum statistic is the size of the smallest metadata operation during the period. The Maximum statistic is the size of the largest metadata operation during the period. The Average statistic is the size of the average metadata operation during the period. The SampleCount statistic provides a count of metadata operations.

Units:

- Bytes are the units for the Minimum, Maximum, Average, and Sum statistics.
- Count for SampleCount.

Valid statistics: Minimum, Maximum, Average, Sum, SampleCount

ClientConnections

The number of client connections to a file system. When using a standard client, there is one connection per mounted Amazon EC2 instance.

Note

To calculate the average ClientConnections for periods greater than one minute, divide the Sum statistic by the number of minutes in the period.

Units: Count of client connections

Valid statistics: Sum

StorageBytes

The size of the file system in bytes, including the amount of data stored in the EFS Standard and EFS Standard-Infrequent Access (EFS Standard-IA) storage classes. This metric is emitted every 15 minutes to CloudWatch. For more information about storage classes, see [EFS storage classes \(p. 20\)](#).

The StorageBytes metric has three dimensions:

- Total is the latest known metered size (in bytes) of data stored in the file system, including both storage classes.
- Standard is the latest known metered size (in bytes) of data stored in the EFS Standard storage class.
- IA is the latest known metered size (in bytes) of data stored in the EFS Standard-IA storage class.

Units: Bytes

Note

StorageBytes is displayed on the Amazon EFS console **File system metrics** page using base 1024 units (kilobytes, mebibytes, gibibytes, and tebibytes).

Bytes reported in CloudWatch

Amazon EFS CloudWatch metrics are reported as raw *bytes*. Bytes are not rounded to either a decimal or binary multiple of the unit. Keep this in mind when calculating your burst rate using the data you get from the metrics. For more information about bursting, see [Bursting Throughput mode \(p. 133\)](#).

How do I use Amazon EFS metrics?

The metrics reported by Amazon EFS provide information that you can analyze in different ways. The following list shows some common uses for the metrics. These are suggestions to get you started, not a comprehensive list.

How do I?	Relevant metrics
How can I determine my throughput?	You can monitor the daily Sum statistic of the TotalI0Bytes metric to see your throughput.
How can I track the number of Amazon EC2 instances that are connected to a file system?	You can monitor the Sum statistic of the ClientConnections metric. To calculate the average ClientConnections for periods greater than one minute, divide the sum by the number of minutes in the period.
How can I see my burst credit balance?	You can see your balance by monitoring the BurstCreditBalance metric for your file system. For more information on bursting and burst credits, see Bursting Throughput mode (p. 133) .

Using CloudWatch metrics to monitor throughput performance

The Amazon EFS CloudWatch metrics for throughput monitoring—TotalI0Bytes, ReadI0Bytes, WriteI0Bytes, and MetadataI0Bytes—represent the actual throughput that you are driving on your file system. The metric MeteredI0Bytes represents the calculation of the overall [metered throughput \(p. 132\)](#) that you are driving. You can use the **Throughput utilization (%)** graph in the Amazon EFS console **Monitoring** section to monitor your throughput utilization. If you use custom Amazon CloudWatch dashboards or another monitoring tool, you can create a [CloudWatch metric math expression \(p. 117\)](#) that compares MeteredI0Bytes to PermittedThroughput.

PermittedThroughput measures the amount of allowed throughput for the file system. This value is based on one of the following methods:

- For file systems in Provisioned Throughput mode, if the amount of data stored in the EFS Standard storage class allows your file system to drive a higher throughput than you provisioned, this metric reflects the higher throughput instead of the provisioned amount.
- For file systems in Bursting Throughput mode, this value is a function of the file system size and BurstCreditBalance.

When the values for MeteredI0Bytes and PermittedThroughput are equal, your file system is consuming all available throughput. For file systems using Provisioned Throughput mode, you can provision additional throughput.

For file systems using Bursting Throughput mode, monitor BurstCreditBalance to ensure that your file system is operating at its burst rate rather than its base rate. If the balance is consistently at or near zero, you must switch to Provisioned Throughput mode to get additional throughput.

Using metric math with Amazon EFS

Using metric math, you can query multiple CloudWatch metrics and use math expressions to create new time series based on these metrics. You can visualize the resulting time series in the CloudWatch console and add them to dashboards. For example, you can use Amazon EFS metrics to take the sample count of DataRead operations divided by 60. The result is the average number of reads per second on your file system for a given 1-minute period. For more information on metric math, see [Use Metric Math](#) in the *Amazon CloudWatch User Guide*.

Following, find some useful metric math expressions for Amazon EFS.

Topics

- [Metric math: Throughput in MiB/second \(p. 116\)](#)
- [Metric math: Percent throughput \(p. 116\)](#)
- [Metric math: Percentage of permitted throughput utilization \(p. 117\)](#)
- [Metric math: Throughput IOPS \(p. 117\)](#)
- [Metric math: Percentage of IOPS \(p. 118\)](#)
- [Metric math: Average I/O size in KiB \(p. 118\)](#)
- [Using metric math through an AWS CloudFormation template for Amazon EFS \(p. 119\)](#)

Metric math: Throughput in MiB/second

To calculate the average throughput (in MiB/second) for a time period, first choose a sum statistic (DataReadI0Bytes, DataWriteI0Bytes, MetadataI0Bytes, or TotalI0Bytes). Then convert the value to MiB, and divide that by the number of seconds in the period.

Suppose that your example logic is this: $(\text{sum of TotalI0Bytes} \div 1,048,576 \text{ (to convert to MiB)}) \div \text{seconds in the period}$

Then your CloudWatch metric information is the following.

ID	Usable metrics	Statistic	Period
m1	<ul style="list-style-type: none">• DataReadI0Bytes• DataWriteI0Bytes• MetadataI0Bytes• TotalI0Bytes	sum	1 minute

Your metric math ID and expression are the following.

ID	Expression
e1	$(m1 / 1048576) / \text{PERIOD}(m1)$

Metric math: Percent throughput

This metric math expression calculates the percent of overall throughput used for the different I/O types—for example, the percentage of total throughput that is driven by read requests. To calculate the percent of overall throughput used by one of the I/O types (DataReadI0Bytes, DataWriteI0Bytes, or MetadataI0Bytes) for a time period, first multiply the respective sum statistic by 100. Then divide the result by the sum statistic of TotalI0Bytes for the same period.

Suppose that your example logic is this: $(\text{sum of DataReadIOBytes} \times 100 \text{ (to convert to percentage)}) \div \text{sum of TotalIOBytes}$

Then your CloudWatch metric information is the following.

ID	Usable metric or metrics	Statistic	Period
m1	• TotalIOBytes	sum	1 minute
m2	• DataReadIOBytes	sum	1 minute

Your metric math ID and expression are the following.

ID	Expression
e1	$(m2 * 100) / m1$

Metric math: Percentage of permitted throughput utilization

To calculate the percentage of permitted throughput utilization (MeteredIOBytes) for a time period, first multiply the throughput in MiB/second by 100. Then divide the result by the sum statistic of PermittedThroughput converted to MiB for the same period.

Suppose that your example logic is this: $(\text{metric math expression for throughput in MiB/second} \times 100 \text{ (to convert to percentage)}) \div (\text{sum of PermittedThroughput} \div 1,048,576 \text{ (to convert bytes to MiB)})$

Then your CloudWatch metric information is the following.

ID	Usable metric or metrics	Statistic	Period
m1	MeteredIOBytes	sum	1 minute
m2	PermittedThroughput	sum	1 minute

Your metric math ID and expression are the following.

ID	Expression
e1	$(m1 / 1048576) / \text{PERIOD}(m1)$
e2	$m2 / 1048576$
e3	$((e1) * 100) / (e2)$

Metric math: Throughput IOPS

To calculate the average operations per second (IOPS) for a time period, divide the sample count statistic (DataReadIOBytes, DataWriteIOBytes, MetadataIOBytes, or TotalIOBytes) by the number of seconds in the period.

Suppose that your example logic is this: sample count of DataWriteIOBytes \div seconds in the period

Then your CloudWatch metric information is the following.

ID	Usable metrics	Statistic	Period
m1	<ul style="list-style-type: none"> • DataReadIOBytes • DataWriteIOBytes • MetadataIOBytes • TotalIOBytes 	sample count	1 minute

Your metric math ID and expression are the following.

ID	Expression
e1	$m1/\text{PERIOD}(m1)$

Metric math: Percentage of IOPS

To calculate the percentage of IOPS per second of the different I/O types (DataReadIOBytes, DataWriteIOBytes, or MetadataIOBytes) for a time period, first multiply the respective sample count statistic by 100. Then divide that value by the sample count statistic of TotalIOBytes for the same period.

Suppose that your example logic is this: (sample count of MetadataIOBytes x 100 (to convert to percentage)) ÷ sample count of TotalIOBytes

Then your CloudWatch metric information is the following.

ID	Usable metrics	Statistic	Period
m1	• TotalIOBytes	sample count	1 minute
m2	<ul style="list-style-type: none"> • DataReadIOBytes • DataWriteIOBytes • MetadataIOBytes 	sample count	1 minute

Your metric math ID and expression are the following.

ID	Expression
e1	$(m2*100)/m1$

Metric math: Average I/O size in KiB

To calculate the average I/O size (in KiB) for a period, divide the respective sum statistic for the DataReadIOBytes, DataWriteIOBytes, or MetadataIOBytes metric by the same sample count statistic of that metric.

Suppose that your example logic is this: (sum of DataReadIOBytes ÷ 1,024 (to convert to KiB)) ÷ sample count of DataReadIOBytes

Then your CloudWatch metric information is the following.

ID	Usable metrics	Statistic	Period
m1	<ul style="list-style-type: none"> • DataReadIOBytes • DataWriteIOBytes • MetadataIOBytes 	sum	1 minute
m2	<ul style="list-style-type: none"> • DataReadIOBytes • DataWriteIOBytes • MetadataIOBytes 	sample count	1 minute

Your metric math ID and expression are the following.

ID	Expression
e1	$(m1/1024)/m2$

Using metric math through an AWS CloudFormation template for Amazon EFS

You can also create metric math expressions through AWS CloudFormation templates. One such template is available for you to download and customize for use from the [Amazon EFS tutorials](#) on GitHub. For more information about using AWS CloudFormation templates, see [Working with AWS CloudFormation Templates](#) in the *AWS CloudFormation User Guide*.

Monitoring EFS file system mount status

You can use Amazon CloudWatch Logs to monitor the status of EFS file system mounts remotely without having to log into the Amazon EC2 instances. The following pre-requisites are required in order to use CloudWatch Logs to monitor for file system mount status:

1. The Amazon EC2 instances are launched with an instance profile that includes the `AmazonElasticFileSystemsUtils` permissions policy. For more information, see [Step 1: Configure an IAM instance profile with the required permissions \(p. 57\)](#).
2. Version 1.28.1 or later of the Amazon EFS client (`amazon-efs-utils` package) is installed on the Amazon EC2 instances. You can use AWS Systems Manager to automatically install the package on your instances. For more information, see [Step 2: Configure an Association used by State Manager for installing or updating the Amazon EFS client \(p. 57\)](#).
3. The `botocore` package is installed on the Amazon EC2 instance. For more information, see [Installing botocore \(p. 63\)](#).
4. The `efs-utils.conf` configuration file is updated to enable CloudWatch Logs. When you use AWS Systems Manager to install and configure the `amazon-efs-utils` package, this update to enable CloudWatch logging is automatically done for you. When you install the `amazon-efs-utils` package from the yum repository, you have to manually update the `/etc/amazon/efs/efs-utils.conf` configuration file by uncommenting the `# enabled = true` line in the `cloudwatch-log` section.

Here are examples of mount status log entries:

```
Successfully mounted fs-12345678.efs.us-east-1.amazonaws.com at /home/ec2-user/efs
```

```
Mount failed, Failed to resolve "fs-01234567.efs.us-east-1.amazonaws.com"
```

To view mount status in CloudWatch Logs

1. Open the CloudWatch console at <https://console.aws.amazon.com/cloudwatch/>.
2. Choose **Log groups** in the left-hand navigation bar.
3. Choose the **/aws/efs/utils** log group. You will see a log stream for each Amazon EC2 instance and EFS file system combination.
4. Choose a log stream to view specific log events including the file system mount status.

Accessing CloudWatch metrics

You can view Amazon EFS metrics for CloudWatch in several ways:

- In the Amazon EFS console
- In the CloudWatch console
- Using the CloudWatch CLI
- Using the CloudWatch API

The following procedures show you how to access the metrics using these various tools.

To view CloudWatch metrics and alarms in the Amazon EFS console


1. Sign in to the AWS Management Console and open the Amazon EFS console at <https://console.aws.amazon.com/efs/>.
2. Choose **File systems**.
3. Choose the file system that you want to view CloudWatch metrics for.
4. Choose **Monitoring** to display the **File system metrics** page.

The **File system metrics** page displays a default set of CloudWatch metrics for the file system. Any CloudWatch alarms that you have configured also display with these metrics. For file systems that use Max I/O performance mode, the default set of metrics includes Burst Credit balance in place of Percent IO limit. You can override the default settings using the **Metrics settings** dialog box, accessed by choosing the settings icon (⚙).

Note

The Throughput utilization (%) metric is not a CloudWatch metric; it is derived using CloudWatch metric math.

5. You can adjust the way metrics and alarms are displayed using the controls on the **File system metric** page, as follows.



- Toggle the **Display mode** between **Time series** or **Single value**.

- Show or hide any CloudWatch alarms configured for the file system.
- Choose **See more in CloudWatch** to view the metrics in CloudWatch.
- Choose **Add to dashboard** to open your CloudWatch dashboard and add the displayed metrics.
- Adjust the metric time window displayed from 1 hour to 1 week.

To view metrics using the CloudWatch console

1. Open the CloudWatch console at <https://console.aws.amazon.com/cloudwatch/>.
2. In the navigation pane, choose **Metrics**.
3. Select the **EFS** namespace.
4. (Optional) To view a metric, enter its name in the search field.
5. (Optional) To filter by dimension, select **FileSystemId**.

To access metrics from the AWS CLI

- Use the `list-metrics` command with the `--namespace` "AWS/EFS" namespace. For more information, see the [AWS CLI Command Reference](#).

To access metrics from the CloudWatch API

- Call `GetMetricStatistics`. For more information, see [Amazon CloudWatch API Reference](#).

Creating CloudWatch alarms to monitor Amazon EFS

You can create a CloudWatch alarm that sends an Amazon SNS message when the alarm changes state. An alarm watches a single metric over a time period that you specify. The alarm then performs one or more actions based on the value of the metric relative to a given threshold over a number of time periods. The action is a notification sent to an Amazon SNS topic or Auto Scaling policy.

Alarms invoke actions for sustained state changes only. CloudWatch alarms don't invoke actions only because they are in a particular state; the state must have changed and been maintained for a specified number of periods.

One important use of CloudWatch alarms for Amazon EFS is to enforce encryption at rest for your file system. You can enable encryption at rest for an Amazon EFS file system when it's created. To enforce data encryption-at-rest policies for Amazon EFS file systems, you can use Amazon CloudWatch and AWS CloudTrail to detect the creation of a file system and verify that encryption at rest is enabled. For more information, see [Walkthrough: Enforcing Encryption on an Amazon EFS File System at Rest \(p. 184\)](#).

Note

Currently, you can't enforce encryption in transit.

The following procedures outline how to create alarms for Amazon EFS.

To set alarms using the CloudWatch console

1. Sign in to the AWS Management Console and open the CloudWatch console at <https://console.aws.amazon.com/cloudwatch/>.
2. Choose **Create Alarm**. This launches the **Create Alarm Wizard**.
3. Choose **EFS Metrics** and scroll through the Amazon EFS metrics to locate the metric you want to place an alarm on. To display only the Amazon EFS metrics in this dialog box, search for the file system ID of your file system. Select the metric to create an alarm on, and choose **Next**.

4. Fill in the **Name**, **Description**, **Whenever** values for the metric.
 5. If you want CloudWatch to send you an email when the alarm state is reached, in the **Whenever this alarm:** field, choose **State is ALARM**. In the **Send notification to:** field, choose an existing SNS topic. If you select **Create topic**, you can set the name and email addresses for a new email subscription list. This list is saved and appears in the field for future alarms.
- Note**
If you use **Create topic** to create a new Amazon SNS topic, the email addresses must be verified before they receive notifications. Emails are only sent when the alarm enters an alarm state. If this alarm state change happens before the email addresses are verified, they do not receive a notification.
6. At this point, the **Alarm Preview** area gives you a chance to preview the alarm you're about to create. Choose **Create Alarm**.

To set an alarm using the AWS CLI

- Call [put-metric-alarm](#). For more information, see the [AWS CLI Command Reference](#).

To set an alarm using the CloudWatch API

- Call [PutMetricAlarm](#). For more information, see the [Amazon CloudWatch API Reference](#).

Logging Amazon EFS API Calls with AWS CloudTrail

Amazon EFS is integrated with AWS CloudTrail, a service that provides a record of actions taken by a user, role, or an AWS service in Amazon EFS. CloudTrail captures all API calls for Amazon EFS as events, including calls from the Amazon EFS console and from code calls to Amazon EFS API operations.

If you create a trail, you can enable continuous delivery of CloudTrail events to an Amazon S3 bucket, including events for Amazon EFS. If you don't configure a trail, you can still view the most recent events in the CloudTrail console in **Event history**. Using the information collected by CloudTrail, you can determine the request that was made to Amazon EFS, the IP address from which the request was made, who made the request, when it was made, and additional details.

To learn more about CloudTrail, see the [AWS CloudTrail User Guide](#).

Amazon EFS Information in CloudTrail

CloudTrail is enabled on your AWS account when you create the account. When activity occurs in Amazon EFS, that activity is recorded in a CloudTrail event along with other AWS service events in **Event history**. You can view, search, and download recent events in your AWS account. For more information, see [Viewing Events with CloudTrail Event History](#).

For an ongoing record of events in your AWS account, including events for Amazon EFS, create a trail. A trail enables CloudTrail to deliver log files to an Amazon S3 bucket. By default, when you create a trail in the console, the trail applies to all AWS Regions. The trail logs events from all AWS Regions in the AWS partition and delivers the log files to the Amazon S3 bucket that you specify. Additionally, you can configure other AWS services to further analyze and act upon the event data collected in CloudTrail logs. For more information, see the following topics in the [AWS CloudTrail User Guide](#):

- [Overview for Creating a Trail](#)
- [CloudTrail Supported Services and Integrations](#)

- [Configuring Amazon SNS Notifications for CloudTrail](#)
- [Receiving CloudTrail Log Files from Multiple Regions](#) and [Receiving CloudTrail Log Files from Multiple Accounts](#)

All Amazon EFS API calls (p. 254) are logged by CloudTrail. For example, calls to the CreateFileSystem, CreateMountTarget and CreateTags operations generate entries in the CloudTrail log files.

Every event or log entry contains information about who generated the request. The identity information helps you determine the following:

- Whether the request was made with root or AWS Identity and Access Management (IAM) user credentials.
- Whether the request was made with temporary security credentials for a role or federated user.
- Whether the request was made by another AWS service.

For more information, see the [CloudTrail userIdentity Element](#) in the *AWS CloudTrail User Guide*.

Understanding Amazon EFS Log File Entries

A *trail* is a configuration that enables delivery of events as log files to an Amazon S3 bucket that you specify. CloudTrail log files contain one or more log entries. An *event* represents a single request from any source and includes information about the requested action, the date and time of the action, request parameters, and so on. CloudTrail log files aren't an ordered stack trace of the public API calls, so they don't appear in any specific order.

The following example shows a CloudTrail log entry that demonstrates the CreateTags operation when a tag for a file system is created from the console.

```
{  
  "eventVersion": "1.06",  
  "userIdentity": {  
    "type": "Root",  
    "principalId": "111122223333",  
    "arn": "arn:aws:iam::111122223333:root",  
    "accountId": "111122223333",  
    "accessKeyId": "AKIAIOSFODNN7EXAMPLE",  
    "sessionContext": {  
      "attributes": {  
        "mfaAuthenticated": "false",  
        "creationDate": "2017-03-01T18:02:37Z"  
      }  
    }  
  },  
  "eventTime": "2017-03-01T19:25:47Z",  
  "eventSource": "elasticfilesystem.amazonaws.com",  
  "eventName": "CreateTags",  
  "awsRegion": "us-west-2",  
  "sourceIPAddress": "192.0.2.0",  
  "userAgent": "console.amazonaws.com",  
  "requestParameters": {  
    "fileSystemId": "fs-00112233",  
    "tags": [{  
      "key": "TagName",  
      "value": "AnotherNewTag"  
    }]  
  },  
  "responseElements": null,  
}
```

```

"requestID": "dEXAMPLE-feb4-11e6-85f0-736EXAMPLE75",
"eventID": "eEXAMPLE-2d32-4619-bd00-657EXAMPLEe4",
"eventType": "AwsApiCall",
"apiVersion": "2015-02-01",
"recipientAccountId": "111122223333"
}

```

The following example shows a CloudTrail log entry that demonstrates the DeleteTags action when a tag for a file system is deleted from the console.

```

{
  "eventVersion": "1.06",
  "userIdentity": {
    "type": "Root",
    "principalId": "111122223333",
    "arn": "arn:aws:iam::111122223333:root",
    "accountId": "111122223333",
    "accessKeyId": "AKIAIOSFODNN7EXAMPLE",
    "sessionContext": {
      "attributes": {
        "mfaAuthenticated": "false",
        "creationDate": "2017-03-01T18:02:37Z"
      }
    }
  },
  "eventTime": "2017-03-01T19:25:47Z",
  "eventSource": "elasticfilesystem.amazonaws.com",
  "eventName": "DeleteTags",
  "awsRegion": "us-west-2",
  "sourceIPAddress": "192.0.2.0",
  "userAgent": "console.amazonaws.com",
  "requestParameters": {
    "fileSystemId": "fs-00112233",
    "tagKeys": []
  },
  "responseElements": null,
  "requestID": "dEXAMPLE-feb4-11e6-85f0-736EXAMPLE75",
  "eventID": "eEXAMPLE-2d32-4619-bd00-657EXAMPLEe4",
  "eventType": "AwsApiCall",
  "apiVersion": "2015-02-01",
  "recipientAccountId": "111122223333"
}

```

Log Entries for EFS Service Linked Roles

The Amazon EFS service linked role makes API calls to AWS resources. You will see CloudTrail log entries with username: `AWSServiceRoleForAmazonElasticFileSystem` for calls made by the EFS service linked role. For more information about EFS and service linked roles, see [Using the Amazon EFS Service-Linked Role \(p. 215\)](#).

The following example shows a CloudTrail log entry that demonstrates a `CreateServiceLinkedRole` action when Amazon EFS creates the `AWSServiceRoleForAmazonElasticFileSystem` service linked role.

```

{
  "eventVersion": "1.05",
  "userIdentity": {
    "type": "IAMUser",
    "principalId": "111122223333",
    "arn": "arn:aws:iam::111122223333:user/user1",
    "accountId": "111122223333",
    "accessKeyId": "AKIAIOSFODNN7EXAMPLE"
  }
}

```

```

    "accessKeyId": "A111122223333",
    "userName": "user1",
    "sessionContext": {
        "attributes": {
            "mfaAuthenticated": "false",
            "creationDate": "2019-10-23T22:45:41Z"
        }
    },
    "invokedBy": "elasticfilesystem.amazonaws.com"
},
"eventTime": "2019-10-23T22:45:41Z",
"eventSource": "iam.amazonaws.com",
"eventName": "CreateServiceLinkedRole",
"awsRegion": "us-east-1",
"sourceIPAddress": "192.0.2.0",
"userAgent": "user_agent",
"requestParameters": {
    "aWSServiceName": "elasticfilesystem.amazonaws.com"
},
"responseElements": {
    "role": {
        "assumeRolePolicyDocument": "111122223333-10-111122223333Statement111122223333Action111122223333AssumeRole111122223333Effect%22%3A%20%22Allow%22%2C%20%22Principal%22%3A%20%7B%22Service%22%3A%20%5B%22elasticfilesystem.amazonaws.com%22%5D%7D%7D%5D%7D",
        "arn": "arn:aws:iam::111122223333:role/aws-service-role/elasticfilesystem.amazonaws.com/AWSServiceRoleForAmazonElasticFileSystem",
        "roleId": "111122223333",
        "createDate": "Oct 23, 2019 10:45:41 PM",
        "roleName": "AWSServiceRoleForAmazonElasticFileSystem",
        "path": "/aws-service-role/elasticfilesystem.amazonaws.com/"
    }
},
"requestID": "11111111-2222-3333-4444-abcdef123456",
"eventID": "11111111-2222-3333-4444-abcdef123456",
"eventType": "AwsApiCall",
"recipientAccountId": "111122223333"
}

```

The following example shows a CloudTrail log entry that demonstrates a `CreateNetworkInterface` action made by the `AWSServiceRoleForAmazonElasticFileSystem` service linked role, noted in the `sessionContext`.

```
{
    "eventVersion": "1.05",
    "userIdentity": {
        "type": "AssumedRole",
        "principalId": "AIDACKCEVSQ6C2EXAMPLE",
        "arn": "arn:aws:sts::0123456789ab:assumed-role/AWSServiceRoleForAmazonElasticFileSystem/0123456789ab",
        "accountId": "0123456789ab",
        "sessionContext": {
            "sessionIssuer": {
                "type": "Role",
                "principalId": "AIDACKCEVSQ6C2EXAMPLE",
                "arn": "arn:aws:iam::0123456789ab:role/aws-service-role/elasticfilesystem.amazonaws.com/AWSServiceRoleForAmazonElasticFileSystem",
                "accountId": "0123456789ab",
                "userName": "AWSServiceRoleForAmazonElasticFileSystem"
            },
            "webIdFederationData": {},
            "attributes": {
                "mfaAuthenticated": "false",
                "creationDate": "2019-10-23T22:50:05Z"
            }
        }
    }
}
```

```

        },
        "invokedBy": "AWS Internal"
    },
    "eventTime": "20You 19-10-23T22:50:05Z",
    "eventSource": "ec2.amazonaws.com",
    "eventName": "CreateNetworkInterface",
    "awsRegion": "us-east-1",
    "sourceIPAddress": "elasticfilesystem.amazonaws.com",
    "userAgent": "elasticfilesystem.amazonaws.com",
    "requestParameters": {
        "subnetId": "subnet-71e2f83a",
        "description": "EFS mount target for fs-1234567 (fsmt-1234567)",
        "groupSet": {},
        "privateIpAddressesSet": {}
    },
    "responseElements": {
        "requestId": "0708e4ad-03f6-4802-b4ce-4ba987d94b8d",
        "networkInterface": {
            "networkInterfaceId": "eni-0123456789abcdef0",
            "subnetId": "subnet-12345678",
            "vpcId": "vpc-01234567",
            "availabilityZone": "us-east-1b",
            "description": "EFS mount target for fs-1234567 (fsmt-1234567)",
            "ownerId": "666051418590",
            "requesterId": "0123456789ab",
            "requesterManaged": true,
            "status": "pending",
            "macAddress": "00:bb:ee:ff:aa:cc",
            "privateIpAddress": "192.0.2.0",
            "privateDnsName": "ip-192-0-2-0.ec2.internal",
            "sourceDestCheck": true,
            "groupSet": {
                "items": [
                    {
                        "groupId": "sg-c16d65b6",
                        "groupName": "default"
                    }
                ]
            },
            "privateIpAddressesSet": {
                "item": [
                    {
                        "privateIpAddress": "192.0.2.0",
                        "primary": true
                    }
                ]
            },
            "tagSet": {}
        }
    },
    "requestID": "11112222-3333-4444-5555-666666777777",
    "eventID": "aaaabbbb-1111-2222-3333-444444555555",
    "eventType": "AwsApiCall",
    "recipientAccountId": "111122223333"
}

```

Log Entries for EFS IAM Authentication

Amazon EFS IAM authorization for NFS clients emits NewClientConnection and UpdateClientConnection CloudTrail events. A NewClientConnection event is emitted when a connection is authorized immediately after an initial connection, and immediately after a reconnection. An UpdateClientConnection is emitted when a connection is reauthorized and the list of permitted actions has changed. It's also emitted when the new list of permitted actions doesn't include

`ClientMount`. For more information about EFS IAM authorization, see [Using IAM to control file system data access \(p. 206\)](#).

The following example shows a CloudTrail log entry that demonstrates a `NewClientConnection` event.

```
{
    "eventVersion": "1.05",
    "userIdentity": {
        "type": "AssumedRole",
        "principalId": "AIDACKCEVSQ6C2EXAMPLE",
        "arn": "arn:aws:sts::0123456789ab:assumed-role/abcdef0123456789",
        "accountId": "0123456789ab",
        "accessKeyId": "AKIAIOSFODNN7EXAMPLE",
        "sessionContext": {
            "sessionIssuer": {
                "type": "Role",
                "principalId": "AIDACKCEVSQ6C2EXAMPLE",
                "arn": "arn:aws:iam::0123456789ab:role/us-east-2",
                "accountId": "0123456789ab",
                "userName": "username"
            },
            "webIdFederationData": {},
            "attributes": {
                "mfaAuthenticated": "false",
                "creationDate": "2019-12-23T17:50:16Z"
            },
            "ec2RoleDelivery": "1.0"
        }
    },
    "eventTime": "2019-12-23T18:02:12Z",
    "eventSource": "elasticfilesystem.amazonaws.com",
    "eventName": "NewClientConnection",
    "awsRegion": "us-east-2",
    "sourceIPAddress": "AWS Internal",
    "userAgent": "elasticfilesystem",
    "requestParameters": null,
    "responseElements": null,
    "eventID": "27859ac9-053c-4112-aee3-f3429719d460",
    "readOnly": true,
    "resources": [
        {
            "accountId": "0123456789ab",
            "type": "AWS::EFS::FileSystem",
            "ARN": "arn:aws:elasticfilesystem:us-east-2:0123456789ab:file-system/fs-01234567"
        },
        {
            "accountId": "0123456789ab",
            "type": "AWS::EFS::AccessPoint",
            "ARN": "arn:aws:elasticfilesystem:us-east-2:0123456789ab:access-point/fsap-0123456789abcdef0"
        }
    ],
    "eventType": "AwsServiceEvent",
    "recipientAccountId": "0123456789ab",
    "serviceEventDetails": {
        "permissions": [
            "ClientRootAccess": true,
            "ClientMount": true,
            "ClientWrite": true
        ],
        "sourceIpAddress": "10.7.3.72"
    }
}
```

Amazon EFS Log File Entries for Encrypted-at-Rest File Systems

Amazon EFS gives you the option of using encryption at rest, encryption in transit, or both, for your file systems. For more information, see [Data encryption in Amazon EFS \(p. 189\)](#).

If you're using an encrypted-at-rest file system, the calls that Amazon EFS makes on your behalf appear in your AWS CloudTrail logs as coming from an AWS-owned account. If you see one of the following account IDs in your CloudTrail logs, depending on the AWS Region that your file system is created in, this ID is one owned by the Amazon EFS service.

AWS Region	Account ID
US East (Ohio)	771736226457
US East (N. Virginia)	055650462987
US West (N. California)	208867197265
US West (Oregon)	736298361104
Africa (Cape Town)	855919597013
Asia Pacific (Hong Kong)	832882505983
Asia Pacific (Mumbai)	063610658798
Asia Pacific (Seoul)	518632624599
Asia Pacific (Singapore)	448676862907
Asia Pacific (Sydney)	288718191711
Asia Pacific (Jakarta)	441759846254
Asia Pacific (Tokyo)	620757817088
Asia Pacific (Osaka)	740446410266
Canada (Central)	838331228873
China (Beijing)	365623262523
China (Ningxia)	361049930386
Europe (Frankfurt)	992038834663
Europe (Ireland)	805538244694
Europe (London)	838331228873
Europe (Milan)	393586363892
Europe (Paris)	063566772258
Europe (Stockholm)	030059730498
Middle East (Bahrain)	545970776878
Middle East (UAE)	762379480081

AWS Region	Account ID
South America (São Paulo)	041656882570
AWS GovCloud (US-East)	167972735943
AWS GovCloud (US-West)	174619389399

Amazon EFS Encryption context for encryption at rest

Amazon EFS sends [encryption context](#) when making AWS KMS API requests to generate data keys and decrypt Amazon EFS data. The file system ID is the encryption context for all file systems that are encrypted at rest. In the `requestParameters` field of a CloudTrail log entry, the encryption context looks similar to the following.

```
"EncryptionContextEquals": {}  
"aws:elasticfilesystem:filesystem:id" : "fs-4EXAMPLE"
```

Amazon EFS performance

Amazon EFS provides a serverless, set-and-forget elastic file system that you can access from any compute service within AWS and on-premises, including:

- Amazon Elastic Compute Cloud (Amazon EC2)
- Amazon Elastic Container Service (Amazon ECS)
- Amazon Elastic Kubernetes Service (Amazon EKS)
- AWS Fargate
- AWS Lambda

Amazon EFS delivers more than 10 gibibytes per second (GiBps) of throughput over 500,000 IOPS, and sub-millisecond or low single digit millisecond latencies.

The following sections provide an overview of Amazon EFS performance, and describe how your file system configuration impacts key performance dimensions. We also provide some important tips and recommendations for optimizing the performance of your file system.

Topics

- [Performance summary \(p. 130\)](#)
- [Storage classes and performance \(p. 131\)](#)
- [Performance modes \(p. 131\)](#)
- [Throughput modes \(p. 132\)](#)
- [Amazon EFS performance tips \(p. 134\)](#)

Performance summary

File system performance is typically measured using the dimensions of latency, throughput, and I/O operations per second (IOPS). Amazon EFS performance across these dimensions depends on your file system's configuration. The following configurations impact the performance of an Amazon EFS file system:

- **Storage class** – EFS One Zone or EFS Standard
- **Performance mode** – General Purpose or Max I/O
- **Throughput mode** – Bursting or Provisioned

The following table illustrates Amazon EFS file system performance for the available combinations of storage class and performance mode settings.

File system performance for storage class and performance mode combinations

File system configuration – Storage class and performance mode	Latency ¹		Maximum IOPS		Maximum throughput		
	Read operations	Write operations	Read operations	Write operations	Per-file-system read ²	Per-file-system write ²	Per-client read/write
EFS Standard	Low	Low	Very High	Very High	Very High	Very High	Very High

	Latency ¹		Maximum IOPS		Maximum throughput		
One Zone storage and General Purpose	As low as 600 µs	Low single-digit (µs)	35,000	7,000	3 – 5 GiBps	1 – 3 GiBps	500 MiBps
Standard storage and General Purpose	As low as 600 µs	Low single-digit milliseconds	35,000	7,000	3 – 5 GiBps	1 – 3 GiBps	500 MiBps
Standard storage and Max I/O	Single-digit milliseconds	Single-digit to double-digit milliseconds	>500,000	>100,000	3 – 5 GiBps	1 – 3 GiBps	500 MiBps

Note

Footnotes:

1. Latencies for file data reads and writes to the cost-optimized storage classes (Standard-IA and One Zone-IA) are double-digit milliseconds.
2. Maximum read and write throughput depend on the AWS Region and on the file system's throughput mode (Bursting or Provisioned). For more information, see the table of [default throughput quotas \(p. 235\)](#) for Bursting and Provisioned Throughput modes.

Throughput in excess of an AWS Region's maximum throughput requires a throughput quota increase. Any request for additional throughput is considered on a case-by-case basis by the Amazon EFS service team. Approval might depend on your type of workload. To learn more about requesting quota increases, see [Amazon EFS quotas and limits \(p. 235\)](#).

Storage classes and performance

Amazon EFS uses the following storage classes:

- **EFS One Zone storage classes** – EFS One Zone and EFS One Zone-Infrequent Access (EFS One Zone-IA). The EFS One Zone storage classes replicate data within a single Availability Zone.
- **EFS Standard storage classes** – EFS Standard and EFS Standard-IA. The EFS Standard storage classes replicate data across multiple Availability Zones (Multi-AZ).

First-byte latency when reading from or writing to either of the IA storage classes is higher than that for the EFS Standard or EFS One Zone storage classes.

For more information about EFS storage classes, see [Storage classes \(p. 20\)](#).

Performance modes

Amazon EFS offers two performance modes, General Purpose and Max I/O:

- **General Purpose mode** supports up to 35,000 IOPS and has the lowest per-operation latency. File systems with EFS One Zone storage classes always use General Purpose performance mode. For file systems with EFS Standard storage classes, you can use either the default General Purpose performance mode or the Max I/O performance mode.
- **Max I/O mode** supports 500,000+ IOPS and has higher per-operation latencies when compared to General Purpose mode.

You set the performance mode when you create a file system, and you can't change it after it is created.

We recommend using General Purpose performance mode for the vast majority of applications. If you are not sure which performance mode to use, choose the General Purpose performance mode. To help ensure that your workload stays within the IOPS limit available to file systems using General Purpose mode, you can monitor the PercentIOLimit CloudWatch metric. For more information, see [Amazon CloudWatch metrics for Amazon EFS \(p. 112\)](#).

Applications can scale their IOPS elastically up to the limit associated with the performance mode. You are not billed separately for IOPS; they are included in a file system's throughput accounting. Every Network File System (NFS) request is accounted for as 4 KB of throughput, or its actual request and response size, whichever is larger. For example, a file system that can drive 100 MBps of throughput can drive up to 25,600 4-KB writes per second (100 MBps divided by 4 KB per request = 25,600 requests per second).

Throughput modes

A file system's throughput mode determines the throughput available to your file system. Amazon EFS offers two throughput modes, Bursting Throughput and Provisioned Throughput. Read throughput is discounted to allow you to drive higher read throughput than write throughput. Depending on the AWS Region, the discount for reads is between 1.66 and 3x. For more information, see the table of [default throughput quotas \(p. 235\)](#) for Bursting and Provisioned Throughput modes. Discounting reduces throughput metered for reads, and does not impact writes or burst credit accruals. Furthermore, read discounting never reduces the throughput metered for a single NFS request below a minimum request size of 4 KB.

Understanding metered throughput

All Amazon EFS file systems have an associated metered throughput. For file systems using Provisioned Throughput mode, the metered throughput is determined by the amount of provisioned throughput. For file systems using Bursting Throughput mode, the metered throughput is determined by the amount of data stored in the EFS Standard or EFS One Zone storage class.

Read requests and write requests are metered at different rates. Amazon EFS meters read requests at one-third the rate of other requests.

Example of EFS metered throughput

For example, if you are driving 30 mebibytes per second (MiBps) of both read throughput and write throughput, the read portion counts as 10 MiBps of metered throughput, the write portion counts as 30 MiBps, and the combined metered throughput is 40 MiBps. This combined throughput adjusted for metering rates is reflected in the MeteredIOBytes Amazon CloudWatch metric. For more information, see [Amazon CloudWatch metrics for Amazon EFS \(p. 112\)](#).

Bursting Throughput mode

Bursting Throughput mode is the default Amazon EFS throughput mode. It is a good fit for traditional applications that have a bursty throughput pattern. When throughput is low, Bursting Throughput mode uses burst buckets to save burst credits. When throughput is higher, it uses burst credits.

In Bursting Throughput mode, file system throughput is proportional to the file system size in the Standard storage class, up to a maximum that depends on the Amazon EFS Region. For more information about per-Region limits, see the table of [default throughput quotas \(p. 235\)](#) for Bursting and Provisioned Throughput modes.

When burst credits are available, a file system can drive up to 100 MBps per terabyte (TB) of storage, with a minimum of 100 MBps. If no burst credits are available, a file system can drive up to 50 MBps per TB of storage with a minimum of 1 MBps.

Read and write throughput are metered, and burst credits are deducted from the burst credit balance for metered throughput. Burst credits accrue in proportion to the file system's size at the file system's base rate. 50 MBps of burst credits are accrued for every TB of storage. Whenever a file system consumes less than its base rate, it accrues burst credits. Whenever a file system consumes more than its base rate, it consumes burst credits. The metered size of [ValueInStandard \(p. 106\)](#) is used to determine your I/O throughput baseline and burst rates. The metered size of the file system for Bursting Throughput performance excludes the amount of data stored in the Infrequent Access storage class.

Amazon EFS burst credits

Amazon EFS uses a credit system to determine when file systems can burst. Each file system earns credits over time at a baseline rate that is determined by the size of the file system that is stored in the EFS Standard or One Zone Standard storage class. A file system uses credits whenever it reads or writes data. The baseline rate is 50 MiBps per TiB of storage (equivalent to 50 KiB/s per GiB of storage). Because Amazon EFS meters read operations at a one-third the rate of other operations toward the baseline rate, an EFS file system can drive up to 150 KiB/s per GiB of read throughput, or 50 KiB/s per GiB of write throughput at this baseline rate.

A file system can drive throughput at its baseline metered rate continuously. A file system accumulates burst credits whenever it is inactive or driving throughput below its baseline metered rate. Accumulated burst credits give the file system the ability to drive throughput above its baseline rate.

For example, a file system with 100 GiB of metered data in Standard storage can burst (at 100 MiBps) for 5 percent of the time if it's inactive for the remaining 95 percent. Over a 24-hour period, the file system earns 432,000 MiB worth of credit, which can be used to burst at 100 MiBps for 72 minutes.

File systems larger than 1 TiB can always burst for up to 50 percent of the time if they are inactive for the remaining 50 percent.

The following table provides examples of bursting behavior.

File system size	Burst throughput	Baseline throughput
A file system with 100 GiB of metered data in Standard storage can...	<ul style="list-style-type: none">Burst to 300 mebibytes per second (MiBps) read-only for up to 72 minutes per dayBurst to 100 MiBps write-only for up to 72 minutes per day, or	<ul style="list-style-type: none">Drive up to 15 MiBps read-only continuouslyDrive up to 5 MiBps write-only continuously
A file system with 1-TiB of metered data in Standard storage can...	<ul style="list-style-type: none">Burst to 300 MiBps read-only for 12 hour per dayBurst to 100 MiBps write-only for 12 hours per day, or	<ul style="list-style-type: none">Drive 150 MiBps read-only continuouslyDrive 50 MiBps write-only continuously

File system size	Burst throughput	Baseline throughput
A file system with 10-TiB of metered data in Standard storage can...	<ul style="list-style-type: none"> Burst to 3 GiBps read-only for 12 hours per day Burst to 1 GiBps write-only for 12 hours per day, or 	<ul style="list-style-type: none"> Drive 1.5 GiBps read-only continuously Drive 500 MiBps write-only continuously
Generally, a larger file system can...	<ul style="list-style-type: none"> Burst to 300 MiBps read-only per TiB of storage for 12 hours per day Burst to 100 MiBps write-only per TiB of storage for 12 hours per day, or 	<ul style="list-style-type: none"> Drive 150 MiBps read-only per TiB of storage continuously Drive 50 MiBps write-only per TiB of storage continuously

Note

Amazon EFS gives a [metered throughput \(p. 132\)](#) of 1 MiBps to all file systems, even if the baseline rate is lower.

The file system size used to determine the baseline and burst rates is the `ValueInStandard` metered size available through the [DescribeFileSystems \(p. 311\)](#) API operation

File systems can earn credits up to a maximum credit balance of 2.1 TiB for file systems smaller than 1 TiB, or 2.1 TiB per TiB stored for file systems larger than 1 TiB. This approach implies that file systems can accumulate enough credits to burst for up to 12 hours continuously.

Provisioned Throughput mode

For applications that have a relatively constant throughput, we recommend Provisioned Throughput mode. In Provisioned Throughput mode, you specify a level of throughput that the file system can drive independent of the file system's size or burst credit balance. You are charged for the amount of throughput you provision that is in excess of the file system's base throughput rate based on the amount of storage if your file system were using Bursting Throughput mode. If the metered size of the data stored in Standard storage of your file system provides higher baseline throughput than the amount of throughput you have provisioned, then your file system will automatically use the Bursting Throughput mode.

Restrictions on switching throughput modes and changing provisioned amount

You can switch an existing file system's throughput mode and change the throughput amount. However, the following actions are restricted for a 24-hour period after switching the throughput mode to Provisioned Throughput or changing the provisioned throughput amount:

- Switching out of Provisioned Throughput mode.
- Decreasing the provisioned throughput amount.

Amazon EFS performance tips

When using Amazon EFS, keep the following performance tips in mind.

Average I/O size

The distributed nature of Amazon EFS enables high levels of availability, durability, and scalability. This distributed architecture results in a small latency overhead for each file operation. Because of this per-

operation latency, overall throughput generally increases as the average I/O size increases, because the overhead is amortized over a larger amount of data.

Request model

If you enable asynchronous writes to your file system, pending write operations are buffered on the Amazon EC2 instance before they're written to Amazon EFS asynchronously. Asynchronous writes typically have lower latencies. When performing asynchronous writes, the kernel uses additional memory for caching.

A file system that has enabled synchronous writes, or one that opens files using an option that bypasses the cache (for example, `O_DIRECT`), issues synchronous requests to Amazon EFS. Every operation goes through a round trip between the client and Amazon EFS.

Note

Your chosen request model has tradeoffs in consistency (if you're using multiple Amazon EC2 instances) and speed. Using synchronous writes provides increased data consistency by completing each write request transaction before processing the next request. Using asynchronous writes provides increased throughput by buffering pending write operations.

NFS client mount settings

Verify that you're using the recommended mount options as outlined in [Mounting EFS file systems \(p. 68\)](#) and in [Additional mounting considerations \(p. 88\)](#).

When mounting your file systems on Amazon EC2 instances, Amazon EFS supports the Network File System version 4.0 and 4.1 (NFSv4) protocols. NFSv4.1 provides better performance for parallel small-file read operations (greater than 10,000 files per second) compared to NFSv4.0 (less than 1,000 files per second). For Amazon EC2 macOS instances running macOS Big Sur, only NFSv4.0 is supported.

Don't use the following mount options:

- `noac`, `actimeo=0`, `acregmax=0`, `acdirmax=0` – These options disable the attribute cache, which has a very large performance impact.
- `lookupcache=pos`, `lookupcache=none` – These options disable the file name lookup cache, which has a very large impact on performance.
- `fsc` – This option enables local file caching, but does not change NFS cache coherency, and does not reduce latencies.

Note

When you mount your file system, consider increasing the size of the read and write buffers for your NFS client to 1 MB.

Optimizing small-file performance

You can improve small-file performance by minimizing file reopens, increasing parallelism, and bundling reference files where possible.

- Minimize the number of round trips to the server.

Don't unnecessarily close files if you will need them later in a workflow. Keeping file descriptors open enables direct access to the local copy in the cache. File open, close, and metadata operations generally cannot be made asynchronously or through a pipeline.

When reading or writing small files, the two additional round trips are significant.

Each round trip (file open, file close) can take as much time as reading or writing megabytes of bulk data. It's more efficient to open an input or output file once, at the beginning of your compute job, and hold it open for the entire length of the job.

- Use parallelism to reduce the impact of round-trip times.
- Bundle reference files in a .zip file. Some applications use a large set of small, mostly read-only reference files. Bundling these in a .zip file allows you to read many files with one open-close round trip.

The .zip format allows for random access to individual files.

Optimizing directory performance

When performing a listing (`ls`) on very large directories (over 100k files) that are being modified concurrently, Linux NFS clients can hang, not returning a response. This issue is fixed in kernel 5.11, which has been ported to Amazon Linux 2 kernels 4.14, 5.4, and 5.10.

We recommend keeping the number of directories on your file system to less than 10,000, if possible. Use nested subdirectories as much as possible.

When listing a directory, avoid getting file attributes if they are not required, because they are not stored in the directory itself.

Optimizing the NFS read_ahead_kb size

The NFS `read_ahead_kb` attribute defines the number of kilobytes for the Linux kernel to read ahead or prefetch during a sequential read operation.

For Linux kernel versions prior to 5.4.*, the `read_ahead_kb` value is set by multiplying `NFS_MAX_READAHEAD` by the value for `rsize` (the client configured read buffer size set in the mount options). When using the [recommended mount options \(p. 88\)](#), this formula sets `read_ahead_kb` to 15 MB.

Note

Starting with Linux kernel versions 5.4.*, the Linux NFS client uses a default `read_ahead_kb` value of 128 KB. We recommend increasing this value to 15 MB.

The Amazon EFS mount helper that is available in `amazon-efs-utils` version 1.33.2 and later automatically modifies the `read_ahead_kb` value to equal `15 * rsize`, or 15 MB, after mounting the file system.

For Linux kernels 5.4 or later, if you do not use the mount helper to mount your file systems, consider manually setting `read_ahead_kb` to 15 MB for improved performance. After mounting the file system, you can reset the `read_ahead_kb` value by using the following command. Before using this command, replace the following values:

- Replace `read-ahead-value-kb` with the desired size in kilobytes.
- Replace `efs-mount-point` with the file system's mount point.

```
device_number=$(stat -c '%d' efs-mount-point)
((major = ($device_number & 0xFFFF00) >> 8))
((minor = ($device_number & 0xFF) | (($device_number >> 12) & 0xFFFF)))
sudo bash -c "echo read-ahead-value-kb > /sys/class/bdi/$major:$minor/read_ahead_kb"
```

The following example sets the `read_ahead_kb` size to 15 MB.

```
device_number=$(stat -c '%d' efs)
((major = ($device_number & 0xFFFF00) >> 8))
((minor = ($device_number & 0xFF) | (($device_number >> 12) & 0xFFFF00)))
sudo bash -c "echo 15000 > /sys/class/bdi/$major:$minor/read_ahead_kb"
```

Backing up your Amazon EFS file systems

There are two options available for protecting your data by backing up your EFS file systems:

- AWS Backup service
- The EFS-to-EFS backup solution

AWS Backup is a simple and cost-effective way to back up your Amazon EFS file systems that are in AWS Regions where the AWS Backup service is available. AWS Backup is a unified backup service designed to simplify the creation, migration, restoration, and deletion of backups, while providing improved reporting and auditing. For more information, see [Using AWS Backup to back up and restore Amazon EFS file systems \(p. 138\)](#).

The EFS-to-EFS backup solution is suitable for all Amazon EFS file systems in all AWS Regions. It includes an AWS CloudFormation template that launches, configures, and runs the AWS services required to deploy this solution. This solution follows AWS best practices for security and availability. For more information, see [EFS-to-EFS Backup Solution](#) in the AWS Solutions Library.

Using AWS Backup to back up and restore Amazon EFS file systems

AWS Backup is a simple and cost-effective way to protect your data by backing up your Amazon EFS file systems. AWS Backup is a unified backup service designed to simplify the creation, migration, restoration, and deletion of backups, while providing improved reporting and auditing. AWS Backup makes it easier to develop a centralized backup strategy for legal, regulatory, and professional compliance. AWS Backup also makes protecting your AWS storage volumes, databases, and file systems simpler by providing a central place where you can do the following:

- Configure and audit the AWS resources that you want to back up
- Automate backup scheduling
- Set retention policies
- Monitor all recent backup and restore activity

Amazon EFS is natively integrated with AWS Backup. You can use the EFS console, API, and AWS Command Line Interface (AWS CLI) to enable automatic backups for your file system. Automatic backups use a default backup plan with the AWS Backup recommended settings for automatic backups. For more information, see [Automatic backups \(p. 140\)](#). You can also use AWS Backup to [manually set \(p. 141\)](#) your own backup plans where you specify the backup frequency, when to back up, how long to retain backups, and a lifecycle policy for backups. You can then assign Amazon EFS file systems, or other AWS resources, to that backup plan.

Incremental backups

AWS Backup performs incremental backups of EFS file systems. During the initial backup, a copy of the entire file system is made. During subsequent backups of that file system, only files and directories

that have been changed, added, or removed are copied. With each incremental backup, AWS Backup retains the necessary reference data to allow a full restore. This approach minimizes the time required to complete the backup and saves on storage costs by not duplicating data.

Backup consistency

Amazon EFS is designed to be highly available. You can access and modify your Amazon EFS file systems while your backup is occurring in AWS Backup. However, inconsistencies, such as duplicated, skewed, or excluded data, can occur if you make modifications to your file system while the backup is occurring. These modifications include write, rename, move, or delete operations. To ensure consistent backups, we recommend that you pause applications or processes that are modifying the file system for the duration of the backup process. Or, schedule your backups to occur during periods when the file system is not being modified.

Performance

In general, you can expect the following backup rates with AWS Backup:

- 100 MB/s for file systems composed of mostly large files
- 500 files/s for file systems composed of mostly small files
- The maximum duration for a backup operation in AWS Backup is thirty days.

Complete restore operations generally take longer than the corresponding backup.

Using AWS Backup doesn't consume accumulated burst credits, and it doesn't count against the General Purpose mode file operation limits. For more information, see [Quotas for Amazon EFS file systems \(p. 237\)](#).

Backup completion window

You can optionally specify a completion window for a backup. This window defines the period of time in which a backup needs to be completed. If you specify a completion window, make sure that you consider the expected performance and the size and makeup of your file system. Doing this helps make sure that your backup can be completed during the window.

Backups that aren't completed during the specified window are flagged with an incomplete status. During the next scheduled backup, AWS Backup resumes at the point that it left off. You can see the status of all of your backups on the [AWS Backup Management Console](#).

EFS storage classes

You can use AWS Backup to back up all data in an EFS file system, whatever storage class the data is in. You don't incur data access charges when backing up an EFS file system that has lifecycle management enabled and has data in the Infrequent Access (IA) storage class.

When you restore a recovery point, all files are restored to the Standard storage class. For more information on storage classes, see [EFS storage classes \(p. 20\)](#) and [Amazon EFS lifecycle management \(p. 100\)](#).

IAM permissions for creating and restoring backups

You can use the `elasticfilesystem:backup` and `elasticfilesystem:restore` actions to allow or deny an IAM entity (such as a user, group, or role) the ability to create or restore backups of an EFS file system. You can use these actions in a file system policy or in an identity-based IAM policy. For more

information, see [Managing access to resources \(p. 198\)](#) and [Using IAM to control file system data access \(p. 206\)](#).

On-demand backups

Using either the [AWS Backup Management Console](#) or the CLI, you can save a single resource to a backup vault on-demand. Unlike with scheduled backups, you don't need to create a backup plan to initiate an on-demand backup. You can still assign a lifecycle to your backup, which automatically moves the recovery point to the cold storage tier and notes when to delete it.

Concurrent backups

AWS Backup limits backups to one concurrent backup per resource. Therefore, scheduled or on-demand backups might fail if a backup job is already in progress. For more information about AWS Backup limits, see [AWS Backup Limits](#) in the *AWS Backup Developer Guide*.

Automatic backups

When you create a file system using the Amazon EFS console, automatic backups are turned on by default. You can turn on automatic backups after creating your file system using the CLI or API. The default EFS backup plan uses the AWS Backup recommended settings for automatic backups—daily backups with a 35-day retention period. The backups created using the default EFS backup plan are stored in a default EFS backup vault, which is also created by EFS on your behalf. The default backup plan and backup vault cannot be deleted. You can edit the default backup plan settings using the AWS Backup console. For more information, see [Option 3: Create Automatic Backups](#) in the *AWS Backup Developer Guide*. You can see all of your automatic backups, and edit the default EFS backup plan settings using the [AWS Backup console](#). You can turn off automatic backups at any time using the Amazon EFS console or CLI, described in the following section.

Amazon EFS applies the `aws:elasticfilesystem:default-backup` system tag key with a value of `enabled` to EFS file systems when automatic backups are enabled.

Note

Automatic backups are exempt from the AWS Backup service opt-out configuration. For more information, see [Getting Started with AWS Backup](#) in the *AWS Backup Developer Guide*.

Turning automatic backups on or off for existing file systems

After you create a file system you can turn automatic backups on or off using the console, the CLI, or the EFS API.

[Turn automatic backups on or off for an existing file system \(console\)](#)

1. Open the Amazon Elastic File System console at <https://console.aws.amazon.com/efs/>.
2. In the **File systems** page, choose the file system that you want to turn automatic backups on or off for and display the **File system details** page.
3. Choose **Edit** in the **General** settings panel.
4.
 - To turn on automatic backups, select **Enable automatic backups**.
 - To turn off automatic backups, clear **Enable automatic backups**.
5. Choose **Save changes**.

[Turn automatic backups on or off for an existing file system \(CLI\)](#)

- Use the `put-backup-policy` CLI command (the corresponding API operation is [PutBackupPolicy \(p. 339\)](#)) turn automatic backups on or off for an existing file system.

- Use the following command to turn on automatic backups.

```
$ aws efs put-backup-policy --file-system-id fs-01234567 \
--backup-policy Status="ENABLED"
```

EFS responds with the new backup policy.

```
{
  "BackupPolicy": {
    "Status": "ENABLING"
  }
}
```

- Use the following command to turn off automatic backups.

```
$ aws efs put-backup-policy --file-system-id fs-01234567 \
--backup-policy Status="DISABLED"
```

EFS responds with the new backup policy.

```
{
  "BackupPolicy": {
    "Status": "DISABLING"
  }
}
```

Using AWS Backup to manually configure backups

When you use AWS Backup to manually set up your file system backups, you first create a backup plan. The backup plan defines backup schedule, backup window, retention policy, lifecycle policy, and tags. You can create a backup plan using the [AWS Backup Management Console](#), the AWS CLI, or the AWS Backup API. As part of a backup plan, you can define the following:

- Schedule – When the backup occurs
- Backup window – The window of time during which the backup must start
- Lifecycle – When to move a recovery point to cold storage and when to delete it
- Backup vault – Which vault is used to organize recovery points created by the Backup rule

After your backup plan is created, you assign the specific Amazon EFS file systems to the backup plan by using either tags or the Amazon EFS file system ID. After a plan is assigned, AWS Backup begins automatically backing up the Amazon EFS file system on your behalf according to the backup plan that you defined. You can use the AWS Backup console to manage backup configurations or monitor backup activity. For more information, see the [AWS Backup Developer Guide](#).

Note

Sockets and named pipes are not supported, and are omitted from backups.

Restore a recovery point

Using either the [AWS Backup console](#) or the CLI, you can restore a recovery point to a new EFS file system or to an existing file system. You can perform a Complete restore, which restores the entire file system. Or, you can restore specific files and directories using a Partial restore. To restore a specific file or directory, you must specify the relative path related to the mount point. For example, if the file system

is mounted to /user/home/myname/efs and the file path is user/home/myname/efs/file1, enter /file1. Paths are case sensitive and cannot contain special characters, wildcard characters, or regular expression (regex) strings.

Note

To restore a recovery point, users must have the backup:StartRestoreJob permission.

When you perform either a Complete or a Partial restore, your recovery point is restored to the restore directory, aws-backup-restore_*timestamp-of-restore*. When the restore is finished, you can see the restore directory at the root of the file system. If you attempt multiple restores for the same path, several directories containing the restored items might exist. If the restore fails to finish, you can see the directory aws-backup-failed-restore_*timestamp-of-restore*. You must manually delete the restore and failed-restore directories when you are through using them.

Note

For Partial restores to an existing EFS file system, AWS Backup restores the files and directories to a new directory under the file system root directory. The full hierarchy of the specified items is preserved in the recovery directory. For example, if directory A contains subdirectories B, C, and D, AWS Backup retains the hierarchical structure when A, B, C, and D are recovered.

After restoring a recovery point, data fragments that can't be restored to the appropriate directory are placed in the aws-backup-lost+found directory. Fragments might be moved to this directory if modifications are made to the file system while the backup is occurring.

Deleting backups

The default EFS backup vault Access policy is set to deny deleting recovery points. To delete existing backups of your EFS file systems, you must change the vault access policy. If you attempt to delete an EFS recovery point without modifying the vault access policy, you receive the following error message:

"Access Denied: Insufficient privileges to perform this action. Please consult with the account administrator for necessary permissions."

To edit the default backup vault access policy, you must have AWS Identity and Access Management (IAM) permissions to edit your EFS policies. To revise IAM policy settings, you must have Admin rights. For example, you can perform these actions using your AWS account root user, or by using an admin role. For more information, see [Allow all IAM actions \(admin access\)](#).

To delete an EFS recovery point in AWS Backup

1. Open the AWS Backup console at <https://console.aws.amazon.com/backup>.
2. In the left navigation pane, choose **Backup vaults**.
3. In the list **Backup vaults**, choose **aws/efs/automatic-backup-vault**.
4. On the vault details page, choose **Manage access** in the upper-right corner of the page. The **Edit access policy** page appears.
5. To allow all actions on the EFS backup vault, find the line "Effect": "Deny", in the JSON editor, and edit the line to read "Effect": "Allow",.
6. Choose **Save policy** to save your changes.
7. On the vault details page, scroll down to the **Backups** section, and select the recovery points that you want to delete from the list of **Backups**. Then choose **Actions**, and then choose **Delete**.
8. Follow the instructions to confirm the deletion. Then choose **Delete recovery points**.

Amazon EFS replication

You can use Amazon EFS replication to create a replica of your Amazon EFS file system in the AWS Region of your preference. When you enable replication on an EFS file system, Amazon EFS automatically and transparently replicates the data and metadata on the source file system to a new destination EFS file system. To manage the process of creating the destination file system and keeping it synced with the source file system, Amazon EFS uses a *replication configuration*.

Amazon EFS automatically keeps the source and destination file systems synchronized. Amazon EFS replication is continual and designed to provide a recovery point objective (RPO) and a recovery time objective (RTO) of minutes. These features should assist you in meeting your compliance and business continuity goals.

EFS replication is not available in AWS Regions that are disabled by default. For more information, see [Enabling a Region](#) in the *AWS General Reference Reference Guide*.

Note

EFS replication does not support using tags for attribute-based access control (ABAC).

Topics

- [Replicating file systems \(p. 143\)](#)
- [Creating a replication configuration \(p. 147\)](#)
- [Viewing replication configurations \(p. 150\)](#)
- [Deleting a replication configuration \(p. 152\)](#)
- [Monitoring replication status \(p. 153\)](#)

Replicating file systems

You have several options to choose from when creating a replication configuration for your EFS file system. The following sections explain the options that are available.

Topics


- [Storage classes \(p. 143\)](#)
- [What's in a replication configuration \(p. 145\)](#)
- [Permissions required \(p. 146\)](#)
- [Costs \(p. 146\)](#)
- [Performance \(p. 147\)](#)
- [Mounting a destination file system \(p. 147\)](#)
- [Failing over to a destination file system \(p. 147\)](#)

Storage classes


You can replicate file systems using EFS Standard storage classes to a destination file system using the same storage classes, or to a destination file system using EFS One Zone storage classes.

To create a replication that has the highest levels of availability and durability, replicate to a destination file system that uses the EFS Standard storage classes. EFS Standard storage stores data redundantly across multiple geographically separated Availability Zones within an AWS Region. For more information, see EFS storage classes.


This diagram illustrates replicating an EFS file system with Standard storage to a file system using Standard storage that is in a different AWS Region.



This diagram illustrates replicating an EFS file system with Standard storage to a file system using One Zone storage.



This diagram illustrates replicating an EFS file system with One Zone storage to a file system using One Zone storage.



What's in a replication configuration

When you create a replication configuration, you specify the following properties for the destination file system:

- **AWS Region** – The AWS Region in which to create the destination file system. Amazon EFS replication is available in all AWS Regions that Amazon EFS is available in, except the AWS opt-in regions. For more information about AWS opt-in regions, see [Managing AWS Regions](#) in the *AWS General Reference Guide*.
- **Availability and durability** – The storage class used by the destination file system, either **Regional** or **One Zone**. For more information about EFS storage classes, see [EFS storage classes \(p. 20\)](#).
- **Availability Zone** – If you choose **One Zone** availability and durability, you must choose the Availability Zone to create the destination file system in.

Note

One Zone storage classes are not available in all Availability Zones in AWS Regions where Amazon EFS is available.

- **Encryption** – All destination file systems are created with encryption at rest enabled. You can specify the AWS Key Management Service (AWS KMS) key that is used to encrypt the destination file system. If you don't specify a KMS key, your service-managed KMS key for Amazon EFS is used.

Important

After the destination file system is created, you cannot change the KMS key.

The following properties are set by default:

- **Automatic backups** – For destination file systems using One Zone storage, automatic backups are enabled by default. After the file system is created, you can [change the automatic backup setting \(p. 140\)](#).

Note

For destination file systems using Standard storage, automatic backups are *not* enabled by default.

- **Performance mode** – The destination file system's performance mode matches that of the source file system, unless the destination file system uses EFS One Zone storage. In that case, the General Purpose performance mode is used. The performance mode cannot be changed.

- **Throughput mode** – The destination file system uses the Bursting Throughput mode by default. After the file system is created, you can modify the throughput mode.

The following properties are turned off by default:

- **Lifecycle management** – EFS lifecycle management and EFS Intelligent-Tiering are not enabled on the destination file system. After the destination file system is created, you can enable [EFS lifecycle management and EFS Intelligent-Tiering \(p. 102\)](#).

Amazon EFS creates the destination file system with read-only permissions. After the destination file system is created, Amazon EFS performs the initial sync that copies all data and metadata on the source to the destination file system. The amount of time that the initial sync takes to finish depends on the size of the source file system. After the initial sync is finished, the replication process continually keeps the destination file system in sync with the source. For more information, see [Performance \(p. 147\)](#).

You can monitor when the last successful sync occurred using the console, the AWS Command Line Interface (AWS CLI), the API, and Amazon CloudWatch. In CloudWatch, use the [TimeSinceLastSync \(p. 112\)](#) EFS metric. For more information, see [Monitoring replication status \(p. 153\)](#).

Note

An Amazon EFS file system can be part of only one replication configuration. You cannot use a destination file system as the source file system in another replication configuration.

Permissions required

Amazon EFS uses the EFS service-linked role named `AWSServiceRoleForAmazonElasticFileSystem` to synchronize the state of the replication between the source and destination file systems. In order to use EFS replication, you must configure the following permissions to allow an IAM entity (such as a user, group, or role) to create a service linked role, a replication configuration, and a file system.

- `elasticfilesystem>CreateReplicationConfiguration*`
- `elasticfilesystem>DeleteReplicationConfiguration*`
- `elasticfilesystem>DescribeReplicationConfigurations*`
- `elasticfilesystem>CreateFileSystem*`
- `iam>CreateServiceLinkedRole` – see the example in [Using the Amazon EFS Service-Linked Role \(p. 215\)](#).

Note

* You can use the `AmazonElasticFileSystemFullAccess` managed policy instead to automatically get all required EFS permissions. For more information, see [AWS managed policy: AmazonElasticFileSystemFullAccess \(p. 229\)](#).

Costs

In order to facilitate replication, Amazon EFS creates hidden directories and metadata on the destination file system. These equate to approximately 12 MiB of metered data for which you are billed. For more information about metering file system storage, see [Metering: How Amazon EFS reports file system and object sizes \(p. 106\)](#).

Performance

After the initial replication is finished, the majority of source file systems have their subsequent changes replicated to their destination file systems within 15 minutes. However, if the source file system has files that change very frequently and has either more than 100 million files or files that are larger than 100 GB, replication will take longer than 15 minutes. For information about monitoring when the last replication successfully finished, see [Monitoring replication status \(p. 153\)](#).

Mounting a destination file system

Amazon EFS does not create any mount targets when it creates the destination file system. To [mount a destination file system \(p. 68\)](#), you must [create one or more mount targets \(p. 37\)](#).

Because a destination file system is read-only while it is a member of a replication configuration, any write operations to it will fail. However, you can use the destination file system for read-only use-cases, including testing and development.

Failing over to a destination file system

To fail over to the destination file system in a replication configuration, you must delete the replication configuration. After the replication configuration is deleted, the destination file system becomes writeable, and you can start using it in your application workflow. This process can take several minutes to complete. For more information, see [Deleting a replication configuration \(p. 152\)](#).

After failing over to a destination file system, that file system can then be used as the source file system in a new replication configuration. However, it cannot be designated as a destination file system again. A replication configuration always creates a new EFS file system for the destination.

Creating a replication configuration

You can use the Amazon EFS console, the API, or the AWS CLI to replicate an existing Amazon EFS file system. The following sections provide you with detailed instructions for using each of these methods.

To create a replication configuration (console)

1. Sign in to the AWS Management Console and open the Amazon EFS console at <https://console.aws.amazon.com/efs/>.
2. In the left navigation pane, choose **File systems**.
3. In the **File systems** list, choose the Amazon EFS file system that you want to replicate. The file system that you choose cannot be a source or destination file system in an existing replication configuration.
4. Choose the **Replication** tab to display the file system's replication section. The section should be blank. If it is not, choose a different file system to be the source.
5. If the file system is not already replicated, choose **Create replication** to display the **Create replication** page.

Create replication

Replicate your file system to your current region or another region. Additional pricing applies. [Learn more](#)

Replication settings

Destination region

Choose the region in which to replicate your file system.

US West (Oregon) us-west-2



Destination file system settings

Your destination file system will be created with default settings based on your source file system. Additional settings will be editable after creation. [Learn more](#)

Availability and durability

Choose Regional (recommended) to create a file system using regional storage classes. Choose One Zone to create a file system using One Zone storage classes. [Learn more](#)



Regional

Stores data redundantly across multiple AZs



One Zone

Stores data redundantly within a single AZ

Encryption

Your destination file system is encrypted by default. Choose or input a KMS key ID or ARN to use instead of the EFS service KMS key. [Learn more](#)



Choose a KMS key or enter an ARN

Create a KMS key



Cancel

Create replication

6. For **Replication settings**, choose the following options:

- **Destination Region** – The AWS Region in which you want to create the destination file system.

Note

EFS replication is not available in AWS Regions that are disabled by default. For more information, see [Enabling a Region](#) in the *AWS General Reference Reference Guide*.

- **Availability and durability** – Choose **Regional** or **One Zone**.

- To create a file system that has the highest levels of availability and durability, choose **Regional**. The destination file system will use EFS Standard storage. With EFS Standard storage, your file system data and metadata are stored redundantly across multiple geographically separated Availability Zones within an AWS Region. For more information, see [EFS storage classes \(p. 20\)](#).
- To create a file system that uses EFS One Zone storage, choose **One Zone**. With EFS One Zone storage, your file system data and metadata are stored redundantly within a single Availability Zone within an AWS Region. For more information, see [EFS storage classes \(p. 20\)](#).

Note

One Zone storage classes are not available in all Availability Zones in the AWS Regions where Amazon EFS is available.

- If you choose **One Zone**, you must also choose the Availability Zone to create the file system in.
- **Encryption** – Encryption of data at rest is automatically enabled on the destination file system. By default, Amazon EFS uses your AWS Key Management Service (AWS KMS) service key for Amazon

EFS (`aws/elasticfilesystem`). To use a different KMS key, choose a KMS key from the list, or enter the ARN for an existing key.

Important

After the file system is created, you cannot change the KMS key.

- Choose **Create replication**. The Replication section is displayed, showing the replication details. The **Replication state** value is initially **Enabling**, and **Last synced** is blank. After the state reads **Enabled**, **Last synced** shows **Initial sync in progress**.

Replication - new		
Replicate your file system to one additional region or the same region.		
Replication state	Replication direction	Last synced
Enabled	fs-0123456789abcdef1 to fs-1234abcd56ef7890a	Initial sync in progress
Replication file systems		
File system ID	Region	Permission
fs-0123456789abcdef1 Source file system	US East (N. Virginia) us-east-1	Writable
fs-1234abcd56ef7890a Destination file system	US West (N. California) us-west-1	Read-only

- To see the destination file system's configuration information, choose the file system ID above **Destination file system**. The **File system details** page for the destination file system displays in a new browser tab (depending on your browser settings).

To create a replication configuration (CLI)

To create a replication configuration for an existing file system, use the `create-replication-configuration` CLI command. The equivalent API command is [CreateReplicationConfiguration \(p. 280\)](#).

- You can specify an `AvailabilityZoneName` parameter, a `Region` parameter, or both. To create a file system that uses EFS One Zone storage, use the `AvailabilityZoneName` parameter and specify the Availability Zone that you want the file system to be created in. Including both a **Region** and an **Availability Zone** also creates a file system with One Zone storage. To create a file system that uses EFS Standard storage, which is redundant across multiple Availability Zones within an AWS Region, specify only the `Region` parameter.
- Encryption of data at rest is automatically enabled on the destination file system. By default, Amazon EFS uses your AWS Key Management Service (AWS KMS) service key for Amazon EFS (`aws/elasticfilesystem`). You can optionally specify a `KmsKeyId` value to use for encryption using by specifying either a KMS key ID or ARN.

Important

After the file system is created, you cannot change the KMS key.

Example – Create a replication configuration using EFS One Zone storage

The following example creates a replication configuration for the file system `fs-0123456789abcdef1`. This example uses the `AvailabilityZoneName` parameter to create a destination file system that uses EFS One Zone storage in the `us-west-2a` Availability Zone. Because no KMS key is specified, the destination file system is encrypted using the account's default AWS KMS service key for Amazon EFS (`aws/elasticfilesystem`).

```
aws efs create-replication-configuration \
```

```
--source-file-system-id fs-0123456789abcdef1 \
--destinations AvailabilityZoneName=us-west-2a
```

Example – Create a Regional replication configuration using EFS Standard storage

The following example creates a replication configuration for the file system **fs-0123456789abcdef1**. This example uses the Region parameter to create a destination file system with EFS Standard storage in the **eu-west-2** AWS Region. The KmsKeyId parameter specifies the KMS key ID to use when encrypting the destination file system.

```
aws efs create-replication-configuration \
--source-file-system-id fs-0123456789abcdef1 \
--destinations "[{\\"Region\\":\\"eu-west-2\", \\"KmsKeyId\\":\\"arn:aws:kms:us-east-2:111122223333:key/abcd1234-ef56-ab78-cd90-1111abcd2222\\"}]"
```

The AWS CLI responds as follows:

```
{
  "SourceFileSystemArn": "arn:aws:elasticfilesystem:us-east-1:111122223333:file-system/fs-0123456789abcdef1",
  "SourceFileSystemRegion": "us-east-1",
  "Destinations": [
    {
      "Status": "ENABLING",
      "FileSystemId": "fs-0123456789abcde22",
      "Region": "eu-west-2"
    }
  ],
  "SourceFileSystemId": "fs-0123456789abcdef1",
  "CreationTime": 1641491892.0,
  "OriginalSourceFileSystemArn": "arn:aws:elasticfilesystem:us-east-1:111122223333:file-system/fs-0123456789abcdef1"
}
```

Viewing replication configurations

To see a file system's replication configuration, you can use the Amazon EFS console or the AWS CLI.

To view a replication configuration (console)

1. Open the Amazon Elastic File System console at <https://console.aws.amazon.com/efs/>.
2. In the left navigation pane, choose **File systems**.
3. Choose a file system from the list.
4. Choose the **Replication** tab to display the **Replication** section.

File system ID	Region	Permission
fs-1253e3fa Source file system	US East (N. Virginia) us-east-1	Writable
fs-07eb6bbb16b0406e4 Destination file system	US East (N. Virginia) us-east-1	Read-only

In the **Replication** section, you can see the following information for the replication configuration:

- **Replication state** reads either **Enabling**, **Enabled**, **Deleting**, or **Error**. The **Error** state occurs when either the source or the destination file system (or both) is in a failed state and is unrecoverable. For more information, see [Monitoring replication status \(p. 153\)](#). To recover, you must delete the replication configuration, and then restore the most recent backup of the failed file system (either the source or the destination) to a new file system.
- **Replication direction** shows the direction in which data is being replicated. The first file system listed is the source, and its data is being replicated to the second file system listed, which is the destination.
- **Last synced** shows when the last successful sync occurred on the destination file system. Any changes to data on the source file system that occurred before this time were successfully replicated to the destination file system. Any changes that occurred after this time might not be fully replicated.
- **Replication file systems** lists each file system in the replication configuration by its file system ID, the role it has in the replication configuration (either source or destination), the AWS Region in which it's located, and its **Permission**. A source file system has a permission of **Writable**, and a destination file system has a permission of **Read-only**.

To view a replication configuration (CLI)

To view a replication configuration, use the `describe-replication-configurations` CLI command. You can view the replication configuration for either a specific file system, or all replication configurations for a particular AWS account in an AWS Region. The equivalent API command is [DescribeReplicationConfigurations \(p. 325\)](#).

To view the replication configuration for a file system, use the `file-system-id` URI request parameter. You can specify the ID of either a source or destination file system.

```
aws efs describe-replication-configurations --file-system-id fs-0123456789abcdef1
```

```
{  
    "Replications": [  
        {  
            "SourceFileSystemArn": "arn:aws:elasticfilesystem:eu-west-1:111122223333:file-  
system/fs-abcdef0123456789a",  
            "CreationTime": 1641491892.0,  
            "SourceFileSystemRegion": "eu-west-1",  
            "OriginalSourceFileSystemArn": "arn:aws:elasticfilesystem:eu-  
west-1:111122223333:file-system/fs-abcdef0123456789a",  
            "SourceFileSystemId": "fs-abcdef0123456789a",  
            "Destinations": [  
                {  
                    "Status": "ENABLED",  
                    "FileSystemId": "fs-0123456789abcdef1",  
                    "Region": "us-east-1"  
                }  
            ]  
        }  
    ]  
}
```

To view all the replication configurations for an account in an AWS Region, don't specify the `file-system-id` parameter.

```
aws efs describe-replication-configurations
```

```
{  
    "Replications": [  
        {  
            "SourceFileSystemArn": "arn:aws:elasticfilesystem:eu-west-1:555555555555:file-system/fs-0123456789abcdef1",  
            "CreationTime": 1641491892.0,  
            "SourceFileSystemRegion": "eu-west-1",  
            "OriginalSourceFileSystemArn": "arn:aws:elasticfilesystem:eu-west-1:555555555555:file-system/fs-0123456789abcdef1",  
            "SourceFileSystemId": "fs-0123456789abcdef1",  
            "Destinations": [  
                {  
                    "Status": "ENABLED",  
                    "FileSystemId": "fs-abcdef0123456789a",  
                    "Region": "us-east-1",  
                    "LastReplicatedTimestamp": 1641491802.375  
                }  
            ]  
        },  
        {  
            "SourceFileSystemArn": "arn:aws:elasticfilesystem:eu-west-1:555555555555:file-system/fs-021345abcdef6789a",  
            "CreationTime": 1641491822.0,  
            "SourceFileSystemRegion": "eu-west-1",  
            "OriginalSourceFileSystemArn": "arn:aws:elasticfilesystem:eu-west-1:555555555555:file-system/fs-021345abcdef6789a",  
            "SourceFileSystemId": "fs-021345abcdef6789a",  
            "Destinations": [  
                {  
                    "Status": "ENABLED",  
                    "FileSystemId": "fs-012abc3456789def1",  
                    "Region": "us-east-1",  
                    "LastReplicatedTimestamp": 1641491823.575  
                }  
            ]  
        }  
    ]  
}
```

Deleting a replication configuration

You can delete an existing replication configuration by using the console, the CLI, or the API. If you need to fail over to the destination file system, delete the replication configuration of which it is a member. After you delete a replication configuration, the destination file system is no longer in a read-only state.

Deleting a replication configuration and changing the destination file system to be writeable can take several minutes to complete. After the configuration is deleted, Amazon EFS might write some data to a `lost+found` directory in the root directory of the destination file system, using the following naming convention:

```
efs-replication-lost+found-source-file-system-id-TIMESTAMP
```

Note

You cannot delete a file system that is part of a replication configuration. You must delete the replication configuration before deleting the file system.

When deleting a replication configuration, you must issue the delete request from the same AWS Region that the destination file system is located in. The Amazon EFS console manages this for you, but you must ensure that you are in the correct AWS Region when using the CLI and API.

To delete a replication configuration (console)

1. Open the Amazon Elastic File System console at <https://console.aws.amazon.com/efs/>.
2. In the left navigation pane, choose **File systems**.
3. Choose either the source or the destination file system that is in the replication configuration that you want to delete.
4. Choose the **Replication** tab to display the **Replication** section.
5. Choose **Delete** to delete the replication configuration. When prompted, confirm your choice.

To delete a replication configuration (CLI)

To delete a replication configuration, use the `delete-replication-configuration` CLI command. The equivalent API command is [DeleteReplicationConfiguration \(p. 297\)](#).

To specify which replication configuration that you're deleting, use the `source-file-system-id` parameter.

Note

The `delete-replication-configuration` CLI request must be called from the same AWS Region in which the destination file system is located.

```
aws efs --region us-west-2 delete-replication-configuration \
--source-file-system-id fs-0123456789abcdef1
```

Monitoring replication status

You can monitor the time when the last successful sync was completed in a replication configuration. Any changes to data on the source file system that occurred before this time have been successfully replicated to the destination file system. Any changes that occurred after this time might not be fully replicated. To monitor when the last replication successfully finished, you can use the console, CLI, API, or Amazon CloudWatch.

- **In the console** – The **Last synced** property in the **File system details > Replication** section shows the time when the last successful sync between the source and destination was completed.
- **In the CLI or API** – The `LastReplicatedTimestamp` property in the `Destination` object shows the time that the last successful sync was completed. To access this property, use the `describe-replication-configurations` CLI command. [DescribeReplicationConfigurations \(p. 325\)](#) is the equivalent API operation.
- **In CloudWatch** – The `TimeSinceLastSync` CloudWatch metric for Amazon EFS shows the time that has elapsed since the last successful sync was completed. For more information, see [Amazon CloudWatch metrics for Amazon EFS \(p. 112\)](#).

You can also monitor a replication configuration's status by using the console, CLI, or API. A replication configuration can have one of the status values described in the following table.

Replication status	Description
ENABLED	The replication configuration is in a healthy state and available for use.

Replication status	Description
ENABLING	Amazon EFS is in the process of creating the replication configuration.
DELETING	Amazon EFS is deleting the replication configuration in response to a user-initiated delete request.
ERROR	One (or both) of the file systems in the replication configuration is in a failed state and is unrecoverable. To access the file system data, restore a backup of the failed file system to a new file system. For more information, see Restore a recovery point (p. 141) .

Amazon Elastic File System Walkthroughs

This section provides walkthroughs that you can use to explore Amazon EFS and test the end-to-end setup.

Topics

- [Walkthrough: Create an Amazon EFS file system and mount it on an Amazon EC2 instance using the AWS CLI \(p. 155\)](#)
- [Walkthrough: Set up an Apache web server and serve Amazon EFS files \(p. 167\)](#)
- [Walkthrough: Create Writable Per-User Subdirectories and Configure Automatic Remounting on Reboot \(p. 172\)](#)
- [Walkthrough: Create and mount a file system on-premises with AWS Direct Connect and VPN \(p. 173\)](#)
- [Walkthrough: Mount a File System from a Different VPC \(p. 180\)](#)
- [Walkthrough: Enforcing Encryption on an Amazon EFS File System at Rest \(p. 184\)](#)
- [Walkthrough: Enable root squashing using IAM authorization for NFS clients \(p. 186\)](#)

Walkthrough: Create an Amazon EFS file system and mount it on an Amazon EC2 instance using the AWS CLI

This walkthrough uses the AWS CLI to explore the Amazon EFS API. In this walkthrough, you create an encrypted Amazon EFS file system, mount it on an Amazon EC2 instance in your VPC, and test the setup.

Note

This walkthrough is similar to the Getting Started exercise. In the [Getting started \(p. 14\)](#) exercise, you use the console to create EC2 and Amazon EFS resources. In this walkthrough, you use the AWS CLI to do the same—primarily to familiarize yourself with the Amazon EFS API.

In this walkthrough, you create the following AWS resources in your account:

- Amazon EC2 resources:
 - Two security groups (for your EC2 instance and Amazon EFS file system).

You add rules to these security groups to authorize appropriate inbound/outbound access. Doing this allows your EC2 instance to connect to the file system through the mount target by using a standard NFSv4.1 TCP port.

- An Amazon EC2 instance in your VPC.
- Amazon EFS resources:
 - A file system.
 - A mount target for your file system.

To mount your file system on an EC2 instance you need to create a mount target in your VPC. You can create one mount target in each of the Availability Zones in your VPC. For more information, see [Amazon EFS: How it works \(p. 3\)](#).

Then, you test the file system on your EC2 instance. The cleanup step at the end of the walkthrough provides information for you to remove these resources.

The walkthrough creates all these resources in the US West (Oregon) Region (`us-west-2`). Whichever AWS Region you use, be sure to use it consistently. All of your resources—your VPC, EC2 resources, and Amazon EFS resources—must be in the same AWS Region.

Before you begin

- You can use the root credentials of your AWS account to sign in to the console and try the Getting Started exercise. However, AWS Identity and Access Management (IAM) recommends that you do not use the root credentials of your AWS account. Instead, create an administrator user in your account and use those credentials to manage resources in your account. For more information, see [Setting Up \(p. 12\)](#).
- You can use a default VPC or a custom VPC that you have created in your account. For this walkthrough, the default VPC configuration works. However, if you use a custom VPC, verify the following:
 - DNS hostnames are enabled. For more information, see [Updating DNS support for your VPC](#) in the *Amazon VPC User Guide*.
 - The Internet gateway is attached to your VPC. For more information, see [Internet Gateways](#) in the *Amazon VPC User Guide*.
 - The VPC subnets are configured to request public IP addresses for instances launched in the VPC subnets. For more information, see [IP Addressing in Your VPC](#) in the *Amazon VPC User Guide*.
 - The VPC route table includes a rule to send all Internet-bound traffic to the Internet gateway.
- You need to set up the AWS CLI and add the adminuser profile.

Setting up the AWS CLI

Use the following instructions to set up the AWS CLI and user profile.

To set up the AWS CLI

1. Download and configure the AWS CLI. For instructions, see the following topics in the *AWS Command Line Interface User Guide*.

[Getting Set Up with the AWS Command Line Interface](#)

[Installing the AWS Command Line Interface](#)

[Configuring the AWS Command Line Interface](#)

2. Set profiles.

You store user credentials in the AWS CLI config file. The example CLI commands in this walkthrough specify the adminuser profile. Create the adminuser profile in the config file. You can also set the administrator user profile as the default in the config file as shown.

```
[profile adminuser]
aws_access_key_id = admin user access key ID
aws_secret_access_key = admin user secret access key
region = us-west-2

[default]
aws_access_key_id = admin user access key ID
aws_secret_access_key = admin user secret access key
region = us-west-2
```

The preceding profile also sets the default AWS Region. If you don't specify a region in the CLI command, the us-west-2 region is assumed.

3. Verify the setup by entering the following command at the command prompt. Both of these commands don't provide credentials explicitly, so the credentials of the default profile are used.

- Try the help command

You can also specify the user profile explicitly by adding the --profile parameter.

```
aws help
```

```
aws help \
--profile adminuser
```

Next step

[Step 1: Create Amazon EC2 resources \(p. 157\)](#)

Step 1: Create Amazon EC2 resources

In this step, you do the following:

- Create two security groups.
- Add rules to the security groups to authorize additional access.
- Launch an EC2 instance. You create and mount an Amazon EFS file system on this instance in the next step.

Topics

- [Step 1.1: Create two security groups \(p. 157\)](#)
- [Step 1.2: Add rules to the security groups to authorize inbound/outbound access \(p. 158\)](#)
- [Step 1.3: Launch an EC2 instance \(p. 159\)](#)

Step 1.1: Create two security groups

In this section, you create security groups in your VPC for your EC2 instance and Amazon EFS mount target. Later in the walkthrough, you assign these security groups to an EC2 instance and an Amazon EFS mount target. For information about security groups, see [Security Groups for EC2-VPC](#) in the *Amazon EC2 User Guide for Linux Instances*.

To create security groups

1. Create two security groups using the `create-security-group` CLI command:

- a. Create a security group (`efs-walkthrough1-ec2-sg`) for your EC2 instance, and provide your VPC ID.

```
$ aws ec2 create-security-group \
--region us-west-2 \
--group-name efs-walkthrough1-ec2-sg \
--description "Amazon EFS walkthrough 1, SG for EC2 instance" \
--vpc-id vpc-id-in-us-west-2 \
--profile adminuser
```

Write down the security group ID. The following is an example response.

```
{  
    "GroupId": "sg-aexample"  
}
```

You can find the VPC ID using the following command.

```
$ aws ec2 describe-vpcs
```

- b. Create a security group (efs-walkthrough1-mt-sg) for your Amazon EFS mount target. You need to provide your VPC ID.

```
$ aws ec2 create-security-group \  
--region us-west-2 \  
--group-name efs-walkthrough1-mt-sg \  
--description "Amazon EFS walkthrough 1, SG for mount target" \  
--vpc-id vpc-id-in-us-west-2 \  
--profile adminuser
```

Write down the security group ID. The following is an example response.

```
{  
    "GroupId": "sg-aexample"  
}
```

2. Verify the security groups.

```
aws ec2 describe-security-groups \  
--group-ids list of security group IDs separated by space \  
--profile adminuser \  
--region us-west-2
```

Both should have only one outbound rule that allows all traffic to leave.

In the next section, you authorize additional access that enables the following:

- Enable you to connect to your EC2 instance.
- Enable traffic between an EC2 instance and an Amazon EFS mount target (with which you associate these security groups later in this walkthrough).

Step 1.2: Add rules to the security groups to authorize inbound/outbound access

In this step, you add rules to the security groups to authorize inbound/outbound access.

To add rules

1. Authorize incoming Secure Shell (SSH) connections to the security group for your EC2 instance (efs-walkthrough1-ec2-sg) so you can connect to your EC2 instance using SSH from any host.

```
$ aws ec2 authorize-security-group-ingress \  
--group-id id of the security group created for EC2 instance \  
--protocol tcp \  
--port 22
```

```
--port 22 \
--cidr 0.0.0.0/0 \
--profile adminuser \
--region us-west-2
```

Verify that the security group has the inbound and outbound rule you added.

```
aws ec2 describe-security-groups \
--region us-west-2 \
--profile adminuser \
--group-id security-group-id
```

2. Authorize inbound access to the security group for the Amazon EFS mount target (efs-walkthrough1-mt-sg).

At the command prompt, run the following AWS CLI `authorize-security-group-ingress` command using the `adminuser` profile to add the inbound rule.

```
$ aws ec2 authorize-security-group-ingress \
--group-id ID of the security group created for Amazon EFS mount target \
--protocol tcp \
--port 2049 \
--source-group ID of the security group created for EC2 instance \
--profile adminuser \
--region us-west-2
```

3. Verify that both security groups now authorize inbound access.

```
aws ec2 describe-security-groups \
--group-names efs-walkthrough1-ec2-sg  efs-walkthrough1-mt-sg \
--profile adminuser \
--region us-west-2
```

Step 1.3: Launch an EC2 instance

In this step, you launch an EC2 instance.

To launch an EC2 instance

1. Gather the following information that you need to provide when launching an EC2 instance:

- Key pair name:
 - For introductory information, see [Setting Up with Amazon EC2](#) in the *Amazon EC2 User Guide for Linux Instances*.
 - For instructions to create a .pem file, see [Create a Key Pair](#) in the *Amazon EC2 User Guide for Linux Instances*.
- The ID of the Amazon Machine Image (AMI) you want to launch.

The AWS CLI command that you use to launch an EC2 instance requires the ID of the AMI that you want to deploy as a parameter. The exercise uses the Amazon Linux HVM AMI.

Note

You can use most general purpose Linux-based AMIs. If you use another Linux AMI, make sure that you use your distribution's package manager to install the NFS client on the instance. Also, you might need to add software packages as you need them.

For the Amazon Linux HVM AMI, you can find the latest IDs at [Amazon Linux AMI](#). You choose the ID value from the Amazon Linux AMI IDs table as follows:

- Choose the **US West Oregon** region. This walkthrough assumes you are creating all resources in the US West (Oregon) Region (us-west-2).
- Choose the **EBS-backed HVM 64-bit** type (because in the CLI command you specify the t2.micro instance type, which does not support instance store).
- ID of the security group you created for an EC2 instance.
- AWS Region. This walkthrough uses the us-west-2 region.
- Your VPC subnet ID where you want to launch the instance. You can get list of subnets using the describe-subnets command.

```
$ aws ec2 describe-subnets \
--region us-west-2 \
--filters "Name=vpc-id,Values=vpc-id" \
--profile adminuser
```

After you choose the subnet ID, write down the following values from the describe-subnets result:

- **Subnet ID** – You need this value when you create a mount target. In this exercise, you create a mount target in the same subnet where you launch an EC2 instance.
- **Availability Zone of the subnet** – You need this value to construct your mount target DNS name, which you use to mount a file system on the EC2 instance.

2. Run the following AWS CLI run-instances command to launch an EC2 instance.

```
$ aws ec2 run-instances \
--image-id AMI ID \
--count 1 \
--instance-type t2.micro \
--associate-public-ip-address \
--key-name key-pair-name \
--security-group-ids ID of the security group created for EC2 instance \
--subnet-id VPC subnet ID \
--region us-west-2 \
--profile adminuser
```

3. Write down the instance ID returned by the run-instances command.
4. The EC2 instance you created must have a public DNS name that you use to connect to the EC2 instance and mount the file system on it. The public DNS name is of the form:

```
ec2-xx-xx-xx-xxx.compute-1.amazonaws.com
```

Run the following CLI command and write down the public DNS name.

```
aws ec2 describe-instances \
--instance-ids EC2 instance ID \
--region us-west-2 \
--profile adminuser
```

If you don't find the public DNS name, check the configuration of the VPC in which you launched the EC2 instance. For more information, see [Before you begin \(p. 156\)](#).

5. (Optional) Assign a name to the EC2 instance that you created. To do so, add a tag with the key name and value set to the name that you want to assign to the instance. You do this by running the following AWS CLI create-tags command.

```
$ aws ec2 create-tags \
--resources EC2-instance-ID \
```

```
--tags Key=Name,Value=Provide-instance-name \
--region us-west-2 \
--profile adminuser
```

Next step

[Step 2: Create Amazon EFS resources \(p. 161\)](#)

Step 2: Create Amazon EFS resources

In this step, you do the following:

- Create an encrypted Amazon EFS file system.
- Enable lifecycle management.
- Create a mount target in the Availability Zone where you have your EC2 instance launched.

Topics

- [Step 2.1: Create an Amazon EFS file system \(p. 161\)](#)
- [Step 2.2: Enable lifecycle management \(p. 162\)](#)
- [Step 2.3: Create a mount target \(p. 162\)](#)

Step 2.1: Create an Amazon EFS file system

In this step, you create an Amazon EFS file system. Write down the `FileSystemId` to use later when you create mount targets for the file system in the next step.

To create a file system

- Create a file system with the optional Name tag.
 - a. At the command prompt, run the following AWS CLI `create-file-system` command.

```
$ aws efs create-file-system \
--encrypted \
--creation-token FileSystemForWalkthrough1 \
--tags Key=Name,Value=SomeExampleNameValue \
--region us-west-2 \
--profile adminuser
```

You get the following response.

```
{
    "OwnerId": "111122223333",
    "CreationToken": "FileSystemForWalkthrough1",
    "FileSystemId": "fs-c657c8bf",
    "CreationTime": 1548950706.0,
    "LifeCycleState": "creating",
    "NumberOfMountTargets": 0,
    "SizeInBytes": {
        "Value": 0,
        "ValueInIA": 0,
        "ValueInStandard": 0
    },
    "PerformanceMode": "generalPurpose",
```

```
"Encrypted": true,  
  "KmsKeyId": "arn:aws:kms:us-west-2:111122223333:a5c11222-7a99-43c8-9dcc-  
  abcdef123456",  
  "ThroughputMode": "bursting",  
  "Tags": [  
    {  
      "Key": "Name",  
      "Value": "SomeExampleNameValue"  
    }  
  ]  
}
```

- b. Note the `FileSystemId` value. You need this value when you create a mount target for this file system in [Step 2.3: Create a mount target \(p. 162\)](#).

Step 2.2: Enable lifecycle management

In this step, you enable lifecycle management on your file system in order to use the Infrequent Access storage class. To learn more, see [Amazon EFS lifecycle management \(p. 100\)](#) and [EFS storage classes \(p. 20\)](#).

To enable lifecycle management

- At the command prompt, run the following AWS CLI `put-lifecycle-configuration` command.

```
$ aws efs put-lifecycle-configuration \  
--file-system-id fs-c657c8bf \  
--lifecycle-policies TransitionToIA=AFTER_30_DAYS \  
--region us-west-2 \  
--profile adminuser
```

You get the following response.

```
{  
  "LifecyclePolicies": [  
    {  
      "TransitionToIA": "AFTER_30_DAYS"  
    }  
  ]  
}
```

Step 2.3: Create a mount target

In this step, you create a mount target for your file system in the Availability Zone where you have your EC2 instance launched.

1. Make sure you have the following information:

- ID of the file system (for example, `fs-example`) for which you are creating the mount target.
- VPC subnet ID where you launched the EC2 instance in [Step 1](#).

For this walkthrough, you create the mount target in the same subnet in which you launched the EC2 instance, so you need the subnet ID (for example, `subnet-example`).

- ID of the security group you created for the mount target in the preceding step.

2. At the command prompt, run the following AWS CLI `create-mount-target` command.

```
$ aws efs create-mount-target \
--file-system-id file-system-id \
--subnet-id subnet-id \
--security-group ID-of-the security-group-created-for-mount-target \
--region us-west-2 \
--profile adminuser
```

You get the following response.

```
{  
    "MountTargetId": "fsmt-example",  
    "NetworkInterfaceId": "eni-example",  
    "FileSystemId": "fs-example",  
    "PerformanceMode" : "generalPurpose",  
    "LifeCycleState": "available",  
    "SubnetId": "fs-subnet-example",  
    "OwnerId": "account-id",  
    "IpAddress": "xxx.xx.xx.xxx"  
}
```

3. You can also use the `describe-mount-targets` command to get descriptions of mount targets you created on a file system.

```
$ aws efs describe-mount-targets \
--file-system-id file-system-id \
--region us-west-2 \
--profile adminuser
```

Next step

[Step 3: Mount the file system on the EC2 instance and test \(p. 163\)](#)

Step 3: Mount the file system on the EC2 instance and test

In this step, you do the following:

Topics

- [Step 3.1: Gather Information \(p. 163\)](#)
- [Step 3.2: Install the NFS Client on Your EC2 Instance \(p. 164\)](#)
- [Step 3.3: Mount the file system on your EC2 instance and test \(p. 164\)](#)

Step 3.1: Gather Information

Make sure you have the following information as you follow the steps in this section:

- Public DNS name of your EC2 instance in the following format:

```
ec2-xx-xxx-xxx-xx.aws-region.compute.amazonaws.com
```

- DNS name of your file system. You can construct this DNS name using the following generic form:

```
file-system-id.efs.aws-region.amazonaws.com
```

The EC2 instance on which you mount the file system by using the mount target can resolve the file system's DNS name to the mount target's IP address.

Note

Amazon EFS doesn't require that your Amazon EC2 instance have either a public IP address or public DNS name. The requirements listed preceding are just for this walkthrough example to ensure that you can connect by using SSH into the instance from outside the VPC.

Step 3.2: Install the NFS Client on Your EC2 Instance

You can connect to your EC2 instance from Windows or from a computer running Linux, or macOS X, or any other Unix variant.

To install an NFS client

1. Connect to your EC2 instance:

- To connect to your instance from a computer running macOS or Linux, specify the .pem file for your SSH command with the `-i` option and the path to your private key.
- To connect to your instance from a computer running Windows, you can use either MindTerm or PuTTY. If you plan to use PuTTY, you need to install it and use the following procedure to convert the .pem file to a .ppk file.

For more information, see the following topics in the *Amazon EC2 User Guide for Linux Instances*:

- [Connecting to Your Linux Instance from Windows Using PuTTY](#)
- [Connecting to Your Linux Instance Using SSH](#)

2. Execute the following commands on the EC2 instance by using the SSH session:

- a. (Optional) Get updates and reboot.

```
$ sudo yum -y update
$ sudo reboot
```

After the reboot, reconnect to your EC2 instance.

- b. Install the NFS client.

```
$ sudo yum -y install nfs-utils
```

Note

If you choose the **Amazon Linux AMI 2016.03.0** Amazon Linux AMI when launching your Amazon EC2 instance, you don't need to install `nfs-utils` because it is already included in the AMI by default.

Step 3.3: Mount the file system on your EC2 instance and test

Now you mount the file system on your EC2 instance.

1. Make a directory ("efs-mount-point").

```
$ mkdir ~/efs-mount-point
```

2. Mount the Amazon EFS file system.

```
$ sudo mount -t nfs -o  
nfsvers=4.1,rsize=1048576,wszie=1048576,hard,timeo=600,retrans=2,noresvport mount-  
target-DNS:/ ~/efs-mount-point
```

The EC2 instance can resolve the mount target DNS name to the IP address. You can optionally specify the IP address of the mount target directly.

```
$ sudo mount -t nfs -o  
nfsvers=4.1,rsize=1048576,wszie=1048576,hard,timeo=600,retrans=2,noresvport mount-  
target-ip:/ ~/efs-mount-point
```

3. Now that you have the Amazon EFS file system mounted on your EC2 instance, you can create files.

- Change the directory.

```
$ cd ~/efs-mount-point
```

- List the directory contents.

```
$ ls -al
```

It should be empty.

```
drwxr-xr-x 2 root      root      4096 Dec 29 22:33 .  
drwx----- 4 ec2-user  ec2-user  4096 Dec 29 22:54 ..
```

- The root directory of a file system, upon creation, is owned by and is writable by the root user, so you need to change permissions to add files.

```
$ sudo chmod go+rwx .
```

Now, if you try the `ls -al` command you see that the permissions have changed.

```
drwxrwxrwx 2 root      root      4096 Dec 29 22:33 .  
drwx----- 4 ec2-user  ec2-user  4096 Dec 29 22:54 ..
```

- Create a text file.

```
$ touch test-file.txt
```

- List directory content.

```
$ ls -l
```

You now have successfully created and mounted an Amazon EFS file system on your EC2 instance in your VPC.

The file system you mounted doesn't persist across reboots. To automatically remount the directory, you can use the `fstab` file. For more information, see [Automatic remounting on reboot \(p. 173\)](#). If you are using an Auto Scaling group to launch EC2 instances, you can also set scripts in a launch configuration. For an example, see [Walkthrough: Set up an Apache web server and serve Amazon EFS files \(p. 167\)](#).

Next step

[Step 4: Clean up \(p. 166\)](#)

Step 4: Clean up

If you no longer need the resources you created, you should remove them. You can do this with the CLI.

- Remove EC2 resources (the EC2 instance and the two security groups). Amazon EFS deletes the network interface when you delete the mount target.
- Remove Amazon EFS resources (file system, mount target).

To delete AWS resources created in this walkthrough

1. Terminate the EC2 instance you created for this walkthrough.

```
$ aws ec2 terminate-instances \
--instance-ids instance-id \
--profile adminuser
```

You can also delete EC2 resources using the console. For instructions, see [Terminating an Instance](#) in the *Amazon EC2 User Guide for Linux Instances*.

2. Delete the mount target.

You must delete the mount targets created for the file system before deleting the file system. You can get a list of mount targets by using the `describe-mount-targets` CLI command.

```
$ aws efs describe-mount-targets \
--file-system-id file-system-ID \
--profile adminuser \
--region aws-region
```

Then delete the mount target by using the `delete-mount-target` CLI command.

```
$ aws efs delete-mount-target \
--mount-target-id ID-of-mount-target-to-delete \
--profile adminuser \
--region aws-region
```

3. (Optional) Delete the two security groups you created. You don't pay for creating security groups.

You must delete the mount target's security group first, before deleting the EC2 instance's security group. The mount target's security group has a rule that references the EC2 security group. Therefore, you cannot first delete the EC2 instance's security group.

For instructions, see [Deleting a Security Group](#) in the *Amazon EC2 User Guide for Linux Instances*.

4. Delete the file system by using the `delete-file-system` CLI command. You can get a list of your file systems by using the `describe-file-systems` CLI command. You can get the file system ID from the response.

```
aws efs describe-file-systems \
--profile adminuser \
--region aws-region
```

Delete the file system by providing the file system ID.

```
$ aws efs delete-file-system \  
--file-system-id ID-of-file-system-to-delete \  
--region aws-region \  
--profile adminuser
```

Walkthrough: Set up an Apache web server and serve Amazon EFS files

You can have EC2 instances running the Apache web server serving files stored on your Amazon EFS file system. It can be one EC2 instance, or if your application needs, you can have multiple EC2 instances serving files from your Amazon EFS file system. The following procedures are described.

- [Set up an Apache web server on an EC2 instance \(p. 167\)](#).
- [Set up an Apache web server on multiple EC2 instances by creating an Auto Scaling group \(p. 169\)](#).
You can create multiple EC2 instances using Amazon EC2 Auto Scaling, an AWS service that allows you to increase or decrease the number of EC2 instances in a group according to your application needs. When you have multiple web servers, you also need a load balancer to distribute request traffic among them.

Note

For both procedures, you create all resources in the US West (Oregon) Region (us-west-2).

Single EC2 instance serving files

Follow the steps to set up an Apache web server on one EC2 instance to serve files you create in your Amazon EFS file system.

1. Follow the steps in the Getting Started exercise so that you have a working configuration consisting of the following:
 - Amazon EFS file system
 - EC2 instance
 - File system mounted on the EC2 instance

For instructions, see [Getting started with Amazon Elastic File System \(p. 14\)](#). As you follow the steps, write down the following:

- Public DNS name of the EC2 instance.
 - Public DNS name of the mount target created in the same Availability Zone where you launched the EC2 instance.
2. (Optional) You may choose to unmount the file system from the mount point you created in the Getting Started exercise.

```
$ sudo umount ~/efs-mount-point
```

In this walkthrough, you create another mount point for the file system.

3. On your EC2 instance, install the Apache web server and configure it as follows:
 - a. Connect to your EC2 instance and install the Apache web server.

```
$ sudo yum -y install httpd
```

- b. Start the service.

```
$ sudo service httpd start
```

- c. Create a mount point.

First note that the DocumentRoot in the /etc/httpd/conf/httpd.conf file points to /var/www/html (DocumentRoot "/var/www/html").

You will mount your Amazon EFS file system on a subdirectory under the document root.

Create a subdirectory named efs-mount-point to use as the mount point for your file system, under /var/www/html.

```
$ sudo mkdir /var/www/html/efs-mount-point
```


- d. Mount your Amazon EFS file system using the following command. replace *file-system-id* with the ID of your file system.

```
$ sudo mount -t efs file-system-id:/ /var/www/html/efs-mount-point
```

4. Test the setup.

- a. Add a rule in the EC2 instance security group, which you created in the Getting Started exercise, to allow HTTP traffic on TCP port 80 from anywhere.

After you add the rule, the EC2 instance security group will have the following inbound rules.



Type	Protocol	Port Range	Source
SSH	TCP	22	0.0.0.0/0
HTTP	TCP	80	0.0.0.0/0

For instructions, see [Creating security groups using the AWS Management Console \(p. 44\)](#).

- b. Create a sample html file.

- i. Change directory to the mount point.

```
$ cd /var/www/html/efs-mount-point
```

- ii. Make a subdirectory called sampledir and change the ownership.

```
$ sudo mkdir sampledir
$ sudo chown ec2-user sampledir
$ sudo chmod -R o+r sampledir
```

Change directory so you can create files in the sampledir subdirectory.

```
$ cd sampledir
```

- iii. Create a sample hello.html file.

```
$ echo "<html><h1>Hello from Amazon EFS</h1></html>" > hello.html
```

- c. Open a browser window and enter the URL to access the file (it is the public DNS name of the EC2 instance followed by the file name). For example:

```
http://EC2-instance-public-DNS/efs-mount-point/sampledir/hello.html
```

Now you are serving web pages stored on an Amazon EFS file system.

Note

This setup does not configure the EC2 instance to automatically start the web server (httpd) on boot, and also does not mount the file system on boot. In the next walkthrough, you create a launch configuration to set this up.

Multiple EC2 instances serving files

Follow the steps to serve the same content in your Amazon EFS file system from multiple EC2 instances for improved scalability or availability.

1. Follow the steps in the [Step 1: Create your Amazon EFS file system \(p. 15\)](#) exercise so that you have an Amazon EFS file system created and tested.

Important

For this walkthrough, you don't use the EC2 instance that you created in the Getting Started exercise. Instead, you launch new EC2 instances.

2. Create a load balancer in your VPC using the following steps.

- a. Define a load balancer

In the **Basic Configuration** section, select your VPC where you also create the EC2 instances on which you mount the file system.

In the **Select Subnets** section, select all of the available subnets . For details, see the cloud-config script in the next section.

- b. Assign security groups

Create a new security group for the load balancer to allow HTTP access from port 80 from anywhere, as shown following:

- Type: HTTP
- Protocol: TCP
- Port Range: 80
- Source: Anywhere (0.0.0.0/0)

Note

When everything works, you can also update the EC2 instance security group inbound rule access to allow HTTP traffic only from the load balancer.

- c. Configure a health check

Set the **Ping Path** value to `/efs-mount-point/test.html`. The `efs-mount-point` is the subdirectory where you have the file system mounted. You add `test.html` page in it later in this procedure.

Note

Don't add any EC2 instances. Later, you create an Auto Scaling Group in which you launch EC2 instance and specify this load balancer.

For instructions to create a load balancer, see [Getting Started with Elastic Load Balancing](#) in the *Elastic Load Balancing User Guide*.

Create an Auto Scaling group with two EC2 instances. First, you create a launch configuration describing the instances. Then, you create an Auto Scaling group by specifying the launch configuration. The following steps provide configuration information that you specify to create an Auto Scaling group from the Amazon EC2 console.

1. Choose **Launch Configurations** under **AUTO SCALING** from the left hand navigation.
2. Choose **Create Auto Scaling group** to launch the wizard.
3. Choose **Create launch configuration**.
4. From **Quick Start**, select the latest version of the **Amazon Linux 2 AMI**. This is same AMI you used in [Step 2: Create your EC2 resources and launch your EC2 instance \(p. 17\)](#) of the Getting Started exercise.
5. In the **Advanced** section, do the following:
 - For **IP Address Type**, choose **Assign a public IP address to every instance**.
 - Copy/paste the following script in the **User data** box.

You must update the script by providing values for the `file-system-id` and `aws-region` (if you followed the Getting Started exercise, you created the file system in the us-west-2 region).

In the script, note the following:

- The script installs the NFS client and the Apache web server.
- The echo command writes the following entry in the `/etc/fstab` file identifying the file system's DNS name and subdirectory on which to mount it. This entry ensures that the file gets mounted after each system reboot. Note that the file system's DNS name is dynamically constructed. For more information, see [Mounting on Amazon EC2 with a DNS name \(p. 401\)](#).

```
file-system-ID.efs.aws-region.amazonaws.com:/ /var/www/html/efs-mount-point nfs4
defaults
```

- Creates `efs-mount-point` subdirectory and mounts the file system on it.
- Creates a `test.html` page so ELB health check can find the file (when creating a load balancer you specified this file as the ping point).

For more information about user data scripts, see [Adding User Data](#) in the *Amazon EC2 User Guide for Linux Instances*.

```
#cloud-config
package_upgrade: true
packages:
- nfs-utils
- httpd
runcmd:
```

```

- echo "$(curl -s http://169.254.169.254/latest/meta-data/placement/availability-
zone).file-system-id.aws-region.amazonaws.com:/    /var/www/html/efs-mount-point
  nfs4    defaults" >> /etc/fstab
- mkdir /var/www/html/efs-mount-point
- mount -a
- touch /var/www/html/efs-mount-point/test.html
- service httpd start
- chkconfig httpd on

```

6. For **Assign a security group**, choose **Select an existing security group**, and then choose the security group you created for the EC2 instance.
7. Now, configure the Auto Scaling group details using the following information.
 - a. For **Group size**, choose **Start with 2 instances**. You will create two EC2 instances.
 - b. Select your VPC from the **Network** list.
 - c. Select a subnet in the same Availability Zone that you used when specifying the mount target ID in the User Data script when creating the launch configuration in the preceding step.
 - d. In the **Advanced Details** section
 - i. For **Load Balancing**, choose **Receive traffic from Elastic Load Balancer(s)**, and then select the load balancer you created for this exercise.
 - ii. For **Health Check Type**, choose **ELB**.
8. Follow the instructions to create an Auto Scaling group at [Set Up a Scaled and Load-Balanced Application](#) in the *Amazon EC2 Auto Scaling User Guide*. Use the information in the preceding tables where applicable.
9. Upon successful creation of the Auto Scaling group, you have two EC2 instances with nfs-utils and the Apache web server installed. On each instance, verify that you have the /var/www/html/efs-mount-point subdirectory with your Amazon EFS file system mounted on it. For instructions to connect to an EC2 instance, see [Connect to Your Linux Instance](#) in the *Amazon EC2 User Guide for Linux Instances*.

Note

If you choose the **Amazon Linux AMI 2016.03.0** Amazon Linux AMI when launching your Amazon EC2 instance, you won't need to install nfs-utils because it is already included in the AMI by default.

10. Create a sample page (index.html).

- a. Change directory.

```
$ cd /var/www/html/efs-mount-point
```

- b. Make a subdirectory for sampledir and change the ownership. And change directory so you can create files in the sampledir subdirectory. If you followed the preceding [Single EC2 instance serving files \(p. 167\)](#), you already created the sampledir subdirectory, so you can skip this step.

```

$ sudo mkdir sampledir
$ sudo chown ec2-user sampledir
$ sudo chmod -R o+r sampledir
$ cd sampledir

```

- c. Create a sample index.html file.

```
$ echo "<html><h1>Hello from Amazon EFS</h1></html>" > index.html
```

11. Now you can test the setup. Using the load balancer's public DNS name, access the index.html page.

```
http://load balancer public DNS Name/efs-mount-point/sampledir/index.html
```

The load balancer sends a request to one of the EC2 instances running the Apache web server. Then, the web server serves the file that is stored in your Amazon EFS file system.

Walkthrough: Create Writable Per-User Subdirectories and Configure Automatic Remounting on Reboot

After you create an Amazon EFS file system and mount it locally on your EC2 instance, it exposes an empty directory called the *file system root*. One common use case is to create a "writable" subdirectory under this file system root for each user you create on the EC2 instance, and mount it on the user's home directory. All files and subdirectories the user creates in their home directory are then created on the Amazon EFS file system.

In this walkthrough, you first create a user "mike" on your EC2 instance. You then mount an Amazon EFS subdirectory onto user mike's home directory. The walkthrough also explains how to configure automatic remounting of subdirectories if the system reboots.

Suppose you have an Amazon EFS file system created and mounted on a local directory on your EC2 instance. Let's call it *EFSroot*.

Note

You can follow the [Getting started \(p. 14\)](#) exercise to create and mount an Amazon EFS file system on your EC2 instance.

In the following steps, you create a user (mike), create a subdirectory for the user (*EFSroot/mike*), make user mike the owner of the subdirectory, granting him full permissions, and finally mount the Amazon EFS subdirectory on the user's home directory (/home/mike).

1. Create user mike:

- Log in to your EC2 instance. Using root privileges (in this case, using the sudo command), create user mike and assign a password.

```
$ sudo useradd -c "Mike Smith" mike
$ sudo passwd mike
```

This also creates a home directory, /home/mike, for the user.

2. Create a subdirectory under *EFSroot* for user mike:


- a. Create subdirectory mike under *EFSroot*.

```
$ sudo mkdir /EFSroot/mike
```

You will need to replace *EFSroot* with your local directory name.

- b. The root user and root group are the owners of the /mike subdirectory (you can verify this by using the ls -l command). To enable full permissions for user mike on this subdirectory, grant mike ownership of the directory.

```
$ sudo chown mike:mike /EFSroot/mike
```



A terminal window showing a directory listing. The entries are:

```
drwxr-xr-x 4 root      root      4096 Feb  5 22:37 .
dr-xr-xr-x 25 root     root      4096 Feb  5 22:20 ..
drwxr-xr-x 2 mike      mike      4096 Feb  4 01:18 mike
```

3. Use the mount command to mount the *EFSroot*/mike subdirectory onto mike's home directory.

```
$ sudo mount -t nfs -o
nfsvers=4.1,rsize=1048576,wszie=1048576,hard,timeo=600,retrans=2,noresvport mount-
target-DNS:/mike /home/mike
```

The *mount-target-DNS* address identifies the remote Amazon EFS file system root.

Now user mike's home directory is a subdirectory, writable by mike, in the Amazon EFS file system. If you unmount this mount target, the user can't access their EFS directory without remounting, which requires root permissions.

Automatic remounting on reboot

You can use the file *fstab* to automatically remount your file system after any system reboots. For more information, see [Mounting your Amazon EFS file system automatically \(p. 79\)](#).

Walkthrough: Create and mount a file system on-premises with AWS Direct Connect and VPN

This walkthrough uses the AWS Management Console to create and mount a file system on an on-premises client. You do so using either an AWS Direct Connect connection or a connection on an AWS Virtual Private Network (AWS VPN).

Note

Using Amazon EFS with Microsoft Windows-based clients isn't supported.

Topics

- [Before you begin \(p. 174\)](#)
- [Step 1: Create your Amazon Elastic File System resources \(p. 174\)](#)
- [Step 2: Install the NFS client \(p. 175\)](#)
- [Step 3: Mount the Amazon EFS file system on your on-premises Client \(p. 176\)](#)
- [Step 4: Clean up resources and protect your AWS account \(p. 177\)](#)
- [Optional: Encrypting data in transit \(p. 177\)](#)

In this walkthrough, we assume that you already have an AWS Direct Connect or VPN connection. If you don't have one, you can begin the connection process now and come back to this walkthrough when your connection is established. For more information on AWS Direct Connect, see the [AWS Direct Connect User Guide](#). For more information on setting up a VPN connection, see [VPN Connections](#) in the [Amazon VPC User Guide](#).

When you have an AWS Direct Connect or VPN connection, you create an Amazon EFS file system and a mount target in your Amazon VPC. After that, you download and install the `amazon-efs-utils` tools. Then, you test the file system from your on-premises client. Finally, the clean-up step at the end of the walkthrough provides information for you to remove these resources.

The walkthrough creates all these resources in the US West (Oregon) Region (`us-west-2`). Whichever AWS Region you use, be sure to use it consistently. All of your resources—your VPC, your mount target, and your Amazon EFS file system—must be in the same AWS Region.

Note

In some cases, your local application might need to know if the EFS file system is available. In these cases, your application should be able to point to a different mount point IP address if the first mount point becomes temporarily unavailable. In this scenario, we recommend that you have two on-premises clients connected to your file system through different Availability Zones (AZs) for higher availability.

Before you begin

You can use the root credentials of your AWS account to sign in to the console and try this exercise. However, AWS Identity and Access Management (IAM) best practices recommend that you don't use the root credentials of your AWS account. Instead, create an administrator user in your account and use those credentials to manage resources in your account. For more information, see [Setting Up \(p. 12\)](#).

You can use a default VPC or a custom VPC that you have created in your account. For this walkthrough, the default VPC configuration works. However, if you use a custom VPC, verify the following:

- The internet gateway is attached to your VPC. For more information, see [Internet Gateways](#) in the [Amazon VPC User Guide](#).
- The VPC route table includes a rule to send all internet-bound traffic to the Internet gateway.

Step 1: Create your Amazon Elastic File System resources

In this step, you create your Amazon EFS file system and mount targets.

To create your Amazon EFS file system

1. Open the Amazon EFS console at <https://console.aws.amazon.com/efs/>.
2. Choose **Create File System**.
3. Choose your default VPC from the **VPC** list.
4. Select the check boxes for all of the Availability Zones. Make sure that they all have the default subnets, automatic IP addresses, and the default security groups chosen. These are your mount targets. For more information, see [Creating and managing mount targets and security groups \(p. 37\)](#).
5. Choose **Next Step**.
6. Name your file system, keep **general purpose** selected as your default performance mode, and choose **Next Step**.
7. Choose **Create File System**.
8. Choose your file system from the list and make a note of the **Security group** value. You need this value for the next step.

The file system you just created has mount targets. Each mount target has an associated security group. The security group acts as a virtual firewall that controls network traffic. If you didn't provide a security group when creating a mount target, Amazon EFS associates the default security group of the VPC with it. If you followed the preceding steps exactly, then your mount targets are using the default security group.

Next, you add a rule to the mount target's security group to allow inbound traffic to the Network File System (NFS) port (2049). You can use the AWS Management Console to add the rule to your mount target's security groups in your VPC.

To allow inbound traffic to the NFS port

1. Sign in to the AWS Management Console and open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
2. Under **NETWORK & SECURITY**, choose **Security Groups**.
3. Choose the security group associated with your file system. You made a note of this at the end of [Step 1: Create your Amazon Elastic File System resources \(p. 174\)](#).
4. In the tabbed pane that appears below the list of security groups, choose the **Inbound** tab.
5. Choose **Edit**.
6. Choose **Add Rule**, and choose a rule of the following type:
 - **Type – NFS**
 - **Source – Anywhere**

We recommend that you only use the **Anywhere** source for testing. You can create a custom source set to the IP address of the on-premises client, or use the console from the client itself, and choose **My IP**.

Note

You don't need to add an outbound rule, because the default outbound rule allows all traffic to leave. If you don't have this default outbound rule, add an outbound rule to open a TCP connection on the NFS port, identifying the mount target security group as the destination.

Step 2: Install the NFS client

In this step, you install the NFS client.

To install the NFS client on your on-premises server

Note

If you require data to be encrypted in transit, use the Amazon EFS mount helper, `amazon-efs-utils`, instead of the NFS client. For information on installing `amazon-efs-utils`, see the section [*Optional: Encrypting Data in Transit*](#).

1. Access the terminal for your on-premises client.
2. Install NFS.

If you're using Red Hat Linux, install NFS with the following command.

```
$ sudo yum -y install nfs-utils
```

If you're using Ubuntu, install NFS with the following command.

```
$ sudo apt-get -y install nfs-common
```

Step 3: Mount the Amazon EFS file system on your on-premises Client

To create a mount directory

1. Make a directory for the mount point with the following command.

Example

```
mkdir ~/efs
```

2. Choose your preferred IP address of the mount target in the Availability Zone. You can measure the latency from your on-premises Linux clients. To do so, use a terminal-based tool like ping against the IP address of your EC2 instances in different Availability Zones to find the one with the lowest latency.
 - Run the mount command to mount the file system using the IP address of the mount target.

```
$ sudo mount -t nfs -o  
nfsvers=4.1,rsiz=1048576,wsiz=1048576,hard,timeo=600,retrans=2,noresvport mount-target-IP:/ ~/efs
```

Now that you've mounted your Amazon EFS file system, you can test it out with the following procedure.

To test the Amazon EFS file system connection

1. Change directories to the new directory that you created with the following command.

```
$ cd ~/efs
```

2. Make a subdirectory and change the ownership of that subdirectory to your EC2 instance user. Then, navigate to that new directory with the following commands.

```
$ sudo mkdir getting-started  
$ sudo chown ec2-user getting-started  
$ cd getting-started
```

3. Create a text file with the following command.

```
$ touch test-file.txt
```

4. List the directory contents with the following command.

```
$ ls -al
```

As a result, the following file is created.

```
-rw-rw-r-- 1 username username 0 Nov 15 15:32 test-file.txt
```

You can also mount your file system automatically by adding an entry to the /etc/fstab file. For more information, see [Mounting your Amazon EFS file system automatically \(p. 79\)](#).

Warning

Use the `_netdev` option, used to identify network file systems, when mounting your file system automatically. If `_netdev` is missing, your EC2 instance might stop responding. This result is because network file systems need to be initialized after the compute instance starts its networking. For more information, see [Automatic mounting fails and the instance is unresponsive \(p. 247\)](#).

Step 4: Clean up resources and protect your AWS account

After you have finished this walkthrough, or if you don't want to explore the walkthroughs, you should follow these steps to clean up your resources and protect your AWS account.

To clean up resources and protect your AWS account

1. Unmount the Amazon EFS file system with the following command.

```
$ sudo umount ~/efs
```

2. Open the Amazon EFS console at <https://console.aws.amazon.com/efs/>.
3. Choose the Amazon EFS file system that you want to delete from the list of file systems.
4. For **Actions**, choose **Delete file system**.
5. In the **Permanently delete file system** dialog box, type the file system ID for the Amazon EFS file system that you want to delete, and then choose **Delete File System**.
6. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
7. In the navigation pane, choose **Security Groups**.
8. Select the name of the security group that you added the rule to for this walkthrough.

Warning

Don't delete the default security group for your VPC.

9. For **Actions**, choose **Edit inbound rules**.
10. Choose the X at the end of the inbound rule you added, and choose **Save**.

Optional: Encrypting data in transit

To encrypt data in transit, use the Amazon EFS mount helper, `amazon-efs-utils`, instead of the NFS client.

The `amazon-efs-utils` package is an open-source collection of Amazon EFS tools. The `amazon-efs-utils` collection comes with a mount helper and tooling that makes it easier to encrypt data in transit for Amazon EFS. For more information on this package, see [Using the `amazon-efs-utils` Tools \(p. 54\)](#). This package is available as a free download from GitHub, which you can get by cloning the package's repository.

To clone `amazon-efs-utils` from GitHub

1. Access the terminal for your on-premises client.
2. From the terminal, clone the `amazon-efs-utils` tool from GitHub to a directory of your choice, with the following command.

```
git clone https://github.com/aws/efs-utils
```

Now that you have the package, you can install it. This installation is handled differently depending on the Linux distribution of your on-premises client. The following distributions are supported:

- Amazon Linux 2
- Amazon Linux
- Red Hat Enterprise Linux (and derivatives such as CentOS) version 7 and newer
- Ubuntu 16.04 LTS and newer

To build and install amazon-efs-utils as an RPM package

1. Open a terminal on your client and navigate to the directory that has the cloned amazon-efs-utils package from GitHub.
2. Build the package with the following command.

```
make rpm
```

Note

If you haven't already, install the rpm-builder package with the following command.

```
sudo yum -y install rpm-build
```

3. Install the package with the following command.

```
sudo yum -y install build/amazon-efs-utils*rpm
```

To build and install amazon-efs-utils as an deb package

1. Open a terminal on your client and navigate to the directory that has the cloned amazon-efs-utils package from GitHub.
2. Build the package with the following command.

```
./build-deb.sh
```

3. Install the package with the following command.

```
sudo apt-get install build/amazon-efs-utils*deb
```

After the package is installed, configure amazon-efs-utils for use in your AWS Region with AWS Direct Connect or VPN.

To configure amazon-efs-utils for use in your AWS Region

1. Using your text editor of choice, open /etc/amazon/efs/efs-utils.conf for editing.
2. Find the line "dns_name_format = {fs_id}.efs.{region}.amazonaws.com".
3. Change **{region}** with the ID for your AWS Region, for example us-west-2.

To mount the EFS file system on your on-premises client, first open a terminal on your on-premises Linux client. To mount the system, you need the file system ID, the mount target IP address for one of your mount targets, and the file system's AWS Region. If you created multiple mount targets for your file system, then you can choose any one of these.

When you have that information, you can mount your file system in three steps:

To create a mount directory

1. Make a directory for the mount point with the following command.

Example

```
mkdir ~/efs
```

2. Choose your preferred IP address of the mount target in the Availability Zone. You can measure the latency from your on-premises Linux clients. To do so, use a terminal-based tool like ping against the IP address of your EC2 instances in different Availability Zones to find the one with the lowest latency.

To update /etc/hosts

- Add an entry to your local /etc/hosts file with the file system ID and the mount target IP address, in the following format.

```
mount-target-IP-Address file-system-ID.efs.region.amazonaws.com
```

Example

```
192.0.2.0 fs-12345678.efs.us-west-2.amazonaws.com
```

To make a mount directory

1. Make a directory for the mount point with the following command.

Example

```
mkdir ~/efs
```

2. Run the mount command to mount the file system.

Example

```
sudo mount -t efs fs-12345678 ~/efs
```

If you want to use encryption of data in transit, your mount command looks something like the following.

Example

```
sudo mount -t efs -o tls fs-12345678 ~/efs
```

Walkthrough: Mount a File System from a Different VPC

In this walkthrough, you set up an Amazon EC2 instance to mount an Amazon EFS file system that is in a different virtual private cloud (VPC). You do this using the EFS mount helper. The mount helper is part of the `amazon-efs-utils` set of tools. For more information about `amazon-efs-utils`, see [Using the amazon-efs-utils Tools \(p. 54\)](#).

The client's VPC and your EFS file system's VPC must be connected using either a VPC peering connection or a VPC transit gateway. When you use a VPC peering connection or transit gateway to connect VPCs, Amazon EC2 instances that are in one VPC can access EFS file systems in another VPC, even if the VPCs belong to different accounts.

Note

Using Amazon EFS with Microsoft Windows-based clients isn't supported.

Topics

- [Before You Begin \(p. 180\)](#)
- [Step 1: Determine the Availability Zone ID of the EFS Mount Target \(p. 180\)](#)
- [Step 2: Determine the Mount Target IP Address \(p. 181\)](#)
- [Step 3: Add a Host Entry for the Mount Target \(p. 182\)](#)
- [Step 4: Mount Your File System Using the EFS Mount Helper \(p. 182\)](#)
- [Step 5: Clean Up Resources and Protect Your AWS Account \(p. 183\)](#)

Before You Begin

In this walkthrough, we assume that you already have the following:

- The `amazon-efs-utils` set of tools is installed on the EC2 instance before using this procedure. For instructions on installing `amazon-efs-utils`, see [Using the amazon-efs-utils Tools \(p. 54\)](#).
- One of the following:
 - A VPC peering connection between the VPC where the EFS file system resides and the VPC where the EC2 instance resides. A *VPC peering connection* is a networking connection between two VPCs. This type of connection enables you to route traffic between them using private Internet Protocol version 4 (IPv4) or Internet Protocol version 6 (IPv6) addresses. You can use VPC peering to connect VPCs within the same AWS Region or between AWS Regions. For more information, see [Creating and Accepting a VPC Peering Connection](#) in the *Amazon VPC Peering Guide*.
 - A transit gateway connecting the VPC where the EFS file system resides and the VPC where the EC2 instance resides. A *transit gateway* is a network transit hub that you can use to interconnect your VPCs and on-premises networks. For more information, see [Getting Started with Transit Gateways](#) in the *Amazon VPC Transit Gateways Guide*.

Step 1: Determine the Availability Zone ID of the EFS Mount Target

To ensure high availability of your file system, we recommend that you always use an EFS mount target IP address that is in the same Availability Zone as your NFS client. If you are mounting an EFS file system that is in another account, ensure that the NFS client and EFS mount target are in the same Availability Zone ID. This requirement applies because Availability Zone names can differ between accounts.

To determine the Availability Zone ID of the EC2 instance

1. Connect to your EC2 instance:

- To connect to your instance from a computer running macOS or Linux, specify the .pem file for your SSH command. To do this, use the `-i` option and the path to your private key.
- To connect to your instance from a computer running Windows, you can use either MindTerm or PuTTY. To use PuTTY, install it and convert the .pem file to a .ppk file.

For more information, see the following topics in the *Amazon EC2 User Guide for Linux Instances*:

- [Connecting to Your Linux Instance Using SSH](#)
- [Connecting to Your Linux Instance from Windows Using PuTTY](#)

2. Determine the Availability Zone ID that the EC2 instance is in using the `describe-availability-zones` CLI command as follows.

```
[ec2-user@ip-10.0.0.1] $ aws ec2 describe-availability-zones --zone-name `curl -s http://169.254.169.254/latest/meta-data/placement/availability-zone`  
{  
    "AvailabilityZones": [  
        {  
            "State": "available",  
            "ZoneName": "us-east-2b",  
            "Messages": [],  
            "ZoneId": "use2-az2",  
            "RegionName": "us-east-2"  
        }  
    ]  
}
```

The Availability Zone ID is returned in the `ZoneId` property, `use2-az2`.

Step 2: Determine the Mount Target IP Address

Now that you know the Availability Zone ID of the EC2 instance, you can now retrieve the IP address of the mount target that is in the same Availability Zone ID.

To determine the mount target IP address in the same Availability Zone ID

- Retrieve the mount target IP address for your file system in the `use2-az2` AZ ID using the `describe-mount-targets` CLI command, as follows.

```
$ aws efs describe-mount-targets --file-system-id file_system_id  
{  
    "MountTargets": [  
        {  
            "OwnerId": "111122223333",  
            "MountTargetId": "fsmt-11223344",  
            =====> "AvailabilityZoneId": "use2-az2",  
            "NetworkInterfaceId": "eni-048c09a306023eeec",  
            "AvailabilityZoneName": "us-east-2b",  
            "FileSystemId": "fs-01234567",  
            "LifeCycleState": "available",  
            "SubnetId": "subnet-06eb0da37ee82a64f",  
            "OwnerId": "958322738406",  
            =====> "IpAddress": "10.0.2.153"  
        },  
        ...  
    ]
```

```
{  
    "OwnerId": "111122223333",  
    "MountTargetId": "fsmt-667788aa",  
    "AvailabilityZoneId": "use2-az3",  
    "NetworkInterfaceId": "eni-0edb579d21ed39261",  
    "AvailabilityZoneName": "us-east-2c",  
    "FileSystemId": "fs-01234567",  
    "LifeCycleState": "available",  
    "SubnetId": "subnet-0ee85556822c441af",  
    "OwnerId": "958322738406",  
    "IpAddress": "10.0.3.107"  
}  
]  
}
```

The mount target in the use2-az2 Availability Zone ID has an IP address of 10.0.2.153.

Step 3: Add a Host Entry for the Mount Target

You can now make an entry in the /etc/hosts file on the EC2 instance that maps the mount target IP address to your EFS file system's hostname.

To add a host entry for the mount target

1. Add a line for the mount target IP address to the EC2 instance's /etc/hosts file. The entry uses the format *mount-target-IP-Address file-system-ID.efs.region.amazonaws.com*. Use the following command to add the line to the file.

```
echo "10.0.2.153 fs-01234567.efs.us-east-2.amazonaws.com" | sudo tee -a /etc/hosts
```

2. Make sure that the VPC security groups for the EC2 instance and mount target have rules that allow access to the EFS system, as needed. For more information, see [Using VPC security groups for Amazon EC2 instances and mount targets \(p. 218\)](#).

Step 4: Mount Your File System Using the EFS Mount Helper

To mount your EFS file system, you first create a mount directory on the EC2 instance. Then, using the EFS mount helper, you can mount the file system with either IAM authorization or an EFS access point. For more information, see [Using IAM to control file system data access \(p. 206\)](#) and [Working with Amazon EFS access points \(p. 224\)](#).

To create a mount directory

- Create a directory for mounting the file system using the following command.

```
$ sudo mkdir /mnt/efs/
```

To mount the file system using IAM authorization

- Use the following command to mount the file system using IAM authorization.

```
$ sudo mount -t efs -o tls,iam file-system-id /mnt/efs/
```

To mount the file system using an EFS access point

- Use the following command to mount the file system using an EFS access point.

```
$ sudo mount -t efs -o tls,accesspoint=access-point-id file-system-id /mnt/efs/
```

Now that you've mounted your Amazon EFS file system, you can test it with the following procedure.

To test the Amazon EFS file system connection

1. Change directories to the new directory that you created with the following command.

```
$ cd ~/mnt/efs
```

2. Make a subdirectory and change the ownership of that subdirectory to your EC2 instance user. Then navigate to that new directory with the following commands.

```
$ sudo mkdir getting-started
$ sudo chown ec2-user getting-started
$ cd getting-started
```

3. Create a text file with the following command.

```
$ touch test-file.txt
```

4. List the directory contents with the following command.

```
$ ls -al
```

As a result, the following file is created.

```
-rw-rw-r-- 1 username username 0 Nov 15 15:32 test-file.txt
```

You can also mount your file system automatically by adding an entry to the `/etc/fstab` file. For more information, see [Using `/etc/fstab` with EFS mount helper to automatically remount EFS file systems \(p. 81\)](#).

Warning

Use the `_netdev` option, used to identify network file systems, when mounting your file system automatically. If `_netdev` is missing, your EC2 instance might stop responding. This result is because network file systems need to be initialized after the compute instance starts its networking. For more information, see [Automatic mounting fails and the instance is unresponsive \(p. 247\)](#).

Step 5: Clean Up Resources and Protect Your AWS Account

After you have finished this walkthrough, or if you don't want to explore the walkthroughs, make sure to take the following steps. These clean up your resources and protect your AWS account.

To clean up resources and protect your AWS account

1. Unmount the Amazon EFS file system with the following command.

```
$ sudo umount ~/efs
```

2. Open the Amazon EFS console at <https://console.aws.amazon.com/efs/>.
3. Choose the Amazon EFS file system that you want to delete from the list of file systems.
4. For **Actions**, choose **Delete file system**.
5. In the **Permanently delete file system** dialog box, type the file system ID for the Amazon EFS file system that you want to delete, and then choose **Delete File System**.
6. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
7. In the navigation pane, choose **Security Groups**.
8. Select the name of the security group that you added the rule to for this walkthrough.

Warning

Don't delete the default security group for your VPC.

9. For **Actions**, choose **Edit inbound rules**.
10. Choose the X at the end of the inbound rule you added, and choose **Save**.

Walkthrough: Enforcing Encryption on an Amazon EFS File System at Rest

Following, you can find details about how to enforce encryption at rest using Amazon CloudWatch and AWS CloudTrail. This walkthrough is based upon the AWS white paper [Encrypt Data at Rest with Amazon EFS Encrypted File Systems](#).

Note

The method for enforcing the creation of Amazon EFS file systems that are encrypted at rest described in this walkthrough is deprecated. The preferred method to enforce the creation of file systems that are encrypted at rest is to use the `elasticfilesystem:Encrypted` condition key in AWS Identity and Access Management identity-based policies. For more information, see [Using IAM to enforce creating encrypted file systems \(p. 209\)](#). You can use this walkthrough to create CloudWatch alarms to validate that your IAM policies are preventing the creation of unencrypted file systems.

Enforcing Encryption at Rest

Your organization might require the encryption at rest of all data that meets a specific classification or that is associated with a particular application, workload, or environment. You can enforce policies for data encryption at rest for Amazon EFS file systems by using detective controls. These controls detect the creation of a file system and verify that encryption at rest is enabled.

If a file system that doesn't have encryption at rest is detected, you can respond in a number of ways. These range from deleting the file system and mount targets to notifying an administrator.

If you want to delete an unencrypted-at-rest file system but want to retain the data, first create a new encrypted-at-rest file system. Next, copy the data over to the new encrypted-at-rest file system. After the data is copied over, you can delete the unencrypted-at-rest file system.

Detecting File Systems That are Unencrypted at Rest

You can create a CloudWatch alarm to monitor CloudTrail logs for the `CreateFileSystem` event. You can then trigger the alarm to notify an administrator if the file system that was created was unencrypted at rest.

Create a Metric Filter

To create a CloudWatch alarm that is triggered when an unencrypted Amazon EFS file system is created, use the following procedure.

Before you begin, you must have an existing trail created that is sending CloudTrail logs to a CloudWatch Logs log group. For more information, see [Sending Events to CloudWatch Logs](#) in the *AWS CloudTrail User Guide*.

To create a metric filter

1. Open the CloudWatch console at <https://console.aws.amazon.com/cloudwatch/>.
2. In the navigation pane, choose **Logs**.
3. In the list of log groups, choose the log group that you created for CloudTrail log events.
4. Choose **Create Metric Filter**.
5. On the **Define Logs Metric Filter** page, choose **Filter Pattern** and then type the following:

```
{ ($.eventName = CreateFileSystem) && ($.responseElements.encrypted IS FALSE) }
```

6. Choose **Assign Metric**.
7. For **Filter Name**, type **UnencryptedFileSystemCreated**.
8. For **Metric Namespace**, type **CloudTrailMetrics**.
9. For **Metric Name**, type **UnencryptedFileSystemCreatedEventCount**.
10. Choose **Show advanced metric settings**.
11. For **Metric Value**, type **1**.
12. Choose **Create Filter**.

Create an Alarm

After you create the metric filter, use the following procedure to create an alarm.

To create an alarm

1. On the **Filters** for the **Log_Group_Name** page, next to the **UnencryptedFileSystemCreated** filter name, choose **Create Alarm**.
2. On the **Create Alarm** page, set the following parameters:
 - For **Name**, type **Unencrypted File System Created**
 - For **Whenever**, do the following:
 - Set **is to** to **> = 1**
 - Set **for:** to **1** consecutive period(s).
 - For **Treat missing data as**, choose **good (not breaching threshold)**.
 - For **Actions**, do the following:
 - For **Whenever this alarm**, choose **State is ALARM**.
 - For **Send notification to**, choose **NotifyMe**, choose **New list**, and then type a unique topic name for this list.
 - For **Email list**, type in the email address where you want notifications sent. You should receive an email at this address to confirm that you created this alarm.
 - For **Alarm Preview**, do the following:
 - For **Period**, choose **1 Minute**.
 - For **Statistic**, choose **Standard and Sum**.

3. Choose **Create Alarm**.

Test the Alarm for the Creation of Unencrypted File Systems

You can test the alarm by creating an unencrypted-at-rest file system, as follows.

To test the alarm by creating an unencrypted-at-rest file system

1. Sign in to the AWS Management Console and open the Amazon EFS console at <https://console.aws.amazon.com/efs/>.
2. Choose **Create file system** to display the **Create file system** dialog box.
3. To create a file system that is unencrypted at rest, choose **Customize** to display the **File system settings** page.
4. For **General** settings, enter the following.
 - a. (Optional) Enter a **Name** for the file system.
 - b. Keep **Lifecycle management**, **Performance mode**, and **Throughput mode** set to the default values.
 - c. Turn off **Encryption** by clearing **Enable encryption of data at rest**.
5. Choose **Next** to continue to the **Network Access** step in the configuration process.
6. Choose the default **Virtual Private Cloud (VPC)**.
7. For **Mount targets**, choose the default **Security groups** for each mount target.
8. Choose **Next** to display the **File system policy** page.
9. Choose **Next** to continue to the **Review and create** page.
10. Review the file system, and choose **Create** to create your file system and return to the **File systems** page.

Your trail logs the `CreateFileSystem` operation and delivers the event to your CloudWatch Logs log group. The event triggers your metric alarm and CloudWatch Logs sends you a notification about the change.

Walkthrough: Enable root squashing using IAM authorization for NFS clients

In this walkthrough, you configure Amazon EFS to prevent root access to your Amazon EFS file system for all AWS principals except for a single management workstation. You do this by configuring AWS Identity and Access Management (IAM) authorization for Network File System (NFS) clients. For more information about IAM authorization for NFS clients in EFS, see [Using IAM to control file system data access \(p. 206\)](#).

To do this requires configuring two IAM permissions policies, as follows:

- Create an EFS file system policy that explicitly allows read and write access to the file system, and implicitly denies root access.
- Assign an IAM identity to the Amazon EC2 management workstation that requires root access to the file system by using an Amazon EC2 instance profile. For more information about Amazon EC2 instance profiles, see [Using Instance Profiles](#) in the *AWS Identity and Access Management User Guide*.
- Assign the `AmazonElasticFileSystemClientFullAccess` AWS managed policy to the IAM role of the management workstation. For more information about AWS managed policies for EFS, see [AWS managed \(predefined\) policies for Amazon EFS \(p. 203\)](#).

To enable root squashing using IAM authorization for NFS clients, use the following procedures.

To prevent root access to the file system

1. Open the Amazon Elastic File System console at <https://console.aws.amazon.com/efs/>.
2. Choose **Filesystems**.
3. On the **File systems** page, choose the file system that you want to enable root squashing on.
4. On the file system details page, choose **File system policy**, and then choose **Edit**. The **File system policy** page appears.

```

1  [
2   "Version": "2012-10-17",
3   "Id": "efs-policy-wizard-e8de3bc2-1cf7-4dad-94ad-4f915b76ed7d",
4   "Statement": [
5     {
6       "Sid": "efs-statement-f6ed069b-fbb8-4ed5-8495-c24c5169df4d",
7       "Effect": "Allow",
8       "Principal": "*",
9       "Action": [
10         "elasticfilesystem:ClientMount",
11         "elasticfilesystem:ClientWrite"
12       ]
13     }
14   ]
15 ]
16 ]
17 ]

```

Manual changes will prevent the use of checkboxes until the editor is cleared.

[Cancel](#) [Save](#)

5. Choose **Prevent root access by default*** under **Policy options**. The policy JSON object appears in the **Policy editor**.
6. Choose **Save** to save the file system policy.

Clients that aren't anonymous can get root access to the file system through an identity-based policy. When you attach the `AmazonElasticFileSystemClientFullAccess` managed policy to the workstation's role, IAM grants root access to the workstation based on its identity policy.

To enable root access from the management workstation

1. Open the IAM console at <https://console.aws.amazon.com/iam/>.
2. Create a role for Amazon EC2 called `EFS-client-root-access`. IAM creates an instance profile with the same name as the EC2 role you created.
3. Assign the AWS managed policy `AmazonElasticFileSystemClientFullAccess` to the EC2 role you created. The contents of this policy is shown following.

```
{
  "Version": "2012-10-17",
  "Statement": [
    {
      "Resource": "*",
      "Effect": "Allow",
      "Action": "elasticfilesystem:Client*"
    }
  ]
}
```

```
    ],
  "Condition": {}
}
```

4. Attach the instance profile to the EC2 instance that you are using as the management workstation, as described following. For more information, see [Attaching an IAM Role to an Instance](#) in the *Amazon EC2 User Guide for Linux Instances*.
 - a. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
 - b. In the navigation pane, choose **Instances**.
 - c. Choose the instance. For **Actions**, choose **Instance Settings**, and then choose **Attach/Replace IAM role**.
 - d. Choose the IAM role that you created in the first step, EFS-client-root-access, and choose **Apply**.
5. Install the EFS mount helper on the management workstation. For more information about the EFS mount helper and the amazon-efs-utils package, see [Using the amazon-efs-utils Tools \(p. 54\)](#).
6. Mount the EFS file system on the management workstation by using the following command with the `iam` mount option.

```
$ sudo mount -t efs -o tls,iam file-system-id:/ efs-mount-point
```

You can configure the Amazon EC2 instance to automatically mount the file system with IAM authorization. For more information about mounting an EFS file system with IAM authorization, see [Mounting with IAM authorization \(p. 78\)](#).

Security in Amazon EFS

The AWS [shared responsibility model](#) applies to data protection in Amazon Elastic File System. As described in this model, AWS is responsible for protecting the global infrastructure that runs all of the AWS Cloud. You are responsible for maintaining control over your content that is hosted on this infrastructure. This content includes the security configuration and management tasks for the AWS services that you use. For more information about data privacy, see the [Data Privacy FAQ](#). For information about data protection in Europe, see the [AWS Shared Responsibility Model and GDPR blog post on the AWS Security Blog](#).

For data protection purposes, we recommend that you protect AWS account credentials and set up individual user accounts with AWS Identity and Access Management (IAM). That way each user is given only the permissions necessary to fulfill their job duties. We also recommend that you secure your data in the following ways:

- Use multi-factor authentication (MFA) with each account.
- Use SSL/TLS to communicate with AWS resources. We recommend TLS 1.2 or later.
- Set up API and user activity logging with AWS CloudTrail.
- Use AWS encryption solutions, along with all default security controls within AWS services.
- Use advanced managed security services such as Amazon Macie, which assists in discovering and securing personal data that is stored in Amazon S3.
- If you require FIPS 140-2 validated cryptographic modules when accessing AWS through a command line interface or an API, use a FIPS endpoint. For more information about the available FIPS endpoints, see [Federal Information Processing Standard \(FIPS\) 140-2](#).

We strongly recommend that you never put confidential or sensitive information, such as your customers' email addresses, into tags or free-form fields such as a **Name** field. This includes when you work with EFS or other AWS services using the console, API, AWS CLI, or AWS SDKs. Any data that you enter into tags or free-form fields used for names may be used for billing or diagnostic logs. If you provide a URL to an external server, we strongly recommend that you do not include credentials information in the URL to validate your request to that server.

Topics

- [Data encryption in Amazon EFS \(p. 189\)](#)
- [Identity and access management for Amazon EFS \(p. 196\)](#)
- [Controlling network access to Amazon EFS file systems for NFS clients \(p. 218\)](#)
- [Working with users, groups, and permissions at the Network File System \(NFS\) Level \(p. 221\)](#)
- [Working with Amazon EFS access points \(p. 224\)](#)
- [Logging and monitoring in Amazon EFS \(p. 228\)](#)
- [AWS managed policies for Amazon EFS \(p. 228\)](#)
- [Compliance Validation for Amazon Elastic File System \(p. 233\)](#)
- [Resilience in Amazon Elastic File System \(p. 233\)](#)
- [Amazon Elastic File System Network Isolation \(p. 234\)](#)

Data encryption in Amazon EFS

Amazon EFS supports two forms of encryption for file systems, encryption of data in transit and encryption at rest. You can enable encryption of data at rest when creating an Amazon EFS file system. You can enable encryption of data in transit when you mount the file system.

If you require FIPS 140-2 validated cryptographic modules when accessing AWS through a command line interface or an API, use a FIPS endpoint. For more information about the available FIPS endpoints, see [Federal Information Processing Standard \(FIPS\) 140-2](#).

When to use encryption

If your organization is subject to corporate or regulatory policies that require encryption of data and metadata at rest, we recommend creating a file system that is encrypted at rest, and mounting your file system using encryption of data in transit.

Related Topics

For more information on encryption with Amazon EFS, see these related topics:

- [Working with Amazon EFS resources \(p. 25\)](#)
- [Managing access to encrypted file systems \(p. 104\)](#)
- [Amazon EFS performance tips \(p. 134\)](#)
- [Amazon EFS API permissions: actions, resources, and conditions reference \(p. 204\)](#)
- [Amazon EFS Log File Entries for Encrypted-at-Rest File Systems \(p. 128\)](#)
- [Troubleshooting encryption \(p. 252\)](#)

Encrypting data at rest

You can create encrypted file systems using the AWS Management Console, the AWS CLI, or programmatically through the Amazon EFS API or one of the AWS SDKs. Your organization might require the encryption of all data that meets a specific classification or is associated with a particular application, workload, or environment.

Once you create an EFS file system, you cannot change its encryption setting. This means that you cannot modify an unencrypted file system to make it encrypted. Instead, you need to create a new, encrypted file system.

Note

The AWS key management infrastructure uses Federal Information Processing Standards (FIPS) 140-2 approved cryptographic algorithms. The infrastructure is consistent with National Institute of Standards and Technology (NIST) 800-57 recommendations.

Enforcing the creation of Amazon EFS file systems encrypted at rest

You can use the `elasticfilesystem:Encrypted` IAM condition key in AWS Identity and Access Management (IAM) identity-based policies to control whether users can create Amazon EFS file systems that are encrypted at rest. For more information about using the condition key, see [Using IAM to enforce creating encrypted file systems \(p. 209\)](#).

You can also define service control policies (SCPs) inside AWS Organizations to enforce EFS encryption for all AWS accounts in your organization. For more information about service control policies in AWS Organizations, see [Service control policies in the AWS Organizations User Guide](#).

Encrypting a file system at rest using the console


When you create a new file system using the Amazon EFS console, encryption at rest is enabled by default. The following procedure describes how to enable encryption for a new file system when you create it from the console.

Note

Encryption at rest is not enabled by default when creating a new file system using the AWS CLI, API, and SDKs. For more information, see [Creating a file system using the AWS CLI \(p. 34\)](#).


To encrypt a new file system using the EFS console

1. Open the Amazon Elastic File System console at <https://console.aws.amazon.com/efs/>.
2. Choose **Create file system** to open the **Create file system** dialog box.



3. (Optional) Enter a **Name** for your file system.
 4. For **Virtual Private Cloud (VPC)**, choose your VPC, or keep it set to your default VPC.
 5. Choose **Create** to create a file system that uses the following service recommended settings:
 - Encryption of data at rest enabled using your default AWS KMS key for Amazon EFS (`aws/elasticfilesystem`).
 - Automatic backups turned on – For more information, see [Using AWS Backup to back up and restore Amazon EFS file systems \(p. 138\)](#).
 - Mount targets – Amazon EFS creates mount targets with the following settings:
 - Located in each Availability Zone in the AWS Region where the file system is created.
 - Located in the default subnets of the VPC that you selected.
 - Use the VPC's default security group. You can manage security groups after the file system is created.
- For more information, see [Managing file system network accessibility \(p. 95\)](#).
- General Purpose performance mode – For more information, see [Performance modes \(p. 131\)](#).
 - Bursting throughput mode – For more information, see [Throughput modes \(p. 132\)](#).
 - Lifecycle management enabled with a 30-day policy – For more information, see [Amazon EFS lifecycle management \(p. 100\)](#).

6. The **File systems** page appears with a banner across the top showing the status of the file system you created. A link to access the file system details page appears in the banner when the file system becomes available.



You now have a new encrypted-at-rest file system.

How encryption at rest works

In an encrypted file system, data and metadata are automatically encrypted before being written to the file system. Similarly, as data and metadata are read, they are automatically decrypted before being presented to the application. These processes are handled transparently by Amazon EFS, so you don't have to modify your applications.

Amazon EFS uses industry-standard AES-256 encryption algorithm to encrypt EFS data and metadata at rest. For more information, see [Cryptography basics in the AWS Key Management Service Developer Guide](#).

How Amazon EFS uses AWS KMS

Amazon EFS integrates with AWS Key Management Service (AWS KMS) for key management. Amazon EFS uses customer managed keys to encrypt your file system in the following way:

- **Encrypting metadata at rest** – Amazon EFS uses the AWS managed key for Amazon EFS, `aws/elasticfilesystem`, to encrypt and decrypt file system metadata (that is, file names, directory names, and directory contents).
- **Encrypting file data at rest** – You choose the customer managed key used to encrypt and decrypt file data (that is, the contents of your files). You can enable, disable, or revoke grants on this customer managed key. This customer managed key can be one of the two following types:
 - **AWS managed key for Amazon EFS** – This is the default customer managed key, `aws/elasticfilesystem`. You're not charged to create and store a customer managed key, but there are usage charges. To learn more, see [AWS Key Management Service pricing](#).
 - **Customer managed key** – This is the most flexible KMS key to use, because you can configure its key policies and grants for multiple users or services. For more information on creating customer managed keys, see [Creating keys](#) in the [AWS Key Management Service Developer Guide](#).

If you use a customer managed key for file data encryption and decryption, you can enable key rotation. When you enable key rotation, AWS KMS automatically rotates your key once per year. Additionally, with a customer managed key, you can choose when to disable, re-enable, delete, or revoke access to your customer managed key at any time. For more information, see [Disabling, deleting, or revoking access to the KMS key for a file system \(p. 105\)](#).

Important

Amazon EFS accepts only symmetric customer managed keys. You cannot use asymmetric customer managed keys with Amazon EFS.

Data encryption and decryption at rest are handled transparently. However, AWS account IDs specific to Amazon EFS appear in your AWS CloudTrail logs related to AWS KMS actions. For more information, see [Amazon EFS Log File Entries for Encrypted-at-Rest File Systems \(p. 128\)](#).

Amazon EFS key policies for AWS KMS

Key policies are the primary way to control access to customer managed keys. For more information on key policies, see [Using key policies in AWS KMS](#) in the *AWS Key Management Service Developer Guide*. The following list describes all the AWS KMS-related permissions that are required or otherwise supported by Amazon EFS for encrypted at rest file systems:

- **kms:Encrypt** – (Optional) Encrypts plaintext into ciphertext. This permission is included in the default key policy.
- **kms:Decrypt** – (Required) Decrypts ciphertext. Ciphertext is plaintext that has been previously encrypted. This permission is included in the default key policy.
- **kms:ReEncrypt** – (Optional) Encrypts data on the server side with a new customer managed key, without exposing the plaintext of the data on the client side. The data is first decrypted and then re-encrypted. This permission is included in the default key policy.
- **kms:GenerateDataKeyWithoutPlaintext** – (Required) Returns a data encryption key encrypted under a customer managed key. This permission is included in the default key policy under **kms:GenerateDataKey***.
- **kms>CreateGrant** – (Required) Adds a grant to a key to specify who can use the key and under what conditions. Grants are alternate permission mechanisms to key policies. For more information on grants, see [Using Grants](#) in the *AWS Key Management Service Developer Guide*. This permission is included in the default key policy.
- **kms:DescribeKey** – (Required) Provides detailed information about the specified customer managed key. This permission is included in the default key policy.
- **kms>ListAliases** – (Optional) Lists all of the key aliases in the account. When you use the console to create an encrypted file system, this permission populates the **Select KMS key** list. We recommend using this permission to provide the best user experience. This permission is included in the default key policy.

AWS managed key for Amazon EFS KMS policy

The KMS policy JSON for the AWS managed key for Amazon EFS, `aws/elasticfilesystem` is as follows:

```
{  
    "Version": "2012-10-17",  
    "Id": "auto-elasticfilesystem-1",  
    "Statement": [  
        {  
            "Sid": "Allow access to EFS for all principals in the account that are  
            authorized to use EFS",  
            "Effect": "Allow",  
            "Principal": "*"  
        }  
    ]  
}
```

```
    "Principal": {
        "AWS": "*"
    },
    "Action": [
        "kms:Encrypt",
        "kms:Decrypt",
        "kms:ReEncrypt*",
        "kms:GenerateDataKey*",
        "kms>CreateGrant",
        "kms:DescribeKey"
    ],
    "Resource": "*",
    "Condition": {
        "StringEquals": {
            "kms:ViaService": "elasticfilesystem.us-east-2.amazonaws.com",
            "kms:CallerAccount": "111122223333"
        }
    }
},
{
    "Sid": "Allow direct access to key metadata to the account",
    "Effect": "Allow",
    "Principal": {
        "AWS": "arn:aws:iam::111122223333:root"
    },
    "Action": [
        "kms:Describe*",
        "kms:Get*",
        "kms>List*",
        "kms:RevokeGrant"
    ],
    "Resource": "*"
}
]
```

Encrypting data in transit

You can encrypt data in transit using an Amazon EFS file system, without needing to modify your applications.

Encrypting data in transit with TLS

Enabling encryption of data in transit for your Amazon EFS file system is done by enabling Transport Layer Security (TLS) when you mount your file system using the Amazon EFS mount helper. For more information, see [Using EFS mount helper to mount EFS file systems \(p. 68\)](#).

When encryption of data in transit is declared as a mount option for your Amazon EFS file system, the mount helper initializes a client stunnel process. Stunnel is an open source multipurpose network relay. The client stunnel process listens on a local port for inbound traffic, and the mount helper redirects Network File System (NFS) client traffic to this local port. The mount helper uses TLS version 1.2 to communicate with your file system.

To mount your Amazon EFS file system with the mount helper with encryption of data in transit enabled

1. Access the terminal for your instance through Secure Shell (SSH), and log in with the appropriate user name. For more information on how to do this, see [Connecting to Your Linux Instance Using SSH in the Amazon EC2 User Guide for Linux Instances](#).
2. Run the following command to mount your file system.

```
sudo mount -t efs -o tls fs-12345678:/ /mnt/efs
```

How encrypting in transit works

To enable encryption of data in transit, you connect to Amazon EFS using TLS. We recommend using the EFS mount helper to mount your file system because it simplifies the mounting process as compared to mounting with NFS mount. The EFS mount helper manages the process using stunnel for TLS. If you're not using the mount helper, you can still enable encryption of data in transit. At a high level, the following are the steps to do so.

To enable encryption of data in transit without using the EFS mount helper

1. Download and install stunnel, and note the port that the application is listening on. For instructions to do so, see [Upgrading stunnel \(p. 64\)](#).
2. Run stunnel to connect to your Amazon EFS file system on port 2049 using TLS.
3. Using the NFS client, mount localhost:*port*, where *port* is the port that you noted in the first step.

Because encryption of data in transit is configured on a per-connection basis, each configured mount has a dedicated stunnel process running on the instance. By default, the stunnel process used by the EFS mount helper listens on local ports 20049 to 21049, and it connects to Amazon EFS on port 2049.

Note

By default, when using the Amazon EFS mount helper with TLS, the mount helper enforces certificate hostname checking. The Amazon EFS mount helper uses the stunnel program for its TLS functionality. Some versions of Linux don't include a version of stunnel that supports these TLS features by default. When using one of those Linux versions, mounting an Amazon EFS file system using TLS fails.

After you've installed the amazon-efs-utils package, to upgrade your system's version of stunnel see [Upgrading stunnel \(p. 64\)](#).

For issues with encryption, see [Troubleshooting encryption \(p. 252\)](#).

When using encryption of data in transit, your NFS client setup is changed. When you inspect your actively mounted file systems, you see one mounted to 127.0.0.1, or localhost, as in the following example.

```
$ mount | column -t
127.0.0.1:/ on /home/ec2-user/efs type nfs4
(rw,relatime,vers=4.1,rsize=1048576,wsize=1048576,namlen=255,hard,proto=tcp,port=20127,timeo=600,retr
```

When mounting with TLS and the Amazon EFS mount helper, you are reconfiguring your NFS client to mount to a local port. The EFS mount helper starts a client stunnel process that is listening on this local port, and stunnel is opening an encrypted connection to the EFS file system using TLS. The EFS mount helper is responsible for setting up and maintaining this encrypted connection and the associated configuration.

To determine which Amazon EFS file system ID corresponds to which local mount point, you can use the following command. Replace *efs-mount-point* with the local path where you mounted your file system.

```
grep -E "Successfully mounted.*efs-mount-point" /var/log/amazon/efs/mount.log | tail -1
```

When you use the mount helper for encryption of data in transit, it also creates a process called amazon-efs-mount-watchdog. This process ensures that each mount's stunnel process is running, and

stops the stunnel when the Amazon EFS file system is unmounted. If for some reason a stunnel process is terminated unexpectedly, the watchdog process restarts it.

Identity and access management for Amazon EFS

Access to Amazon EFS requires credentials that AWS can use to authenticate your requests. Those credentials must have permissions to access AWS resources, such as an Amazon EFS file system or an Amazon EC2 instance. The following sections provide details on how you can use [What is IAM](#) and Amazon EFS to help secure your resources by controlling who can access them.

- [Authentication \(p. 196\)](#)
- [Access control \(p. 197\)](#)

Authentication

You can access AWS as any of the following types of identities:

- **AWS account root user** – When you sign up for AWS, you provide an email address and password that is associated with your AWS account. This is your *AWS account root user*. Its credentials provide complete access to all of your AWS resources.

Important

For security reasons, we recommend that you use the root user only to create an *administrator*, which is an *IAM user* with full permissions to your AWS account. You can then use this administrator user to create other IAM users and roles with limited permissions. For more information, see [IAM Best Practices](#) and [Creating an Admin User and Group](#) in the *IAM User Guide*.

- **IAM user** – An *IAM user* is simply an identity within your AWS account that has specific custom permissions (for example, permissions to create a file system in Amazon EFS). You can use an IAM user name and password to sign in to secure AWS web pages like the [AWS Management Console](#), [AWS Discussion Forums](#), or the [AWS Support Center](#).

In addition to a user name and password, you can also generate [access keys](#) for each user. You can use these keys when you access AWS services programmatically, either through [one of the several SDKs](#) or by using the [AWS Command Line Interface \(CLI\)](#). The SDK and CLI tools use the access keys to cryptographically sign your request. If you don't use the AWS tools, you must sign the request yourself. Amazon EFS supports *Signature Version 4*, a protocol for authenticating inbound API requests. For more information about authenticating requests, see [Signature Version 4 Signing Process](#) in the *AWS General Reference*.

- **IAM role** – An *IAM role* is another IAM identity that you can create in your account that has specific permissions. It is similar to an *IAM user*, but it is not associated with a specific person. An IAM role enables you to obtain temporary access keys that can be used to access AWS services and resources. IAM roles with temporary credentials are useful in the following situations:
 - **Federated user access** – Instead of creating an IAM user, you can use preexisting user identities from AWS Directory Service, your enterprise user directory, or a web identity provider. These are known as *federated users*. AWS assigns a role to a federated user when access is requested through an *identity provider*. For more information about federated users, see [Federated Users and Roles](#) in the *IAM User Guide*.

- **Cross-account administration** – You can use an IAM role in your account to grant another AWS account permissions to administer your account's Amazon EFS resources. For an example, see [Tutorial: Delegate Access Across AWS accounts Using IAM Roles](#) in the *IAM User Guide*. You can't mount Amazon EFS file systems from across VPCs or accounts. For more information, see [Managing file system network accessibility \(p. 95\)](#).
- **AWS service access** – You can use an IAM role in your account to grant an AWS service permissions to access your account's resources. For example, you can create a role that allows Amazon Redshift to access an Amazon S3 bucket on your behalf and then load data from that bucket into an Amazon Redshift cluster. For more information, see [Creating a Role to Delegate Permissions to an AWS Service](#) in the *IAM User Guide*.
- **Applications running on Amazon EC2** – You can use an IAM role to manage temporary credentials for applications running on an EC2 instance and making AWS API requests. This is preferable to storing access keys within the EC2 instance. To assign an AWS role to an EC2 instance and make it available to all of its applications, you create an instance profile that is attached to the instance. An instance profile contains the role and enables programs running on the EC2 instance to get temporary credentials. For more information, see [Using Roles for Applications on Amazon EC2](#) in the *IAM User Guide*.

Access control

You can have valid credentials to authenticate your requests, but unless you have permissions you can't create or access Amazon Elastic File System resources. For example, you must have permissions to create an Amazon EFS file system.

The following sections describe how to manage permissions for Amazon EFS. We recommend that you read the overview first.

- [Overview of managing access permissions to your Amazon EFS resources \(p. 197\)](#)
- [Controlling access to the EFS API \(p. 201\)](#)

Overview of managing access permissions to your Amazon EFS resources

Every AWS resource is owned by an AWS account, and permissions to create or access a resource are governed by permissions policies. An account administrator can attach permissions policies to IAM identities (that is, users, groups, and roles). Some services, including Amazon EFS, also support attaching permissions policies to resources.

Note

An *account administrator* (or administrator user) is a user with administrator privileges. For more information, see [IAM Best Practices](#) in the *IAM User Guide*.

When granting permissions, you decide who is getting the permissions, the resources they get permissions for, and the specific actions that you want to allow on those resources.

Topics

- [Amazon EFS resources and operations \(p. 198\)](#)

- [Understanding resource ownership \(p. 198\)](#)
- [Managing access to resources \(p. 198\)](#)
- [Specifying policy elements: actions, effects, and principals \(p. 200\)](#)
- [Specifying conditions in a policy \(p. 200\)](#)

Amazon EFS resources and operations

In Amazon EFS, the primary resource is a *file system*. Amazon EFS also supports additional resource types, the *mount target* and *access point*. However, for Amazon EFS, you can create mount targets and access points only in the context of an existing file system. Mount targets and access points are referred to as *sub-resources*.

These resources and sub-resources have unique Amazon Resource Names (ARNs) associated with them as shown in the following table.

Amazon EFS provides a set of operations to work with Amazon EFS resources. For a list of available operations, see [Amazon EFS Actions \(p. 255\)](#) and [EFS actions for clients \(p. 207\)](#).

Note

You cannot restrict the response of the `DescribeFileSystem` or `DescribeAccessPoint` API actions to specific EFS resources in an IAM policy.

Understanding resource ownership

The AWS account owns the resources that are created in the account, regardless of who created the resources. Specifically, the resource owner is the AWS account of the [principal entity](#) (that is, the root account, an IAM user, or an IAM role) that authenticates the resource creation request. The following examples illustrate how this works:

- If you use the root account credentials of your AWS account to create a file system, your AWS account is the owner of the resource (in Amazon EFS, the resource is the file system).
- If you create an IAM user in your AWS account and grant permissions to create a file system to that user, the user can create a file system. However, your AWS account, to which the user belongs, owns the file system resource.
- If you create an IAM role in your AWS account with permissions to create a file system, anyone who can assume the role can create a file system. Your AWS account, to which the role belongs, owns the file system resource.

Managing access to resources

A *permissions policy* describes who has access to what. The following section explains the available options for creating permissions policies.

Note

This section discusses using IAM in the context of Amazon EFS. It doesn't provide detailed information about the IAM service. For complete IAM documentation, see [What Is IAM?](#) in the *IAM User Guide*. For information about IAM policy syntax and descriptions, see [IAM Policy Reference](#) in the *IAM User Guide*.

Policies attached to an IAM identity are referred to as *identity-based* policies (IAM policies) and policies attached to a resource are referred to as *resource-based* policies. Amazon EFS supports both identity-based policies and resource-based policies.

Topics

- [Identity-based policies \(IAM policies\) \(p. 199\)](#)

- [Resource-based policies \(p. 199\)](#)

Identity-based policies (IAM policies)

You can attach policies to IAM identities to control access to the EFS API or to control NFS client access. For example, to grant a user permissions to create an Amazon EFS resource, such as a file system, you can attach a permissions policy to a user or group that the user belongs to.

For more information about using IAM to delegate permissions, see [Access Management](#) in the *IAM User Guide*.

The following is an example policy that provides the EFS and EC2 permissions required for a user to perform the `CreateFileSystem` action for your AWS account.

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid" : "Stmt1EFSPermissions",  
            "Effect": "Allow",  
            "Action": [  
                "elasticfilesystem>CreateFileSystem",  
                "elasticfilesystem>CreateMountTarget"  
            ],  
            "Resource": "arn:aws:elasticfilesystem:us-west-2:account-id:file-system/*"  
        },  
        {  
            "Sid" : "Stmt2EC2permissions",  
            "Effect": "Allow",  
            "Action": [  
                "ec2:DescribeSubnets",  
                "ec2:CreateNetworkInterface",  
                "ec2:DescribeNetworkInterfaces"  
            ],  
            "Resource": "*"  
        }  
    ]  
}
```

For more information about using identity-based policies with Amazon EFS, see [Controlling access to the EFS API \(p. 201\)](#). For more information about users, groups, roles, and permissions, see [Identities \(Users, Groups, and Roles\)](#) in the *IAM User Guide*.

Resource-based policies

You can use file system policies to control API access and NFS client access to the file system. Amazon EFS supports a resource-based policy for file systems, called a `FileSystemPolicy`. Using an EFS `FileSystemPolicy` you can specify who has access to the file system and what actions they can perform on it. Using file system policies provides you an easy way to control access to your file systems, and lets you grant usage permission to other accounts on a per-file system basis. The following file system policy grants `ClientMount`, or read-only, permissions to the `EfsReadOnly` IAM role.

```
{  
    "Version": "2012-10-17",  
    "Id": "read-only-example-policy02",  
    "Statement": [  
        {  
            "Sid": "efs-statement-example02",  
            "Effect": "Allow",  
            "Principal": {  
                "AWS": "account-id:*"  
            },  
            "Action": "elasticfilesystem:ClientMount",  
            "Resource": "arn:aws:elasticfilesystem:us-west-2:account-id:file-system/*"  
        }  
    ]  
}
```

```
        "AWS": "arn:aws:iam::111122223333:role/EfsReadOnly"
    },
    "Action": [
        "elasticfilesystem:ClientMount"
    ]
}
]
```

Note

Amazon EFS file system policies have a 20,000 character limit.

For more information about using EFS file system policies to control access to file system data, see [Using IAM to control file system data access \(p. 206\)](#).

Specifying policy elements: actions, effects, and principals

For each Amazon EFS resource (see [Amazon EFS resources and operations \(p. 198\)](#)), the service defines a set of actions API operations (see [Actions \(p. 255\)](#) and [EFS actions for clients \(p. 207\)](#)) that you can grant permissions for. For the Amazon EFS file system resource, example actions are: `CreateFileSystem`, `DeleteFileSystem`, and `DescribeFileSystems`. Performing an API operation can require permissions for more than one action.

The following are the most basic policy elements:

- **Resource** – In resource-based policies (file system policies), the resource that the policy is attached to is the implicit resource. For identity-based policies, you use an Amazon Resource Name (ARN) to identify the resource to which the policy applies. For more information, see [Amazon EFS resources and operations \(p. 198\)](#).
- **Action** – You use action keywords to identify resource operations that you want to allow or deny. For example, depending on the specified Effect, `elasticfilesystem:CreateFileSystem` either allows or denies the user permissions to perform the Amazon EFS `CreateFileSystem` operation.
- **Effect** – You specify the effect when the user requests the specific action—this can be either allow or deny. If you don't explicitly grant access to (allow) a resource, access is implicitly denied. You can also explicitly deny access to a resource, which you might do to make sure that a user cannot access it, even if a different policy grants access.
- **Principal** – In identity-based policies (IAM policies), the user that the policy is attached to is the implicit principal. For resource-based policies, you specify the user, account, service, or other entity that you want to receive permissions (applies to resource-based policies only).

To learn more about IAM policy syntax and descriptions, see [IAM Policy Reference](#) in the *IAM User Guide*.

For a table showing all of the Amazon EFS API actions, see [Amazon EFS API permissions: actions, resources, and conditions reference \(p. 204\)](#).

For a table showing all of the Amazon EFS NFS client actions, see [Using IAM to control file system data access \(p. 206\)](#).

Specifying conditions in a policy

When you grant permissions, you can use the IAM policy language to specify the conditions when a policy should take effect. For more information about specifying conditions in a policy, see [IAM JSON Policy Elements: Condition](#) in the *IAM User Guide*.

There are both EFS-specific and AWS-wide condition keys that you can use as appropriate. For a complete list of AWS-wide keys, see [Available Keys for Conditions](#) in the *IAM User Guide*. For a complete list of EFS-specific condition keys, see [EFS condition keys for clients \(p. 207\)](#).

Note

The `aws:SourceIp` AWS-wide condition can be used to control what hosts are able to use EFS actions like `CreateFileSystem`, `CreateMountTarget`, `DeleteMountTarget`, `DescribeMountTargetSecurityGroups`, or `ModifyMountTargetSecurityGroup` actions. The `aws:SourceIp` condition can be used to control NFS access to EFS mount targets, but it is not the recommended approach due to security considerations. To control access to EFS mount targets, see [Controlling network access to Amazon EFS file systems for NFS clients \(p. 218\)](#).

Controlling access to the EFS API

You can use both IAM identity policies and resource policies to grant permissions to perform API operations on Amazon EFS resources. This topic provides examples of identity-based policies that demonstrate how an account administrator can attach permissions policies to IAM identities (that is, users, groups, and roles) because this is the most common way of controlling access to the Amazon EFS API.

Important

We recommend that you first review the introductory topics that explain the basic concepts and options available for you to manage access to your Amazon EFS resources. For more information, see [Overview of managing access permissions to your Amazon EFS resources \(p. 197\)](#).

The sections in this topic cover the following:

- [Permissions Required to Use the Amazon EFS Console \(p. 202\)](#)
- [AWS managed \(predefined\) policies for Amazon EFS \(p. 203\)](#)
- [Customer managed policy examples \(p. 203\)](#)

The following shows an example of a permissions policy.

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid" : "AllowFileSystemPermissions",  
            "Effect": "Allow",  
            "Action": [  
                "elasticfilesystem>CreateFileSystem",  
                "elasticfilesystem>CreateMountTarget"  
            ],  
            "Resource": "arn:aws:elasticfilesystem:us-west-2:account-id:file-system/*"  
        },  
        {  
            "Sid" : "AllowEC2Permissions",  
            "Effect": "Allow",  
            "Action": [  
                "ec2:DescribeSubnets",  
                "ec2>CreateNetworkInterface",  
                "ec2:DescribeNetworkInterfaces"  
            ],  
            "Resource": "*"  
        }  
    ]  
}
```

The policy has two statements:

- The first statement grants permissions for two Amazon EFS actions (`elasticfilesystem/CreateFileSystem` and `elasticfilesystem/CreateMountTarget`) on

a resource using the Amazon Resource Name (ARN) for the file system. The ARN specifies a wild card character (*) because you don't know the file system ID until after you create a file system.

- The second statement grants permissions for some of the Amazon EC2 actions because the elasticfilesystem:CreateMountTarget action in the first statement requires permissions for specific Amazon EC2 actions. Because these Amazon EC2 actions don't support resource-level permissions, the policy specifies the wild card character (*) as the Resource value instead of specifying a file system ARN.

The policy doesn't specify the Principal element because in an identity-based policy you don't specify the principal who gets the permission. When you attach policy to a user, the user is the implicit principal. When you attach a permissions policy to an IAM role, the principal identified in the role's trust policy gets the permissions.

For a table showing all of the Amazon EFS API actions and the resources that they apply to, see [Amazon EFS API permissions: actions, resources, and conditions reference \(p. 204\)](#).

Permissions Required to Use the Amazon EFS Console

The permissions reference table lists the Amazon EFS API operations and shows the required permissions for each operation. For more information about Amazon EFS API operations, see [Amazon EFS API permissions: actions, resources, and conditions reference \(p. 204\)](#).

To use the Amazon EFS console, you need to grant permissions for additional actions as shown in the following permissions policy.

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid": "Stmt1AdditionalEC2PermissionsForConsole",  
            "Effect": "Allow",  
            "Action": [  
                "ec2:DescribeAvailabilityZones",  
                "ec2:DescribeSecurityGroups",  
                "ec2:DescribeVpcs",  
                "ec2:DescribeVpcAttribute"  
            ],  
            "Resource": "*"  
        },  
        {  
            "Sid": "Stmt2AdditionalKMSPermissionsForConsole",  
            "Effect": "Allow",  
            "Action": [  
                "kms>ListAliases",  
                "kms:DescribeKey"  
            ],  
            "Resource": "*"  
        }  
    ]  
}
```

The Amazon EFS console needs these additional permissions for the following reasons:

- Permissions for the Amazon EFS actions enable the console to display Amazon EFS resources in the account.
- The console needs permissions for the ec2 actions to query Amazon EC2 so it can display Availability Zones, VPCs, security groups, and account attributes.

- The console needs permissions for the kms actions to create an encrypted file system. For more information on encrypted file systems, see [Data encryption in Amazon EFS \(p. 189\)](#).

AWS managed (predefined) policies for Amazon EFS

AWS addresses many common use cases by providing standalone IAM policies that are created and administered by AWS. Managed policies grant necessary permissions for common use cases so you can avoid having to investigate what permissions are needed. For more information, see [AWS Managed Policies](#) in the *IAM User Guide*.

The following AWS managed policies, which you can attach to users in your account, are specific to Amazon EFS:

- **AmazonElasticFileSystemReadOnlyAccess** – Grants read-only access to Amazon EFS resources.
- **AmazonElasticFileSystemFullAccess** – Grants full access to Amazon EFS resources.

Note

You can review these permissions policies by signing in to the IAM management console and searching for specific policies there.

You can also create your own custom IAM policies to allow permissions for Amazon EFS API actions. You can attach these custom policies to the IAM users or groups that require those permissions.

Customer managed policy examples

In this section, you can find example user policies that grant permissions for various Amazon EFS actions. These policies work when you are using AWS SDKs or the AWS CLI. When you are using the console, you need to grant additional permissions specific to the console, which is discussed in [Permissions Required to Use the Amazon EFS Console \(p. 202\)](#).

Note

All examples use the us-west-2 AWS Region and contain fictitious account IDs.

Examples

- [Example 1: Allow a user to create a mount target and tags on an existing file system \(p. 203\)](#)
- [Example 2: Allow a user to perform all Amazon EFS actions \(p. 204\)](#)

Example 1: Allow a user to create a mount target and tags on an existing file system

The following permissions policy grants the user permissions to create mount targets and tags on a particular file system in the us-west-2 Region. To create mount targets, permissions for specific Amazon EC2 actions are also required and are included in the permissions policy.

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Sid" : "Stmt1CreateMountTargetAndTag",  
            "Effect": "Allow",  
            "Action": [  
                "elasticfilesystem>CreateMountTarget",  
                "elasticfilesystem>DescribeMountTargets",  
                "elasticfilesystem>CreateTags",  
                "elasticfilesystem>DescribeTags"  
            ]  
        }  
    ]  
}
```

```

        ],
        "Resource": "arn:aws:elasticfilesystem:us-west-2:123456789012:file-system/file-
system-ID"
    },
    {
        "Sid" : "Stmt2AdditionalEC2PermissionsToCreateMountTarget",
        "Effect": "Allow",
        "Action": [
            "ec2:DescribeSubnets",
            "ec2:CreateNetworkInterface",
            "ec2:DescribeNetworkInterfaces"
        ],
        "Resource": "*"
    }
]
}

```

Example 2: Allow a user to perform all Amazon EFS actions

The following permissions policy uses a wild card character ("elasticfilesystem:*") to allow all Amazon EFS actions in the us-west-2 Region. Because some of the Amazon EFS actions also require permissions for Amazon EC2 actions, the policy also grants permissions for all those actions.

```

{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid" : "Stmt1PermissionForAllEFSActions",
            "Effect": "Allow",
            "Action": "elasticfilesystem:*",
            "Resource": "arn:aws:elasticfilesystem:us-west-2:123456789012:file-system/*"
        },
        {
            "Sid" : "Stmt2RequiredEC2PermissionsForAllEFSActions",
            "Effect": "Allow",
            "Action": [
                "ec2:DescribeSubnets",
                "ec2:CreateNetworkInterface",
                "ec2:DescribeNetworkInterfaces",
                "ec2:DeleteNetworkInterface",
                "ec2:ModifyNetworkInterfaceAttribute",
                "ec2:DescribeNetworkInterfaceAttribute"
            ],
            "Resource": "*"
        }
    ]
}

```

Amazon EFS API permissions: actions, resources, and conditions reference

When you are setting up [Access control \(p. 197\)](#) and writing a permissions policy that you can attach to an IAM identity (identity-based policies), you can use the following list as a reference. The list includes each Amazon EFS API operation, the corresponding actions for which you can grant permissions to perform the action, and the AWS resource for which you can grant the permissions. You specify the actions in the policy's Action field, and you specify the resource value in the policy's Resource field.

You can use AWS-wide condition keys in your Amazon EFS policies to express conditions. For a complete list of AWS-wide keys, see [Available Keys](#) in the *IAM User Guide*.

Note

To specify an action, use the `elasticfilesystem:` prefix followed by the API operation name (for example, `elasticfilesystem:CreateFileSystem`).

Amazon EFS API and Required Permissions for Actions

[CreateFileSystem \(p. 262\)](#)

Action or Actions: `elasticfilesystem:CreateFileSystem`

Resource: `arn:aws:elasticfilesystem:region:account-id:file-system/*`

[CreateMountTarget \(p. 272\)](#)

Action or Actions: `elasticfilesystem:CreateMountTarget, ec2:DescribeSubnets, ec2:DescribeNetworkInterfaces, ec2:CreateNetworkInterface`

Resource: `arn:aws:elasticfilesystem:region:account-id:file-system/file-system-id`

[CreateTags \(p. 285\)](#)

Action or Actions: `elasticfilesystem:CreateTags`

Resource: `arn:aws:elasticfilesystem:region:account-id:file-system/file-system-id`

[DeleteFileSystem \(p. 289\)](#)

Action or Actions: `elasticfilesystem:DeleteFileSystem`

Resource: `arn:aws:elasticfilesystem:region:account-id:file-system/file-system-id`

[DeleteMountTarget \(p. 294\)](#)

Action or Actions: `elasticfilesystem:DeleteMountTarget, ec2:DeleteNetworkInterface`

Resource: `arn:aws:elasticfilesystem:region:account-id:file-system/file-system-id`

[DeleteTags \(p. 299\)](#)

Action or Actions: `elasticfilesystem:DeleteTags`

Resource: `arn:aws:elasticfilesystem:region:account-id:file-system/file-system-id`

[DescribeFileSystems \(p. 311\)](#)

Action or Actions: `elasticfilesystem:DescribeFileSystems`

Resource: `arn:aws:elasticfilesystem:region:account-id:file-system/file-system-id, arn:aws:elasticfilesystem:region:account-id:file-system/*`

[DescribeLifecycleConfiguration \(p. 315\)](#)

Action or Actions: `elasticfilesystem:DescribeLifecycleConfiguration`

Resource: `arn:aws:elasticfilesystem:region:account-id:file-system/file-system-id`

[DescribeMountTargetSecurityGroups \(p. 322\)](#)

Action or Actions: `elasticfilesystem:DescribeMountTargetSecurityGroups, ec2:DescribeNetworkInterfaceAttribute`

Resource: arn:aws:elasticfilesystem:*region:account-id:file-system/file-system-id*

[DescribeMountTargets](#) (p. 318)

Action or Actions: elasticfilesystem:DescribeMountTargets

Resource: arn:aws:elasticfilesystem:*region:account-id:file-system/file-system-id*

[DescribeTags](#) (p. 328)

Action or Actions: elasticfilesystem:DescribeTags

Resource: arn:aws:elasticfilesystem:*region:account-id:file-system/file-system-id*

[ModifyMountTargetSecurityGroups](#) (p. 334)

Action or Actions: elasticfilesystem:ModifyMountTargetSecurityGroups,
ec2:ModifyNetworkInterfaceAttribute

Resource: arn:aws:elasticfilesystem:*region:account-id:file-system/file-system-id*

[PutFileSystemPolicy](#) (p. 341)

Action or Actions: elasticfilesystem:PutFileSystemPolicy

Resource: arn:aws:elasticfilesystem:*region:account-id:file-system/file-system-id*

[PutLifecycleConfiguration](#) (p. 345)

Action or Actions: elasticfilesystem:PutLifecycleConfiguration

Resource: arn:aws:elasticfilesystem:*region:account-id:file-system/file-system-id*

[TagResource](#) (p. 350)

Action or Actions: elasticfilesystem:TagResource

Resource: arn:aws:elasticfilesystem:*region:account-id:file-system/file-system-id*

[UntagResource](#) (p. 353)

Action or Actions: elasticfilesystem:UntagResource

Resource: arn:aws:elasticfilesystem:*region:account-id:file-system/file-system-id*

[UpdateFileSystem](#) (p. 355)

Action or Actions: elasticfilesystem:UpdateFileSystem,
elasticfilesystem:UpdateFileSystem

Resource: arn:aws:elasticfilesystem:*region:account-id:file-system/file-system-id*

Using IAM to control file system data access

You can use both IAM identity policies and resource policies to control client access to Amazon EFS resources in a way that is scalable and optimized for cloud environments. Using IAM, you can permit

clients to perform specific actions on a file system, including read-only, write, and root access. An "allow" permission on an action in *either* an IAM identity policy *or* a file system resource policy allows access for that action. The permission does not need to be granted in *both* an identity *and* a resource policy.

NFS clients can identify themselves using an IAM role when connecting to an EFS file system. When a client connects to a file system, Amazon EFS evaluates the file system's IAM resource policy, which is called a file system policy, along with any identity-based IAM policies to determine the appropriate file system access permissions to grant.

When you use IAM authorization for NFS clients, client connections and IAM authorization decisions are logged to AWS CloudTrail. For more information about how to log Amazon EFS API calls with CloudTrail, see [Logging Amazon EFS API Calls with AWS CloudTrail \(p. 122\)](#).

Important

You must use the EFS mount helper to mount your Amazon EFS file systems in order to use IAM authorization to control client access. For more information, see [Mounting with IAM authorization \(p. 78\)](#).

Default EFS file system policy

The default EFS file system policy does not use IAM to authenticate, and grants full access to any anonymous client that can connect to the file system using a mount target. The default policy is in effect whenever a user-configured file system policy is not in effect, including at file system creation. Whenever the default file system policy is in effect, a [DescribeFileSystemPolicy \(p. 308\)](#) API operation returns a PolicyNotFound response.

EFS actions for clients

You can specify the following actions for clients accessing a file system using a file system policy.

Action	Description
elasticfilesystem:ClientMount	Provides read-only access to a file system.
elasticfilesystem:ClientWrite	Provides write permissions on a file system.
elasticfilesystem:ClientRoot	Provides use of the root user when accessing a file system.

EFS condition keys for clients

To express conditions, you use predefined condition keys. Amazon EFS has the following predefined condition keys for NFS clients.

EFS Condition Key	Description	Operator
aws:SecureTransport	Use this key to require clients to use TLS when connecting to an EFS file system.	Boolean
elasticfilesystem:AccessPointARN	ARN of the EFS access point to which the client is connecting.	String
elasticfilesystem:AccessedMountTargets	Use this key to prevent access to an EFS file system by clients that are not using file system mount targets.	Boolean

File system policy examples

In this section, you can find example file system policies that grant or deny permissions for various Amazon EFS actions. Amazon EFS file system policies have a 20,000 character limit. For information about the elements of a resource-based policy, see [Specifying policy elements: actions, effects, and principals \(p. 200\)](#).

Important

If you grant permission to an individual IAM user or role in a file system policy, don't delete or recreate that user or role while the policy is in effect on the file system. If this happens, that user or role is effectively locked out from file system and will not be able to access it. For more information, see [Specifying a Principal](#) in the *IAM User Guide*.

For information about how to create a file system policy, see [Creating file system policies \(p. 45\)](#).

Example 1: Grant read and write access to a specific AWS role

This example EFS file system policy has the following characteristics:

- The effect is Allow.
- The principal is set to the Testing_Role in the AWS account.
- The action is set to ClientMount (read), and ClientWrite.
- The condition for granting permissions is set to AccessedViaMountTarget.

```
{  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Principal": {  
                "AWS": "arn:aws:iam::111122223333:role/Testing_Role"  
            },  
            "Action": [  
                "elasticfilesystem:ClientWrite",  
                "elasticfilesystem:ClientMount"  
            ],  
            "Resource": "arn:aws:elasticfilesystem:us-east-2:111122223333:file-system/  
fs-1234abcd",  
            "Condition": {  
                "Bool": {  
                    "elasticfilesystem:AccessedViaMountTarget": "true"  
                }  
            }  
        }  
    ]  
}
```

Example 2: Grant read-only access

The following file system policy only grants ClientMount, or read-only, permissions to the EfsReadOnly IAM role.

```
{  
    "Id": "read-only-example-policy02",  
    "Statement": [  
        {  
            "Sid": "efs-statement-example02",  
            "Effect": "Allow",  
            "Principal": {  
                "AWS": "arn:aws:iam::111122223333:role/EfsReadOnly"  
            }  
        }  
    ]  
}
```

```

        },
        "Action": [
            "elasticfilesystem:ClientMount"
        ],
        "Resource": "arn:aws:elasticfilesystem:us-east-2:111122223333:file-system/
fs-12345678"
    }
}

```

To learn how to set additional file system policies, including denying root access to all IAM principals, except for a specific management workstation, see [Walkthrough: Enable root squashing using IAM authorization for NFS clients \(p. 186\)](#).

Example 3: Grant access to an EFS Access Point

You use an EFS access policy to provide an NFS client with an application-specific view into shared file-based datasets on an EFS file system. You grant the access point permissions on the file system using a file system policy. This file policy example uses a condition element to grant a specific access point that is identified by its ARN full access to the file system. For more information about using EFS access points, see [Working with Amazon EFS access points \(p. 224\)](#).

```

{
    "Id": "access-point-example03",
    "Statement": [
        {
            "Sid": "access-point-statement-example03",
            "Effect": "Allow",
            "Principal": {"AWS": "arn:aws:iam::555555555555:role/
EfsAccessPointFullAccess"},
            "Action": "elasticfilesystem:Client*",
            "Resource": "arn:aws:elasticfilesystem:us-east-2:111122223333:file-system/
fs-12345678",
            "Condition": {
                "StringEquals": {
                    "elasticfilesystem:AccessPointArn": "arn:aws:elasticfilesystem:us-
east-2:555555555555:access-point/fsap-12345678" }
            }
        }
    ]
}

```

Using IAM to enforce creating encrypted file systems

You can create an AWS Identity and Access Management (IAM) identity-based policy to control whether users can create Amazon EFS file systems that are encrypted at rest. The Boolean condition key `elasticfilesystem:Encrypted` specifies the type of file system, encrypted or unencrypted, that the policy applies to. You use the condition key with the `elasticfilesystem>CreateFileSystem` action and the policy effect, allow or deny, to create a policy for creating encrypted or unencrypted file systems.

For example, an IAM policy that explicitly *allows* users to create only encrypted EFS file systems uses the following combination of effect, action, and condition:

- The Effect is Allow.
- The Action is `elasticfilesystem>CreateFileSystem`.
- The Condition `elasticfilesystem:Encrypted` is True.

The following example illustrates an IAM identity-based policy that authorizes principals to create only encrypted file systems.

```
{
  "Statement": [
    {
      "Effect": "Allow",
      "Action": "elasticfilesystem>CreateFileSystem",
      "Condition": {
        "Bool": {
          "elasticfilesystem:Encrypted": "true"
        }
      },
      "Resource": "*"
    }
  ]
}
```

If this policy is attached to a user who tries to create an unencrypted file system, the request fails. The user sees a message similar to the following, whether they are using the AWS Management Console, the AWS CLI, or the AWS API or SDK:

```
User: arn:aws:iam::111122223333:user/username is not authorized to
perform: elasticfilesystem>CreateFileSystem on the specified resource.
```

An IAM policy that explicitly *allows* creating only unencrypted EFS file systems can use the following combination of effect, action, and condition:

- The Effect is Allow.
- The Action is elasticfilesystem>CreateFileSystem.
- The Condition elasticfilesystem:Encrypted is False.

The following example illustrates an IAM identity-based policy that authorizes principals to create only unencrypted file systems.

```
{
  "Statement": [
    {
      "Effect": "Allow",
      "Action": "elasticfilesystem>CreateFileSystem",
      "Condition": {
        "Bool": {
          "elasticfilesystem:Encrypted": "false"
        }
      },
      "Resource": "*"
    }
  ]
}
```

If this policy is attached to a user who tries to create an encrypted file system, the request fails. The user sees a message similar to the following, whether they are using the AWS Management Console, the AWS CLI, or the AWS API or SDK:

```
User: arn:aws:iam::111122223333:user/username is not authorized to
perform: elasticfilesystem>CreateFileSystem on the specified resource.
```

You can also use policies like the previous examples in an AWS Organizations service control policy (SCP) to enforce the creation of encrypted Amazon EFS file systems for all AWS accounts in your organization.

For more information about service control policies in AWS Organizations, see [Service control policies](#) in the *AWS Organizations User Guide*.

Create an IAM policy that authorizes users to create only encrypted efs file systems

You can create an IAM identity-based policy that authorizes users to create only encrypted Amazon EFS file systems using the console, the AWS CLI, and the API. The following procedure describes how to create such a policy using the IAM console, and then apply the policy to a user in your account.

To create an IAM policy to enforce creating encrypted EFS file systems

1. Sign in to the AWS Management Console and open the IAM console at <https://console.aws.amazon.com/iam/>.
2. In the navigation pane, under **Access management**, choose **Policies**.
3. Choose **Create policy** to display the **Create policy** page.
4. Enter the following information using the **Visual editor**:
 - For **Service**, choose **EFS**.
 - For **Actions**, enter **create** in the search field, and then choose **CreateFileSystem**.
 - For **Request conditions**, choose **Encrypted**.
5. Choose **Review policy** to display the **Review policy** page.
6. Provide a **Name** and a **Description** for the policy. Verify the policy summary, including the **Encrypted** request condition. Choose **Create policy** to create the policy.

To apply the policy to a user in your account

1. In the IAM console, under **Access management**, choose **Users**.
2. Select the user that you want to apply the policy to.
3. Choose **Add permissions** to display the **Add permissions** page.
4. Choose **Attach existing policies directly**.
5. Enter the name of the EFS policy that you created in the previous procedure.
6. Select and expand the policy. Then choose **{JSON}** to verify the policy content. It should look like the following JSON policy.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "VisualEditor0",
            "Effect": "Allow",
            "Action": "elasticfilesystem>CreateFileSystem",
            "Condition": {
                "Bool": {
                    "elasticfilesystem:Encrypted": "true"
                }
            },
            "Resource": "*"
        }
    ]
}
```

7. Choose **Next: Review**.
8. Choose **Add permissions** to apply the policy to the user. This user can now only create Amazon EFS file systems that are encrypted at rest.

Blocking public access

The Amazon EFS block public access feature provides settings to help you manage public access to Amazon EFS file systems. By default, new Amazon EFS file systems don't allow public access. However, you can modify file system policies to allow public access.

Topics

- Blocking public access with AWS Transfer Family (p. 212)
 - The meaning of "public" (p. 212)

Blocking public access with AWS Transfer Family

When you use Amazon EFS with AWS Transfer Family, file system access requests received from a Transfer Family server that is owned by a different account than the file system are blocked if the file system allows public access. Amazon EFS evaluates the file system's IAM policies, and if the policy is public, it blocks the request. To permit AWS Transfer Family access to your file system, update your file system policy so that it is not considered public.

Note

Using Transfer Family with Amazon EFS is disabled by default for AWS accounts that have EFS file systems with policies that allow public access that were created before January 6, 2021. To enable using Transfer Family to access your file system, contact AWS Support.

The meaning of "public"

When evaluating whether a file system allows public access, Amazon EFS assumes that the file system policy is public. It then evaluates the file system policy to determine if it qualifies as non-public. To be considered non-public, a file system policy must grant access only to fixed values (values that don't contain a wild card) of one or more of the following:

- A set of Classless Inter-Domain Routings (CIDRs), using aws:SourceIp. For more information about CIDR, see [RFC 4632](#) on the RFC Editor website.
 - An AWS principal, user, role, or service principal (for example, aws:PrincipalOrgID)
 - aws:SourceArn
 - aws:SourceVpc
 - aws:SourceVpce
 - aws:SourceOwner
 - aws:SourceAccount
 - elasticfilesystem:AccessedViaMountTarget
 - aws:userid, outside the pattern "AROLEID:*

Under these rules, the following example policy is considered public.

```
{
    "Version": "2012-10-17",
    "Id": "efs-policy-wizard-15ad9567-2546-4bbb-8168-5541b6fc0e55",
    "Statement": [
        {
            "Sid": "efs-statement-14a7191c-9401-40e7-a388-6af6cfb7dd9c",
            "Effect": "Allow",
            "Principal": {
                "AWS": "*"
            },
            "Action": [
```

```
        "elasticfilesystem:ClientMount",
        "elasticfilesystem:ClientWrite",
        "elasticfilesystem:ClientRootAccess"
    ]
}
}
```

You can make this file system policy non-public by using the EFS condition key `elasticfilesystem:AccessedViaMountTarget` set to true. You can use `elasticfilesystem:AccessedViaMountTarget` to allow the specified EFS actions to clients accessing the EFS file system using a file system mount target. The following non-public policy uses the `elasticfilesystem:AccessedViaMountTarget` condition key set to true.

```
{
    "Version": "2012-10-17",
    "Id": "efs-policy-wizard-15ad9567-2546-4bbb-8168-5541b6fc0e55",
    "Statement": [
        {
            "Sid": "efs-statement-14a7191c-9401-40e7-a388-6af6cfb7dd9c",
            "Effect": "Allow",
            "Principal": {
                "AWS": "*"
            },
            "Action": [
                "elasticfilesystem:ClientMount",
                "elasticfilesystem:ClientWrite",
                "elasticfilesystem:ClientRootAccess"
            ],
            "Condition": {
                "Bool": {
                    "elasticfilesystem:AccessedViaMountTarget": "true"
                }
            }
        }
    ]
}
```

For more information about Amazon EFS condition keys, see [EFS condition keys for clients \(p. 207\)](#). For more information about creating file system policies, see [Creating file system policies \(p. 45\)](#).

Using tags with Amazon EFS

You can use tags to control access to Amazon EFS resources and to implement attribute-based access control (ABAC). To apply tags to Amazon EFS resources during creation, users must have certain AWS Identity and Access Management (IAM) permissions.

Tagging resources during creation

With some resource-creating Amazon EFS API actions, you can specify tags when you create the resource. You can use these resource tags to implement attribute-based access control (ABAC). For more information, see [What is ABAC for AWS?](#) in the *IAM User Guide*.

You can tag resources on creation using the action that creates the resource, such as `elasticfilesystem>CreateFileSystem` and `elasticfilesystem>CreateAccessPoint`. If tags are specified in the resource-creating action, IAM performs additional authorization on the `elasticfilesystem:TagResource` action to verify if users have permissions to create tags. Therefore, users must also have explicit permissions to use the `elasticfilesystem:TagResource` action.

Note

EFS replication does not support using tags for attribute-based access control (ABAC).

Using tags to control access to your Amazon EFS resources

To control access to Amazon EFS resources and actions, you can use IAM policies based on tags. You can provide this control in two ways:

- You can control access to Amazon EFS resources based on the tags on those resources.
- You can control which tags can be passed in an IAM request condition.

For information about how to use tags to control access to AWS resources, see [Controlling access using tags](#) in the *IAM User Guide*. For more information about tagging Amazon FSx resources at creation, see [Tagging resources during creation \(p. 213\)](#). For more information about tagging resources, see [Tag your resources \(p. 51\)](#).

Controlling access based on tags on a resource

To control which actions a user or role can perform on an Amazon FSx resource, you can use tags on the resource. For example, you might want to allow or deny specific API operations on a file system resource based on the key-value pair of the tag on the resource.

Example Example policy – Create a file system only when a specific tag is used

This policy allows the user to create a file system only when they tag it with a specific tag key-value pair, in this example, key=Department, value=Finance.

```
{  
    "Effect": "Allow",  
    "Action": [  
        "elasticfilesystem>CreateFileSystem",  
        "elasticfilesystem>TagResource"  
    ],  
    "Resource": "arn:aws:efs:region:account-id:file-system/*",  
    "Condition": {  
        "StringEquals": {  
            "aws:RequestTag/Department": "Finance"  
        }  
    }  
}
```

Example Example policy – Delete file systems with specific tags

This policy allows a user to delete only file systems that are tagged with Department=Finance.

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": [  
                "elasticfilesystem>DeleteFileSystem"  
            ],  
            "Resource": "arn:aws:efs:region:account-id:file-system/*",  
            "Condition": {  
                "StringEquals": {  
                    "aws:ResourceTag/Department": "Finance"  
                }  
            }  
        }  
    ]  
}
```

]
}

Using the Amazon EFS Service-Linked Role

Amazon Elastic File System uses an AWS Identity and Access Management (IAM) [service-linked role](#). The Amazon EFS service-linked role is a unique type of IAM role that is linked directly to Amazon EFS. The predefined Amazon EFS service-linked role includes permissions that the service requires to call other AWS services on your behalf.

A service-linked role makes setting up Amazon EFS easier because you don't have to manually add the necessary permissions. Amazon EFS defines the permissions of its service-linked role, and only Amazon EFS can assume its role. The defined permissions include the trust policy and the permissions policy, and that permissions policy can't be attached to any other IAM entity.

You can delete the Amazon EFS service-linked role only after first deleting your Amazon EFS file systems. This protects your Amazon EFS resources because you can't inadvertently remove permission to access the resources.

The service-linked role enables all API calls to be visible through AWS CloudTrail. This helps with monitoring and auditing requirements because you can track all actions that Amazon EFS performs on your behalf. For more information, see [Log Entries for EFS Service Linked Roles \(p. 124\)](#).

Service-Linked Role Permissions for Amazon EFS

Amazon EFS uses the service-linked role named `AWSServiceRoleForAmazonElasticFileSystem` to allow Amazon EFS to call and manage AWS resources on behalf of your EFS file systems.

The `AWSServiceRoleForAmazonElasticFileSystem` service-linked role trusts the following services to assume the role:

- `elasticfilesystem.amazonaws.com`

The role permissions policy allows Amazon EFS to complete the actions included in the policy definition JSON:

```
{  
    "Version": "2012-10-17",  
    "Statement": [  
        {  
            "Effect": "Allow",  
            "Action": [  
                "backup-storage:MountCapsule",  
                "ec2:CreateNetworkInterface",  
                "ec2:DeleteNetworkInterface",  
                "ec2:DescribeSecurityGroups",  
                "ec2:DescribeSubnets",  
                "ec2:DescribeNetworkInterfaceAttribute",  
                "ec2:ModifyNetworkInterfaceAttribute",  
                "tag:GetResources"  
            ],  
            "Resource": "*"  
        },  
        {  
            "Effect": "Allow",  
            "Action": [  
                "kms:DescribeKey"  
            ],  
            "Resource": "arn:aws:kms:*.*:key/*"  
        },  
    ]  
}
```

```
{  
    "Effect": "Allow",  
    "Action": [  
        "backup>CreateBackupVault",  
        "backup:PutBackupVaultAccessPolicy"  
    ],  
    "Resource": [  
        "arn:aws:backup:*:*:backup-vault:aws/efs/automatic-backup-vault"  
    ]  
},  
{  
    "Effect": "Allow",  
    "Action": [  
        "backup>CreateBackupPlan",  
        "backup>CreateBackupSelection"  
    ],  
    "Resource": [  
        "arn:aws:backup:*:*:backup-plan:/*"  
    ]  
},  
{  
    "Effect": "Allow",  
    "Action": [  
        "iam>CreateServiceLinkedRole"  
    ],  
    "Resource": "*",  
    "Condition": {  
        "StringEquals": {  
            "iam:AWSServiceName": [  
                "backup.amazonaws.com"  
            ]  
        }  
    }  
},  
{  
    "Effect": "Allow",  
    "Action": [  
        "iam:PassRole"  
    ],  
    "Resource": [  
        "arn:aws:iam::*:role/aws-service-role/backup.amazonaws.com/  
AWSServiceRoleForBackup"  
    ],  
    "Condition": {  
        "StringLike": {  
            "iam:PassedToService": "backup.amazonaws.com"  
        }  
    }  
},  
{  
    "Effect": "Allow",  
    "Action": [  
        "elasticfilesystem:DescribeFileSystems",  
        "elasticfilesystem>CreateReplicationConfiguration",  
        "elasticfilesystem:DescribeReplicationConfigurations",  
        "elasticfilesystem>DeleteReplicationConfiguration"  
    ],  
    "Resource": "*"  
}  
]
```

Note

You must manually configure IAM permissions for AWS KMS when creating a new Amazon EFS file system that is encrypted at rest. To learn more, see [Encrypting data at rest \(p. 190\)](#).

Creating a Service-Linked Role for Amazon EFS

You must configure permissions to allow an IAM entity (such as a user, group, or role) to create a service-linked role. Do this by adding the `iam:CreateServiceLinkedRole` permission to an IAM entity as shown in the following example.

```
{  
    "Action": "iam:CreateServiceLinkedRole",  
    "Effect": "Allow",  
    "Resource": "*",  
    "Condition": {  
        "StringEquals": {  
            "iam:AWSServiceName": [  
                "elasticfilesystem.amazonaws.com"  
            ]  
        }  
    }  
}
```

For more information, see [Service-Linked Role Permissions](#) in the *IAM User Guide*.

You don't need to manually create a service-linked role. When you create mount targets or a replication configuration for your EFS file system in the AWS Management Console, the AWS CLI, or the AWS API, Amazon EFS creates the service-linked role for you.

If you delete this service-linked role, and then need to create it again, you can use the same process to recreate the role in your account. When you create mount targets or a replication configuration for your EFS file system, Amazon EFS creates the service-linked role for you again.

Editing a Service-Linked Role for Amazon EFS

Amazon EFS doesn't allow you to edit the `AWSServiceRoleForAmazonElasticFileSystem` service-linked role. After you create a service-linked role, you cannot change the name of the role because various entities might reference the role. However, you can edit the description of the role using IAM. For more information, see [Editing a Service-Linked Role](#) in the *IAM User Guide*.

Deleting a Service-Linked Role for Amazon EFS

If you no longer need to use a feature or service that requires a service-linked role, we recommend that you delete that role. That way you don't have an unused entity that is not actively monitored or maintained. However, you must clean up the resources for your service-linked role before you can manually delete it.

Note

If the Amazon EFS service is using the role when you try to delete the resources, then the deletion might fail. If that happens, wait for a few minutes and try the operation again.

To delete Amazon EFS resources used by the `AWSServiceRoleForAmazonElasticFileSystem`

Complete the following steps to delete Amazon EFS resources used by the `AWSServiceRoleForAmazonElasticFileSystem`. For the detailed procedure, see [Step 4: Clean up resources and protect your AWS account \(p. 19\)](#).

1. On your Amazon EC2 instance, unmount the Amazon EFS file system.
2. Delete the Amazon EFS file system.
3. Delete the custom security group for the file system.

Warning

If you used the default security group for your virtual private cloud (VPC), **do not** delete that security group.

To manually delete the service-linked role using IAM

Use the IAM console, the AWS CLI, or the AWS API to delete the `AWSServiceRoleForAmazonElasticFileSystem` service-linked role. For more information, see [Deleting a Service-Linked Role](#) in the *IAM User Guide*.

Controlling network access to Amazon EFS file systems for NFS clients

You can control access by NFS clients to Amazon EFS file systems using network layer security and EFS file system policies. You can use the network layer security mechanisms available with Amazon EC2, such as VPC security group rules and network ACLs. You can also use AWS IAM to control NFS access with an EFS file system policy and identity-based policies.

Topics

- [Using VPC security groups for Amazon EC2 instances and mount targets \(p. 218\)](#)
- [Source ports for working with EFS \(p. 219\)](#)
- [Security considerations for network access \(p. 219\)](#)
- [Working with Interface VPC Endpoints in Amazon EFS \(p. 220\)](#)

Using VPC security groups for Amazon EC2 instances and mount targets

When using Amazon EFS, you specify Amazon EC2 security groups for your EC2 instances and security groups for the EFS mount targets associated with the file system. A security group acts as a firewall, and the rules that you add define the traffic flow. In the Getting Started exercise, you created one security group when you launched the EC2 instance. You then associated another with the EFS mount target (that is, the default security group for your default VPC). That approach works for the Getting Started exercise. However, for a production system, you should set up security groups with minimal permissions for use with EFS.

You can authorize inbound and outbound access to your EFS file system. To do so, you add rules that allow your EC2 instance to connect to your Amazon EFS file system through the mount target using the Network File System (NFS) port. Take the following steps to create and update your security groups.

To create security groups for EC2 instances and mount targets

1. Create two security groups in your VPC.

For instructions, see the procedure "To create a security group" in [Creating a Security Group](#) in the *Amazon VPC User Guide*.

2. Open the Amazon VPC Management Console at <https://console.aws.amazon.com/vpc/>, and verify the default rules for these security groups. Both security groups should have only an outbound rule that allows traffic to leave.

To update the necessary access for your security groups


1. Open the Amazon VPC console at <https://console.aws.amazon.com/vpc/>.
2. Add a rule for your EC2 security group to allow inbound access using Secure Shell (SSH) from any host. Optionally, restrict the **Source** address.

You don't need to add an outbound rule, because the default outbound rule allows all traffic to leave. If this were not the case, you'd need to add an outbound rule to open the TCP connection on the NFS port, identifying the mount target security group as the destination.



For instructions, see [Adding and Removing Rules](#) in the *Amazon VPC User Guide*.

3. Add a rule for the mount target security group to allow inbound access from the EC2 security group as shown following. The EC2 security group is identified as the source.



4. Verify that both security groups now authorize inbound and outbound access.

For more information about security groups, see [Security Groups for EC2-VPC](#) in the *Amazon EC2 User Guide for Linux Instances*.

Source ports for working with EFS

To support a broad set of NFS clients, Amazon EFS allows connections from any source port. If you require that only privileged users can access Amazon EFS, we recommend using the following client firewall rule. Connect to your file system using SSH and run the following command:

```
iptables -I OUTPUT 1 -m owner --uid-owner 1-4294967294 -m tcp -p tcp --dport 2049 -j DROP
```

This command inserts a new rule at the start of the OUTPUT chain (-I OUTPUT 1). The rule prevents any unprivileged, nonkernel process (-m owner --uid-owner 1-4294967294) from opening a connection to the NFS port (-m tcp -p tcp -dport 2049).

Security considerations for network access

An NFS version 4.1 (NFSv4.1) client can only mount a file system if it can make a network connection to the NFS port (TCP port 2049) of one of the file system's mount targets. Similarly, an NFSv4.1 client can only assert a user and group ID when accessing a file system if it can make this network connection.

Whether you can make this network connection is governed by a combination of the following:

- **Network isolation provided by the mount targets' VPC** – File system mount targets can't have public IP addresses associated with them. The only targets that can mount file systems are the following:
 - Amazon EC2 instances in the local Amazon VPC

- EC2 instances in connected VPCs
- On-premises servers connected to an Amazon VPC by using AWS Direct Connect and an AWS Virtual Private Network (VPN)
- **Network access control lists (ACLs) for the VPC subnets of the client and mount targets, for access from outside the mount target's subnets** – To mount a file system, the client must be able to make a TCP connection to the NFS port of a mount target and receive return traffic.
- **Rules of the client's and mount targets' VPC security groups, for all access** – For an EC2 instance to mount a file system, the following security group rules must be in effect:
 - The file system must have a mount target whose network interface has a security group with a rule that enables inbound connections on the NFS port from the instance. You can enable inbound connections either by IP address (CIDR range) or security group. The source of the security group rules for the inbound NFS port on mount target network interfaces is a key element of file system access control. Inbound rules other than the one for the NFS port, and any outbound rules, aren't used by network interfaces for file system mount targets.
 - The mounting instance must have a network interface with a security group rule that enables outbound connections to the NFS port on one of the file system's mount targets. You can enable outbound connections either by IP address (CIDR range) or security group.

For more information, see [Creating and managing mount targets and security groups \(p. 37\)](#).

Working with Interface VPC Endpoints in Amazon EFS

To establish a private connection between your virtual private cloud (VPC) and the Amazon EFS API, you can create an interface VPC endpoint. The endpoint provides secure connectivity to the Amazon EFS API without requiring an internet gateway, NAT instance, or virtual private network (VPN) connection. For more information, see [Interface VPC Endpoints](#) in the *Amazon VPC User Guide*.

Interface VPC endpoints are powered by AWS PrivateLink, a feature that enables private communication between AWS services using private IP addresses. To use AWS PrivateLink, create an interface VPC endpoint for Amazon EFS in your VPC using the Amazon VPC console, API, or CLI. Doing this creates an elastic network interface in your subnet with a private IP address that serves Amazon EFS API requests. You can also access a VPC endpoint from on-premises environments or from other VPCs using AWS VPN, AWS Direct Connect, or VPC peering. To learn more, see [Accessing Services Through AWS PrivateLink](#) in the *Amazon VPC User Guide*.

Creating an Interface Endpoint for Amazon EFS

To create an interface VPC endpoint for Amazon EFS, use one of the following:

- `com.amazonaws.region.elasticfilesystem` – Creates an endpoint for Amazon EFS API operations.
- `com.amazonaws.region.elasticfilesystem-fips` – Creates an endpoint for the Amazon EFS API that complies with [Federal Information Processing Standard \(FIPS\) 140-2](#).

For a complete list of Amazon EFS endpoints, see [Amazon Elastic File System](#) in the *Amazon Web Services General Reference*.

For more information about how to create an interface endpoint, see [Creating an Interface Endpoint](#) in the *Amazon VPC User Guide*.

Creating a VPC Endpoint Policy for Amazon EFS

To control access to the Amazon EFS API, you can attach an AWS Identity and Access Management (IAM) policy to your VPC endpoint. The policy specifies the following:

- The principal that can perform actions.
- The actions that can be performed.
- The resources on which actions can be performed.

For more information, see [Controlling Access to Services with VPC Endpoints](#) in the *Amazon VPC User Guide*.

The following example shows a VPC endpoint policy that denies everyone permission to create an EFS file system through the endpoint. The example policy also grants everyone permission to perform all other actions.

```
{  
    "Statement": [  
        {  
            "Action": "*",
            "Effect": "Allow",
            "Resource": "*",
            "Principal": "*"
        },
        {
            "Action": "elasticfilesystem>CreateFileSystem",
            "Effect": "Deny",
            "Resource": "*",
            "Principal": "*"
        }
    ]
}
```

For more information, see [Using VPC Endpoint Policies](#) in the *Amazon VPC User Guide*.

Working with users, groups, and permissions at the Network File System (NFS) Level

Topics

- [File and directory permissions \(p. 222\)](#)
- [Example Amazon EFS file system use cases and permissions \(p. 222\)](#)
- [User and Group ID Permissions for Files and Directories Within a File System \(p. 223\)](#)
- [No root squashing \(p. 224\)](#)
- [Permissions caching \(p. 224\)](#)
- [Changing file system object ownership \(p. 224\)](#)
- [EFS access points \(p. 224\)](#)

After creating a file system, by default only the root user (UID 0) has read, write, and execute permissions. For other users to modify the file system, the root user must explicitly grant them access. You can use access points to automate the creation of directories that a nonroot user can write from. For more information, see [Working with Amazon EFS access points \(p. 224\)](#).

Amazon EFS file system objects have a Unix-style mode associated with them. This mode value defines the permissions for performing actions on that object. Users familiar with Unix-style systems can easily understand how Amazon EFS behaves with respect to these permissions.

Additionally, on Unix-style systems, users and groups are mapped to numeric identifiers, which Amazon EFS uses to represent file ownership. For Amazon EFS, file system objects (that is, files, directories, and so

on) are owned by a single owner and a single group. Amazon EFS uses the mapped numeric IDs to check permissions when a user attempts to access a file system object.

Following, you can find examples of permissions and a discussion about NFS permissions considerations for Amazon EFS.

File and directory permissions

Files and directories in an EFS file system support standard Unix-style read, write, and execute permissions based on the user and group ID asserted by the mounting NFSv4.1 client, unless overridden by an EFS access point. For more information, see [Working with users, groups, and permissions at the Network File System \(NFS\) Level \(p. 221\)](#).

Note

By default, this layer of access control depends on trusting the NFSv4.1 client in its assertion of the user and group ID. You can use AWS Identity and Access Management (IAM) resource-based policies and identity policies to authorize NFS clients and provide read-only, write, and root access permissions. You can use EFS access points to override the operating system user and group identity information provided by the NFS client. For more information, see [Using IAM to control file system data access \(p. 206\)](#) and [Creating and deleting access points \(p. 47\)](#).

As an example of read, write, and execute permissions for files and directories, Alice might have permissions to read and write to any files that she wants to in her personal directory on a file system, /alice. However, in this example Alice is not allowed to read or write to any files in Mark's personal directory on the same file system, /mark. Both Alice and Mark are allowed to read but not write files in the shared directory /share.

Example Amazon EFS file system use cases and permissions

After you create an Amazon EFS file system and mount targets for the file system in your VPC, you can mount the remote file system locally on your Amazon EC2 instance. The `mount` command can mount any directory in the file system. However, when you first create the file system, there is only one root directory at /.

The following mount command mounts the root directory of an Amazon EFS file system, identified by the file system DNS name, on the /efs-mount-point local directory.

```
sudo mount -t nfs -o
nfsvers=4.1,rsize=1048576,wsize=1048576,hard,timeo=600,retrans=2,noresvport file-system-id.efs.aws-region.amazonaws.com:/ efs-mount-point
```

The root user and root group own the mounted directory.

```
[ec2-user@ip-172-31-43-70 efs]$ ls -al
total 8
drwxr-xr-x 2 root      root      6144 Aug 29  2016 .
drwx----- 5 ec2-user   ec2-user  4096 May  1 21:44 ..
[ec2-user@ip-172-31-43-70 efs]$
```

The initial permissions mode allows:

- read-write-execute permissions to the owner *root*
- read-execute permissions to the group *root*
- read-execute permissions to others

Only the root user can modify this directory. The root user can also grant other users permissions to write to this directory, for example:

- Create writable per-user subdirectories. For step-by-step instructions, see [Walkthrough: Create Writable Per-User Subdirectories and Configure Automatic Remounting on Reboot \(p. 172\)](#).
- Allow users to write to the Amazon EFS file system root. A user with root privileges can grant other users access to the file system.
 - To change the Amazon EFS file system ownership to a non-root user and group, use the following:

```
$ sudo chown user:group /EFSroot
```

- To change permissions of the file system to something more permissive, use the following:

```
$ sudo chmod 777 /EFSroot
```

This command grants read-write-execute privileges to all users on all EC2 instances that have the file system mounted.

User and Group ID Permissions for Files and Directories Within a File System

Files and directories in an Amazon EFS file system support standard Unix-style read, write, and execute permissions based on the user ID and group IDs. When an NFS client mounts an EFS file system without using an access point, the user ID and group ID provided by the client is trusted. You can use EFS access points to override user ID and group IDs used by the NFS client. When users attempt to access files and directories, Amazon EFS checks their user IDs and group IDs to verify that each user has permission to access the objects. Amazon EFS also uses these IDs to indicate the owner and group owner for new files and directories that the user creates. Amazon EFS doesn't examine user or group names—it only uses the numeric identifiers.

Note

When you create a user on an EC2 instance, you can assign any numeric user ID (UID) and group ID (GID) to the user. The numeric user IDs are set in the `/etc/passwd` file on Linux systems. The numeric group IDs are in the `/etc/group` file. These files define the mappings between names and IDs. Outside of the EC2 instance, Amazon EFS doesn't perform any authentication of these IDs, including the root ID of 0.

If a user accesses an Amazon EFS file system from two different EC2 instances, depending on whether the UID for the user is the same or different on those instances you see different behavior, as follows:

- If the user IDs are the same on both EC2 instances, Amazon EFS considers them to indicate the same user, regardless of the EC2 instance used. The user experience when accessing the file system is the same from both EC2 instances.
- If the user IDs aren't the same on both EC2 instances, Amazon EFS considers the users to be different users. The user experience isn't the same when accessing the Amazon EFS file system from the two different EC2 instances.
- If two different users on different EC2 instances share an ID, Amazon EFS considers them to be the same user.

You might consider managing user ID mappings across EC2 instances consistently. Users can check their numeric ID using the `id` command, as shown following.

```
$ id
```

```
uid=502(joe) gid=502(joe) groups=502(joe)
```

Turn Off the ID Mapper

The NFS utilities in the operating system include a daemon called an ID Mapper that manages mapping between user names and IDs. In Amazon Linux, the daemon is called `rpc.idmapd` and on Ubuntu is called `idmapd`. It translates user and group IDs into names, and vice versa. However, Amazon EFS deals only with numeric IDs. We recommend that you turn this process off on your EC2 instances. On Amazon Linux, the ID mapper is usually disabled, and if it is don't enable it. To turn off the ID mapper, use the commands shown following.

```
$ service rpcidmapd status  
$ sudo service rpcidmapd stop
```

No root squashing

By default, root squashing is disabled on EFS file systems. Amazon EFS behaves like a Linux NFS server with `no_root_squash`. If a user or group ID is 0, Amazon EFS treats that user as the `root` user, and bypasses permissions checks (allowing access and modification to all file system objects). Root squashing can be enabled on a client connection when the AWS Identity and Access Management (AWS IAM) identity or resource policy does not allow access to the `ClientRootAccess` action. When root squashing is enabled, the `root` user is converted to a user with limited permissions on the NFS server.

For more information, see [Using IAM to control file system data access \(p. 206\)](#) and [Walkthrough: Enable root squashing using IAM authorization for NFS clients \(p. 186\)](#).

Permissions caching

Amazon EFS caches file permissions for a small time period. As a result, there might be a brief window where a user whose access was revoked recently can still access that object.

Changing file system object ownership

Amazon EFS enforces the POSIX `chown_restricted` attribute. This means only the `root` user can change the owner of a file system object. The `root` or the owner user can change the owner group of a file system object. However, unless the user is `root`, the group can only be changed to one that the owner user is a member of.

EFS access points

An *access point* applies an operating system user, group, and file system path to any file system request made using the access point. The access point's operating system user and group override any identity information provided by the NFS client. The file system path is exposed to the client as the access point's root directory. This approach ensures that each application always uses the correct operating system identity and the correct directory when accessing shared file-based datasets. Applications using the access point can only access data in its own directory and below. For more information about access points, see [Working with Amazon EFS access points \(p. 224\)](#).

Working with Amazon EFS access points

Amazon EFS *access points* are application-specific entry points into an EFS file system that make it easier to manage application access to shared datasets. Access points can enforce a user identity, including the user's POSIX groups, for all file system requests that are made through the access point. Access points

can also enforce a different root directory for the file system so that clients can only access data in the specified directory or its subdirectories.

You can use AWS Identity and Access Management (IAM) policies to enforce that specific applications use a specific access point. By combining IAM policies with access points, you can easily provide secure access to specific datasets for your applications.

Note

You need to create at least one mount target on your EFS file system to use access points.

For more information on creating an access point, see [Creating and deleting access points \(p. 47\)](#).

Topics

- [Creating an access point \(p. 225\)](#)
- [Mounting a file system using an access point \(p. 225\)](#)
- [Enforcing a user identity using an access point \(p. 225\)](#)
- [Enforcing a root directory with an access point \(p. 226\)](#)
- [Using access points in IAM policies \(p. 227\)](#)

Creating an access point

You can create access points for an existing Amazon EFS file system using the AWS Management Console, the AWS Command Line Interface (AWS CLI), and the EFS API. An Amazon EFS file system can have a [maximum of 120 access points \(p. 237\)](#). You cannot modify an existing access point after it's created.

For step-by-step procedures to create an access point, see [Creating and deleting access points \(p. 47\)](#).

Mounting a file system using an access point

You use the EFS mount helper when mounting a file system using an access point. In the mount command, include file system ID, the access point ID, and the `tls` mount option, as shown in the following example.

```
$ mount -t efs -o tls,iam,accesspoint=fsap-abcdef0123456789a fs-
abc0123def456789a: /localmountpoint
```

For more information on mounting file systems using an access point, see [Mounting with EFS access points \(p. 78\)](#).

Enforcing a user identity using an access point

You can use an access point to enforce user and group information for all file system requests made through the access point. To enable this feature, you need to specify the operating system identity to enforce when you create the access point.

As part of this, you provide the following:

- User ID – The numeric POSIX user ID for the user.
- Group ID – The numeric POSIX group ID for the user.
- Secondary group IDs – An optional list of secondary group IDs.

When user enforcement is enabled, Amazon EFS replaces the NFS client's user and group IDs with the identity configured on the access point for all file system operations. User enforcement also does the following:

- The owner and group for new files and directories are set to the user ID and group ID of the access point.
- EFS considers the user ID, group ID, and secondary group IDs of the access point when evaluating file system permissions. EFS ignores the NFS client's IDs.

Important

Enforcing a user identity is subject to the `ClientRootAccess` IAM permission.

For example, in some cases you might configure the access point user ID, group ID, or both to be root (that is, setting the UID, GID, or both to 0). In such cases, you must grant the `ClientRootAccess` IAM permission to the NFS client.

Enforcing a root directory with an access point

You can use an access point to override the root directory for a file system. When you enforce a root directory, the NFS client using the access point uses the root directory configured on the access point instead of the file system's root directory.

You enable this feature by setting the access point `Path` attribute when creating an access point. The `Path` attribute is the full path of the root directory of the file system for all file system requests made through this access point. The full path can't exceed 100 characters in length. It can include up to four subdirectories.

When you specify a root directory on an access point, it becomes the root directory of the file system for the NFS client mounting the access point. For example, suppose that the root directory of your access point is `/data`. In this case, mounting `fs-12345678:/` using the access point has the same effect as mounting `fs-12345678:/data` without using the access point.

When specifying a root directory in your access point, ensure that the directory permissions are configured to allow the user of the access point to successfully mount the file system. Specifically, make sure that the execute bit is set for the access point user or group, or for everyone. For example, a directory permission value of 755 allows the directory user owner to list files, create files, and mount, and all other users to list files and mount.

Creating the root directory for an access point

If a root directory path for an access point doesn't exist on the file system, Amazon EFS automatically creates that root directory with the ownership and permissions specified. Amazon EFS will not create the root directory if you do not specify the directory ownership and permissions at creation. This approach makes it possible to provision file system access for a specific user or application without mounting your file system from a Linux host. To create a root directory, you have to configure the root directory ownership and permission by using the following attributes when creating an access point:

- `OwnerUid` – The numeric POSIX user ID to use as the root directory owner.
- `OwnerGid` – The numeric POSIX group ID to use as the root directory owner group.
- `Permissions` – The Unix mode of the directory. A common configuration is 755. Ensure that the execute bit is set for the access point user so they are able to mount. This configuration gives the directory owner permission to enter, list, and write new files in the directory. It gives all other users permission to enter and list files. For more information on working with Unix file and directory modes, see [Working with users, groups, and permissions at the Network File System \(NFS\) Level \(p. 221\)](#).

Amazon EFS creates an access point root directory only if the `OwnUid`, `OwnGid`, and permissions are specified for the directory. If you do not provide this information, Amazon EFS does not create the root directory. If the root directory does not exist, attempts to mount using the access point will fail.

When you mount a file system with an access point, the root directory for the access point is created if the directory doesn't already exist, provided that the root directory's `OwnerUid` and `Permissions` were

specified when the access point was created. If the access point's root directory already exists before mount time, the existing permissions aren't overwritten by the access point. If you delete the root directory, EFS recreates it the next time that the file system is mounted using the access point.

Note

If you do not specify the ownership and permissions for an access point root directory, Amazon EFS will not create the root directory. All attempts to mount the access point will fail.

Security model for access point root directories

When a root directory override is in effect, Amazon EFS behaves like a Linux NFS server with the no_subtree_check option enabled.

In the NFS protocol, servers generate file handles that are used by clients as unique references when accessing files. EFS securely generates file handles that are unpredictable and specific to an EFS file system. When a root directory override is in place, EFS doesn't disclose file handles for files outside the specified root directory. However, in some cases a user might get a file handle for a file outside of their access point by using an out-of-band mechanism. For example, they might do so if they have access to a second access point. If they do this, they can perform read and write operations on the file.

File ownership and access permissions are always enforced, for access to files within and outside of a user's access point root directory.

Using access points in IAM policies

You can use an IAM policy to enforce that a specific NFS client, identified by its IAM role, can only access a specific access point. To do this, you use the elasticfilesystem:AccessPointArn IAM condition key. The AccessPointArn is the Amazon Resource Name (ARN) of the access point that the file system is mounted with.

Following is an example of a file system policy that allows the IAM role app1 to access the file system using access point fsap-01234567. The policy also allows app2 to use the file system using access point fsap-89abcdef.

```
{  
    "Version": "2012-10-17",  
    "Id": "MyFileSystemPolicy",  
    "Statement": [  
        {  
            "Sid": "App1Access",  
            "Effect": "Allow",  
            "Principal": { "AWS": "arn:aws:iam::111122223333:role/app1" },  
            "Action": [  
                "elasticfilesystem:ClientMount",  
                "elasticfilesystem:ClientWrite"  
            ],  
            "Condition": {  
                "StringEquals": {  
                    "elasticfilesystem:AccessPointArn" : "arn:aws:elasticfilesystem:us-east-1:222233334444:access-point/fsap-01234567"  
                }  
            }  
        },  
        {  
            "Sid": "App2Access",  
            "Effect": "Allow",  
            "Principal": { "AWS": "arn:aws:iam::111122223333:role/app2" },  
            "Action": [  
                "elasticfilesystem:ClientMount",  
                "elasticfilesystem:ClientWrite"  
            ],  
            "Condition": {  
                "StringEquals": {  
                    "elasticfilesystem:AccessPointArn" : "arn:aws:elasticfilesystem:us-east-1:222233334444:access-point/fsap-89abcdef"  
                }  
            }  
        }  
    ]  
}
```

```
        "Condition": {
            "StringEquals": {
                "elasticfilesystem:AccessPointArn" : "arn:aws:elasticfilesystem:us-
east-1:222233334444:access-point/fsap-89abcdef"
            }
        }
    ]
}
```

Logging and monitoring in Amazon EFS

Monitoring is an important part of maintaining the reliability, availability, and performance of Amazon EFS and your AWS solutions. You should collect monitoring data from all of the parts of your AWS solution so that you can more easily debug a multi-point failure if one occurs. AWS provides several tools for monitoring your Amazon EFS resources and responding to potential incidents:

Amazon CloudWatch alarms

Using Amazon CloudWatch events, you watch a single metric over a time period that you specify. If the metric exceeds a given threshold, a notification is sent to an Amazon Simple Notification Service (Amazon SNS) topic or Amazon EC2 Auto Scaling policy. CloudWatch events do not invoke actions simply because they are in a particular state; the state must have changed and been maintained for a specified number of periods. For more information, see [Monitoring Amazon EFS with Amazon CloudWatch \(p. 111\)](#).

Amazon CloudWatch Logs

You can use Amazon CloudWatch Logs to monitor, store, and access your log files from AWS CloudTrail or other sources. For more information, see [Monitoring Log Files in the Amazon CloudWatch User Guide](#).

Amazon CloudWatch Events

Match events and route them to one or more target functions or streams to make changes, capture state information, and take corrective action. For more information, see [What is Amazon CloudWatch Events in the Amazon CloudWatch User Guide](#).

AWS CloudTrail log monitoring

CloudTrail provides a record of actions taken by a user, role, or an AWS service in Amazon EFS. Using the information collected by CloudTrail, you can determine the request that was made to Amazon EFS, the IP address from which the request was made, who made the request, when it was made, and additional details. For more information, see [Logging Amazon EFS API Calls with AWS CloudTrail \(p. 122\)](#).

AWS managed policies for Amazon EFS

To add permissions to users, groups, and roles, it is easier to use AWS managed policies than to write policies yourself. It takes time and expertise to [create IAM customer managed policies](#) that provide your team with only the permissions they need. To get started quickly, you can use our AWS managed policies. These policies cover common use cases and are available in your AWS account. For more information about AWS managed policies, see [AWS managed policies in the IAM User Guide](#).

AWS services maintain and update AWS managed policies. You can't change the permissions in AWS managed policies. Services occasionally add additional permissions to an AWS managed policy to support new features. This type of update affects all identities (users, groups, and roles) where the policy is attached. Services are most likely to update an AWS managed policy when a new feature is launched.

or when new operations become available. Services do not remove permissions from an AWS managed policy, so policy updates won't break your existing permissions.

Additionally, AWS supports managed policies for job functions that span multiple services. For example, the `ViewOnlyAccess` AWS managed policy provides read-only access to many AWS services and resources. When a service launches a new feature, AWS adds read-only permissions for new operations and resources. For a list and descriptions of job function policies, see [AWS managed policies for job functions](#) in the *IAM User Guide*.

AWS managed policy: AmazonElasticFileSystemFullAccess

You can attach the `AmazonElasticFileSystemFullAccess` policy to your IAM identities.

This policy grants administrative permissions that allow full access to Amazon EFS and access to related AWS services via the AWS Management Console.

Permissions details

This policy includes the following permissions.

- **elasticfilesystem** – Allows principals to perform all actions in the Amazon EFS console. It also allows principals to create (`elasticfilesystem:Backup`) and restore (`elasticfilesystem:Restore`) backups using AWS Backup.
 - **cloudwatch** – Allows principals to describe Amazon CloudWatch file system metrics and alarms for a metric in the Amazon EFS console.
 - **ec2** – Allows principals to create, delete, and describe network interfaces, describe and modify network interface attributes, describe Availability Zones, security groups, subnets, virtual private clouds (VPCs) and VPC attributes associated with an Amazon EFS file system in the Amazon EFS console.
 - **kms** – Allows principals to list aliases for AWS Key Management Service (AWS KMS) keys and to describe KMS keys in the Amazon EFS console.
 - **iam** – Grants permission to create a service linked role that allows Amazon EFS to manage AWS resources on the user's behalf.

```
"elasticfilesystem>CreateMountTarget",
"elasticfilesystem>CreateTags",
"elasticfilesystem>CreateAccessPoint",
"elasticfilesystem>CreateReplicationConfiguration",
"elasticfilesystem>DeleteFileSystem",
"elasticfilesystem>DeleteMountTarget",
"elasticfilesystem>DeleteTags",
"elasticfilesystem>DeleteAccessPoint",
"elasticfilesystem>DeleteFileSystemPolicy",
"elasticfilesystem>DeleteReplicationConfiguration",
"elasticfilesystem>DescribeAccountPreferences",
"elasticfilesystem>DescribeBackupPolicy",
"elasticfilesystem>DescribeFileSystems",
"elasticfilesystem>DescribeFileSystemPolicy",
"elasticfilesystem>DescribeLifecycleConfiguration",
"elasticfilesystem>DescribeMountTargets",
"elasticfilesystem>DescribeMountTargetSecurityGroups",
"elasticfilesystem>DescribeReplicationConfigurations",
"elasticfilesystem>DescribeTags",
"elasticfilesystem>DescribeAccessPoints",
"elasticfilesystem>ModifyMountTargetSecurityGroups",
"elasticfilesystem>PutAccountPreferences",
"elasticfilesystem>PutBackupPolicy",
"elasticfilesystem>PutLifecycleConfiguration",
"elasticfilesystem>PutFileSystemPolicy",
"elasticfilesystem>UpdateFileSystem",
"elasticfilesystem>TagResource",
"elasticfilesystem>UntagResource",
"elasticfilesystem>ListTagsForResource",
"elasticfilesystem>Restore",
"kms>DescribeKey",
"kms>ListAliases"
],
"Effect": "Allow",
"Resource": "*"
},
{
"Action": "iam>CreateServiceLinkedRole",
"Effect": "Allow",
"Resource": "*",
"Condition": {
    "StringEquals": [
        "iam:AWSServiceName": [
            "elasticfilesystem.amazonaws.com"
        ]
    ]
}
}
]
}
```

AWS managed policy: AmazonElasticFileSystemReadOnlyAccess

You can attach the AmazonElasticFileSystemReadOnlyAccess policy to your IAM identities.

This policy grants read only access to Amazon EFS via the AWS Management Console.

Permissions details

This policy includes the following permissions.

- **elasticfilesystem** – Allows principals to describe attributes of Amazon EFS file systems, including account preferences, backup and file system policies, lifecycle configuration, mount targets and their security groups, tags, and access points in the Amazon EFS console.
- **cloudwatch** – Allows principals to retrieve CloudWatch metrics and describe alarms for metrics in the Amazon EFS console.
- **ec2** – Allows principals to view Availability Zones, network interfaces and their attributes, security groups, subnets, VPCs and their attributes in the Amazon EFS console.
- **kms** – Allows principals to list aliases for AWS KMS keys in the Amazon EFS console.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": [
                "cloudwatch:DescribeAlarmsForMetric",
                "cloudwatch:GetMetricData",
                "ec2:DescribeAvailabilityZones",
                "ec2:DescribeNetworkInterfaceAttribute",
                "ec2:DescribeNetworkInterfaces",
                "ec2:DescribeSecurityGroups",
                "ec2:DescribeSubnets",
                "ec2:DescribeVpcAttribute",
                "ec2:DescribeVpcs",
                "elasticfilesystem:DescribeAccountPreferences",
                "elasticfilesystem:DescribeBackupPolicy",
                "elasticfilesystem:DescribeFileSystems",
                "elasticfilesystem:DescribeFileSystemPolicy",
                "elasticfilesystem:DescribeLifecycleConfiguration",
                "elasticfilesystem:DescribeMountTargets",
                "elasticfilesystem:DescribeMountTargetSecurityGroups",
                "elasticfilesystem:DescribeTags",
                "elasticfilesystem:DescribeAccessPoints",
                "elasticfilesystem:DescribeReplicationConfigurations",
                "elasticfilesystem>ListTagsForResource",
                "kms>ListAliases"
            ],
            "Resource": "*"
        }
    ]
}
```

AWS managed policy: [AmazonElasticFileSystemClientReadWriteAccess](#)

You can attach the [AmazonElasticFileSystemClientReadWriteAccess](#) policy to an IAM entity.

This policy grants read and write client access to an Amazon EFS file system. This policy allows NFS clients to mount, read and write to Amazon EFS file systems.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": [
                "elasticfilesystem:ClientMount",

```

```

        "elasticfilesystem:ClientWrite",
        "elasticfilesystem:DescribeMountTargets"
    ],
    "Resource": "*"
}
]
}
}
```

Amazon EFS updates to AWS managed policies

View details about updates to AWS managed policies for Amazon EFS since this service began tracking these changes. For automatic alerts about changes to this page, subscribe to the RSS feed on the [Amazon EFS Document History \(p. 405\)](#) page.

Change	Description	Date
AmazonElasticFileSystemServiceRole – Update to an existing policy	<p>Amazon (EFS 2.15) added new permissions to allow principals to create, describe, and delete Amazon EFS replications, and to create Amazon EFS file systems.</p> <p>This is required so that Amazon EFS can manage files system replication configurations on the user's behalf.</p>	January 25, 2022
AmazonElasticFileSystemReadOnly – Update to an existing policy	<p>Amazon (EFS 2.0) added a new permission to allow principals to describe Amazon EFS replications.</p> <p>This is required so that users can view files system replication configurations.</p>	January 25, 2022
AmazonElasticFileSystemFullAccess – Update to an existing policy	<p>Amazon (EFS 2.0) added new permissions to allow principals to create, describe, and delete Amazon EFS replications.</p> <p>This is required so that users can manage files system replication configurations.</p>	January 25, 2022
AmazonElasticFileSystemClientRead – Started tracking policy	<p>Grants read and write privileges on Amazon EFS file systems to NFS clients.</p>	January 3, 2022
AmazonElasticFileSystemServiceRole – Started tracking policy	<p>The service (linked) role permissions for Amazon EFS.</p>	October 8, 2021
AmazonElasticFileSystemFullAccess – Update to an existing policy	<p>Amazon (EFS 2.0) added new permissions to allow principals to modify and describe Amazon EFS account preferences.</p> <p>This is required so that users can view and set account preferences settings in the Amazon EFS console.</p>	May 7, 2021
AmazonElasticFileSystemReadOnly – Update to an existing policy	<p>Amazon (EFS 2.0) added new permissions to allow principals to describe Amazon EFS account preferences.</p> <p>This is required so that users can view account preferences settings in the Amazon EFS console.</p>	May 7, 2021

Change	Description	Date
Amazon EFS started tracking changes	Amazon EFS started tracking changes for its AWS managed policies.	May 7, 2021

Compliance Validation for Amazon Elastic File System

Third-party auditors assess the security and compliance of Amazon Elastic File System as part of multiple AWS compliance programs. These include SOC, PCI, FedRAMP, HIPAA, DoD CC SRG, HITRUST CSF, OSPAR, CS, and ENS High.

For a list of AWS services in scope of specific compliance programs, see [AWS Services in Scope by Compliance Program](#). For general information, see [AWS Compliance Programs](#).

You can download third-party audit reports using AWS Artifact. For more information, see [Downloading Reports in AWS Artifact](#).

Your compliance responsibility when using EFS is determined by the sensitivity of your data, your company's compliance objectives, and applicable laws and regulations. AWS provides the following resources to help with compliance:

- [Security and Compliance Quick Start Guides](#) – These deployment guides discuss architectural considerations and provide steps for deploying security- and compliance-focused baseline environments on AWS.
- [Architecting for HIPAA Security and Compliance Whitepaper](#) – This whitepaper describes how companies can use AWS to create HIPAA-compliant applications.
- [AWS Compliance Resources](#) – This collection of workbooks and guides might apply to your industry and location.
- [Evaluating Resources with Rules](#) in the *AWS Config Developer Guide* – The AWS Config service assesses how well your resource configurations comply with internal practices, industry guidelines, and regulations.
- [AWS Security Hub](#) – This AWS service provides a comprehensive view of your security state within AWS that helps you check your compliance with security industry standards and best practices.

Resilience in Amazon Elastic File System

The AWS global infrastructure is built around AWS Regions and Availability Zones. AWS Regions provide multiple physically separated and isolated Availability Zones, which are connected with low-latency, high-throughput, and highly redundant networking. With Availability Zones, you can design and operate applications and databases that automatically fail over between zones without interruption. Availability Zones are more highly available, fault tolerant, and scalable than traditional single or multiple data center infrastructures.

Amazon EFS file systems are resilient to one or more Availability Zone failures within an AWS Region. Mount targets themselves are designed to be highly available. As you design for high availability and failover to other Availability Zones (AZs), keep in mind that while the IP addresses and DNS for your mount targets in each AZ are static, they are redundant components backed by multiple resources. For more information, see [How Amazon EFS works with Amazon EC2 and other supported compute instances \(p. 4\)](#).

For more information about AWS Regions and Availability Zones, see [AWS Global Infrastructure](#).

Amazon Elastic File System Network Isolation

As a managed service, Amazon Elastic File System is protected by the AWS global network security procedures described in the [Amazon Web Services: Overview of Security Processes](#) whitepaper.

Access to Amazon EFS by using the network is through AWS published APIs. Clients must support Transport Layer Security (TLS) 1.0. We recommend TLS 1.2. Clients must also support cipher suites with Perfect Forward Secrecy (PFS) such as Ephemeral Diffie-Hellman (DHE) or Elliptic Curve Ephemeral Diffie-Hellman (ECDHE). Most modern systems such as Java 7 and later support these modes. Additionally, requests must be signed by using either an access key ID and a secret access key that is associated with an IAM principal or the [AWS Security Token Service \(STS\)](#) to generate temporary security credentials to sign requests.

These APIs are callable from any network location, but Amazon EFS does support resource-based access policies which can include restrictions based on the source IP address. You can also use Amazon EFS policies to control access from specific Amazon Virtual Private Cloud (Amazon VPC) endpoints, or specific VPCs. Effectively, this isolates network access to a given Amazon EFS resource from only the specific VPC within the AWS network.

Amazon EFS quotas and limits

Following, you can find out about quotas when working with Amazon EFS.

Topics

- [Amazon EFS quotas that you can increase \(p. 235\)](#)
- [Amazon EFS resource quotas that you cannot change \(p. 237\)](#)
- [Quotas for NFS clients \(p. 237\)](#)
- [Quotas for Amazon EFS file systems \(p. 237\)](#)
- [Unsupported NFSv4.0 and 4.1 features \(p. 238\)](#)
- [Additional considerations \(p. 239\)](#)

Amazon EFS quotas that you can increase

Service Quotas is an AWS service that helps you manage your quotas, or limits, from one location. You can view all Amazon EFS limit values in the [Service Quotas console](#). You can also request a quota increase for the number of EFS file systems in an AWS Region using the Service Quotas console.

You can also request an increase to the following Amazon EFS quotas by contacting AWS Support. To learn more, see [Requesting a quota increase \(p. 236\)](#). The Amazon EFS service team reviews each request individually.

Resource	Default quota
Number of file systems for each customer account in an AWS Region	1,000

The following table lists the default throughput quotas for Bursting and Provisioned throughput modes. For more information about EFS throughput modes, see [Amazon EFS performance \(p. 130\)](#).

Resource	AWS Region	Maximum metered (p. 132) throughput	Maximum bursting read throughput
Total bursting throughput for all connected clients	US East (Ohio) Region	3 Gibibytes per second (GiBps)	5 GiBps
	US East (N. Virginia) Region	3 GiBps	5 GiBps
	US West (N. California) Region	1 GiBps	3 GiBps
	US West (Oregon) Region	3 GiBps	5 GiBps
	Africa (Cape Town) Region	1 GiBps	3 GiBps
	Asia Pacific (Hong Kong) Region	1 GiBps	3 GiBps
	Asia Pacific (Mumbai) Region	1 GiBps	3 GiBps

Resource	AWS Region	Maximum metered (p. 132) throughput	Maximum bursting read throughput
	Asia Pacific (Seoul) Region	1 GiBps	3 GiBps
	Asia Pacific (Singapore) Region	1 GiBps	3 GiBps
	Asia Pacific (Sydney) Region	3 GiBps	5 GiBps
	Asia Pacific (Jakarta) Region	1 GiBps	3 GiBps
	Asia Pacific (Tokyo) Region	1 GiBps	3 GiBps
	Asia Pacific (Osaka) Region	1 GiBps	3 GiBps
	Canada (Central) Region	1 GiBps	3 GiBps
	China (Beijing) Region	1 GiBps	3 GiBps
	China (Ningxia) Region	1 GiBps	3 GiBps
	Europe (Frankfurt) Region	1 GiBps	3 GiBps
	Europe (Ireland) Region	3 GiBps	5 GiBps
	Europe (London) Region	1 GiBps	3 GiBps
	Europe (Milan) Region	1 GiBps	3 GiBps
	Europe (Paris) Region	1 GiBps	3 GiBps
	Europe (Stockholm) Region	1 GiBps	3 GiBps
	Middle East (Bahrain) Region	1 GiBps	3 GiBps
	Middle East (UAE) Region	1 GiBps	3 GiBps
	South America (São Paulo) Region	1 GiBps	3 GiBps
	AWS GovCloud (US-East)	1 GiBps	3 GiBps
	AWS GovCloud (US-West)	1 GiBps	3 GiBps
Total provisioned throughput for all connected clients	All AWS Regions	1 GiBps	3 GiBps

Requesting a quota increase

To request an increase for these quotas through AWS Support, take the following steps. The Amazon EFS team reviews each quota increase request.

To request a quota increase through AWS Support

1. Open the [AWS Support Center](#) page, and sign in if necessary. Then choose **Create Case**.
2. Under **Create case**, choose **Service Limit Increase**.
3. For **Limit Type**, choose the type of limit to increase. Fill in the necessary fields in the form, and then choose your preferred method of contact.

Amazon EFS resource quotas that you cannot change

Following are the quotas on Amazon EFS resources for each customer account in an AWS Region. These quotas cannot be changed.

Resource	Quota
Number of access points for each file system	120
Number of connections for each file system	25,000
Number of mount targets for each file system in an Availability Zone	1
Number of mount targets for each VPC	400
Number of security groups for each mount target	5
Number of tags for each file system	50
Number of VPCs for each file system	1

Note

Clients can also connect to mount targets that are in an account or VPC that is different from that of the file system. For more information, see [Mounting EFS file systems from another AWS account or VPC \(p. 85\)](#).

Quotas for NFS clients

The following quotas for NFS clients apply, assuming a Linux NFSv4.1 client:

- The maximum throughput you can drive for each NFS client is 500 mebibytes per second (MiBps). NFS client throughput is calculated as the total number of bytes that are sent and received, with a minimum NFS request size of 4KB (after applying a 1/3 metering rate for read requests).
- Up to 128 active user accounts for each client can have files open at the same time. Each user account represents one local user logged in to the instance. A user account that is logged in multiple times counts as one active user.
- Up to 32,768 files open at the same time on the instance. Listing directory contents doesn't count as opening a file.
- Each unique mount on the client can acquire up to a total of 65,536 locks per connection.
- When connecting to Amazon EFS, NFS clients located on-premises or in another AWS Region can observe lower throughput than when connecting to EFS from the same AWS Region. This effect is because of increased network latency. Network latency of 1 ms or less is required to achieve maximum per-client throughput. Use the DataSync data migration service when migrating large datasets from on-premises NFS servers to EFS.
- Using Amazon EFS with Microsoft Windows isn't supported.

Quotas for Amazon EFS file systems

The following quotas are specific to Amazon EFS file systems:

- Maximum name length: 255 bytes.
- Maximum symbolic link (symlink) length: 4,080 bytes.
- Maximum number of hard links to a file: 177.
- Maximum size of a single file: 52,673,613,135,872 bytes (47.9 TiB).
- Maximum directory depth: 1,000 levels deep.
- Any one particular file can have up to 512 locks across all instances connected and users accessing the file.
- Amazon EFS file system policies have a 20,000 character limit.
- In General Purpose mode, there is a limit of 35,000 file operations per second. Operations that read data or metadata consume one file operation, operations that write data or update metadata consume five file operations. This means that a file system can support 35,000 read operations per second, or 7,000 write operations, or some combination of the two. For example, 20,000 read operations and 3,000 write operations (20,000 reads x 1 file operation per read + 3,000 writes x 5 file operations per write = 35,000 file operations). File operations are counted from all connecting clients.

Unsupported NFSv4.0 and 4.1 features

Although Amazon Elastic File System doesn't support NFSv2, or NFSv3, Amazon EFS supports both NFSv4.1 and NFSv4.0, except for the following features:

- pNFS
- Client delegation or callbacks of any type
 - Operation OPEN always returns OPEN_DELEGATE_NONE as the delegation type.
 - The operation OPEN returns NFSERR_NOTSUPP for the CLAIM_DELEGATE_CUR and CLAIM_DELEGATE_PREV claim types.
- Mandatory locking

All locks in Amazon EFS are advisory, which means that read and write operations don't check for conflicting locks before the operation is executed.

- Deny share

NFS supports the concept of a share deny. A *share deny* is primarily used by Windows clients for users to deny others access to a particular file that has been opened. Amazon EFS doesn't support this, and returns the NFS error NFS4ERR_NOTSUPP for any OPEN commands specifying a share deny value other than OPEN4_SHARE_DENY_NONE. Linux NFS clients don't use anything other than OPEN4_SHARE_DENY_NONE.

- Access control lists (ACLs)
- Amazon EFS doesn't update the time_access attribute on file reads. Amazon EFS updates time_access in the following events:
 - When a file is created (an inode is created).
 - When an NFS client makes an explicit setattr call.
 - On a write to the inode caused by, for example, file size changes or file metadata changes.
 - Any inode attribute is updated.
- Namespaces
- Persistent reply cache
- Kerberos based security
- NFSv4.1 data retention
- SetUID on directories
- Unsupported file types when using the CREATE operation: Block devices (NF4BLK), character devices (NF4CHR), attribute directory (NF4ATTRDIR), and named attribute (NF4NAMEDATTR).

- Unsupported attributes: FATTR4_ARCHIVE, FATTR4_FILES_AVAIL, FATTR4_FILES_FREE, FATTR4_FILES_TOTAL, FATTR4_FS_LOCATIONS, FATTR4_MIMETYPE, FATTR4_QUOTA_AVAIL_HARD, FATTR4_QUOTA_AVAIL_SOFT, FATTR4_QUOTA_USED, FATTR4_TIME_BACKUP, and FATTR4_ACL.

An attempt to set these attributes results in an NFS4ERR_ATTRNOTSUPP error that is sent back to the client.

Additional considerations

In addition, note the following:

- For a list of AWS Regions where you can create Amazon EFS file systems, see the [AWS General Reference](#).
- Amazon EFS does not support the nconnect mount option.
- You can mount an Amazon EFS file system from on-premises data center servers using AWS Direct Connect and VPN. For more information, see [Mounting with on-premises clients \(p. 79\)](#).

Troubleshooting Amazon EFS

You can find information about how to troubleshoot the following issues for Amazon Elastic File System (Amazon EFS).

Topics

- [Troubleshooting Amazon EFS: general issues \(p. 240\)](#)
- [Troubleshooting file operation errors \(p. 243\)](#)
- [Troubleshooting AMI and kernel issues \(p. 245\)](#)
- [Troubleshooting mount issues \(p. 246\)](#)
- [Troubleshooting encryption \(p. 252\)](#)

Troubleshooting Amazon EFS: general issues

Use this information to troubleshoot general Amazon EFS issues. For information about performance, see [Amazon EFS performance \(p. 130\)](#).

In general, if you encounter issues with Amazon EFS that you have trouble resolving, confirm that you're using a recent Linux kernel. If you are using an enterprise Linux distribution, we recommend the following:

- Amazon Linux 2
- Amazon Linux 2015.09 or newer
- RHEL 7.3 or newer
- All versions of Ubuntu 16.04
- Ubuntu 14.04 with kernel 3.13.0-83 or newer
- SLES 12 Sp2 or later

If you are using another distribution or a custom kernel, we recommend kernel version 4.3 or newer.

Note

RHEL 6.9 might be suboptimal for certain workloads due to [Poor performance when opening many files in parallel \(p. 242\)](#).

Topics

- [Unable to create an EFS file system \(p. 240\)](#)
- [Errors when accessing the Amazon EFS console \(p. 241\)](#)
- [Amazon EC2 instance hangs \(p. 241\)](#)
- [Application writing large amounts of data hangs \(p. 241\)](#)
- [Poor performance when opening many files in parallel \(p. 242\)](#)
- [Custom NFS settings causing write delays \(p. 242\)](#)
- [Creating backups with Oracle Recovery Manager is slow \(p. 243\)](#)

Unable to create an EFS file system

A request to create an EFS file system fails with the following message:

```
User: arn:aws:iam::111122223333:user/username is not authorized to
perform: elasticfilesystem>CreateFileSystem on the specified resource.
```

Action to take

Check your AWS Identity and Access Management (IAM) policy to confirm that you are authorized to create EFS file systems with the specified resource conditions. For more information, see [Identity and access management for Amazon EFS \(p. 196\)](#).

Errors when accessing the Amazon EFS console

This section describes errors users might experience when accessing the Amazon EFS management console.

Error authenticating credentials for ec2:DescribeVPCs

The following error message displays when accessing the Amazon EFS console:

```
AuthFailure: An error occurred authenticating your credentials for ec2:DescribeVPCs.
```

This error indicates that your login credentials did not successfully authenticate with the Amazon EC2 service. The Amazon EFS console calls the Amazon EC2 service on your behalf when creating EFS file systems in the VPC that you choose.

Action to take

Ensure that the time on the client accessing the Amazon EFS console is set correctly.

Amazon EC2 instance hangs

An Amazon EC2 instance can hang because you deleted a file system mount target without first unmounting the file system.

Action to take

Before you delete a file system mount target, unmount the file system. For more information about unmounting your Amazon EFS file system, see [Unmounting file systems \(p. 89\)](#).

Application writing large amounts of data hangs

An application that writes a large amount of data to Amazon EFS hangs and causes the instance to reboot.

Action to take

If an application takes too long to write all of its data to Amazon EFS, Linux might reboot because it appears that the process has become unresponsive. Two kernel configuration parameters define this behavior, `kernel.hung_task_panic` and `kernel.hung_task_timeout_secs`.

In the example following, the state of the hung process is reported by the `ps` command with D before the instance reboot, indicating that the process is waiting on I/O.

```
$ ps aux | grep large_io.py
root 33253 0.5 0.0 126652 5020 pts/3 D+ 18:22 0:00 python large_io.py
```

```
/efs/large_file
```

To prevent a reboot, increase the timeout period or disable kernel panics when a hung task is detected. The following command disables hung task kernel panics on most Linux systems.

```
$ sudo sysctl -w kernel.hung_task_panic=0
```

Poor performance when opening many files in parallel

Applications that open multiple files in parallel do not experience the expected increase in performance of I/O parallelization.

Action to take

This issue occurs on Network File System version 4 (NFSv4) clients and on RHEL 6 clients using NFSv4.1 because these NFS clients serialize NFS OPEN and CLOSE operations. Use NFS protocol version 4.1 and one of the suggested [Linux distributions \(p. 240\)](#) that does not have this issue.

If you can't use NFSv4.1, be aware that the Linux NFSv4.0 client serializes open and close requests by user ID and group IDs. This serialization happens even if multiple processes or multiple threads issue requests at the same time. The client only sends one open or close operation to an NFS server at a time, when all of the IDs match. To work around these issues, you can perform any of the following actions:

- You can run each process from a different user ID on the same Amazon EC2 instance.
- You can leave the user IDs the same across all open requests, and modify the set of group IDs instead.
- You can run each process from a separate Amazon EC2 instance.

Custom NFS settings causing write delays

You have custom NFS client settings, and it takes up to three seconds for an Amazon EC2 instance to see a write operation performed on a file system from another Amazon EC2 instance.

Action to take

If you encounter this issue, you can resolve it in one of the following ways:

- If the NFS client on the Amazon EC2 instance that's reading data has attribute caching activated, unmount your file system. Then remount it with the noac option to disable attribute caching. Attribute caching in NFSv4.1 is enabled by default.

Note

Disabling client-side caching can potentially reduce your application's performance.

- You can also clear your attribute cache on demand by using a programming language compatible with the NFS procedures. To do this, you can send an ACCESS procedure request immediately before a read request.

For example, using the Python programming language, you can construct the following call.

```
# Does an NFS ACCESS procedure request to clear the attribute cache, given a path to the
# file
import os
os.access(path, os.W_OK)
```

Creating backups with Oracle Recovery Manager is slow

Creating backups with Oracle Recovery Manager can be slow if Oracle Recovery Manager pauses for 120 seconds before starting a backup job.

Action to take

If you encounter this issue, disable Oracle Direct NFS, as described in [Enabling and Disabling Direct NFS Client Control of NFS](#) in the Oracle Help Center.

Note

Amazon EFS doesn't support Oracle Direct NFS.

Troubleshooting file operation errors

When you access Amazon EFS file systems, certain limits on the files in the file system apply. Exceeding these limits causes file operation errors. For more information on client and file-based limits in Amazon EFS, see [Quotas for NFS clients \(p. 237\)](#). Following, you can find some common file operation errors and the limits associated with each error.

Topics

- [Command fails with "Disk quota exceeded" error \(p. 243\)](#)
- [Command fails with "I/O error" \(p. 243\)](#)
- [Command fails with "File name is too long" error \(p. 244\)](#)
- [Command fails with "File not found" error \(p. 244\)](#)
- [Command fails with "Too many links" error \(p. 244\)](#)
- [Command fails with "File too large" error \(p. 244\)](#)

Command fails with "Disk quota exceeded" error

Amazon EFS doesn't currently support user disk quotas. This error can occur if any of the following limits have been exceeded:

- Up to 128 active user accounts can have files open at once for an instance.
- Up to 32,768 files can be open at once for an instance.
- Each unique mount on the instance can acquire up to a total of 8,192 locks across 256 unique file-process pairs. For example, a single process can acquire one or more locks on 256 separate files, or eight processes can each acquire one or more locks on 32 files.

Action to take

If you encounter this issue, you can resolve it by identifying which of the preceding limits you are exceeding, and then making changes to meet that limit.

Command fails with "I/O error"

This error occurs when you encounter one of the following issues:

- More than 128 active user accounts for each instance have files open at once.

Action to take

If you encounter this issue, you can resolve it by meeting the supported limit of open files on your instances. To do so, reduce the number of active users that have files from your Amazon EFS file system open simultaneously on your instances.

- The AWS KMS key encrypting your file system was deleted.

Action to take

If you encounter this issue, you can no longer decrypt the data that was encrypted under that key, which means that data becomes unrecoverable.

Command fails with "File name is too long" error

This error occurs when the size of a file name or its symbolic link (symlink) is too long. File names have the following limits:

- A name can be up to 255 bytes long.
- A symlink can be up to 4080 bytes in size.

Action to take

If you encounter this issue, you can resolve it by reducing the size of your file name or symlink length to meet the supported limits.

Command fails with "File not found" error

This error occurs because some older 32-bit versions of Oracle E-Business suite use 32-bit file I/O interfaces, and EFS uses 64-bit inode numbers. System calls that may fail include `stat()` and `readdir()`.

Action to take

If you encounter this error, you can resolve it by using the **nfs.enable_ino64=0 kernel** boot option. This option compresses the 64-bit EFS inode numbers to 32 bits. Kernel boot options are handled differently for different Linux distributions. On Amazon Linux, turn on this option by adding `nfs.enable_ino64=0 kernel` to the `GRUB_CMDLINE_LINUX_DEFAULT` variable in `/etc/default/grub`. Please consult your distribution for specific documentation on how to turn on kernel boot options.

Command fails with "Too many links" error

This error occurs when there are too many hard links to a file. You can have up to 177 hard links in a file.

Action to take

If you encounter this issue, you can resolve it by reducing the number of hard links to a file to meet the supported limit.

Command fails with "File too large" error

This error occurs when a file is too large. A single file can be up to 52,673,613,135,872 bytes (47.9 TiB) in size.

Action to take

If you encounter this issue, you can resolve it by reducing the size of a file to meet the supported limit.

Troubleshooting AMI and kernel issues

Following, you can find information about troubleshooting issues related to certain Amazon Machine Image (AMI) or kernel versions when using Amazon EFS from an Amazon EC2 instance.

Topics

- [Unable to chown \(p. 245\)](#)
- [File system keeps performing operations repeatedly due to client bug \(p. 245\)](#)
- [Deadlocked client \(p. 245\)](#)
- [Listing files in a large directory takes a long time \(p. 246\)](#)

Unable to chown

You're unable to change the ownership of a file/directory using the Linux chown command.

Kernel versions with this bug

2.6.32

Action to take

You can resolve this error by doing the following:

- If you're performing chown for the one-time setup step necessary to change ownership of the EFS root directory, you can run the chown command from an instance running a newer kernel. For example, use the newest version of Amazon Linux.
- If chown is part of your production work flow, you must update the kernel version to use chown.

File system keeps performing operations repeatedly due to client bug

A file system gets stuck performing repeated operations due to a client bug.

Action to take

Update the client software to the latest version.

Deadlocked client

A client becomes deadlocked.

Kernel versions with this bug

- CentOS-7 with kernel Linux 3.10.0-229.20.1.el7.x86_64
- Ubuntu 15.10 with kernel Linux 4.2.0-18-generic

Action to take

Do one of the following:

- Upgrade to a newer kernel version. For CentOS-7, kernel version **Linux 3.10.0-327** or later contains the fix.
- Downgrade to an older kernel version.

Listing files in a large directory takes a long time

This can happen if the directory is changing while your NFS client iterates through the directory to finish the list operation. Whenever the NFS client notices that the contents of the directory changed during this iteration, the NFS client restarts iterating from the beginning. As a result, the `ls` command can take a long time to complete for a large directory with frequently changing files.

Kernel versions with this bug

CentOS and RHEL kernel versions lower than 2.6.32-696.el6

Action to take

To resolve this issue, upgrade to a newer kernel version.

Troubleshooting mount issues

Following, you can find information about troubleshooting file-system mounting issues for Amazon EFS.

- [File system mount on Windows instance fails \(p. 246\)](#)
- [Access denied by server \(p. 247\)](#)
- [Automatic mounting fails and the instance is unresponsive \(p. 247\)](#)
- [Mounting multiple Amazon EFS file systems in /etc/fstab fails \(p. 247\)](#)
- [Mount command fails with "wrong fs type" error message \(p. 248\)](#)
- [Mount command fails with "incorrect mount option" error message \(p. 248\)](#)
- [Mounting with access point fails \(p. 249\)](#)
- [File system mount fails immediately after file system creation \(p. 249\)](#)
- [File system mount hangs and then fails with timeout error \(p. 249\)](#)
- [File system mount with NFS using DNS name fails \(p. 250\)](#)
- [File system mount fails with "nfs not responding" \(p. 250\)](#)
- [mount target lifecycle state is stuck \(p. 251\)](#)
- [Mount does not respond \(p. 251\)](#)
- [Operations on newly mounted file system return "bad file handle" Error \(p. 251\)](#)
- [Unmounting a file system fails \(p. 251\)](#)

File system mount on Windows instance fails

A file system mount on an Amazon EC2 instance on Microsoft Windows fails.

Action to take

Don't use Amazon EFS with Windows EC2 instances, which isn't supported.

Access denied by server

A file system mount fails with the following message:

```
/efs mount.nfs4: access denied by server while mounting 127.0.0.1:/
```

This issue can occur if your NFS client does not have permission to mount the file system.

Action to take

If you are attempting to mount the file system using IAM, make sure you are using the `-o iam` option in your mount command. This tells the EFS mount helper to pass your credentials to the EFS mount target. If you still don't have access, check your file system policy and your identity policy to ensure there are no DENY clauses that apply to your connection, and that there is at least one ALLOW clause that applies to the connection. For more information, see [Using IAM to control file system data access \(p. 206\)](#) and [Creating file system policies \(p. 45\)](#).

Automatic mounting fails and the instance is unresponsive

This issue can occur if the file system was mounted automatically on an instance and the `_netdev` option wasn't declared. If `_netdev` is missing, your EC2 instance might stop responding. This result is because network file systems need to be initialized after the compute instance starts its networking.

Action to take

If this issue occurs, contact AWS Support.

Mounting multiple Amazon EFS file systems in /etc/fstab fails

For instances that use the systemd init system with two or more Amazon EFS entries at `/etc/fstab`, there might be times where some or all of these entries are not mounted. In this case, the `dmesg` output shows one or more lines similar to the following.

```
NFS: nfs4_discover_server_trunking unhandled error -512. Exiting with error EIO
```

Action to take

In this case, we recommend that you create a new systemd service file in `/etc/systemd/system/mount-nfs-sequentially.service`. The code to include in the file depends on whether you are manually mounting the file systems or using the Amazon EFS mount helper.

- If you are manually mounting the file systems, then the `ExecStart` command must point to Network File System (NFS4). Include the following code in the file:

```
[Unit]
Description=Workaround for mounting NFS file systems sequentially at boot time
After=remote-fs.target

[Service]
Type=oneshot
ExecStart=/bin/mount -avt nfs4
RemainAfterExit=yes
```

```
[Install]
WantedBy=multi-user.target
```

- If you are using the Amazon EFS mount helper, then the ExecStart command must point to EFS instead of NFS4 to use Transport Layer Security (TLS). Include the following code in the file:

```
[Unit]
Description=Workaround for mounting NFS file systems sequentially at boot time
After=remote-fs.target

[Service]
Type=oneshot
ExecStart=/bin/mount -avt efs
RemainAfterExit=yes

[Install]
WantedBy=multi-user.target
```

After you create the file, run the following two commands:

1. sudo systemctl daemon-reload
2. sudo systemctl enable mount-nfs-sequentially.service

Then restart your Amazon EC2 instance. The file systems are mounted on demand, generally within a second.

Mount command fails with "wrong fs type" error message

The mount command fails with the following error message.

```
mount: wrong fs type, bad option, bad superblock on 10.1.25.30:/,
missing codepage or helper program, or other error (for several filesystems
(e.g. nfs, cifs) you might need a /sbin/mount.<type> helper program)
In some cases useful info is found in syslog - try dmesg | tail or so.
```

Action to take

If you receive this message, install the nfs-utils (or nfs-common on Ubuntu) package. For more information, see [Installing the NFS client \(p. 399\)](#).

Mount command fails with "incorrect mount option" error message

The mount command fails with the following error message.

```
mount.nfs: an incorrect mount option was specified
```

Action to take

This error message most likely means that your Linux distribution doesn't support Network File System versions 4.0 and 4.1 (NFSv4). To confirm this is the case, you can run the following command.

```
$ grep CONFIG_NFS_V4_1 /boot/config*
```

If the preceding command returns # CONFIG_NFS_V4_1 is not set, NFSv4.1 is not supported on your Linux distribution. For a list of the Amazon Machine Images (AMIs) for Amazon Elastic Compute Cloud (Amazon EC2) that support NFSv4.1, see [NFS support \(p. 398\)](#).

Mounting with access point fails

The mount command fails when mounting with an access point, with the following error message:

```
mount.nfs4: mounting access_point failed, reason given by server: No such file or directory
```

Action to take

This error message indicates that the specified EFS path does not exist. Make sure that you provide the ownership and permissions for the access point root directory. EFS will not create the root directory without this information. For more information, see [Working with Amazon EFS access points \(p. 224\)](#).

If you don't specify any root directory ownership and permissions, and the root directory does not already exist, EFS will not create the root directory. When this happens, any attempts to mount the file system using the access point will fail.

File system mount fails immediately after file system creation

It can take up to 90 seconds after creating a mount target for the Domain Name Service (DNS) records to propagate fully in an AWS Region.

Action to take

If you're programmatically creating and mounting file systems, for example with an AWS CloudFormation template, we recommend that you implement a wait condition.


File system mount hangs and then fails with timeout error

The file system mount command hangs for a minute or two, and then fails with a timeout error. The following code shows an example.

```
$ sudo mount -t nfs -o
nfsvers=4.1,rsize=1048576,wsize=1048576,hard,timeo=600,retrans=2,noresvport mount-target-ip:/ mnt
[2+ minute wait here]
mount.nfs: Connection timed out
$Â
```

Action to take

This error can occur because either the Amazon EC2 instance or the mount target security groups are not configured properly. Make sure that the mount target security group has an inbound rule that allows NFS access from the EC2 security group.



For more information, see [Creating security groups \(p. 43\)](#).

Verify that the mount target IP address that you specified is valid. If you specify the wrong IP address and there is nothing else at that IP address to reject the mount, you might experience this issue.

File system mount with NFS using DNS name fails

Attempts to mount a file system with nfs (not using the `amazon-efs-utils` client) using the file system's DNS name fails, as shown in the following example:

```
$ sudo mount -t nfs -o
nfsvers=4.1,rsize=1048576,wsize=1048576,hard,timeo=600,retrans=2,noresvport file-system-
id.efs.aws-region.amazonaws.com:/ mnt
mount.nfs: Failed to resolve server file-system-id.efs.aws-region.amazonaws.com:
Name or service not known.

$
```

Action to take

Check your VPC configuration. If you are using a custom VPC, make sure that DNS settings are enabled. For more information, see [Using DNS with Your VPC](#) in the *Amazon VPC User Guide*. Also, file system and mount target DNS names are not resolvable from outside the VPC where they exist.

To specify a DNS name in the mount command, you must do the following:

- Ensure that there's an Amazon EFS mount target in the same Availability Zone as the Amazon EC2 instance.
- Ensure that there's a mount target in the same VPC as the Amazon EC2 instance. Otherwise, you can't use DNS name resolution for EFS mount targets that are in another VPC. For more information, see [Mounting EFS file systems from another AWS account or VPC \(p. 85\)](#).
- Connect your Amazon EC2 instance inside an Amazon VPC configured to use the DNS server provided by Amazon. For more information, see [DHCP Options Sets](#) in the *Amazon VPC User Guide*.
- Ensure that the Amazon VPC of the connecting Amazon EC2 instance has DNS hostnames enabled. For more information, see [Updating DNS Support for Your VPC](#) in the *Amazon VPC User Guide*.

File system mount fails with "nfs not responding"

An Amazon EFS file system mount fails on a Transmission Control Protocol (TCP) reconnection event with "nfs: server_name still not responding".

Action to take

Use the `noresvport` mount option to make sure that the NFS client uses a new TCP source port when a network connection is reestablished. Doing this helps ensure uninterrupted availability after a network recovery event.

mount target lifecycle state is stuck

The mount target lifecycle state is stuck in the **creating** or **deleting** state.

Action to take

Retry the `CreateMountTarget` or `DeleteMountTarget` call.

Mount does not respond

An Amazon EFS mount appears unresponsive. For example, commands like `ls` hang.

Action to take

This error can occur if another application is writing large amounts of data to the file system. Access to the files that are being written might be blocked until the operation is complete. In general, any commands or applications that attempt to access files that are being written to might appear to hang. For example, the `ls` command might hang when it gets to the file that is being written. This result is because some Linux distributions alias the `ls` command so that it retrieves file attributes in addition to listing the directory contents.

To resolve this issue, verify that another application is writing files to the Amazon EFS mount, and that it is in the `Uninterruptible sleep (D)` state, as in the following example:

```
$ ps aux | grep large_io.py
root 33253 0.5 0.0 126652 5020 pts/3 D+ 18:22 0:00 python large_io.py /efs/large_file
```

After you've verified that this is the case, you can address the issue by waiting for the other write operation to complete, or by implementing a workaround. In the example of `ls`, you can use the `/bin/ls` command directly, instead of an alias. Doing this allows the command to proceed without hanging on the file being written. In general, if the application writing the data can force a data flush periodically, perhaps by using `fsync(2)`, doing so can help improve the responsiveness of your file system for other applications. However, this improvement might be at the expense of performance when the application writes data.

Operations on newly mounted file system return "bad file handle" Error

Operations performed on a newly mounted file system return a `bad file handle` error.

This error can happen if an Amazon EC2 instance was connected to one file system and one mount target with a specified IP address, and then that file system and mount target were deleted. If you create a new file system and mount target to connect to that Amazon EC2 instance with the same mount target IP address, this issue can occur.

Action to take

You can resolve this error by unmounting the file system, and then remounting the file system on the Amazon EC2 instance. For more information about unmounting your Amazon EFS file system, see [Unmounting file systems \(p. 89\)](#).

Unmounting a file system fails

If your file system is busy, you can't unmount it.

Action to take

You can resolve this issue in the following ways:

- Use lazy unmount, **umount -l** which detaches the filesystem from the filesystem hierarchy when run, then cleans up all references to the filesystem as soon as it is not busy anymore.
- Wait for all read and write operations to finish, and then attempt the **umount** command again.
- Force an unmount using the **umount -f** command.

Warning

Forcing an unmount interrupts any data read or write operations that are currently in process for the file system. See the [umount man page](#) for more information and guidance when using this option.

Troubleshooting encryption

Following, you can find information about troubleshooting encryption issues for Amazon EFS.

- [Mounting with encryption of data in transit fails \(p. 252\)](#)
- [Mounting with encryption of data in transit is interrupted \(p. 252\)](#)
- [Encrypted-at-rest file system can't be created \(p. 253\)](#)
- [Unusable encrypted file system \(p. 253\)](#)

Mounting with encryption of data in transit fails

By default, when you use the Amazon EFS mount helper with Transport Layer Security (TLS), it enforces hostname checking. Some systems don't support this feature, such as when you use Red Hat Enterprise Linux or CentOS. In these cases, mounting an EFS file system using TLS fails.

Action to take

We recommend that you upgrade the version of stunnel on your client to support hostname checking. For more information, see [Upgrading stunnel \(p. 64\)](#).

Mounting with encryption of data in transit is interrupted

It's possible, however unlikely, that your encrypted connection to your Amazon EFS file system can hang or be interrupted by client-side events.

Action to take

If your connection to your Amazon EFS file system with encryption of data in transit is interrupted, take the following steps:

1. Ensure that the stunnel service is running on the client.
2. Confirm that the watchdog application `amazon-efs-mount-watchdog` is running on the client. You can find out whether this application is running with the following command:

```
ps aux | grep [a]mazon-efs-mount-watchdog
```

3. Check your support logs. For more information, see [Getting support logs \(p. 70\)](#).

4. Optionally, you can enable your stunnel logs and check the information in those as well. You can change the configuration of your logs in `/etc/amazon/efs/efs-utils.conf` to enable the stunnel logs. However, doing so requires unmounting and then remounting the file system with the mount helper for the changes to take effect.

Important

Enabling the stunnel logs can use up a nontrivial amount of space on your file system.

If the interruptions continue, contact AWS Support.

Encrypted-at-rest file system can't be created

You've tried to create a new encrypted-at-rest file system. However, you get an error message saying that AWS KMS is unavailable.

Action to take

This error can occur in the rare case that AWS KMS becomes temporarily unavailable in your AWS Region. If this happens, wait until AWS KMS returns to full availability, and then try again to create the file system.

Unusable encrypted file system

An encrypted file system consistently returns NFS server errors. These errors can occur when EFS can't retrieve your master key from AWS KMS for one of the following reasons:

- The key was disabled.
- The key was deleted.
- Permission for Amazon EFS to use the key was revoked.
- AWS KMS is temporarily unavailable.

Action to take

First, confirm that the AWS KMS key is enabled. You can do so by viewing the keys in the console. For more information, see [Viewing Keys](#) in the *AWS Key Management Service Developer Guide*.

If the key is not enabled, enable it. For more information, see [Enabling and Disabling Keys](#) in the *AWS Key Management Service Developer Guide*.

If the key is pending deletion, then this status disables the key. You can cancel the deletion, and re-enable the key. For more information, see [Scheduling and Canceling Key Deletion](#) in the *AWS Key Management Service Developer Guide*.

If the key is enabled, and you're still experiencing an issue, or if you encounter an issue re-enabling your key, contact AWS Support.

Amazon EFS API

The Amazon EFS API is a network protocol based on [HTTP \(RFC 2616\)](#). For each API call, you make an HTTP request to the region-specific Amazon EFS API endpoint for the AWS Region where you want to manage file systems. The API uses JSON (RFC 4627) documents for HTTP request/response bodies.

The Amazon EFS API is an RPC model. In this model, there is a fixed set of operations and the syntax for each operation is known to clients without any prior interaction. In the following section, you can find a description of each API operation using an abstract RPC notation. Each has an operation name that doesn't appear on the wire. For each operation, the topic specifies the mapping to HTTP request elements.

The specific Amazon EFS operation to which a given request maps is determined by a combination of the request's method (GET, PUT, POST, or DELETE) and which of the various patterns its Request-URI matches. If the operation is PUT or POST, Amazon EFS extracts call arguments from the Request-URI path segment, query parameters, and the JSON object in the request body.

Note

Although operation names, such as `CreateFileSystem`, don't appear on the wire, these names are meaningful in AWS Identity and Access Management (IAM) policies. For more information, see [Identity and access management for Amazon EFS \(p. 196\)](#).

The operation name is also used to name commands in command-line tools and elements of the AWS SDK APIs. For example, there is a AWS CLI command named `create-file-system` that maps to the `CreateFileSystem` operation.

The operation name also appears in AWS CloudTrail logs for Amazon EFS API calls.

API endpoint

The API endpoint is the DNS name used as a host in the HTTP URI for the API calls. These API endpoints are specific to AWS Regions and take the following form.

```
elasticfilesystem.aws-region.amazonaws.com
```

For example, the Amazon EFS API endpoint for the US West (Oregon) Region is the following.

```
elasticfilesystem.us-west-2.amazonaws.com
```

For a list of AWS Regions that Amazon EFS supports (where you can create and manage file systems), see [Amazon Elastic File System](#) in the [AWS General Reference](#).

The region-specific API endpoint defines the scope of the Amazon EFS resources that are accessible when you make an API call. For example, when you call the `DescribeFileSystems` operation using the preceding endpoint, you get a list of file systems in the US West (Oregon) Region that have been created in your account.

API version

The version of the API being used for a call is identified by the first path segment of the request URI, and its form is an ISO 8601 date. For example, see [CreateFileSystem \(p. 262\)](#).

The documentation describes API version 2015-02-01.

Related topics

The following sections provide descriptions of the API operations, how to create a signature for request authentication, and how to grant permissions for these API operations using the IAM policies.

- [Identity and access management for Amazon EFS \(p. 196\)](#)
- [Actions \(p. 255\)](#)
- [Data Types \(p. 360\)](#)

Working with the query API request rate for Amazon EFS

Amazon EFS API requests are throttled for each AWS account on a per-region basis to help service performance. All Amazon EFS API calls together, whether they originate from an application, the AWS CLI, or the Amazon EFS console, must not exceed the maximum allowed API request rate. The maximum API request rate can vary across AWS Regions. API requests made by AWS Identity and Access Management (IAM) users are attributed to the underlying AWS account.

If an API request exceeds the API request rate for its category, the request returns the `ThrottlingException` error code. To prevent this error, ensure that your application doesn't retry API requests at a high rate. You can do this by using care when polling and by using exponential backoff retries.

Polling

Your application might need to call an API operation repeatedly to check for an update in status. Before you start polling, give the request time to potentially complete. When you begin polling, use an appropriate sleep interval between successive requests. For best results, use an increasing sleep interval.

Retries or batch processing

Your application might need to retry an API request after it fails, or to process multiple resources (for example, all of your Amazon EFS file systems). To lower the rate of API requests, use an appropriate sleep interval between successive requests. For best results, use an increasing or variable sleep interval.

Calculating the sleep interval

When you have to poll or retry an API request, we recommend using an exponential backoff algorithm to calculate the sleep interval between API calls. The idea behind exponential backoff is to use progressively longer waits between retries for consecutive error responses. For more information, and implementation examples of this algorithm, see [Error Retries and Exponential Backoff in AWS](#) in the *Amazon Web Services General Reference*.

Actions

The following actions are supported:

- [CreateAccessPoint \(p. 257\)](#)
- [CreateFileSystem \(p. 262\)](#)
- [CreateMountTarget \(p. 272\)](#)
- [CreateReplicationConfiguration \(p. 280\)](#)
- [CreateTags \(p. 285\)](#)
- [DeleteAccessPoint \(p. 287\)](#)
- [DeleteFileSystem \(p. 289\)](#)
- [DeleteFileSystemPolicy \(p. 292\)](#)
- [DeleteMountTarget \(p. 294\)](#)
- [DeleteReplicationConfiguration \(p. 297\)](#)
- [DeleteTags \(p. 299\)](#)
- [DescribeAccessPoints \(p. 301\)](#)
- [DescribeAccountPreferences \(p. 304\)](#)
- [DescribeBackupPolicy \(p. 306\)](#)
- [DescribeFileSystemPolicy \(p. 308\)](#)
- [DescribeFileSystems \(p. 311\)](#)
- [DescribeLifecycleConfiguration \(p. 315\)](#)
- [DescribeMountTargets \(p. 318\)](#)
- [DescribeMountTargetSecurityGroups \(p. 322\)](#)
- [DescribeReplicationConfigurations \(p. 325\)](#)
- [DescribeTags \(p. 328\)](#)
- [ListTagsForResource \(p. 331\)](#)
- [ModifyMountTargetSecurityGroups \(p. 334\)](#)
- [PutAccountPreferences \(p. 337\)](#)
- [PutBackupPolicy \(p. 339\)](#)
- [PutFileSystemPolicy \(p. 341\)](#)
- [PutLifecycleConfiguration \(p. 345\)](#)
- [TagResource \(p. 350\)](#)
- [UntagResource \(p. 353\)](#)
- [UpdateFileSystem \(p. 355\)](#)

CreateAccessPoint

Creates an EFS access point. An access point is an application-specific view into an EFS file system that applies an operating system user and group, and a file system path, to any file system request made through the access point. The operating system user and group override any identity information provided by the NFS client. The file system path is exposed as the access point's root directory. Applications using the access point can only access data in the application's own directory and any subdirectories. To learn more, see [Mounting a file system using EFS access points](#).

Note

If multiple requests to create access points on the same file system are sent in quick succession, and the file system is near the limit of 120 access points, you may experience a throttling response for these requests. This is to ensure that the file system does not exceed the stated access point limit.

This operation requires permissions for the elasticfilesystem:CreateAccessPoint action.

Request Syntax

```
POST /2015-02-01/access-points HTTP/1.1
Content-type: application/json

{
    "ClientToken": "string",
    "FileSystemId": "string",
    "PosixUser": {
        "Gid": number,
        "SecondaryGids": [ number ],
        "Uid": number
    },
    "RootDirectory": {
        "CreateInfo": {
            "OwnerGid": number,
            "OwnerUid": number,
            "Permissions": "string"
        },
        "Path": "string"
    },
    "Tags": [
        {
            "Key": "string",
            "Value": "string"
        }
    ]
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

[ClientToken \(p. 257\)](#)

A string of up to 64 ASCII characters that Amazon EFS uses to ensure idempotent creation.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: .+

Required: Yes

[FileSystemId \(p. 257\)](#)

The ID of the EFS file system that the access point provides access to.

Type: String

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})\$

Required: Yes

[PosixUser \(p. 257\)](#)

The operating system user and group applied to all file system requests made using the access point.

Type: [PosixUser \(p. 379\)](#) object

Required: No

[RootDirectory \(p. 257\)](#)

Specifies the directory on the Amazon EFS file system that the access point exposes as the root directory of your file system to NFS clients using the access point. The clients using the access point can only access the root directory and below. If the RootDirectory > Path specified does not exist, EFS creates it and applies the CreationInfo settings when a client connects to an access point. When specifying a RootDirectory, you must provide the Path, and the CreationInfo.

Amazon EFS creates a root directory only if you have provided the CreationInfo: OwnUid, OwnGID, and permissions for the directory. If you do not provide this information, Amazon EFS does not create the root directory. If the root directory does not exist, attempts to mount using the access point will fail.

Type: [RootDirectory \(p. 383\)](#) object

Required: No

[Tags \(p. 257\)](#)

Creates tags associated with the access point. Each tag is a key-value pair, each key must be unique. For more information, see [Tagging AWS resources](#) in the [AWS General Reference Guide](#).

Type: Array of [Tag \(p. 384\)](#) objects

Required: No

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "AccessPointArn": "string",
    "AccessPointId": "string",
    "ClientToken": "string",
    "FileSystemId": "string",
```

```
"LifeCycleState": "string",
"Name": "string",
"OwnerId": "string",
"PosixUser": {
    "Gid": number,
    "SecondaryGids": [ number ],
    "Uid": number
},
"RootDirectory": {
    "CreationInfo": {
        "OwnerGid": number,
        "OwnerUid": number,
        "Permissions": "string"
    },
    "Path": "string"
},
"Tags": [
    {
        "Key": "string",
        "Value": "string"
    }
]
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

[AccessPointArn \(p. 258\)](#)

The unique Amazon Resource Name (ARN) associated with the access point.

Type: String

Length Constraints: Maximum length of 128.

Pattern: ^arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:access-point/fsap-[0-9a-f]{8,40}\$

[AccessPointId \(p. 258\)](#)

The ID of the access point, assigned by Amazon EFS.

Type: String

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:access-point/fsap-[0-9a-f]{8,40}|fsap-[0-9a-f]{8,40})\$

[ClientToken \(p. 258\)](#)

The opaque string specified in the request to ensure idempotent creation.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: .+

[FileSystemId \(p. 258\)](#)

The ID of the EFS file system that the access point applies to.

Type: String

Length Constraints: Maximum length of 128.

Pattern: `^arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9a-f]{8,40}|fs-[0-9a-f]{8,40}$`

[LifeCycleState \(p. 258\)](#)

Identifies the lifecycle phase of the access point.

Type: String

Valid Values: `creating | available | updating | deleting | deleted | error`

[Name \(p. 258\)](#)

The name of the access point. This is the value of the Name tag.

Type: String

[OwnerId \(p. 258\)](#)

Identified the AWS account that owns the access point resource.

Type: String

Length Constraints: Maximum length of 14.

Pattern: `^(\\d{12})|(\\d{4}-\\d{4}-\\d{4})$`

[PosixUser \(p. 258\)](#)

The full POSIX identity, including the user ID, group ID, and secondary group IDs on the access point that is used for all file operations by NFS clients using the access point.

Type: [PosixUser \(p. 379\)](#) object

[RootDirectory \(p. 258\)](#)

The directory on the Amazon EFS file system that the access point exposes as the root directory to NFS clients using the access point.

Type: [RootDirectory \(p. 383\)](#) object

[Tags \(p. 258\)](#)

The tags associated with the access point, presented as an array of Tag objects.

Type: Array of [Tag \(p. 384\)](#) objects

Errors

AccessPointAlreadyExists

Returned if the access point that you are trying to create already exists, with the creation token you provided in the request.

HTTP Status Code: 409

AccessPointLimitExceeded

Returned if the AWS account has already created the maximum number of access points allowed per file system. For more information, see <https://docs.aws.amazon.com/efs/latest/ug/limits.html#limits-efs-resources-per-account-per-region>.

HTTP Status Code: 403

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified FileSystemId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

IncorrectFileSystemLifeCycleState

Returned if the file system's lifecycle state is not "available".

HTTP Status Code: 409

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

ThrottlingException

Returned when the CreateAccessPoint API action is called too quickly and the number of Access Points on the file system is nearing the [limit of 120](#).

HTTP Status Code: 429

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

CreateFileSystem

Creates a new, empty file system. The operation requires a creation token in the request that Amazon EFS uses to ensure idempotent creation (calling the operation with same creation token has no effect). If a file system does not currently exist that is owned by the caller's AWS account with the specified creation token, this operation does the following:

- Creates a new, empty file system. The file system will have an Amazon EFS assigned ID, and an initial lifecycle state `creating`.
- Returns with the description of the created file system.

Otherwise, this operation returns a `FileSystemAlreadyExists` error with the ID of the existing file system.

Note

For basic use cases, you can use a randomly generated UUID for the creation token.

The idempotent operation allows you to retry a `CreateFileSystem` call without risk of creating an extra file system. This can happen when an initial call fails in a way that leaves it uncertain whether or not a file system was actually created. An example might be that a transport level timeout occurred or your connection was reset. As long as you use the same creation token, if the initial call had succeeded in creating a file system, the client can learn of its existence from the `FileSystemAlreadyExists` error.

For more information, see [Creating a file system](#) in the *Amazon EFS User Guide*.

Note

The `CreateFileSystem` call returns while the file system's lifecycle state is still `creating`. You can check the file system creation status by calling the [DescribeFileSystems \(p. 311\)](#) operation, which among other things returns the file system state.

This operation accepts an optional `PerformanceMode` parameter that you choose for your file system. We recommend `generalPurpose` performance mode for most file systems. File systems using the `maxIO` performance mode can scale to higher levels of aggregate throughput and operations per second with a tradeoff of slightly higher latencies for most file operations. The performance mode can't be changed after the file system has been created. For more information, see [Amazon EFS performance modes](#).

You can set the throughput mode for the file system using the `ThroughputMode` parameter.

After the file system is fully created, Amazon EFS sets its lifecycle state to `available`, at which point you can create one or more mount targets for the file system in your VPC. For more information, see [CreateMountTarget \(p. 272\)](#). You mount your Amazon EFS file system on an EC2 instances in your VPC by using the mount target. For more information, see [Amazon EFS: How it Works](#).

This operation requires permissions for the `elasticfilesystem:CreateFileSystem` action.

Request Syntax

```
POST /2015-02-01/file-systems HTTP/1.1
Content-type: application/json

{
    "AvailabilityZoneName": "string",
    "Backup": boolean,
    "CreationToken": "string",
    "Encrypted": boolean,
    "KmsKeyId": "string",
    "PerformanceMode": "string",
    "ProvisionedThroughputInMbps": number,
```

```
"Tags": [  
    {  
        "Key": "string",  
        "Value": "string"  
    }  
,  
    "ThroughputMode": "string"  
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

[AvailabilityZoneName \(p. 262\)](#)

Used to create a file system that uses One Zone storage classes. It specifies the AWS Availability Zone in which to create the file system. Use the format us-east-1a to specify the Availability Zone. For more information about One Zone storage classes, see [Using EFS storage classes](#) in the *Amazon EFS User Guide*.

Note

One Zone storage classes are not available in all Availability Zones in AWS Regions where Amazon EFS is available.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: .+

Required: No

[Backup \(p. 262\)](#)

Specifies whether automatic backups are enabled on the file system that you are creating. Set the value to true to enable automatic backups. If you are creating a file system that uses One Zone storage classes, automatic backups are enabled by default. For more information, see [Automatic backups](#) in the *Amazon EFS User Guide*.

Default is false. However, if you specify an AvailabilityZoneName, the default is true.

Note

AWS Backup is not available in all AWS Regions where Amazon EFS is available.

Type: Boolean

Required: No

[CreationToken \(p. 262\)](#)

A string of up to 64 ASCII characters. Amazon EFS uses this to ensure idempotent creation.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: .+

Required: Yes

[Encrypted \(p. 262\)](#)

A Boolean value that, if true, creates an encrypted file system. When creating an encrypted file system, you have the option of specifying an existing AWS Key Management Service key (KMS key). If you don't specify a KMS key, then the default KMS key for Amazon EFS, /aws/elasticfilesystem, is used to protect the encrypted file system.

Type: Boolean

Required: No

[KmsKeyId \(p. 262\)](#)

The ID of the KMS key that you want to use to protect the encrypted file system. This parameter is required only if you want to use a non-default KMS key. If this parameter is not specified, the default KMS key for Amazon EFS is used. You can specify a KMS key ID using the following formats:

- Key ID - A unique identifier of the key, for example 1234abcd-12ab-34cd-56ef-1234567890ab.
- ARN - An Amazon Resource Name (ARN) for the key, for example arn:aws:kms:us-west-2:111122223333:key/1234abcd-12ab-34cd-56ef-1234567890ab.
- Key alias - A previously created display name for a key, for example alias/projectKey1.
- Key alias ARN - An ARN for a key alias, for example arn:aws:kms:us-west-2:444455556666:alias/projectKey1.

If you use KmsKeyId, you must set the [CreateFileSystem:Encrypted \(p. 264\)](#) parameter to true.

Important

EFS accepts only symmetric KMS keys. You cannot use asymmetric KMS keys with Amazon EFS file systems.

Type: String

Length Constraints: Maximum length of 2048.

Pattern: ^([0-9a-f]{8}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{12})|mrk-[0-9a-f]{32}|alias/[a-zA-Z0-9/_-]+|(arn:aws[-a-z]*:kms:[a-zA-Z0-9-]+:\d{12}:(key/[0-9a-f]{8}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{12})|(key/mrk-[0-9a-f]{32})|(alias/[a-zA-Z0-9/_-]+)))\$

Required: No

[PerformanceMode \(p. 262\)](#)

The performance mode of the file system. We recommend generalPurpose performance mode for most file systems. File systems using the maxIO performance mode can scale to higher levels of aggregate throughput and operations per second with a tradeoff of slightly higher latencies for most file operations. The performance mode can't be changed after the file system has been created.

Note

The maxIO mode is not supported on file systems using One Zone storage classes.

Type: String

Valid Values: generalPurpose | maxIO

Required: No

[ProvisionedThroughputInMibps \(p. 262\)](#)

The throughput, measured in MiB/s, that you want to provision for a file system that you're creating. Valid values are 1-1024. Required if ThroughputMode is set to provisioned. The upper limit for

throughput is 1024 MiB/s. To increase this limit, contact AWS Support. For more information, see [Amazon EFS quotas that you can increase](#) in the *Amazon EFS User Guide*.

Type: Double

Valid Range: Minimum value of 1.0.

Required: No

[Tags \(p. 262\)](#)

Use to create one or more tags associated with the file system. Each tag is a user-defined key-value pair. Name your file system on creation by including a "Key": "Name", "Value": "{value}" key-value pair. Each key must be unique. For more information, see [Tagging AWS resources](#) in the *AWS General Reference Guide*.

Type: Array of [Tag \(p. 384\)](#) objects

Required: No

[ThroughputMode \(p. 262\)](#)

Specifies the throughput mode for the file system, either bursting or provisioned.

If you set ThroughputMode to provisioned, you must also set a value for ProvisionedThroughputInMbps. After you create the file system, you can decrease your file system's throughput in Provisioned Throughput mode or change between the throughput modes, as long as it's been more than 24 hours since the last decrease or throughput mode change. For more information, see [Specifying throughput with provisioned mode](#) in the *Amazon EFS User Guide*.

Default is bursting.

Type: String

Valid Values: bursting | provisioned

Required: No

Response Syntax

```
HTTP/1.1 201
Content-type: application/json

{
    "AvailabilityZoneId": "string",
    "AvailabilityZoneName": "string",
    "CreationTime": number,
    "CreationToken": "string",
    "Encrypted": boolean,
    "FileSystemArn": "string",
    "FileSystemId": "string",
    "KmsKeyId": "string",
    "LifeCycleState": "string",
    "Name": "string",
    "NumberOfMountTargets": number,
    "OwnerId": "string",
    "PerformanceMode": "string",
    "ProvisionedThroughputInMbps": number,
    "SizeInBytes": {
        "Timestamp": number,
        "Value": number,
        "ValueInIA": number,
```

```
        "ValueInStandard": number
    },
    "Tags": [
        {
            "Key": "string",
            "Value": "string"
        }
    ],
    "ThroughputMode": "string"
}
```

Response Elements

If the action is successful, the service sends back an HTTP 201 response.

The following data is returned in JSON format by the service.

[AvailabilityZoneId](#) (p. 265)

The unique and consistent identifier of the Availability Zone in which the file system's One Zone storage classes exist. For example, use1-az1 is an Availability Zone ID for the us-east-1 AWS Region, and it has the same location in every AWS account.

Type: String

[AvailabilityZoneName](#) (p. 265)

Describes the AWS Availability Zone in which the file system is located, and is valid only for file systems using One Zone storage classes. For more information, see [Using EFS storage classes](#) in the *Amazon EFS User Guide*.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: .+

[CreationTime](#) (p. 265)

The time that the file system was created, in seconds (since 1970-01-01T00:00:00Z).

Type: Timestamp

[CreationToken](#) (p. 265)

The opaque string specified in the request.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: .+

[Encrypted](#) (p. 265)

A Boolean value that, if true, indicates that the file system is encrypted.

Type: Boolean

[FileSystemArn](#) (p. 265)

The Amazon Resource Name (ARN) for the EFS file system, in the format `arn:aws:elasticfilesystem:region:account-id:file-system/file-`

system-id . Example with sample data: arn:aws:elasticfilesystem:us-west-2:1111333322228888:file-system/fs-01234567

Type: String

[FileSystemId \(p. 265\)](#)

The ID of the file system, assigned by Amazon EFS.

Type: String

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})\$

[KmsKeyId \(p. 265\)](#)

The ID of an AWS KMS key used to protect the encrypted file system.

Type: String

Length Constraints: Maximum length of 2048.

Pattern: ^([0-9a-f]{8}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{12}|\m\k-[0-9a-f]{32}|alias/[a-zA-Z0-9/_-]+|(arn:aws[-a-z]*:kms:[a-zA-Z0-9_-]+\:\d{12}:((key/[0-9a-f]{8}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{12})|(key/\m\k-[0-9a-f]{32}))|(alias/[a-zA-Z0-9/_-]+)))\$

[LifeCycleState \(p. 265\)](#)

The lifecycle phase of the file system.

Type: String

Valid Values: creating | available | updating | deleting | deleted | error

[Name \(p. 265\)](#)

You can add tags to a file system, including a Name tag. For more information, see [CreateFileSystem \(p. 262\)](#). If the file system has a Name tag, Amazon EFS returns the value in this field.

Type: String

Length Constraints: Maximum length of 256.

Pattern: ^([\p{L}\p{Z}\p{N}_-.:=/=+\-\@]*)\$

[NumberOfMountTargets \(p. 265\)](#)

The current number of mount targets that the file system has. For more information, see [CreateMountTarget \(p. 272\)](#).

Type: Integer

Valid Range: Minimum value of 0.

[OwnerId \(p. 265\)](#)

The AWS account that created the file system. If the file system was created by an IAM user, the parent account to which the user belongs is the owner.

Type: String

Length Constraints: Maximum length of 14.

Pattern: ^(\d{12})|(\d{4}-\d{4}-\d{4})\$

[PerformanceMode \(p. 265\)](#)

The performance mode of the file system.

Type: String

Valid Values: generalPurpose | maxIO

[ProvisionedThroughputInMibps \(p. 265\)](#)

The amount of provisioned throughput, measured in MiB/s, for the file system. Valid for file systems using ThroughputMode set to provisioned.

Type: Double

Valid Range: Minimum value of 1.0.

[SizeInBytes \(p. 265\)](#)

The latest known metered size (in bytes) of data stored in the file system, in its Value field, and the time at which that size was determined in its Timestamp field. The Timestamp value is the integer number of seconds since 1970-01-01T00:00:00Z. The SizeInBytes value doesn't represent the size of a consistent snapshot of the file system, but it is eventually consistent when there are no writes to the file system. That is, SizeInBytes represents actual size only if the file system is not modified for a period longer than a couple of hours. Otherwise, the value is not the exact size that the file system was at any point in time.

Type: [FileSystemSize \(p. 374\)](#) object

[Tags \(p. 265\)](#)

The tags associated with the file system, presented as an array of Tag objects.

Type: Array of [Tag \(p. 384\)](#) objects

[ThroughputMode \(p. 265\)](#)

Displays the file system's throughput mode. For more information, see [Throughput modes](#) in the *Amazon EFS User Guide*.

Type: String

Valid Values: bursting | provisioned

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemAlreadyExists

Returned if the file system you are trying to create already exists, with the creation token you provided.

HTTP Status Code: 409

FileSystemLimitExceeded

Returned if the AWS account has already created the maximum number of file systems allowed per account.

HTTP Status Code: 403

InsufficientThroughputCapacity

Returned if there's not enough capacity to provision additional throughput. This value might be returned when you try to create a file system in provisioned throughput mode, when you attempt to increase the provisioned throughput of an existing file system, or when you attempt to change an existing file system from Bursting Throughput to Provisioned Throughput mode. Try again later.

HTTP Status Code: 503

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

ThroughputLimitExceeded

Returned if the throughput mode or amount of provisioned throughput can't be changed because the throughput limit of 1024 MiB/s has been reached.

HTTP Status Code: 400

UnsupportedAvailabilityZone

Returned if the requested Amazon EFS functionality is not available in the specified Availability Zone.

HTTP Status Code: 400

Examples

Create an encrypted EFS file system

The following example sends a POST request to create a file system in the us-west-2 Region with automatic backups enabled. The request specifies myFileSystem1 as the creation token for idempotency.

Sample Request

```
POST /2015-02-01/file-systems HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20140620T215117Z
Authorization: <...>
Content-Type: application/json
Content-Length: 42

{
    "CreationToken" : "myFileSystem1",
    "PerformanceMode" : "generalPurpose",
    "Backup": true,
    "Encrypted": true,
    "Tags": [
        {
            "Key": "Name",
            "Value": "Test Group1"
        }
    ]
}
```

```
    ]  
}
```

Sample Response

```
HTTP/1.1 201 Created  
x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef  
Content-Type: application/json  
Content-Length: 319  
  
{  
    "ownerId": "251839141158",  
    "CreationToken": "myFileSystem1",  
    "Encrypted": true,  
    "PerformanceMode": "generalPurpose",  
    "fileSystemId": "fs-01234567",  
    "CreationTime": "1403301078",  
    "LifeCycleState": "creating",  
    "numberOfMountTargets": 0,  
    "SizeInBytes": {  
        "Timestamp": 1403301078,  
        "Value": 29313417216,  
        "ValueInIA": 675432,  
        "ValueInStandard": 29312741784  
    },  
    "Tags": [  
        {  
            "Key": "Name",  
            "Value": "Test Group1"  
        }  
    ],  
    "ThroughputMode": "bursting"  
}
```

Create an encrypted EFS file system that uses One Zone storage classes

The following example sends a POST request to create a file system in the us-west-2 Region with automatic backups enabled. The file system will have One Zone storage redundancy in the us-west-2b Availability Zone.

Sample Request

```
POST /2015-02-01/file-systems HTTP/1.1  
Host: elasticfilesystem.us-west-2.amazonaws.com  
x-amz-date: 20140620T215117Z  
Authorization: <...>  
Content-Type: application/json  
Content-Length: 42  
  
{  
    "CreationToken": "myFileSystem2",  
    "PerformanceMode": "generalPurpose",  
    "Backup": true,  
    "AvailabilityZoneName": "us-west-2b",  
    "Encrypted": true,  
    "ThroughputMode": "provisioned",  
    "ProvisionedThroughputInMbps": 60,  
    "Tags": [  
        {  
            "Key": "Name",  
            "Value": "Test Group1"  
        }  
    ]
```

```
    ]  
}
```

Sample Response

```
HTTP/1.1 201 Created  
x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef  
Content-Type: application/json  
Content-Length: 319  
  
{  
    "ownerId": "251839141158",  
    "CreationToken": "myFileSystem1",  
    "Encrypted": true,  
    "AvailabilityZoneId": "usew2-az2",  
    "AvailabilityZoneName": "us-west-2b",  
    "PerformanceMode": "generalPurpose",  
    "fileSystemId": "fs-01234567",  
    "CreationTime": "1403301078",  
    "LifeCycleState": "creating",  
    "numberOfMountTargets": 0,  
    "ProvisionedThroughputInMbps": 60,  
    "SizeInBytes": {  
        "Timestamp": 1403301078,  
        "Value": 29313417216,  
        "ValueInIA": 675432,  
        "ValueInStandard": 29312741784  
    },  
    "Tags": [  
        {  
            "Key": "Name",  
            "Value": "Test Group1"  
        }  
    ],  
    "ThroughputMode": "provisioned"  
}
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

CreateMountTarget

Creates a mount target for a file system. You can then mount the file system on EC2 instances by using the mount target.

You can create one mount target in each Availability Zone in your VPC. All EC2 instances in a VPC within a given Availability Zone share a single mount target for a given file system. If you have multiple subnets in an Availability Zone, you create a mount target in one of the subnets. EC2 instances do not need to be in the same subnet as the mount target in order to access their file system.

You can create only one mount target for an EFS file system using One Zone storage classes. You must create that mount target in the same Availability Zone in which the file system is located. Use the `AvailabilityZoneName` and `AvailabilityZoneId` properties in the [DescribeFileSystems \(p. 311\)](#) response object to get this information. Use the `subnetId` associated with the file system's Availability Zone when creating the mount target.

For more information, see [Amazon EFS: How it Works](#).

To create a mount target for a file system, the file system's lifecycle state must be available. For more information, see [DescribeFileSystems \(p. 311\)](#).

In the request, provide the following:

- The file system ID for which you are creating the mount target.
- A subnet ID, which determines the following:
 - The VPC in which Amazon EFS creates the mount target
 - The Availability Zone in which Amazon EFS creates the mount target
 - The IP address range from which Amazon EFS selects the IP address of the mount target (if you don't specify an IP address in the request)

After creating the mount target, Amazon EFS returns a response that includes, a `MountTargetId` and an `IpAddress`. You use this IP address when mounting the file system in an EC2 instance. You can also use the mount target's DNS name when mounting the file system. The EC2 instance on which you mount the file system by using the mount target can resolve the mount target's DNS name to its IP address. For more information, see [How it Works: Implementation Overview](#).

Note that you can create mount targets for a file system in only one VPC, and there can be only one mount target per Availability Zone. That is, if the file system already has one or more mount targets created for it, the subnet specified in the request to add another mount target must meet the following requirements:

- Must belong to the same VPC as the subnets of the existing mount targets
- Must not be in the same Availability Zone as any of the subnets of the existing mount targets

If the request satisfies the requirements, Amazon EFS does the following:

- Creates a new mount target in the specified subnet.
- Also creates a new network interface in the subnet as follows:
 - If the request provides an `IpAddress`, Amazon EFS assigns that IP address to the network interface. Otherwise, Amazon EFS assigns a free address in the subnet (in the same way that the Amazon EC2 `CreateNetworkInterface` call does when a request does not specify a primary private IP address).
 - If the request provides `SecurityGroups`, this network interface is associated with those security groups. Otherwise, it belongs to the default security group for the subnet's VPC.

- Assigns the description Mount target *fsmt-id* for file system *fs-id* where *fsmt-id* is the mount target ID, and *fs-id* is the FileSystemId.
- Sets the requesterManaged property of the network interface to true, and the requesterId value to EFS.

Each Amazon EFS mount target has one corresponding requester-managed EC2 network interface. After the network interface is created, Amazon EFS sets the NetworkInterfaceId field in the mount target's description to the network interface ID, and the IpAddress field to its address. If network interface creation fails, the entire CreateMountTarget operation fails.

Note

The CreateMountTarget call returns only after creating the network interface, but while the mount target state is still creating, you can check the mount target creation status by calling the [DescribeMountTargets \(p. 318\)](#) operation, which among other things returns the mount target state.

We recommend that you create a mount target in each of the Availability Zones. There are cost considerations for using a file system in an Availability Zone through a mount target created in another Availability Zone. For more information, see [Amazon EFS](#). In addition, by always using a mount target local to the instance's Availability Zone, you eliminate a partial failure scenario. If the Availability Zone in which your mount target is created goes down, then you can't access your file system through that mount target.

This operation requires permissions for the following action on the file system:

- elasticfilesystem:CreateMountTarget

This operation also requires permissions for the following Amazon EC2 actions:

- ec2:DescribeSubnets
- ec2:DescribeNetworkInterfaces
- ec2>CreateNetworkInterface

Request Syntax

```
POST /2015-02-01/mount-targets HTTP/1.1
Content-type: application/json

{
    "FileSystemId": "string",
    "IpAddress": "string",
    "SecurityGroups": [ "string" ],
    "SubnetId": "string"
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

[FileSystemId \(p. 273\)](#)

The ID of the file system for which to create the mount target.

Type: String

Length Constraints: Maximum length of 128.

Pattern: `^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9a-f]{8,40}|fs-[0-9a-f]{8,40})$`

Required: Yes

[IpAddress \(p. 273\)](#)

Valid IPv4 address within the address range of the specified subnet.

Type: String

Length Constraints: Minimum length of 7. Maximum length of 15.

Pattern: `^[0-9]{1,3}\.[0-9]{1,3}\.[0-9]{1,3}\.[0-9]{1,3}$`

Required: No

[SecurityGroups \(p. 273\)](#)

Up to five VPC security group IDs, of the form sg-xxxxxxxx. These must be for the same VPC as subnet specified.

Type: Array of strings

Array Members: Maximum number of 100 items.

Length Constraints: Minimum length of 11. Maximum length of 43.

Pattern: `^sg-[0-9a-f]{8,40}`

Required: No

[SubnetId \(p. 273\)](#)

The ID of the subnet to add the mount target in. For file systems that use One Zone storage classes, use the subnet that is associated with the file system's Availability Zone.

Type: String

Length Constraints: Minimum length of 15. Maximum length of 47.

Pattern: `^subnet-[0-9a-f]{8,40}$`

Required: Yes

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "AvailabilityZoneId": "string",
    "AvailabilityZoneName": "string",
    "FileSystemId": "string",
```

```
"IpAddress": "string",
"LifeCycleState": "string",
"MountTargetId": "string",
"NetworkInterfaceId": "string",
"OwnerId": "string",
"SubnetId": "string",
"VpcId": "string"
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

[AvailabilityZoneId \(p. 274\)](#)

The unique and consistent identifier of the Availability Zone that the mount target resides in. For example, use1-az1 is an AZ ID for the us-east-1 Region and it has the same location in every AWS account.

Type: String

[AvailabilityZoneName \(p. 274\)](#)

The name of the Availability Zone in which the mount target is located. Availability Zones are independently mapped to names for each AWS account. For example, the Availability Zone us-east-1a for your AWS account might not be the same location as us-east-1a for another AWS account.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: .+

[FileSystemId \(p. 274\)](#)

The ID of the file system for which the mount target is intended.

Type: String

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})\$

[IpAddress \(p. 274\)](#)

Address at which the file system can be mounted by using the mount target.

Type: String

Length Constraints: Minimum length of 7. Maximum length of 15.

Pattern: ^[0-9]{1,3}\.[0-9]{1,3}\.[0-9]{1,3}\.[0-9]{1,3}\$

[LifeCycleState \(p. 274\)](#)

Lifecycle state of the mount target.

Type: String

Valid Values: creating | available | updating | deleting | deleted | error

[MountTargetId \(p. 274\)](#)

System-assigned mount target ID.

Type: String

Length Constraints: Minimum length of 13. Maximum length of 45.

Pattern: ^fsmt-[0-9a-f]{8,40}\$

[NetworkInterfaceId \(p. 274\)](#)

The ID of the network interface that Amazon EFS created when it created the mount target.

Type: String

[OwnerId \(p. 274\)](#)

AWS account ID that owns the resource.

Type: String

Length Constraints: Maximum length of 14.

Pattern: ^(\d{12})|(\d{4}-\d{4}-\d{4})\$

[SubnetId \(p. 274\)](#)

The ID of the mount target's subnet.

Type: String

Length Constraints: Minimum length of 15. Maximum length of 47.

Pattern: ^subnet-[0-9a-f]{8,40}\$

[VpcId \(p. 274\)](#)

The virtual private cloud (VPC) ID that the mount target is configured in.

Type: String

Errors

AvailabilityZonesMismatch

Returned if the Availability Zone that was specified for a mount target is different from the Availability Zone that was specified for One Zone storage. For more information, see [Regional and One Zone storage redundancy](#).

HTTP Status Code: 400

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified FileSystemId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

IncorrectFileSystemLifeCycleState

Returned if the file system's lifecycle state is not "available".

HTTP Status Code: 409

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

IpAddressInUse

Returned if the request specified an `IpAddress` that is already in use in the subnet.

HTTP Status Code: 409

MountTargetConflict

Returned if the mount target would violate one of the specified restrictions based on the file system's existing mount targets.

HTTP Status Code: 409

NetworkInterfaceLimitExceeded

The calling account has reached the limit for elastic network interfaces for the specific AWS Region. Either delete some network interfaces or request that the account quota be raised. For more information, see [Amazon VPC Quotas](#) in the *Amazon VPC User Guide* (see the **Network interfaces per Region** entry in the **Network interfaces** table).

HTTP Status Code: 409

NoFreeAddressesInSubnet

Returned if `IpAddress` was not specified in the request and there are no free IP addresses in the subnet.

HTTP Status Code: 409

SecurityGroupLimitExceeded

Returned if the size of `SecurityGroups` specified in the request is greater than five.

HTTP Status Code: 400

SecurityGroupNotFound

Returned if one of the specified security groups doesn't exist in the subnet's virtual private cloud (VPC).

HTTP Status Code: 400

SubnetNotFound

Returned if there is no subnet with ID `SubnetId` provided in the request.

HTTP Status Code: 400

UnsupportedAvailabilityZone

Returned if the requested Amazon EFS functionality is not available in the specified Availability Zone.

HTTP Status Code: 400

Examples

Add a mount target to a file system

The following request creates a mount target for a file system. The request specifies values for only the required `FileSystemId` and `SubnetId` parameters. The request does not provide the optional `IpAddress` and `SecurityGroups` parameters. For `IpAddress`, the operation uses one of the available IP addresses in the specified subnet. And, the operation uses the default security group associated with the VPC for the `SecurityGroups`.

Sample Request

```
POST /2015-02-01/mount-targets HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20140620T221118Z
Authorization: <...>
Content-Type: application/json
Content-Length: 160

{"SubnetId": "subnet-748c5d03", "FileSystemId": "fs-01234567"}
```

Sample Response

```
HTTP/1.1 200 OK
x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef
Content-Type: application/json
Content-Length: 252

{
    "MountTargetId": "fsmt-55a4413c",
    "NetworkInterfaceId": "eni-01234567",
    "FileSystemId": "fs-01234567",
    "LifeCycleState": "available",
    "SubnetId": "subnet-01234567",
    "OwnerId": "231243201240",
    "IpAddress": "172.31.22.183"
}
```

Add a mount target to a file system

The following request specifies all the request parameters to create a mount target.

Sample Request

```
POST /2015-02-01/mount-targets HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20140620T221118Z
Authorization: <...>
Content-Type: application/json
Content-Length: 160

{
    "FileSystemId": "fs-01234567",
    "SubnetId": "subnet-01234567",
    "IpAddress": "10.0.2.42",
    "SecurityGroups": [
        "sg-01234567"
    ]
}
```

Sample Response

```
HTTP/1.1 200 OK
x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef
Content-Type: application/json
Content-Length: 252

{
    "OwnerId": "251839141158",
    "MountTargetId": "fsmt-9a13661e",
    "FileSystemId": "fs-01234567",
    "SubnetId": "subnet-fd04ff94",
    "LifeCycleState": "available",
    "IpAddress": "10.0.2.42",
    "NetworkInterfaceId": "eni-1bcb7772"
}
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

CreateReplicationConfiguration

Creates a replication configuration that replicates an existing EFS file system to a new, read-only file system. For more information, see [Amazon EFS replication](#) in the *Amazon EFS User Guide*. The replication configuration specifies the following:

- **Source file system** - An existing EFS file system that you want replicated. The source file system cannot be a destination file system in an existing replication configuration.
- **Destination file system configuration** - The configuration of the destination file system to which the source file system will be replicated. There can only be one destination file system in a replication configuration. The destination file system configuration consists of the following properties:
 - **AWS Region** - The AWS Region in which the destination file system is created. Amazon EFS replication is available in all AWS Regions that Amazon EFS is available in, except Africa (Cape Town), Asia Pacific (Hong Kong), Asia Pacific (Jakarta), Europe (Milan), and Middle East (Bahrain).
 - **Availability Zone** - If you want the destination file system to use EFS One Zone availability and durability, you must specify the Availability Zone to create the file system in. For more information about EFS storage classes, see [Amazon EFS storage classes](#) in the *Amazon EFS User Guide*.
 - **Encryption** - All destination file systems are created with encryption at rest enabled. You can specify the AWS Key Management Service (AWS KMS) key that is used to encrypt the destination file system. If you don't specify a KMS key, your service-managed KMS key for Amazon EFS is used.

Note

After the file system is created, you cannot change the KMS key.

The following properties are set by default:

- **Performance mode** - The destination file system's performance mode matches that of the source file system, unless the destination file system uses EFS One Zone storage. In that case, the General Purpose performance mode is used. The performance mode cannot be changed.
- **Throughput mode** - The destination file system uses the Bursting Throughput mode by default. After the file system is created, you can modify the throughput mode.

The following properties are turned off by default:

- **Lifecycle management** - EFS lifecycle management and EFS Intelligent-Tiering are not enabled on the destination file system. After the destination file system is created, you can enable EFS lifecycle management and EFS Intelligent-Tiering.
- **Automatic backups** - Automatic daily backups not enabled on the destination file system. After the file system is created, you can change this setting.

For more information, see [Amazon EFS replication](#) in the *Amazon EFS User Guide*.

Request Syntax

```
POST /2015-02-01/file-systems/SourceFileSystemId/replication-configuration HTTP/1.1
Content-type: application/json

{
  "Destinations": [
    {
      "AvailabilityZoneName": "string",
      "KmsKeyId": "string",
      "Region": "string"
    }
  ]
}
```

}

URI Request Parameters

The request uses the following URI parameters.

[SourceFileSystemId \(p. 280\)](#)

Specifies the Amazon EFS file system that you want to replicate. This file system cannot already be a source or destination file system in another replication configuration.

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9a-f]{8,40}|fs-[0-9a-f]{8,40})\$

Required: Yes

Request Body

The request accepts the following data in JSON format.

[Destinations \(p. 280\)](#)

An array of destination configuration objects. Only one destination configuration object is supported.

Type: Array of [DestinationToCreate \(p. 368\)](#) objects

Required: Yes

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "CreationTime": number,
    "Destinations": [
        {
            "FileSystemId": "string",
            "LastReplicatedTimestamp": number,
            "Region": "string",
            "Status": "string"
        }
    ],
    "OriginalSourceFileSystemArn": "string",
    "SourceFileSystemArn": "string",
    "SourceFileSystemId": "string",
    "SourceFileSystemRegion": "string"
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

[CreationTime \(p. 281\)](#)

Describes when the replication configuration was created.

Type: Timestamp

[Destinations \(p. 281\)](#)

An array of destination objects. Only one destination object is supported.

Type: Array of [Destination \(p. 366\)](#) objects

[OriginalSourceFileSystemArn \(p. 281\)](#)

The Amazon Resource Name (ARN) of the original source Amazon EFS file system in the replication configuration.

Type: String

[SourceFileSystemArn \(p. 281\)](#)

The Amazon Resource Name (ARN) of the current source file system in the replication configuration.

Type: String

[SourceFileSystemId \(p. 281\)](#)

The ID of the source Amazon EFS file system that is being replicated.

Type: String

Length Constraints: Maximum length of 128.

Pattern: `^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})$`

[SourceFileSystemRegion \(p. 281\)](#)

The AWS Region in which the source Amazon EFS file system is located.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: `^[a-z]{2}-((iso[a-z]{0,1}-)|(gov-)){0,1}[a-z]+-{0,1}[0-9]{0,1}$`

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemLimitExceeded

Returned if the AWS account has already created the maximum number of file systems allowed per account.

HTTP Status Code: 403

FileSystemNotFound

Returned if the specified `FileSystemId` value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

IncorrectFileSystemLifeCycleState

Returned if the file system's lifecycle state is not "available".

HTTP Status Code: 409

InsufficientThroughputCapacity

Returned if there's not enough capacity to provision additional throughput. This value might be returned when you try to create a file system in provisioned throughput mode, when you attempt to increase the provisioned throughput of an existing file system, or when you attempt to change an existing file system from Bursting Throughput to Provisioned Throughput mode. Try again later.

HTTP Status Code: 503

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

ReplicationNotFound

Returned if the specified file system does not have a replication configuration.

HTTP Status Code: 404

ThroughputLimitExceeded

Returned if the throughput mode or amount of provisioned throughput can't be changed because the throughput limit of 1024 MiB/s has been reached.

HTTP Status Code: 400

UnsupportedAvailabilityZone

Returned if the requested Amazon EFS functionality is not available in the specified Availability Zone.

HTTP Status Code: 400

ValidationException

Returned if the AWS Backup service is not available in the AWS Region in which the request was made.

HTTP Status Code: 400

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)

- [AWS SDK for Ruby V3](#)

CreateTags

Note

DEPRECATED - CreateTags is deprecated and not maintained. To create tags for EFS resources, use the [TagResource \(p. 350\)](#) API action.

Creates or overwrites tags associated with a file system. Each tag is a key-value pair. If a tag key specified in the request already exists on the file system, this operation overwrites its value with the value provided in the request. If you add the Name tag to your file system, Amazon EFS returns it in the response to the [DescribeFileSystems \(p. 311\)](#) operation.

This operation requires permission for the elasticfilesystem:CreateTags action.

Request Syntax

```
POST /2015-02-01/create-tags/FileSystemId HTTP/1.1
Content-type: application/json

{
  "Tags": [
    {
      "Key": "string",
      "Value": "string"
    }
  ]
}
```

URI Request Parameters

The request uses the following URI parameters.

[FileSystemId \(p. 285\)](#)

The ID of the file system whose tags you want to modify (String). This operation modifies the tags only, not the file system.

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9a-f]{8,40}|fs-[0-9a-f]{8,40})\$

Required: Yes

Request Body

The request accepts the following data in JSON format.

[Tags \(p. 285\)](#)

An array of Tag objects to add. Each Tag object is a key-value pair.

Type: Array of [Tag \(p. 384\)](#) objects

Required: Yes

Response Syntax

```
HTTP/1.1 204
```

Response Elements

If the action is successful, the service sends back an HTTP 204 response with an empty HTTP body.

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified FileSystemId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DeleteAccessPoint

Deletes the specified access point. After deletion is complete, new clients can no longer connect to the access points. Clients connected to the access point at the time of deletion will continue to function until they terminate their connection.

This operation requires permissions for the elasticfilesystem:DeleteAccessPoint action.

Request Syntax

```
DELETE /2015-02-01/access-points/AccessPointId HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

AccessPointId (p. 287)

The ID of the access point that you want to delete.

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:access-point/fsap-[0-9a-f]{8,40}|fsap-[0-9a-f]{8,40})\$

Required: Yes

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 204
```

Response Elements

If the action is successful, the service sends back an HTTP 204 response with an empty HTTP body.

Errors

AccessPointNotFound

Returned if the specified AccessPointId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DeleteFileSystem

Deletes a file system, permanently severing access to its contents. Upon return, the file system no longer exists and you can't access any contents of the deleted file system.

You need to manually delete mount targets attached to a file system before you can delete an EFS file system. This step is performed for you when you use the AWS console to delete a file system.

Note

You cannot delete a file system that is part of an EFS Replication configuration. You need to delete the replication configuration first.

You can't delete a file system that is in use. That is, if the file system has any mount targets, you must first delete them. For more information, see [DescribeMountTargets \(p. 318\)](#) and [DeleteMountTarget \(p. 294\)](#).

Note

The DeleteFileSystem call returns while the file system state is still deleting. You can check the file system deletion status by calling the [DescribeFileSystems \(p. 311\)](#) operation, which returns a list of file systems in your account. If you pass file system ID or creation token for the deleted file system, the [DescribeFileSystems \(p. 311\)](#) returns a 404 FileSystemNotFound error.

This operation requires permissions for the elasticfilesystem:DeleteFileSystem action.

Request Syntax

```
DELETE /2015-02-01/file-systems/FileSystemId HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

[FileSystemId \(p. 289\)](#)

The ID of the file system you want to delete.

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})\$

Required: Yes

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 204
```

Response Elements

If the action is successful, the service sends back an HTTP 204 response with an empty HTTP body.

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemInUse

Returned if a file system has mount targets.

HTTP Status Code: 409

FileSystemNotFound

Returned if the specified FileSystemId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

Examples

Delete a file system

The following example sends a DELETE request to the file-systems endpoint (`elasticfilesystem.us-west-2.amazonaws.com/2015-02-01/file-systems/fs-01234567`) to delete a file system whose ID is `fs-01234567`.

Sample Request

```
DELETE /2015-02-01/file-systems/fs-01234567 HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20140622T233021Z
Authorization: <...>
```

Sample Response

```
HTTP/1.1 204 No Content
x-amzn-RequestId: a2d125b3-7ebd-4d6a-ab3d-5548630bff33
Content-Length: 0
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)

- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DeleteFileSystemPolicy

Deletes the `FileSystemPolicy` for the specified file system. The default `FileSystemPolicy` goes into effect once the existing policy is deleted. For more information about the default file system policy, see [Using Resource-based Policies with EFS](#).

This operation requires permissions for the `elasticfilesystem:DeleteFileSystemPolicy` action.

Request Syntax

```
DELETE /2015-02-01/file-systems/FileSystemId/policy HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

FileSystemId (p. 292)

Specifies the EFS file system for which to delete the `FileSystemPolicy`.

Length Constraints: Maximum length of 128.

Pattern: `^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})$`

Required: Yes

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 200
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified `FileSystemId` value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

IncorrectFileSystemLifeCycleState

Returned if the file system's lifecycle state is not "available".

HTTP Status Code: 409

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DeleteMountTarget

Deletes the specified mount target.

This operation forcibly breaks any mounts of the file system by using the mount target that is being deleted, which might disrupt instances or applications using those mounts. To avoid applications getting cut off abruptly, you might consider unmounting any mounts of the mount target, if feasible. The operation also deletes the associated network interface. Uncommitted writes might be lost, but breaking a mount target using this operation does not corrupt the file system itself. The file system you created remains. You can mount an EC2 instance in your VPC by using another mount target.

This operation requires permissions for the following action on the file system:

- elasticfilesystem:DeleteMountTarget

Note

The DeleteMountTarget call returns while the mount target state is still deleting. You can check the mount target deletion by calling the [DescribeMountTargets \(p. 318\)](#) operation, which returns a list of mount target descriptions for the given file system.

The operation also requires permissions for the following Amazon EC2 action on the mount target's network interface:

- ec2:DeleteNetworkInterface

Request Syntax

```
DELETE /2015-02-01/mount-targets/MountTargetId HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

MountTargetId (p. 294)

The ID of the mount target to delete (String).

Length Constraints: Minimum length of 13. Maximum length of 45.

Pattern: ^fsmt-[0-9a-f]{8,40}\$

Required: Yes

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 204
```

Response Elements

If the action is successful, the service sends back an HTTP 204 response with an empty HTTP body.

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

DependencyTimeout

The service timed out trying to fulfill the request, and the client should try the call again.

HTTP Status Code: 504

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

MountTargetNotFound

Returned if there is no mount target with the specified ID found in the caller's AWS account.

HTTP Status Code: 404

Examples

Remove a file system's mount target

The following example sends a DELETE request to delete a specific mount target.

Sample Request

```
DELETE /2015-02-01/mount-targets/fsmt-9a13661e HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20140622T232908Z
Authorization: <...>
```

Sample Response

```
HTTP/1.1 204 No Content
x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)

- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DeleteReplicationConfiguration

Deletes an existing replication configuration. To delete a replication configuration, you must make the request from the AWS Region in which the destination file system is located. Deleting a replication configuration ends the replication process. After a replication configuration is deleted, the destination file system is no longer read-only. You can write to the destination file system after its status becomes `Writable`.

Request Syntax

```
DELETE /2015-02-01/file-systems/SourceFileSystemId/replication-configuration HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

SourceFileSystemId (p. 297)

The ID of the source file system in the replication configuration.

Length Constraints: Maximum length of 128.

Pattern: `^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})$`

Required: Yes

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 204
```

Response Elements

If the action is successful, the service sends back an HTTP 204 response with an empty HTTP body.

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified `FileSystemId` value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

ReplicationNotFound

Returned if the specified file system does not have a replication configuration.

HTTP Status Code: 404

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DeleteTags

Note

DEPRECATED - DeleteTags is deprecated and not maintained. To remove tags from EFS resources, use the [UntagResource \(p. 353\)](#) API action.

Deletes the specified tags from a file system. If the DeleteTags request includes a tag key that doesn't exist, Amazon EFS ignores it and doesn't cause an error. For more information about tags and related restrictions, see [Tag restrictions](#) in the *AWS Billing and Cost Management User Guide*.

This operation requires permissions for the elasticfilesystem:DeleteTags action.

Request Syntax

```
POST /2015-02-01/delete-tags/FileSystemId HTTP/1.1
Content-type: application/json

{
    "TagKeys": [ "string" ]
}
```

URI Request Parameters

The request uses the following URI parameters.

[FileSystemId \(p. 299\)](#)

The ID of the file system whose tags you want to delete (String).

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9af]{8,40})\$

Required: Yes

Request Body

The request accepts the following data in JSON format.

[TagKeys \(p. 299\)](#)

A list of tag keys to delete.

Type: Array of strings

Array Members: Minimum number of 1 item. Maximum number of 50 items.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: ^(?![aA]{1}[wW]{1}[sS]{1}:)([\p{L}\p{Z}\p{N}_.:/=+\-\@]+)\$

Required: Yes

Response Syntax

```
HTTP/1.1 204
```

Response Elements

If the action is successful, the service sends back an HTTP 204 response with an empty HTTP body.

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified FileSystemId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DescribeAccessPoints

Returns the description of a specific Amazon EFS access point if the AccessPointId is provided. If you provide an EFS FileSystemId, it returns descriptions of all access points for that file system. You can provide either an AccessPointId or a FileSystemId in the request, but not both.

This operation requires permissions for the elasticfilesystem:DescribeAccessPoints action.

Request Syntax

```
GET /2015-02-01/access-points?  
AccessPointId=AccessPointId&FileSystemId=FileSystemId&MaxResults=MaxResults&NextToken=NextToken  
HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

[AccessPointId \(p. 301\)](#)

(Optional) Specifies an EFS access point to describe in the response; mutually exclusive with FileSystemId.

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:access-point/fsap-[0-9a-f]{8,40}|fsap-[0-9a-f]{8,40})\$

[FileSystemId \(p. 301\)](#)

(Optional) If you provide a FileSystemId, EFS returns all access points for that file system; mutually exclusive with AccessPointId.

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9a-f]{8,40}|fs-[0-9a-f]{8,40})\$

[MaxResults \(p. 301\)](#)

(Optional) When retrieving all access points for a file system, you can optionally specify the MaxItems parameter to limit the number of objects returned in a response. The default value is 100.

Valid Range: Minimum value of 1.

[NextToken \(p. 301\)](#)

NextToken is present if the response is paginated. You can use NextMarker in the subsequent request to fetch the next page of access point descriptions.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "AccessPoints": [
        {
            "AccessPointArn": "string",
            "AccessPointId": "string",
            "ClientToken": "string",
            "FileSystemId": "string",
            "LifeCycleState": "string",
            "Name": "string",
            "OwnerId": "string",
            "PosixUser": {
                "Gid": number,
                "SecondaryGids": [ number ],
                "Uid": number
            },
            "RootDirectory": {
                "CreateInfo": {
                    "OwnerGid": number,
                    "OwnerUid": number,
                    "Permissions": "string"
                },
                "Path": "string"
            },
            "Tags": [
                {
                    "Key": "string",
                    "Value": "string"
                }
            ]
        },
        ...
    ],
    "NextToken": "string"
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

[AccessPoints \(p. 302\)](#)

An array of access point descriptions.

Type: Array of [AccessPointDescription \(p. 361\)](#) objects

[NextToken \(p. 302\)](#)

Present if there are more access points than returned in the response. You can use the NextMarker in the subsequent request to fetch the additional descriptions.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

Errors

AccessPointNotFound

Returned if the specified AccessPointId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified FileSystemId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DescribeAccountPreferences

Returns the account preferences settings for the AWS account associated with the user making the request, in the current AWS Region. For more information, see [Managing Amazon EFS resource IDs](#).

Request Syntax

```
GET /2015-02-01/account-preferences HTTP/1.1
Content-type: application/json

{
    "MaxResults": number,
    "NextToken": "string"
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

[MaxResults \(p. 304\)](#)

(Optional) When retrieving account preferences, you can optionally specify the MaxItems parameter to limit the number of objects returned in a response. The default value is 100.

Type: Integer

Valid Range: Minimum value of 1.

Required: No

[NextToken \(p. 304\)](#)

(Optional) You can use NextToken in a subsequent request to fetch the next page of AWS account preferences if the response payload was paginated.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

Required: No

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "NextToken": "string",
    "ResourceIdPreference": {
        "ResourceIdType": "string",
        "Resources": [ "string" ]
```

```
    }
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

[NextToken \(p. 304\)](#)

Present if there are more records than returned in the response. You can use the NextToken in the subsequent request to fetch the additional descriptions.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

[ResourceIdPreference \(p. 304\)](#)

Describes the resource ID preference setting for the AWS account associated with the user making the request, in the current AWS Region.

Type: [ResourceIdPreference \(p. 382\)](#) object

Errors

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DescribeBackupPolicy

Returns the backup policy for the specified EFS file system.

Request Syntax

```
GET /2015-02-01/file-systems/FileSystemId/backup-policy HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

FileSystemId (p. 306)

Specifies which EFS file system to retrieve the BackupPolicy for.

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})\$

Required: Yes

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "BackupPolicy": {
        "Status": "string"
    }
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

BackupPolicy (p. 306)

Describes the file system's backup policy, indicating whether automatic backups are turned on or off.

Type: [BackupPolicy \(p. 363\)](#) object

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified FileSystemId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

PolicyNotFound

Returned if the default file system policy is in effect for the EFS file system specified.

HTTP Status Code: 404

ValidationException

Returned if the AWS Backup service is not available in the AWS Region in which the request was made.

HTTP Status Code: 400

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DescribeFileSystemPolicy

Returns the `FileSystemPolicy` for the specified EFS file system.

This operation requires permissions for the `elasticfilesystem:DescribeFileSystemPolicy` action.

Request Syntax

```
GET /2015-02-01/file-systems/FileSystemId/policy HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

`FileSystemId` (p. 308)

Specifies which EFS file system to retrieve the `FileSystemPolicy` for.

Length Constraints: Maximum length of 128.

Pattern: `^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9a-f]{8,40}|fs-[0-9a-f]{8,40})$`

Required: Yes

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "FileSystemId": "string",
    "Policy": "string"
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

`FileSystemId` (p. 308)

Specifies the EFS file system to which the `FileSystemPolicy` applies.

Type: String

Length Constraints: Maximum length of 128.

Pattern: `^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9a-f]{8,40}|fs-[0-9a-f]{8,40})$`

Policy (p. 308)

The JSON formatted `FileSystemPolicy` for the EFS file system.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 20000.

Pattern: `[\s\S]+`

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified `FileSystemId` value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

PolicyNotFound

Returned if the default file system policy is in effect for the EFS file system specified.

HTTP Status Code: 404

Examples

Example

This example illustrates one usage of `DescribeFileSystemPolicy`.

Sample Request

```
GET /2015-02-01/file-systems/fs-01234567/policy HTTP/1.1
```

Sample Response

```
{
    "FileSystemId": "fs-01234567",
    "Policy": "{",
        "Version": "2012-10-17",
        "Id": "efs-policy-wizard-cdef0123-aaaa-6666-5555-444455556666",
        "Statement": [
            {
                "Sid": "efs-statement-abcdef01-1111-bbbb-2222-111122224444",
                "Effect" : "Deny",
                "Principal": {
                    "AWS": "*"
                }
            }
        ]
    }
}
```

```
        },
        "Action": "*",
        "Resource": "arn:aws:elasticfilesystem:us-east-2:111122223333:file-system/
fs-01234567",
        "Condition": {
            "Bool": {
                "aws:SecureTransport": "false"
            }
        }
    },
    {
        "Sid": "efs-statement-01234567-aaaa-3333-4444-111122223333",
        "Effect": "Allow",
        "Principal": {
            "AWS": "*"
        },
        "Action": [
            "elasticfilesystem:ClientMount",
            "elasticfilesystem:ClientWrite"
        ],
        "Resource" : "arn:aws:elasticfilesystem:us-east-2:111122223333:file-system/
fs-01234567"
    }
}
}
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DescribeFileSystems

Returns the description of a specific Amazon EFS file system if either the file system `CreationToken` or the `FileSystemId` is provided. Otherwise, it returns descriptions of all file systems owned by the caller's AWS account in the AWS Region of the endpoint that you're calling.

When retrieving all file system descriptions, you can optionally specify the `MaxItems` parameter to limit the number of descriptions in a response. Currently, this number is automatically set to 10. If more file system descriptions remain, Amazon EFS returns a `NextMarker`, an opaque token, in the response. In this case, you should send a subsequent request with the `Marker` request parameter set to the value of `NextMarker`.

To retrieve a list of your file system descriptions, this operation is used in an iterative process, where `DescribeFileSystems` is called first without the `Marker` and then the operation continues to call it with the `Marker` parameter set to the value of the `NextMarker` from the previous response until the response has no `NextMarker`.

The order of file systems returned in the response of one `DescribeFileSystems` call and the order of file systems returned across the responses of a multi-call iteration is unspecified.

This operation requires permissions for the `elasticfilesystem:DescribeFileSystems` action.

Request Syntax

```
GET /2015-02-01/file-systems?  
CreationToken=CreationToken&FileSystemId=FileSystemId&Marker=Marker&MaxItems=MaxItems  
HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

CreationToken (p. 311)

(Optional) Restricts the list to the file system with this creation token (String). You specify a creation token when you create an Amazon EFS file system.

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: .+

FileSystemId (p. 311)

(Optional) ID of the file system whose description you want to retrieve (String).

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})\$

Marker (p. 311)

(Optional) Opaque pagination token returned from a previous `DescribeFileSystems` operation (String). If present, specifies to continue the list from where the returning call had left off.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

MaxItems (p. 311)

(Optional) Specifies the maximum number of file systems to return in the response (integer). This number is automatically set to 100. The response is paginated at 100 per page if you have more than 100 file systems.

Valid Range: Minimum value of 1.

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "FileSystems": [
        {
            "AvailabilityZoneId": "string",
            "AvailabilityZoneName": "string",
            "CreationTime": "number",
            "CreationToken": "string",
            "Encrypted": "boolean",
            "FileSystemArn": "string",
            "FileSystemId": "string",
            "KmsKeyId": "string",
            "LifeCycleState": "string",
            "Name": "string",
            "NumberOfMountTargets": "number",
            "OwnerId": "string",
            "PerformanceMode": "string",
            "ProvisionedThroughputInMbps": "number",
            "SizeInBytes": {
                "Timestamp": "number",
                "Value": "number",
                "ValueInIA": "number",
                "ValueInStandard": "number"
            },
            "Tags": [
                {
                    "Key": "string",
                    "Value": "string"
                }
            ],
            "ThroughputMode": "string"
        }
    ],
    "Marker": "string",
    "NextMarker": "string"
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

[FileSystems \(p. 312\)](#)

An array of file system descriptions.

Type: Array of [FileSystemDescription \(p. 370\)](#) objects

[Marker \(p. 312\)](#)

Present if provided by caller in the request (String).

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

[NextMarker \(p. 312\)](#)

Present if there are more file systems than returned in the response (String). You can use the `NextMarker` in the subsequent request to fetch the descriptions.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified `FileSystemId` value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

Examples

[Retrieve a list of 10 file systems](#)

The following example sends a GET request to the `file-systems` endpoint (`elasticfilesystem.us-west-2.amazonaws.com/2015-02-01/file-systems`). The request specifies a `MaxItems` query parameter to limit the number of file system descriptions to 10.

[Sample Request](#)

```
GET /2015-02-01/file-systems?MaxItems=10 HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20140622T191208Z
```

Authorization: <...>

Sample Response

```
HTTP/1.1 200 OK
x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef
Content-Type: application/json
Content-Length: 499
{
    "FileSystems": [
        {
            "OwnerId": "251839141158",
            "CreationToken": "MyFileSystem1",
            "FileSystemId": "fs-01234567",
            "PerformanceMode": "generalPurpose",
            "CreationTime": "1403301078",
            "LifeCycleState": "created",
            "Name": "my first file system",
            "NumberOfMountTargets": 1,
            "SizeInBytes": {
                "Timestamp": 1403301078,
                "Value": 29313417216,
                "ValueInIA": 675432,
                "ValueInStandard": 29312741784
            }
        }
    ]
}
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DescribeLifecycleConfiguration

Returns the current LifecycleConfiguration object for the specified Amazon EFS file system. EFS lifecycle management uses the LifecycleConfiguration object to identify which files to move to the EFS Infrequent Access (IA) storage class. For a file system without a LifecycleConfiguration object, the call returns an empty array in the response.

When EFS Intelligent-Tiering is enabled, TransitionToPrimaryStorageClass has a value of AFTER_1_ACCESS.

This operation requires permissions for the elasticfilesystem:DescribeLifecycleConfiguration operation.

Request Syntax

```
GET /2015-02-01/file-systems/FileSystemId/lifecycle-configuration HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

FileSystemId (p. 315)

The ID of the file system whose LifecycleConfiguration object you want to retrieve (String).

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})\$

Required: Yes

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "LifecyclePolicies": [
        {
            "TransitionToIA": "string",
            "TransitionToPrimaryStorageClass": "string"
        }
    ]
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

LifecyclePolicies (p. 315)

An array of lifecycle management policies. EFS supports a maximum of one policy per file system.

Type: Array of [LifecyclePolicy \(p. 375\)](#) objects

Array Members: Maximum number of 2 items.

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified `FileSystemId` value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

Examples

Retrieve the lifecycle configuration for a file system

The following request retrieves the `LifecycleConfiguration` object for the specified file system.

Sample Request

```
GET /2015-02-01/file-systems/fs-01234567/lifecycle-configuration HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20181120T221118Z
Authorization: <...>
```

Sample Response

```
HTTP/1.1 200 OK
x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef
Content-Type: application/json
Content-Length: 86
{
    "LifecyclePolicies": [
        {
            "TransitionToIA": "AFTER_14_DAYS"
        },
        {
            "TransitionToPrimaryStorageClass": "AFTER_1_ACCESS"
        }
    ]
}
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DescribeMountTargets

Returns the descriptions of all the current mount targets, or a specific mount target, for a file system. When requesting all of the current mount targets, the order of mount targets returned in the response is unspecified.

This operation requires permissions for the elasticfilesystem:DescribeMountTargets action, on either the file system ID that you specify in `FileSystemId`, or on the file system of the mount target that you specify in `MountTargetId`.

Request Syntax

```
GET /2015-02-01/mount-targets?  
AccessPointId=AccessPointId&FileSystemId=FileSystemId&Marker=Marker&MaxItems=MaxItems&MountTargetId=MountTargetId  
HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

[AccessPointId \(p. 318\)](#)

(Optional) The ID of the access point whose mount targets that you want to list. It must be included in your request if a `FileSystemId` or `MountTargetId` is not included in your request. Accepts either an access point ID or ARN as input.

Length Constraints: Maximum length of 128.

Pattern: ^(`arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:access-point/fsap-[0-9a-f]{8,40}|fsap-[0-9a-f]{8,40}`)\$

[FileSystemId \(p. 318\)](#)

(Optional) ID of the file system whose mount targets you want to list (String). It must be included in your request if an `AccessPointId` or `MountTargetId` is not included. Accepts either a file system ID or ARN as input.

Length Constraints: Maximum length of 128.

Pattern: ^(`arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9a-f]{8,40}|fs-[0-9a-f]{8,40}`)\$

[Marker \(p. 318\)](#)

(Optional) Opaque pagination token returned from a previous `DescribeMountTargets` operation (String). If present, it specifies to continue the list from where the previous returning call left off.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

[MaxItems \(p. 318\)](#)

(Optional) Maximum number of mount targets to return in the response. Currently, this number is automatically set to 10, and other values are ignored. The response is paginated at 100 per page if you have more than 100 mount targets.

Valid Range: Minimum value of 1.

[MountTargetId \(p. 318\)](#)

(Optional) ID of the mount target that you want to have described (String). It must be included in your request if FileSystemId is not included. Accepts either a mount target ID or ARN as input.

Length Constraints: Minimum length of 13. Maximum length of 45.

Pattern: ^fsmt-[0-9a-f]{8,40}\$

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "Marker": "string",
    "MountTargets": [
        {
            "AvailabilityZoneId": "string",
            "AvailabilityZoneName": "string",
            "FileSystemId": "string",
            "IpAddress": "string",
            "LifeCycleState": "string",
            "MountTargetId": "string",
            "NetworkInterfaceId": "string",
            "OwnerId": "string",
            "SubnetId": "string",
            "VpcId": "string"
        }
    ],
    "NextMarker": "string"
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

[Marker \(p. 319\)](#)

If the request included the Marker, the response returns that value in this field.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

[MountTargets \(p. 319\)](#)

Returns the file system's mount targets as an array of MountTargetDescription objects.

Type: Array of [MountTargetDescription \(p. 376\)](#) objects

[NextMarker \(p. 319\)](#)

If a value is present, there are more mount targets to return. In a subsequent request, you can provide `Marker` in your request with this value to retrieve the next set of mount targets.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

Errors

AccessPointNotFound

Returned if the specified `AccessPointId` value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified `FileSystemId` value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

MountTargetNotFound

Returned if there is no mount target with the specified ID found in the caller's AWS account.

HTTP Status Code: 404

Examples

[Retrieve descriptions of mount targets created for a file system](#)

The following request retrieves descriptions of mount targets created for the specified file system.

[Sample Request](#)

```
GET /2015-02-01/mount-targets?FileSystemId=fs-01234567 HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20140622T191252Z
Authorization: <...>
```

[Sample Response](#)

```
HTTP/1.1 200 OK
```

```
x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef
Content-Type: application/json
Content-Length: 357

{
    "MountTargets": [
        {
            "OwnerId": "251839141158",
            "MountTargetId": "fsmt-01234567",
            "FileSystemId": "fs-01234567",
            "SubnetId": "subnet-01234567",
            "LifeCycleState": "added",
            "IpAddress": "10.0.2.42",
            "NetworkInterfaceId": "eni-1bcb7772"
        }
    ]
}
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DescribeMountTargetSecurityGroups

Returns the security groups currently in effect for a mount target. This operation requires that the network interface of the mount target has been created and the lifecycle state of the mount target is not deleted.

This operation requires permissions for the following actions:

- `elasticfilesystem:DescribeMountTargetSecurityGroups` action on the mount target's file system.
- `ec2:DescribeNetworkInterfaceAttribute` action on the mount target's network interface.

Request Syntax

```
GET /2015-02-01/mount-targets/MountTargetId/security-groups HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

MountTargetId (p. 322)

The ID of the mount target whose security groups you want to retrieve.

Length Constraints: Minimum length of 13. Maximum length of 45.

Pattern: ^fsmt-[0-9a-f]{8,40}\$

Required: Yes

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "SecurityGroups": [ "string" ]
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

SecurityGroups (p. 322)

An array of security groups.

Type: Array of strings

Array Members: Maximum number of 100 items.

Length Constraints: Minimum length of 11. Maximum length of 43.

Pattern: ^sg-[0-9a-f]{8,40}

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

IncorrectMountTargetState

Returned if the mount target is not in the correct state for the operation.

HTTP Status Code: 409

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

MountTargetNotFound

Returned if there is no mount target with the specified ID found in the caller's AWS account.

HTTP Status Code: 404

Examples

Retrieve security groups in effect for a file system

The following example retrieves the security groups that are in effect for the network interface associated with a mount target.

Sample Request

```
GET /2015-02-01/mount-targets/fsmt-9a13661e/security-groups HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20140620T223513Z
Authorization: <...>
```

Sample Response

```
HTTP/1.1 200 OK
x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef
Content-Length: 57

{
"SecurityGroups" : [
"sg-188d9f74"
]
}
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DescribeReplicationConfigurations

Retrieves the replication configuration for a specific file system. If a file system is not specified, all of the replication configurations for the AWS account in an AWS Region are retrieved.

Request Syntax

```
GET /2015-02-01/file-systems/replication-configurations?  
FileSystemId=FileSystemId&MaxResults=MaxResults&NextToken=NextToken HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

FileSystemId (p. 325)

You can retrieve the replication configuration for a specific file system by providing its file system ID.

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9a-f]{8,40}|fs-[0-9a-f]{8,40})\$

MaxResults (p. 325)

(Optional) To limit the number of objects returned in a response, you can specify the **MaxItems** parameter. The default value is 100.

Valid Range: Minimum value of 1.

NextToken (p. 325)

NextToken is present if the response is paginated. You can use **NextToken** in a subsequent request to fetch the next page of output.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 200  
Content-type: application/json  
  
{  
    "NextToken": "string",  
    "Replications": [  
        {  
            "CreationTime": number,  
            "Destinations": [  
                {  
                    "FileSystemId": "string",  
                    "LastReplicatedTimestamp": number,  
                    "Region": "string",  
                    "Status": "string"  
                }  
            ]  
        }  
    ]  
}
```

```
        }
    ],
    "OriginalSourceFileSystemArn": "string",
    "SourceFileSystemArn": "string",
    "SourceFileSystemId": "string",
    "SourceFileSystemRegion": "string"
}
]
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

[NextToken \(p. 325\)](#)

You can use the `NextToken` from the previous response in a subsequent request to fetch the additional descriptions.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

[Replications \(p. 325\)](#)

The collection of replication configurations that is returned.

Type: Array of [ReplicationConfigurationDescription \(p. 380\)](#) objects

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified `FileSystemId` value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

ReplicationNotFound

Returned if the specified file system does not have a replication configuration.

HTTP Status Code: 404

ValidationException

Returned if the AWS Backup service is not available in the AWS Region in which the request was made.

HTTP Status Code: 400

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

DescribeTags

Note

DEPRECATED - The `DescribeTags` action is deprecated and not maintained. To view tags associated with EFS resources, use the `ListTagsForResource` API action.

Returns the tags associated with a file system. The order of tags returned in the response of one `DescribeTags` call and the order of tags returned across the responses of a multiple-call iteration (when using pagination) is unspecified.

This operation requires permissions for the `elasticfilesystem:DescribeTags` action.

Request Syntax

```
GET /2015-02-01/tags/FileSystemId?Marker=Marker&MaxItems=MaxItems HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

[FileSystemId](#) (p. 328)

The ID of the file system whose tag set you want to retrieve.

Length Constraints: Maximum length of 128.

Pattern: ^([arn:aws\[-a-z\]*:elasticfilesystem:\[0-9a-z-:\]+:file-system/fs-\[0-9af\]{8,40}|fs-\[0-9a-f\]{8,40}\)\\$](#)

Required: Yes

[Marker](#) (p. 328)

(Optional) An opaque pagination token returned from a previous `DescribeTags` operation (String). If present, it specifies to continue the list from where the previous call left off.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

[MaxItems](#) (p. 328)

(Optional) The maximum number of file system tags to return in the response. Currently, this number is automatically set to 100, and other values are ignored. The response is paginated at 100 per page if you have more than 100 tags.

Valid Range: Minimum value of 1.

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 200
Content-type: application/json
```

```
{  
    "Marker": "string",  
    "NextMarker": "string",  
    "Tags": [  
        {  
            "Key": "string",  
            "Value": "string"  
        }  
    ]  
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

[Marker \(p. 328\)](#)

If the request included a `Marker`, the response returns that value in this field.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

[NextMarker \(p. 328\)](#)

If a value is present, there are more tags to return. In a subsequent request, you can provide the value of `NextMarker` as the value of the `Marker` parameter in your next request to retrieve the next set of tags.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

[Tags \(p. 328\)](#)

Returns tags associated with the file system as an array of Tag objects.

Type: Array of [Tag \(p. 384\)](#) objects

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified `FileSystemId` value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

Examples

Retrieve tags associated with a file system

The following request retrieves tags (key-value pairs) associated with the specified file system.

Sample Request

```
GET /2015-02-01/tags/fs-01234567/ HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20140620T215404Z
Authorization: <...>
```

Sample Response

```
HTTP/1.1 200 OK
x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef
Content-Type: application/json
Content-Length: 288

{
    "Tags": [
        {
            "Key": "Name",
            "Value": "my first file system"
        },
        {
            "Key": "Fleet",
            "Value": "Development"
        },
        {
            "Key": "Developer",
            "Value": "Alice"
        }
    ]
}
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

ListTagsForResource

Lists all tags for a top-level EFS resource. You must provide the ID of the resource that you want to retrieve the tags for.

This operation requires permissions for the elasticfilesystem:DescribeAccessPoints action.

Request Syntax

```
GET /2015-02-01/resource-tags/ResourceId?MaxResults=MaxResults&NextToken=NextToken HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

MaxResults (p. 331)

(Optional) Specifies the maximum number of tag objects to return in the response. The default value is 100.

Valid Range: Minimum value of 1.

NextToken (p. 331)

(Optional) You can use NextToken in a subsequent request to fetch the next page of access point descriptions if the response payload was paginated.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

ResourceId (p. 331)

Specifies the EFS resource you want to retrieve tags for. You can retrieve tags for EFS file systems and access points using this API endpoint.

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:(access-point/fsap|file-system/fs)-[0-9a-f]{8,40}|fs(ap)?-[0-9a-f]{8,40})\$

Required: Yes

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "NextToken": "string",
    "Tags": [
        {
            "Key": "string",
            "Value": "string"
        }
    ]
}
```

```
    ]  
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

[NextToken \(p. 331\)](#)

NextToken is present if the response payload is paginated. You can use NextToken in a subsequent request to fetch the next page of access point descriptions.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: .+

[Tags \(p. 331\)](#)

An array of the tags for the specified EFS resource.

Type: Array of [Tag \(p. 384\)](#) objects

Errors

AccessPointNotFound

Returned if the specified AccessPointId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified FileSystemId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

ModifyMountTargetSecurityGroups

Modifies the set of security groups in effect for a mount target.

When you create a mount target, Amazon EFS also creates a new network interface. For more information, see [CreateMountTarget \(p. 272\)](#). This operation replaces the security groups in effect for the network interface associated with a mount target, with the `SecurityGroups` provided in the request. This operation requires that the network interface of the mount target has been created and the lifecycle state of the mount target is not deleted.

The operation requires permissions for the following actions:

- `elasticfilesystem:ModifyMountTargetSecurityGroups` action on the mount target's file system.
- `ec2:ModifyNetworkInterfaceAttribute` action on the mount target's network interface.

Request Syntax

```
PUT /2015-02-01/mount-targets/MountTargetId/security-groups HTTP/1.1
Content-type: application/json

{
    "SecurityGroups": [ "string" ]
}
```

URI Request Parameters

The request uses the following URI parameters.

[MountTargetId \(p. 334\)](#)

The ID of the mount target whose security groups you want to modify.

Length Constraints: Minimum length of 13. Maximum length of 45.

Pattern: ^fsmt-[0-9a-f]{8,40}\$

Required: Yes

Request Body

The request accepts the following data in JSON format.

[SecurityGroups \(p. 334\)](#)

An array of up to five VPC security group IDs.

Type: Array of strings

Array Members: Maximum number of 100 items.

Length Constraints: Minimum length of 11. Maximum length of 43.

Pattern: ^sg-[0-9a-f]{8,40}

Required: No

Response Syntax

```
HTTP/1.1 204
```

Response Elements

If the action is successful, the service sends back an HTTP 204 response with an empty HTTP body.

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

IncorrectMountTargetState

Returned if the mount target is not in the correct state for the operation.

HTTP Status Code: 409

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

MountTargetNotFound

Returned if there is no mount target with the specified ID found in the caller's AWS account.

HTTP Status Code: 404

SecurityGroupLimitExceeded

Returned if the size of SecurityGroups specified in the request is greater than five.

HTTP Status Code: 400

SecurityGroupNotFound

Returned if one of the specified security groups doesn't exist in the subnet's virtual private cloud (VPC).

HTTP Status Code: 400

Examples

Replace a mount target's security groups

The following example replaces security groups in effect for the network interface associated with a mount target.

Sample Request

```
PUT /2015-02-01/mount-targets/fsmt-9a13661e/security-groups HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20140620T223446Z
```

```
Authorization: <...>
Content-Type: application/json
Content-Length: 57

{
    "SecurityGroups" : [
        "sg-188d9f74"
    ]
}
```

Sample Response

```
HTTP/1.1 204 No Content
x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

PutAccountPreferences

Use this operation to set the account preference in the current AWS Region to use long 17 character (63 bit) or short 8 character (32 bit) resource IDs for new EFS file system and mount target resources. All existing resource IDs are not affected by any changes you make. You can set the ID preference during the opt-in period as EFS transitions to long resource IDs. For more information, see [Managing Amazon EFS resource IDs](#).

Note

Starting in October, 2021, you will receive an error if you try to set the account preference to use the short 8 character format resource ID. Contact AWS support if you receive an error and must use short IDs for file system and mount target resources.

Request Syntax

```
PUT /2015-02-01/account-preferences HTTP/1.1
Content-type: application/json

{
    "ResourceIdType": "string"
}
```

URI Request Parameters

The request does not use any URI parameters.

Request Body

The request accepts the following data in JSON format.

ResourceIdType (p. 337)

Specifies the EFS resource ID preference to set for the user's AWS account, in the current AWS Region, either LONG_ID (17 characters), or SHORT_ID (8 characters).

Note

Starting in October, 2021, you will receive an error when setting the account preference to SHORT_ID. Contact AWS support if you receive an error and must use short IDs for file system and mount target resources.

Type: String

Valid Values: LONG_ID | SHORT_ID

Required: Yes

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "ResourceIdPreference": {
        "ResourceIdType": "string",
        "Resources": [ "string" ]
    }
}
```

}

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

ResourceIdPreference (p. 337)

Describes the resource type and its ID preference for the user's AWS account, in the current AWS Region.

Type: [ResourceIdPreference \(p. 382\)](#) object

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

PutBackupPolicy

Updates the file system's backup policy. Use this action to start or stop automatic backups of the file system.

Request Syntax

```
PUT /2015-02-01/file-systems/FileSystemId/backup-policy HTTP/1.1
Content-type: application/json

{
    "BackupPolicy": {
        "Status": "string"
    }
}
```

URI Request Parameters

The request uses the following URI parameters.

[FileSystemId \(p. 339\)](#)

Specifies which EFS file system to update the backup policy for.

Length Constraints: Maximum length of 128.

Pattern: ^([arn:aws\[-a-z\]*:elasticfilesystem:\[0-9a-z-:\]+:file-system/fs-\[0-9af\]{8,40}|fs-\[0-9a-f\]{8,40}](#))\$

Required: Yes

Request Body

The request accepts the following data in JSON format.

[BackupPolicy \(p. 339\)](#)

The backup policy included in the PutBackupPolicy request.

Type: [BackupPolicy \(p. 363\)](#) object

Required: Yes

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "BackupPolicy": {
        "Status": "string"
    }
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

BackupPolicy (p. 339)

Describes the file system's backup policy, indicating whether automatic backups are turned on or off.

Type: [BackupPolicy \(p. 363\)](#) object

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified `FileSystemId` value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

IncorrectFileSystemLifeCycleState

Returned if the file system's lifecycle state is not "available".

HTTP Status Code: 409

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

ValidationException

Returned if the AWS Backup service is not available in the AWS Region in which the request was made.

HTTP Status Code: 400

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

PutFileSystemPolicy

Applies an Amazon EFS `FileSystemPolicy` to an Amazon EFS file system. A file system policy is an IAM resource-based policy and can contain multiple policy statements. A file system always has exactly one file system policy, which can be the default policy or an explicit policy set or updated using this API operation. EFS file system policies have a 20,000 character limit. When an explicit policy is set, it overrides the default policy. For more information about the default file system policy, see [Default EFS File System Policy](#).

Note

EFS file system policies have a 20,000 character limit.

This operation requires permissions for the `elasticfilesystem:PutFileSystemPolicy` action.

Request Syntax

```
PUT /2015-02-01/file-systems/FileSystemId/policy HTTP/1.1
Content-type: application/json

{
  "BypassPolicyLockoutSafetyCheck": boolean,
  "Policy": "string"
}
```

URI Request Parameters

The request uses the following URI parameters.

`FileSystemId` (p. 341)

The ID of the EFS file system that you want to create or update the `FileSystemPolicy` for.

Length Constraints: Maximum length of 128.

Pattern: `^arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40}$`

Required: Yes

Request Body

The request accepts the following data in JSON format.

`BypassPolicyLockoutSafetyCheck` (p. 341)

(Optional) A boolean that specifies whether or not to bypass the `FileSystemPolicy` lockout safety check. The lockout safety check determines whether the policy in the request will lock out, or prevent, the IAM principal that is making the request from making future `PutFileSystemPolicy` requests on this file system. Set `BypassPolicyLockoutSafetyCheck` to `True` only when you intend to prevent the IAM principal that is making the request from making subsequent `PutFileSystemPolicy` requests on this file system. The default value is `False`.

Type: Boolean

Required: No

[Policy \(p. 341\)](#)

The `FileSystemPolicy` that you're creating. Accepts a JSON formatted policy definition. EFS file system policies have a 20,000 character limit. To find out more about the elements that make up a file system policy, see [EFS Resource-based Policies](#).

Type: String

Length Constraints: Minimum length of 1. Maximum length of 20000.

Pattern: `[\s\S]+`

Required: Yes

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
  "FileSystemId": "string",
  "Policy": "string"
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

[FileSystemId \(p. 342\)](#)

Specifies the EFS file system to which the `FileSystemPolicy` applies.

Type: String

Length Constraints: Maximum length of 128.

Pattern: `^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})$`

[Policy \(p. 342\)](#)

The JSON formatted `FileSystemPolicy` for the EFS file system.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 20000.

Pattern: `[\s\S]+`

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified FileSystemId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

IncorrectFileSystemLifeCycleState

Returned if the file system's lifecycle state is not "available".

HTTP Status Code: 409

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

InvalidPolicyException

Returned if the FileSystemPolicy is malformed or contains an error such as a parameter value that is not valid or a missing required parameter. Returned in the case of a policy lockout safety check error.

HTTP Status Code: 400

Examples

Create an EFS FileSystemPolicy

The following request creates a FileSystemPolicy that allows all AWS principals to mount the specified EFS file system with read and write permissions.

Sample Request

```
PUT /2015-02-01/file-systems/fs-01234567/file-system-policy HTTP/1.1
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": [
                "elasticfilesystem:ClientMount",
                "elasticfilesystem:ClientWrite"
            ],
            "Principal": {
                "AWS": ["*"]
            }
        }
    ]
}
```

Sample Response

```
{
    "Version": "2012-10-17",
    "Id": "1",
    "Statement": [
        {
            "Sid": "efs-statement-abcdef01-1111-bbbb-2222-111122224444",
            "Effect": "Allow",
            "Action": [

```

```
        "elasticfilesystem:ClientMount",
        "elasticfilesystem:ClientWrite"
    ],
    "Principal": {
        "AWS": ["*"]
    },
    "Resource": "arn:aws:elasticfilesystem:us-east-1:1111222233334444:file-system/
fs-01234567"
}
]
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

PutLifecycleConfiguration

Use this action to manage EFS lifecycle management and intelligent tiering. A `LifecycleConfiguration` consists of one or more `LifecyclePolicy` objects that define the following:

- **EFS Lifecycle management** - When Amazon EFS automatically transitions files in a file system into the lower-cost Infrequent Access (IA) storage class.

To enable EFS Lifecycle management, set the value of `TransitionToIA` to one of the available options.

- **EFS Intelligent tiering** - When Amazon EFS automatically transitions files from IA back into the file system's primary storage class (Standard or One Zone Standard).

To enable EFS Intelligent Tiering, set the value of `TransitionToPrimaryStorageClass` to `AFTER_1_ACCESS`.

For more information, see [EFS Lifecycle Management](#).

Each Amazon EFS file system supports one lifecycle configuration, which applies to all files in the file system. If a `LifecycleConfiguration` object already exists for the specified file system, a `PutLifecycleConfiguration` call modifies the existing configuration. A `PutLifecycleConfiguration` call with an empty `LifecyclePolicies` array in the request body deletes any existing `LifecycleConfiguration` and turns off lifecycle management and intelligent tiering for the file system.

In the request, specify the following:

- The ID for the file system for which you are enabling, disabling, or modifying lifecycle management and intelligent tiering.
- A `LifecyclePolicies` array of `LifecyclePolicy` objects that define when files are moved into IA storage, and when they are moved back to Standard storage.

Note

Amazon EFS requires that each `LifecyclePolicy` object have only have a single transition, so the `LifecyclePolicies` array needs to be structured with separate `LifecyclePolicy` objects. See the example requests in the following section for more information.

This operation requires permissions for the `elasticfilesystem:PutLifecycleConfiguration` operation.

To apply a `LifecycleConfiguration` object to an encrypted file system, you need the same AWS Key Management Service permissions as when you created the encrypted file system.

Request Syntax

```
PUT /2015-02-01/file-systems/FileSystemId/lifecycle-configuration HTTP/1.1
Content-type: application/json

{
  "LifecyclePolicies": [
    {
      "TransitionToIA": "string",
      "TransitionToPrimaryStorageClass": "string"
    }
  ]
}
```

}

URI Request Parameters

The request uses the following URI parameters.

[FileSystemId \(p. 345\)](#)

The ID of the file system for which you are creating the LifecycleConfiguration object (String).

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})\$

Required: Yes

Request Body

The request accepts the following data in JSON format.

[LifecyclePolicies \(p. 345\)](#)

An array of LifecyclePolicy objects that define the file system's LifecycleConfiguration object. A LifecycleConfiguration object informs EFS lifecycle management and EFS Intelligent-Tiering of the following:

- When to move files in the file system from primary storage to the IA storage class.
- When to move files that are in IA storage to primary storage.

Note

When using the `put-lifecycle-configuration` CLI command or the `PutLifecycleConfiguration` API action, Amazon EFS requires that each `LifecyclePolicy` object have only a single transition. This means that in a request body, `LifecyclePolicies` must be structured as an array of `LifecyclePolicy` objects, one object for each transition, `TransitionToIA`, `TransitionToPrimaryStorageClass`. See the example requests in the following section for more information.

Type: Array of [LifecyclePolicy \(p. 375\)](#) objects

Array Members: Maximum number of 2 items.

Required: Yes

Response Syntax

```
HTTP/1.1 200
Content-type: application/json

{
    "LifecyclePolicies": [
        {
            "TransitionToIA": "string",
            "TransitionToPrimaryStorageClass": "string"
        }
    ]
}
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response.

The following data is returned in JSON format by the service.

[LifecyclePolicies \(p. 346\)](#)

An array of lifecycle management policies. EFS supports a maximum of one policy per file system.

Type: Array of [LifecyclePolicy \(p. 375\)](#) objects

Array Members: Maximum number of 2 items.

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified `FileSystemId` value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

IncorrectFileSystemLifeCycleState

Returned if the file system's lifecycle state is not "available".

HTTP Status Code: 409

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

Examples

Create a lifecycle configuration

The following example creates a `LifecyclePolicy` object using the `PutLifecycleConfiguration` action. This example creates a lifecycle policy that instructs EFS lifecycle management to do the following:

- Move all files in the file system that haven't been accessed in the last 30 days to the IA storage class.
- Move files that are in IA storage to primary storage (Standard or One Zone Standard) after they are first accessed.

For more information, see [EFS storage classes](#) and [EFS lifecycle management and intelligent tiering](#).

Sample Request

```
PUT /2015-02-01/file-systems/fs-0123456789abcdefb/lifecycle-configuration HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20181122T232908Z
Authorization: <...>
Content-type: application/json
Content-Length: 86

{
    "LifecyclePolicies": [
        {
            "TransitionToIA": "AFTER_60_DAYS"
        },
        {
            "TransitionToPrimaryStorage": "AFTER_1_ACCESS"
        }
    ]
}
```

Sample Response

```
HTTP/1.1 200 OK
x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef
Content-type: application/json
Content-Length: 86

{
    "LifecyclePolicies": [
        {
            "TransitionToIA": "AFTER_60_DAYS"
        },
        {
            "TransitionToPrimaryStorage": "AFTER_1_ACCESS"
        }
    ]
}
```

Example put-lifecycle-configuration CLI request

This example illustrates one usage of PutLifecycleConfiguration.

Sample Request

```
aws efs put-lifecycle-configuration \
--file-system-id fs-0123456789abcdefb \
--lifecycle-policies "[{"TransitionToIA":"AFTER_30_DAYS"}, {"TransitionToPrimaryStorageClass":"AFTER_1_ACCESS"}]" \
--region us-west-2 \
--profile adminuser
```

Sample Response

```
{
    "LifecyclePolicies": [
        {
            "TransitionToIA": "AFTER_30_DAYS"
        },
        {
            "TransitionToPrimaryStorageClass": "AFTER_1_ACCESS"
        }
    ]
}
```

}

Disable lifecycle management

The following example disables lifecycle management for the specified file system.

Sample Request

```
PUT /2015-02-01/file-systems/fs-01234567/lifecycle-configuration HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20181122T232908Z
Authorization: <...>
Content-type: application/json
Content-Length: 86

{
    "LifecyclePolicies": [ ]
}
```

Sample Response

```
HTTP/1.1 200 OK
x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef
Content-type: application/json
Content-Length: 86

{
    "LifecyclePolicies": [ ]
}
```

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

TagResource

Creates a tag for an EFS resource. You can create tags for EFS file systems and access points using this API operation.

This operation requires permissions for the elasticfilesystem:TagResource action.

Request Syntax

```
POST /2015-02-01/resource-tags/ResourceId HTTP/1.1
Content-type: application/json

{
  "Tags": [
    {
      "Key": "string",
      "Value": "string"
    }
  ]
}
```

URI Request Parameters

The request uses the following URI parameters.

ResourceId (p. 350)

The ID specifying the EFS resource that you want to create a tag for.

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:(access-point/fsap|file-system/fs)-[0-9a-f]{8,40}|fs(ap)?-[0-9a-f]{8,40})\$

Required: Yes

Request Body

The request accepts the following data in JSON format.

Tags (p. 350)

An array of Tag objects to add. Each Tag object is a key-value pair.

Type: Array of [Tag](#) (p. 384) objects

Required: Yes

Response Syntax

```
HTTP/1.1 200
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

Errors

AccessPointNotFound

Returned if the specified AccessPointId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified FileSystemId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

Examples

Create Tags on a File System

The following request creates three tags ("key1", "key2", and "key3") on the specified file system.

Sample Request

```
POST /2015-02-01/tag-resource/fs-01234567 HTTP/1.1
Host: elasticfilesystem.us-west-2.amazonaws.com
x-amz-date: 20140620T221118Z
Authorization: <...>
Content-Type: application/json
Content-Length: 160

{
    "Tags": [
        {
            "Key": "key1",
            "Value": "value1"
        },
        {
            "Key": "key2",
            "Value": "value2"
        },
        {
            "Key": "key3",
            "Value": "value3"
        }
    ]
}
```

Sample Response

```
HTTP/1.1 204 no content
```

x-amzn-RequestId: 01234567-89ab-cdef-0123-456789abcdef

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

UntagResource

Removes tags from an EFS resource. You can remove tags from EFS file systems and access points using this API operation.

This operation requires permissions for the elasticfilesystem:UntagResource action.

Request Syntax

```
DELETE /2015-02-01/resource-tags/ResourceId?tagKeys=TagKeys HTTP/1.1
```

URI Request Parameters

The request uses the following URI parameters.

ResourceId (p. 353)

Specifies the EFS resource that you want to remove tags from.

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:(access-point/fsap|file-system/fs)-[0-9a-f]{8,40}|fs(ap)?-[0-9a-f]{8,40})\$

Required: Yes

TagKeys (p. 353)

The keys of the key-value tag pairs that you want to remove from the specified EFS resource.

Array Members: Minimum number of 1 item. Maximum number of 50 items.

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: ^(?![aA]{1}[wW]{1}[sS]{1}:[)([\p{L}\p{Z}\p{N}_.:/=+\-@]+)\$

Required: Yes

Request Body

The request does not have a request body.

Response Syntax

```
HTTP/1.1 200
```

Response Elements

If the action is successful, the service sends back an HTTP 200 response with an empty HTTP body.

Errors

AccessPointNotFound

Returned if the specified AccessPointId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified FileSystemId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

UpdateFileSystem

Updates the throughput mode or the amount of provisioned throughput of an existing file system.

Request Syntax

```
PUT /2015-02-01/file-systems/FileSystemId HTTP/1.1
Content-type: application/json

{
    "ProvisionedThroughputInMbps": number,
    "ThroughputMode": "string"
}
```

URI Request Parameters

The request uses the following URI parameters.

FileSystemId (p. 355)

The ID of the file system that you want to update.

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})\$

Required: Yes

Request Body

The request accepts the following data in JSON format.

ProvisionedThroughputInMbps (p. 355)

(Optional) Sets the amount of provisioned throughput, in MiB/s, for the file system. Valid values are 1-1024. If you are changing the throughput mode to provisioned, you must also provide the amount of provisioned throughput. Required if ThroughputMode is changed to provisioned on update.

Type: Double

Valid Range: Minimum value of 1.0.

Required: No

ThroughputMode (p. 355)

(Optional) Updates the file system's throughput mode. If you're not updating your throughput mode, you don't need to provide this value in your request. If you are changing the ThroughputMode to provisioned, you must also set a value for ProvisionedThroughputInMbps.

Type: String

Valid Values: bursting | provisioned

Required: No

Response Syntax

```
HTTP/1.1 202
Content-type: application/json

{
    "AvailabilityZoneId": "string",
    "AvailabilityZoneName": "string",
    "CreationTime": number,
    "CreationToken": "string",
    "Encrypted": boolean,
    "FileSystemArn": "string",
    "FileSystemId": "string",
    "KmsKeyId": "string",
    "LifeCycleState": "string",
    "Name": "string",
    "NumberOfMountTargets": number,
    "OwnerId": "string",
    "PerformanceMode": "string",
    "ProvisionedThroughputInMbps": number,
    "SizeInBytes": {
        "Timestamp": number,
        "Value": number,
        "ValueInIA": number,
        "ValueInStandard": number
    },
    "Tags": [
        {
            "Key": "string",
            "Value": "string"
        }
    ],
    "ThroughputMode": "string"
}
```

Response Elements

If the action is successful, the service sends back an HTTP 202 response.

The following data is returned in JSON format by the service.

AvailabilityZoneId (p. 356)

The unique and consistent identifier of the Availability Zone in which the file system's One Zone storage classes exist. For example, use1-az1 is an Availability Zone ID for the us-east-1 AWS Region, and it has the same location in every AWS account.

Type: String

AvailabilityZoneName (p. 356)

Describes the AWS Availability Zone in which the file system is located, and is valid only for file systems using One Zone storage classes. For more information, see [Using EFS storage classes](#) in the *Amazon EFS User Guide*.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: .+

CreationTime (p. 356)

The time that the file system was created, in seconds (since 1970-01-01T00:00:00Z).

Type: Timestamp

[CreationToken \(p. 356\)](#)

The opaque string specified in the request.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: .+

[Encrypted \(p. 356\)](#)

A Boolean value that, if true, indicates that the file system is encrypted.

Type: Boolean

[FileSystemArn \(p. 356\)](#)

The Amazon Resource Name (ARN) for the EFS file system, in the format `arn:aws:elasticfilesystem:region:account-id:file-system/file-system-id`. Example with sample data: `arn:aws:elasticfilesystem:us-west-2:1111333322228888:file-system/fs-01234567`

Type: String

[FileSystemId \(p. 356\)](#)

The ID of the file system, assigned by Amazon EFS.

Type: String

Length Constraints: Maximum length of 128.

Pattern: `^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})$`

[KmsKeyId \(p. 356\)](#)

The ID of an AWS KMS key used to protect the encrypted file system.

Type: String

Length Constraints: Maximum length of 2048.

Pattern: `^([0-9a-f]{8}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{12})|mrk-[0-9a-f]{32}|alias/[a-zA-Z0-9/_-]+|(arn:aws[-a-z]*:kms:[a-zA-Z-]+:\d{12}:((key/[0-9a-f]{8}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{12}))(key/mrk-[0-9a-f]{32})|(alias/[a-zA-Z0-9/_-]+))$`

[LifeCycleState \(p. 356\)](#)

The lifecycle phase of the file system.

Type: String

Valid Values: `creating | available | updating | deleting | deleted | error`

[Name \(p. 356\)](#)

You can add tags to a file system, including a Name tag. For more information, see [CreateFileSystem \(p. 262\)](#). If the file system has a Name tag, Amazon EFS returns the value in this field.

Type: String

Length Constraints: Maximum length of 256.

Pattern: ^([\p{L}\p{Z}\p{N}_.:/-+@\"]*)\$

[NumberOfMountTargets \(p. 356\)](#)

The current number of mount targets that the file system has. For more information, see [CreateMountTarget \(p. 272\)](#).

Type: Integer

Valid Range: Minimum value of 0.

[OwnerId \(p. 356\)](#)

The AWS account that created the file system. If the file system was created by an IAM user, the parent account to which the user belongs is the owner.

Type: String

Length Constraints: Maximum length of 14.

Pattern: ^(\d{12})|(\d{4}-\d{4}-\d{4})\$

[PerformanceMode \(p. 356\)](#)

The performance mode of the file system.

Type: String

Valid Values: generalPurpose | maxIO

[ProvisionedThroughputInMbps \(p. 356\)](#)

The amount of provisioned throughput, measured in MiB/s, for the file system. Valid for file systems using ThroughputMode set to provisioned.

Type: Double

Valid Range: Minimum value of 1.0.

[SizeInBytes \(p. 356\)](#)

The latest known metered size (in bytes) of data stored in the file system, in its Value field, and the time at which that size was determined in its Timestamp field. The Timestamp value is the integer number of seconds since 1970-01-01T00:00:00Z. The SizeInBytes value doesn't represent the size of a consistent snapshot of the file system, but it is eventually consistent when there are no writes to the file system. That is, SizeInBytes represents actual size only if the file system is not modified for a period longer than a couple of hours. Otherwise, the value is not the exact size that the file system was at any point in time.

Type: [FileSystemSize \(p. 374\)](#) object

[Tags \(p. 356\)](#)

The tags associated with the file system, presented as an array of Tag objects.

Type: Array of [Tag \(p. 384\)](#) objects

[ThroughputMode \(p. 356\)](#)

Displays the file system's throughput mode. For more information, see [Throughput modes](#) in the [Amazon EFS User Guide](#).

Type: String

Valid Values: bursting | provisioned

Errors

BadRequest

Returned if the request is malformed or contains an error such as an invalid parameter value or a missing required parameter.

HTTP Status Code: 400

FileSystemNotFound

Returned if the specified FileSystemId value doesn't exist in the requester's AWS account.

HTTP Status Code: 404

IncorrectFileSystemLifeCycleState

Returned if the file system's lifecycle state is not "available".

HTTP Status Code: 409

InsufficientThroughputCapacity

Returned if there's not enough capacity to provision additional throughput. This value might be returned when you try to create a file system in provisioned throughput mode, when you attempt to increase the provisioned throughput of an existing file system, or when you attempt to change an existing file system from Bursting Throughput to Provisioned Throughput mode. Try again later.

HTTP Status Code: 503

InternalServerError

Returned if an error occurred on the server side.

HTTP Status Code: 500

ThroughputLimitExceeded

Returned if the throughput mode or amount of provisioned throughput can't be changed because the throughput limit of 1024 MiB/s has been reached.

HTTP Status Code: 400

TooManyRequests

Returned if you don't wait at least 24 hours before either changing the throughput mode, or decreasing the Provisioned Throughput value.

HTTP Status Code: 429

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS Command Line Interface](#)
- [AWS SDK for .NET](#)
- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)

- [AWS SDK for JavaScript](#)
- [AWS SDK for PHP V3](#)
- [AWS SDK for Python](#)
- [AWS SDK for Ruby V3](#)

Data Types

The following data types are supported:

- [AccessPointDescription \(p. 361\)](#)
- [BackupPolicy \(p. 363\)](#)
- [CreateInfo \(p. 364\)](#)
- [Destination \(p. 366\)](#)
- [DestinationToCreate \(p. 368\)](#)
- [FileSystemDescription \(p. 370\)](#)
- [FileSystemSize \(p. 374\)](#)
- [LifecyclePolicy \(p. 375\)](#)
- [MountTargetDescription \(p. 376\)](#)
- [PosixUser \(p. 379\)](#)
- [ReplicationConfigurationDescription \(p. 380\)](#)
- [ResourceIdPreference \(p. 382\)](#)
- [RootDirectory \(p. 383\)](#)
- [Tag \(p. 384\)](#)

AccessPointDescription

Provides a description of an EFS file system access point.

Contents

AccessPointArn

The unique Amazon Resource Name (ARN) associated with the access point.

Type: String

Length Constraints: Maximum length of 128.

Pattern: ^arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:access-point/fsap-[0-9a-f]{8,40}\$

Required: No

AccessPointId

The ID of the access point, assigned by Amazon EFS.

Type: String

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:access-point/fsap-[0-9a-f]{8,40}|fsap-[0-9a-f]{8,40})\$

Required: No

ClientToken

The opaque string specified in the request to ensure idempotent creation.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: .+

Required: No

FileSystemId

The ID of the EFS file system that the access point applies to.

Type: String

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9a-f]{8,40}|fs-[0-9a-f]{8,40})\$

Required: No

LifeCycleState

Identifies the lifecycle phase of the access point.

Type: String

Valid Values: creating | available | updating | deleting | deleted | error

Required: No

Name

The name of the access point. This is the value of the Name tag.

Type: String

Required: No

OwnerId

Identified the AWS account that owns the access point resource.

Type: String

Length Constraints: Maximum length of 14.

Pattern: ^(\d{12})|(\d{4}-\d{4}-\d{4})\$

Required: No

PosixUser

The full POSIX identity, including the user ID, group ID, and secondary group IDs on the access point that is used for all file operations by NFS clients using the access point.

Type: [PosixUser \(p. 379\)](#) object

Required: No

RootDirectory

The directory on the Amazon EFS file system that the access point exposes as the root directory to NFS clients using the access point.

Type: [RootDirectory \(p. 383\)](#) object

Required: No

Tags

The tags associated with the access point, presented as an array of Tag objects.

Type: Array of [Tag \(p. 384\)](#) objects

Required: No

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for Ruby V3](#)

BackupPolicy

The backup policy for the file system used to create automatic daily backups. If status has a value of ENABLED, the file system is being automatically backed up. For more information, see [Automatic backups](#).

Contents

Status

Describes the status of the file system's backup policy.

- **ENABLED** - EFS is automatically backing up the file system.
- **ENABLING** - EFS is turning on automatic backups for the file system.
- **DISABLED** - Automatic back ups are turned off for the file system.
- **DISABLING** - EFS is turning off automatic backups for the file system.

Type: String

Valid Values: ENABLED | ENABLING | DISABLED | DISABLING

Required: Yes

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for Ruby V3](#)

CreationInfo

Required if the RootDirectory > Path specified does not exist. Specifies the POSIX IDs and permissions to apply to the access point's RootDirectory > Path. If the access point root directory does not exist, EFS creates it with these settings when a client connects to the access point. When specifying CreationInfo, you must include values for all properties.

Amazon EFS creates a root directory only if you have provided the CreationInfo: OwnUid, OwnGID, and permissions for the directory. If you do not provide this information, Amazon EFS does not create the root directory. If the root directory does not exist, attempts to mount using the access point will fail.

Important

If you do not provide CreationInfo and the specified RootDirectory does not exist, attempts to mount the file system using the access point will fail.

Contents

OwnerGid

Specifies the POSIX group ID to apply to the RootDirectory. Accepts values from 0 to 2³² (4294967295).

Type: Long

Valid Range: Minimum value of 0. Maximum value of 4294967295.

Required: Yes

OwnerUid

Specifies the POSIX user ID to apply to the RootDirectory. Accepts values from 0 to 2³² (4294967295).

Type: Long

Valid Range: Minimum value of 0. Maximum value of 4294967295.

Required: Yes

Permissions

Specifies the POSIX permissions to apply to the RootDirectory, in the format of an octal number representing the file's mode bits.

Type: String

Length Constraints: Minimum length of 3. Maximum length of 4.

Pattern: ^[0-7]{3,4}\$

Required: Yes

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)

- [AWS SDK for Ruby V3](#)

Destination

Describes the destination file system in the replication configuration.

Contents

FileSystemId

The ID of the destination Amazon EFS file system.

Type: String

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9a-f]{8,40}|fs-[0-9a-f]{8,40})\$

Required: Yes

LastReplicatedTimestamp

The time when the most recent sync was successfully completed on the destination file system. Any changes to data on the source file system that occurred before this time have been successfully replicated to the destination file system. Any changes that occurred after this time might not be fully replicated.

Type: Timestamp

Required: No

Region

The AWS Region in which the destination file system is located.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: ^[a-z]{2}-((iso[a-z]{0,1}-)|(gov-)){0,1}[a-z]+-{0,1}[0-9]{0,1}\$

Required: Yes

Status

Describes the status of the destination Amazon EFS file system. If the status is ERROR, the destination file system in the replication configuration is in a failed state and is unrecoverable. To access the file system data, restore a backup of the failed file system to a new file system.

Type: String

Valid Values: ENABLED | ENABLING | DELETING | ERROR

Required: Yes

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)

- [AWS SDK for Java V2](#)
- [AWS SDK for Ruby V3](#)

DestinationToCreate

Describes the destination file system to create in the replication configuration.

Contents

AvailabilityZoneName

To create a file system that uses EFS One Zone storage, specify the name of the Availability Zone in which to create the destination file system.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: .+

Required: No

KmsKeyId

Specifies the AWS Key Management Service (AWS KMS) key that you want to use to encrypt the destination file system. If you do not specify a KMS key, Amazon EFS uses your default KMS key for Amazon EFS, /aws/elasticfilesystem. This ID can be in one of the following formats:

- Key ID - The unique identifier of the key, for example 1234abcd-12ab-34cd-56ef-1234567890ab.
- ARN - The Amazon Resource Name (ARN) for the key, for example arn:aws:kms:us-west-2:111122223333:key/1234abcd-12ab-34cd-56ef-1234567890ab.
- Key alias - A previously created display name for a key, for example alias/projectKey1.
- Key alias ARN - The ARN for a key alias, for example arn:aws:kms:us-west-2:444455556666:alias/projectKey1.

Type: String

Length Constraints: Maximum length of 2048.

Pattern: ^([0-9a-f]{8}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{12})|mrk-[0-9a-f]{32}|alias/[a-zA-Z0-9/_-]+|(arn:aws[-a-z]*:kms:[a-zA-Z0-9_-]+\:\d{12}:(key/[0-9a-f]{8}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{12}))|(key/mrk-[0-9a-f]{32})|(alias/[a-zA-Z0-9/_-]+))\$

Required: No

Region

To create a file system that uses Regional storage, specify the AWS Region in which to create the destination file system.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: ^[a-z]{2}-((iso[a-z]{0,1}-)|(gov-)){0,1}[a-z]+-{0,1}[0-9]{0,1}\$

Required: No

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for Ruby V3](#)

FileSystemDescription

A description of the file system.

Contents

AvailabilityZoneId

The unique and consistent identifier of the Availability Zone in which the file system's One Zone storage classes exist. For example, `use1-az1` is an Availability Zone ID for the `us-east-1` AWS Region, and it has the same location in every AWS account.

Type: String

Required: No

AvailabilityZoneName

Describes the AWS Availability Zone in which the file system is located, and is valid only for file systems using One Zone storage classes. For more information, see [Using EFS storage classes](#) in the *Amazon EFS User Guide*.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: `.+`

Required: No

CreationTime

The time that the file system was created, in seconds (since 1970-01-01T00:00:00Z).

Type: Timestamp

Required: Yes

CreationToken

The opaque string specified in the request.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: `.+`

Required: Yes

Encrypted

A Boolean value that, if true, indicates that the file system is encrypted.

Type: Boolean

Required: No

FileSystemArn

The Amazon Resource Name (ARN) for the EFS file system, in the format `arn:aws:elasticfilesystem:region:account-id:file-system/file-system-id`. Example with sample data: `arn:aws:elasticfilesystem:us-west-2:1111333322228888:file-system/fs-01234567`

Type: String

Required: No

FileSystemId

The ID of the file system, assigned by Amazon EFS.

Type: String

Length Constraints: Maximum length of 128.

Pattern: ^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9a-f]{8,40}|fs-[0-9a-f]{8,40})\$

Required: Yes

KmsKeyId

The ID of an AWS KMS key used to protect the encrypted file system.

Type: String

Length Constraints: Maximum length of 2048.

Pattern: ^([0-9a-f]{8}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{12}|\mrk-[0-9a-f]{32}|alias/[a-zA-Z0-9/_-]+|(arn:aws[-a-z]*:kms:[a-zA-Z0-9_-]+\:\d{12}:((key/[0-9a-f]{8}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{4}-[0-9a-f]{12})|(key/\mrk-[0-9a-f]{32}))|(alias/[a-zA-Z0-9/_-]+))))\$

Required: No

LifeCycleState

The lifecycle phase of the file system.

Type: String

Valid Values: creating | available | updating | deleting | deleted | error

Required: Yes

Name

You can add tags to a file system, including a Name tag. For more information, see [CreateFileSystem \(p. 262\)](#). If the file system has a Name tag, Amazon EFS returns the value in this field.

Type: String

Length Constraints: Maximum length of 256.

Pattern: ^([\p{L}\p{Z}\p{N}_.:/=+\-\@]*)\$

Required: No

NumberOfMountTargets

The current number of mount targets that the file system has. For more information, see [CreateMountTarget \(p. 272\)](#).

Type: Integer

Valid Range: Minimum value of 0.

Required: Yes

OwnerId

The AWS account that created the file system. If the file system was created by an IAM user, the parent account to which the user belongs is the owner.

Type: String

Length Constraints: Maximum length of 14.

Pattern: ^(\d{12})|(\d{4}-\d{4}-\d{4})\$

Required: Yes

PerformanceMode

The performance mode of the file system.

Type: String

Valid Values: generalPurpose | maxIO

Required: Yes

ProvisionedThroughputInMbps

The amount of provisioned throughput, measured in MiB/s, for the file system. Valid for file systems using ThroughputMode set to provisioned.

Type: Double

Valid Range: Minimum value of 1.0.

Required: No

SizeInBytes

The latest known metered size (in bytes) of data stored in the file system, in its Value field, and the time at which that size was determined in its Timestamp field. The Timestamp value is the integer number of seconds since 1970-01-01T00:00:00Z. The SizeInBytes value doesn't represent the size of a consistent snapshot of the file system, but it is eventually consistent when there are no writes to the file system. That is, SizeInBytes represents actual size only if the file system is not modified for a period longer than a couple of hours. Otherwise, the value is not the exact size that the file system was at any point in time.

Type: [FileSystemSize \(p. 374\)](#) object

Required: Yes

Tags

The tags associated with the file system, presented as an array of Tag objects.

Type: Array of [Tag \(p. 384\)](#) objects

Required: Yes

ThroughputMode

Displays the file system's throughput mode. For more information, see [Throughput modes](#) in the *Amazon EFS User Guide*.

Type: String

Valid Values: bursting | provisioned

Required: No

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for Ruby V3](#)

FileSystemSize

The latest known metered size (in bytes) of data stored in the file system, in its `Value` field, and the time at which that size was determined in its `Timestamp` field. The value doesn't represent the size of a consistent snapshot of the file system, but it is eventually consistent when there are no writes to the file system. That is, the value represents the actual size only if the file system is not modified for a period longer than a couple of hours. Otherwise, the value is not necessarily the exact size the file system was at any instant in time.

Contents

Timestamp

The time at which the size of data, returned in the `Value` field, was determined. The value is the integer number of seconds since 1970-01-01T00:00:00Z.

Type: `Timestamp`

Required: No

Value

The latest known metered size (in bytes) of data stored in the file system.

Type: `Long`

Valid Range: Minimum value of 0.

Required: Yes

ValueInIA

The latest known metered size (in bytes) of data stored in the Infrequent Access storage class.

Type: `Long`

Valid Range: Minimum value of 0.

Required: No

ValueInStandard

The latest known metered size (in bytes) of data stored in the Standard storage class.

Type: `Long`

Valid Range: Minimum value of 0.

Required: No

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for Ruby V3](#)

LifecyclePolicy

Describes a policy used by EFS lifecycle management and EFS Intelligent-Tiering that specifies when to transition files into and out of the file system's Infrequent Access (IA) storage class. For more information, see [EFS Intelligent-Tiering and EFS Lifecycle Management](#).

Note

When using the `put-lifecycle-configuration` CLI command or the `PutLifecycleConfiguration` API action, Amazon EFS requires that each `LifecyclePolicy` object have only a single transition. This means that in a request body, `LifecyclePolicies` must be structured as an array of `LifecyclePolicy` objects, one object for each transition, `TransitionToIA`, `TransitionToPrimaryStorageClass`. For more information, see the request examples in [PutLifecycleConfiguration \(p. 345\)](#).

Contents

TransitionToIA

Describes the period of time that a file is not accessed, after which it transitions to IA storage. Metadata operations such as listing the contents of a directory don't count as file access events.

Type: String

Valid Values: `AFTER_7_DAYS` | `AFTER_14_DAYS` | `AFTER_30_DAYS` | `AFTER_60_DAYS` | `AFTER_90_DAYS`

Required: No

TransitionToPrimaryStorageClass

Describes when to transition a file from IA storage to primary storage. Metadata operations such as listing the contents of a directory don't count as file access events.

Type: String

Valid Values: `AFTER_1_ACCESS`

Required: No

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for Ruby V3](#)

MountTargetDescription

Provides a description of a mount target.

Contents

AvailabilityZoneId

The unique and consistent identifier of the Availability Zone that the mount target resides in. For example, `use1-az1` is an AZ ID for the `us-east-1` Region and it has the same location in every AWS account.

Type: String

Required: No

AvailabilityZoneName

The name of the Availability Zone in which the mount target is located. Availability Zones are independently mapped to names for each AWS account. For example, the Availability Zone `us-east-1a` for your AWS account might not be the same location as `us-east-1a` for another AWS account.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: `.+`

Required: No

FileSystemId

The ID of the file system for which the mount target is intended.

Type: String

Length Constraints: Maximum length of 128.

Pattern: `^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})$`

Required: Yes

IpAddress

Address at which the file system can be mounted by using the mount target.

Type: String

Length Constraints: Minimum length of 7. Maximum length of 15.

Pattern: `^[0-9]{1,3}\.[0-9]{1,3}\.[0-9]{1,3}\.[0-9]{1,3}$`

Required: No

LifeCycleState

Lifecycle state of the mount target.

Type: String

Valid Values: `creating | available | updating | deleting | deleted | error`

Required: Yes

MountTargetId

System-assigned mount target ID.

Type: String

Length Constraints: Minimum length of 13. Maximum length of 45.

Pattern: ^fsmt-[0-9a-f]{8,40}\$

Required: Yes

NetworkInterfaceId

The ID of the network interface that Amazon EFS created when it created the mount target.

Type: String

Required: No

OwnerId

AWS account ID that owns the resource.

Type: String

Length Constraints: Maximum length of 14.

Pattern: ^(\d{12})|(\d{4}-\d{4}-\d{4})\$

Required: No

SubnetId

The ID of the mount target's subnet.

Type: String

Length Constraints: Minimum length of 15. Maximum length of 47.

Pattern: ^subnet-[0-9a-f]{8,40}\$

Required: Yes

VpcId

The virtual private cloud (VPC) ID that the mount target is configured in.

Type: String

Required: No

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for Ruby V3](#)

PosixUser

The full POSIX identity, including the user ID, group ID, and any secondary group IDs, on the access point that is used for all file system operations performed by NFS clients using the access point.

Contents

Gid

The POSIX group ID used for all file system operations using this access point.

Type: Long

Valid Range: Minimum value of 0. Maximum value of 4294967295.

Required: Yes

SecondaryGids

Secondary POSIX group IDs used for all file system operations using this access point.

Type: Array of longs

Array Members: Minimum number of 0 items. Maximum number of 16 items.

Valid Range: Minimum value of 0. Maximum value of 4294967295.

Required: No

Uid

The POSIX user ID used for all file system operations using this access point.

Type: Long

Valid Range: Minimum value of 0. Maximum value of 4294967295.

Required: Yes

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for Ruby V3](#)

ReplicationConfigurationDescription

Contents

CreationTime

Describes when the replication configuration was created.

Type: Timestamp

Required: Yes

Destinations

An array of destination objects. Only one destination object is supported.

Type: Array of [Destination \(p. 366\)](#) objects

Required: Yes

OriginalSourceFileSystemArn

The Amazon Resource Name (ARN) of the original source Amazon EFS file system in the replication configuration.

Type: String

Required: Yes

SourceFileSystemArn

The Amazon Resource Name (ARN) of the current source file system in the replication configuration.

Type: String

Required: Yes

SourceFileSystemId

The ID of the source Amazon EFS file system that is being replicated.

Type: String

Length Constraints: Maximum length of 128.

Pattern: `^(arn:aws[-a-z]*:elasticfilesystem:[0-9a-z-:]+:file-system/fs-[0-9af]{8,40}|fs-[0-9a-f]{8,40})$`

Required: Yes

SourceFileSystemRegion

The AWS Region in which the source Amazon EFS file system is located.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 64.

Pattern: `^[a-z]{2}-((iso[a-z]{0,1}-)|(gov-)){0,1}[a-z]+-{0,1}[0-9]{0,1}$`

Required: Yes

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for Ruby V3](#)

ResourceIdPreference

Describes the resource type and its ID preference for the user's AWS account, in the current AWS Region.

Contents

ResourceIdType

Identifies the EFS resource ID preference, either LONG_ID (17 characters) or SHORT_ID (8 characters).

Type: String

Valid Values: LONG_ID | SHORT_ID

Required: No

Resources

Identifies the Amazon EFS resources to which the ID preference setting applies, FILE_SYSTEM and MOUNT_TARGET.

Type: Array of strings

Valid Values: FILE_SYSTEM | MOUNT_TARGET

Required: No

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for Ruby V3](#)

RootDirectory

Specifies the directory on the Amazon EFS file system that the access point provides access to. The access point exposes the specified file system path as the root directory of your file system to applications using the access point. NFS clients using the access point can only access data in the access point's RootDirectory and its subdirectories.

Contents

CreationInfo

(Optional) Specifies the POSIX IDs and permissions to apply to the access point's RootDirectory. If the RootDirectory > Path specified does not exist, EFS creates the root directory using the CreationInfo settings when a client connects to an access point. When specifying the CreationInfo, you must provide values for all properties.

Important

If you do not provide CreationInfo and the specified RootDirectory > Path does not exist, attempts to mount the file system using the access point will fail.

Type: [CreationInfo \(p. 364\)](#) object

Required: No

Path

Specifies the path on the EFS file system to expose as the root directory to NFS clients using the access point to access the EFS file system. A path can have up to four subdirectories. If the specified path does not exist, you are required to provide the CreationInfo.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 100.

Pattern: `^(\/|(\\/(?!\.)+[^\$#<>;`|&?{}^*/\n]+){1,4})$`

Required: No

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for Ruby V3](#)

Tag

A tag is a key-value pair. Allowed characters are letters, white space, and numbers that can be represented in UTF-8, and the following characters: + - = . _ : /.

Contents

Key

The tag key (String). The key can't start with aws:.

Type: String

Length Constraints: Minimum length of 1. Maximum length of 128.

Pattern: ^(?![aA]{1}[wW]{1}[sS]{1}:)([\p{L}\p{Z}\p{N}_.:=/+\\-@]+)\$

Required: Yes

Value

The value of the tag key.

Type: String

Length Constraints: Maximum length of 256.

Pattern: ^([\p{L}\p{Z}\p{N}_.:=/+\\-@]+)\$

Required: Yes

See Also

For more information about using this API in one of the language-specific AWS SDKs, see the following:

- [AWS SDK for C++](#)
- [AWS SDK for Go](#)
- [AWS SDK for Java V2](#)
- [AWS SDK for Ruby V3](#)

Additional information for Amazon EFS

Following, you can find some additional information about Amazon EFS, including features that are still supported but not necessarily recommended.

Topics

- [Backing up Amazon EFS file systems using AWS Data Pipeline \(p. 385\)](#)
- [Mounting file systems without the EFS mount helper \(p. 397\)](#)

Backing up Amazon EFS file systems using AWS Data Pipeline

Note

Using the AWS Data Pipeline to back up your EFS file systems is a legacy solution.

Recommended Amazon EFS backup solutions

There are two recommended solutions available for backing up your Amazon EFS file systems.

- AWS Backup service
- The EFS-to-EFS backup solution

AWS Backup is a simple and cost-effective way to back up your Amazon EFS file systems. AWS Backup is a unified backup service designed to simplify the creation, migration, restoration, and deletion of backups, while providing improved reporting and auditing. For more information, see [Using AWS Backup to back up and restore Amazon EFS file systems \(p. 138\)](#).

The EFS-to-EFS backup solution is suitable for all Amazon EFS file systems in all AWS Regions. It includes an AWS CloudFormation template that launches, configures, and runs the AWS services required to deploy this solution. This solution follows AWS best practices for security and availability. For more information, see [EFS-to-EFS Backup Solution](#) in AWS Answers.

Legacy EFS backup solution using AWS Data Pipeline

Using AWS Data Pipeline to back up EFS file systems is a legacy backup solution. In this backup solution, you create a data pipeline by using the AWS Data Pipeline service. This pipeline copies data from your Amazon EFS file system (called the *production file system*) to another Amazon EFS file system (called the *backup file system*).

This solution consists of AWS Data Pipeline templates that implement the following:

- Automated EFS backups based on a schedule that you define (for example, hourly, daily, weekly, or monthly).

- Automated rotation of the backups, where the oldest backup is replaced with the newest backup based on the number of backups that you want to retain.
- Quicker backups using rsync, which only back up the changes made between one backup to the next.
- Efficient storage of backups using hard links. A *hard link* is a directory entry that associates a name with a file in a file system. By setting up a hard link, you can perform a full restoration of data from any backup while only storing what changed from backup to backup.

After you set up the backup solution, this walk-through shows you how to access your backups to restore your data. This backup solution depends on running scripts that are hosted on GitHub, and is therefore subject to GitHub availability. If you'd prefer to eliminate this reliance and host the scripts in an Amazon S3 bucket instead, see [Hosting the rsync scripts in an Amazon S3 bucket \(p. 396\)](#).

Important

This solution requires using AWS Data Pipeline in the same AWS Region as your file system. Because AWS Data Pipeline is not supported in US East (Ohio), this solution doesn't work in that AWS Region. We recommend that if you want to back up your file system using this solution, you use your file system in one of the other supported AWS Regions.

Topics

- [Performance for Amazon EFS backups using AWS Data Pipeline \(p. 386\)](#)
- [Considerations for Amazon EFS backup using AWS Data Pipeline \(p. 387\)](#)
- [Assumptions for Amazon EFS backup with AWS Data Pipeline \(p. 387\)](#)
- [How to back up an Amazon EFS file system with AWS Data Pipeline \(p. 388\)](#)
- [Additional backup resources \(p. 393\)](#)

Performance for Amazon EFS backups using AWS Data Pipeline

When performing data backups and restorations, your file system performance is subject to [Amazon EFS performance \(p. 130\)](#), including baseline and burst throughput capacity. The throughput used by your backup solution counts toward your total file system throughput. The following table provides some recommendations for the Amazon EFS file system and Amazon EC2 instance sizes that work for this solution, assuming that your backup window is 15 minutes long.

EFS size (30 MB average file size)	Daily change volume	Remaining burst hours	Minimum number of backup agents
256 GB	Less than 25 GB	6.75	1 - m3.medium
512 GB	Less than 50 GB	7.75	1 - m3.large
1.0 TB	Less than 75 GB	11.75	2 - m3.large*
1.5 TB	Less than 125 GB	11.75	2 - m3.xlarge*
2.0 TB	Less than 175 GB	11.75	3 - m3.large*
3.0 TB	Less than 250 GB	11.75	4 - m3.xlarge*

* These estimates are based on the assumption that data stored in an EFS file system that is 1 TB or larger is organized so that the backup can be spread across multiple backup nodes. The multiple-node

example scripts divide the backup load across nodes based on the contents of the first-level directory of your EFS file system.

For example, if there are two backup nodes, one node backs up all of the even files and directories located in the first-level directory. The odd node does the same for the odd files and directories. In another example, with six directories in the Amazon EFS file system and four backup nodes, the first node backs up the first and the fifth directories. The second node backs up the second and the sixth directories, and the third and fourth nodes back up the third and the fourth directories respectively.

Considerations for Amazon EFS backup using AWS Data Pipeline

Consider the following when you're deciding whether to implement an Amazon EFS backup solution using AWS Data Pipeline:

- This approach to EFS backup involves a number of AWS resources. For this solution, you need to create the following:
 - One production file system and one backup file system that contains a full copy of the production file system. The system also contains any incremental changes to your data over the backup rotation period.
 - Amazon EC2 instances, whose lifecycles are managed by AWS Data Pipeline, that perform restorations and scheduled backups.
 - One regularly scheduled AWS Data Pipeline for backing up data.
 - An AWS Data Pipeline for restoring backups.

When this solution is implemented, it results in billing to your account for these services. For more information, see the pricing pages for [Amazon EFS](#), [Amazon EC2](#), and [AWS Data Pipeline](#).


- This solution isn't an offline backup solution. To ensure a fully consistent and complete backup, pause any file writes to the file system or unmount the file system while the backup occurs. We recommend that you perform all backups during scheduled downtime or off hours.

Assumptions for Amazon EFS backup with AWS Data Pipeline

This walkthrough makes several assumptions and declares example values as follows:

- Before you get started, this walkthrough assumes that you already completed [Getting started \(p. 14\)](#).
- After you've completed the Getting Started exercise, you have two security groups, a VPC subnet, and a file system mount target for the file system that you want to back up. For the rest of this walkthrough, you use the following example values:
 - The ID of the file system that you back up in this walkthrough is `fs-12345678`.
 - The security group for the file system that is associated with the mount target is called `efs-mt-sg` (`sg-1111111a`).
 - The security group that grants Amazon EC2 instances the ability to connect to the production EFS mount point is called `efs-ec2-sg` (`sg-1111111b`).
 - The VPC subnet has the ID value of `subnet-abcd1234`.
 - The source file system mount target IP address for the file system that you want to back up is `10.0.1.32:/`.
 - The example assumes that the production file system is a content management system serving media files with an average size of 30 MB.

The preceding assumptions and examples are reflected in the following initial setup diagram.



How to back up an Amazon EFS file system with AWS Data Pipeline

Follow the steps in this section to back up or restore your Amazon EFS file system with AWS Data Pipeline.

Topics


- [Step 1: Create your backup Amazon EFS file system \(p. 388\)](#)
- [Step 2: Download the AWS Data Pipeline template for backups \(p. 389\)](#)
- [Step 3: Create a data pipeline for backup \(p. 389\)](#)
- [Step 4: Access your Amazon EFS backups \(p. 390\)](#)

Step 1: Create your backup Amazon EFS file system

In this walkthrough, you create separate security groups, file systems, and mount points to separate your backups from your data source. In this first step, you create those resources:

1. First, create two new security groups. The example security group for the backup mount target is `efs-backup-mt-sg` (`sg-9999999a`). The example security group for the EC2 instance to access the mount target is `efs-backup-ec2-sg` (`sg-9999999b`). Remember to create these security groups in the same VPC as the EFS volume that you want to back up. In this example, the VPC associated with the `subnet-abcd1234` subnet. For more information about creating security groups, see [Creating security groups \(p. 43\)](#).
2. Next, create a backup Amazon EFS file system. In this example, the file system ID is `fs-abcdefaa`. For more information about creating file systems, see [Creating Amazon EFS file systems \(p. 26\)](#).
3. Finally, create a mount point for the EFS backup file system and assume that it has the value of `10.0.1.75:/`. For more information about creating mount targets, see [Creating and managing mount targets and security groups \(p. 37\)](#).

After you've completed this first step, your setup should look similar to the following example diagram.



Step 2: Download the AWS Data Pipeline template for backups

AWS Data Pipeline helps you reliably process and move data between different AWS compute and storage services at specified intervals. By using the AWS Data Pipeline console, you can create preconfigured pipeline definitions, known as templates. You can use these templates to get started with AWS Data Pipeline quickly. For this walkthrough, a template is provided to make the process of setting up your backup pipeline easier.

When implemented, this template creates a data pipeline that launches a single Amazon EC2 instance on the schedule that you specify to back up data from the production file system to the backup file system. This template has a number of placeholder values. You provide the matching values for those placeholders in the **Parameters** section of the AWS Data Pipeline console. Download the AWS Data Pipeline template for backups at [1-Node-EFSBackupDataPipeline.json](#) from GitHub.

Note

This template also references and runs a script to perform the backup commands. You can download the script before creating the pipeline to review what it does. To review the script, download [efs-backup.sh](#) from GitHub. This backup solution depends on running scripts that are hosted on GitHub and is subject to GitHub availability. If you'd prefer to eliminate this reliance and host the scripts in an Amazon S3 bucket instead, see [Hosting the rsync scripts in an Amazon S3 bucket \(p. 396\)](#).

Step 3: Create a data pipeline for backup

Use the following procedure to create your data pipeline.

To create a data pipeline for Amazon EFS backups

1. Open the AWS Data Pipeline console at <https://console.aws.amazon.com/datapipeline/>.
Important
Make sure that you're working in the same AWS Region as your Amazon EFS file systems.
2. Choose **Create new pipeline**.
3. Add values for **Name** and optionally for **Description**.
4. For **Source**, choose **Import a definition**, and then choose **Load local file**.
5. In the file explorer, navigate to the template that you saved in [Step 2: Download the AWS Data Pipeline template for backups \(p. 389\)](#), and then choose **Open**.
6. In **Parameters**, provide the details for both your backup and production EFS file systems.

Parameters

Production EFS mount target IP address.	10.0.1.32:/
Security group that can connect to the Production EFS mount point.	sg-1111111b
Interval for backups.	daily
Security group that can connect to the Backup EFS mount point.	sg-9999999b
Number of backups to retain.	7
Backup EFS mount target IP address.	10.0.1.75:/
VPC subnet for your backup EC2 instance (ideally the same subnet used for the production EFS mount point).	subnet-1234abcd
Instance type for creating backups.	m3.medium
Name for the directory that will contain your backups.	backup-fs-12345678
Shell command to run.	wget https://raw.githubusercontent.com/awslabs/data-pipeline-

- Configure the options in **Schedule** to define your Amazon EFS backup schedule. The backup in the example runs once every day, and the backups are kept for a week. When a backup is seven days old, it is replaced with next oldest backup.

Schedule

You can run your pipeline once or specify a schedule. [More](#)

Run	<input type="radio"/> once on pipeline activation
	<input checked="" type="radio"/> on a schedule
Run every	1 day(s)
Starting	<input checked="" type="radio"/> on pipeline activation
	<input type="radio"/> 2015-05-28 02:46 UTC (Current time is 02:48 UTC) YYYY-MM-DD HH:MM
Ending	<input checked="" type="radio"/> never
	<input type="radio"/> after 1 occurrence(s) 2015-05-29 02:46 UTC (Current time is 02:48 UTC) YYYY-MM-DD HH:MM

Note

We recommend that you specify a run time that occurs during your off-peak hours.

- (Optional) Specify an Amazon S3 location for storing pipeline logs, configure a custom IAM role, or add tags to describe your pipeline.
- When your pipeline is configured, choose **Activate**.

You've now configured and activated your Amazon EFS backup data pipeline. For more information about AWS Data Pipeline, see the [AWS Data Pipeline Developer Guide](#). At this stage, you can perform the backup now as a test, or you can wait until the backup is performed at the scheduled time.

Step 4: Access your Amazon EFS backups

Your Amazon EFS backup has now been created, activated, and is running on the schedule you defined. This step outlines how you can access your EFS backups. Your backups are stored in the EFS backup file system that you created in the following format.

```
backup-efs-mount-target:/efs-backup-id/[backup interval].[0-backup retention]-->
```

Using the values from the example scenario, the backup of the file system is located in `10.1.0.75:/fs-12345678/daily.[0-6]`, where `daily.0` is the most recent backup and `daily.6` is the oldest of the seven rotating backups.

Accessing your backups gives you the ability to restore data to your production file system. You can choose to restore an entire file system, or you can choose to restore individual files.

Step 4.1: Restore an entire Amazon EFS backup

Restoring a backup copy of an Amazon EFS file system requires another AWS Data Pipeline, similar to the one you configured in [Step 3: Create a data pipeline for backup \(p. 389\)](#). However, this restoration pipeline works in the reverse of the backup pipeline. Typically, these restorations aren't scheduled to begin automatically.

As with backups, restores can be done in parallel to meet your recovery time objective. Keep in mind that when you create a data pipeline, you need to schedule when you want it run. If you choose to run on activation, you start the restoration process immediately. We recommend that you only create a restoration pipeline when you need to do a restoration, or when you already have a specific window of time in mind.

Burst capacity is consumed by both the backup EFS and restoration EFS. For more information about performance, see [Amazon EFS performance \(p. 130\)](#). The following procedure shows you how to create and implement your restoration pipeline.

To create a data pipeline for EFS data restoration

1. Download the data pipeline template for restoring data from your backup EFS file system. This template launches a single Amazon EC2 instance based on the specified size. It launches only when you specify it to launch. Download the AWS Data Pipeline template for backups at [1-Node-EFSRestoreDataPipeline.json](#) from GitHub.

Note

This template also references and runs a script to perform the restoration commands. You can download the script before creating the pipeline to review what it does. To review the script, download [efs-restore.sh](#) from GitHub.

2. Open the AWS Data Pipeline console at <https://console.aws.amazon.com/datapipeline/>.

Important

Make sure that you're working in the same AWS Region as your Amazon EFS file systems and Amazon EC2.

3. Choose **Create new pipeline**.
4. Add values for **Name** and optionally for **Description**.
5. For **Source**, choose **Import a definition**, and then choose **Load local file**.
6. In the file explorer, navigate to the template that you saved in [Step 1: Create your backup Amazon EFS file system \(p. 388\)](#), and then choose **Open**.
7. In **Parameters**, provide the details for both your backup and production EFS file systems.

Parameters

Production EFS mount target IP address.	10.0.1.32:/
Security group that can connect to the Production EFS mount point.	sg-1111111b
Instance type for performing the restore.	m3.large
Security group that can connect to the Backup EFS mount point.	sg-9999999b
Name for the directory that already contains your backups.	backup-fs-12345678
Backup number to restore (0 = the most recent backup).	0
Backup EFS mount target IP address.	10.0.1.75:/
Interval that you chose for the backup your going to restore.	daily
VPC subnet for your restoration EC2 instance (ideally the same subnet used for the backup EFS mount point).	subnet-1234abcd

8. Because you typically perform restorations only when you need them, you can schedule the restoration to run **once on pipeline activation**. Or schedule a one-time restoration at a future time of your choosing, like during an off-peak window of time.
9. (Optional) Specify an Amazon S3 location for storing pipeline logs, configure a custom IAM role, or add tags to describe your pipeline.
10. When your pipeline is configured, choose **Activate**.

You've now configured and activated your Amazon EFS restoration data pipeline. Now when you need to restore a backup to your production EFS file system, you just activate it from the AWS Data Pipeline console. For more information, see the [AWS Data Pipeline Developer Guide](#).

Step 4.2: Restore individual files from your Amazon EFS backups

You can restore files from your Amazon EFS file system backups by launching an Amazon EC2 instance to temporarily mount both the production and backup EFS file systems. The EC2 instance must be a member of both of the EFS client security groups (in this example, **efs-ec2-sg** and **efs-backup-clients-sg**). Both EFS mount targets can be mounted by this restoration instance. For example, a recovery EC2 instance can create the following mount points. Here, the **-o ro** option is used to mount the backup EFS as read-only to prevent accidentally modifying the backup when attempting to restore from a backup.

```
mount -t nfs source-efs-mount-target:/ /mnt/data
```

```
mount -t nfs -o ro backup-efs-mount-target:/fs-12345678/daily.0 /mnt/backup>
```

After you've mounted the targets, you can copy files from **/mnt/backup** to the appropriate location in **/mnt/data** in the terminal using the **cp -p** command. For example, an entire home directory (with its file system permissions) can be recursively copied with the following command.

```
sudo cp -rp /mnt/backup/users/my_home /mnt/data/users/my_home
```

You can restore a single file by running the following command.

```
sudo cp -p /mnt/backup/user/my_home/.profile /mnt/data/users/my_home/.profile
```

Warning

When you are manually restoring individual data files, be careful that you don't accidentally modify the backup itself. Otherwise, you might corrupt it.

Additional backup resources

The backup solution presented in this walkthrough uses templates for AWS Data Pipeline. The templates used in [Step 2: Download the AWS Data Pipeline template for backups \(p. 389\)](#) and [Step 4.1: Restore an entire Amazon EFS backup \(p. 391\)](#) both use a single Amazon EC2 instance to perform their work. However, there's no real limit to the number of parallel instances that you can run for backing up or restoring your data in Amazon EFS file systems. In this topic, you can find links to other AWS Data Pipeline templates configured for multiple EC2 instances that you can download and use for your backup solution. You can also find instructions for how to modify the templates to include additional instances.

Topics

- [Using additional templates \(p. 393\)](#)
- [Adding additional backup instances \(p. 393\)](#)
- [Adding additional restoration instances \(p. 395\)](#)
- [Hosting the rsync scripts in an Amazon S3 bucket \(p. 396\)](#)

Using additional templates

You can download the following additional templates from GitHub:

- [2-Node-EFSBackupPipeline.json](#) – This template starts two parallel Amazon EC2 instances to back up your production Amazon EFS file system.
- [2-Node-EFSRestorePipeline.json](#) – This template starts two parallel Amazon EC2 instances to restore a backup of your production Amazon EFS file system.

Adding additional backup instances

You can add additional nodes to the backup templates used in this walkthrough. To add a node, modify the following sections of the `2-Node-EFSBackupDataPipeline.json` template.

Important

If you're using additional nodes, you can't use spaces in file names and directories stored in the top-level directory. If you do, those files and directories aren't backed up or restored. All files and subdirectories that are at least one level below the top level are backed up and restored as expected.

- Create an additional EC2Resource for each additional node you want to create (in this example, a fourth EC2 instance).

```
{  
  "id": "EC2Resource4",  
  "terminateAfter": "70 Minutes",  
  "instanceType": "#{myInstanceType}",  
  "name": "EC2Resource4",  
  "type": "Ec2Resource",  
  "securityGroupIds": [ "#{mySrcSecGroupID}", "#{myBackupSecGroupID}" ],  
  "subnetId": "#{mySubnetID}",  
  "associatePublicIpAddress": "true"  
},
```

- Create an additional data pipeline activity for each additional node (in this case, activity `BackupPart4`), make sure to configure the following sections:
 - Update the `runsOn` reference to point to the EC2Resource created previously (`EC2Resource4` in the following example).
 - Increment the last two `scriptArgument` values to equal the backup part that each node is responsible for and the total number of nodes. For "2" and "3" in the example following, the backup part is "3" for the fourth node because in this example our modulus logic needs to count starting with 0.

```
{
  "id": "BackupPart4",
  "name": "BackupPart4",
  "runsOn": {
    "ref": "EC2Resource4"
  },
  "command": "wget https://raw.githubusercontent.com/awslabs/data-pipeline-samples/master/samples/EFSBackup/efs-backup-rsync.sh\nchmod a+x efs-backup-rsync.sh\n./efs-backup-rsync.sh $1 $2 $3 $4 $5 $6 $7",
  "scriptArgument": ["#{myEfsSource}", "#{myEfsBackup}", "#{myInterval}",
    "#{myRetainedBackups}", "#{myEfsID}", "3", "4"],
  "type": "ShellCommandActivity",
  "dependsOn": {
    "ref": "InitBackup"
  },
  "stage": "true"
},
```

- Increment the last value in all existing `scriptArgument` values to the number of nodes (in this example, "4").

```
{
  "id": "BackupPart1",
  ...
  "scriptArgument": ["#{myEfsSource}", "#{myEfsBackup}", "#{myInterval}",
    "#{myRetainedBackups}", "#{myEfsID}", "1", "4"],
  ...
},
{
  "id": "BackupPart2",
  ...
  "scriptArgument": ["#{myEfsSource}", "#{myEfsBackup}", "#{myInterval}",
    "#{myRetainedBackups}", "#{myEfsID}", "2", "4"],
  ...
},
{
  "id": "BackupPart3",
  ...
  "scriptArgument": ["#{myEfsSource}", "#{myEfsBackup}", "#{myInterval}",
    "#{myRetainedBackups}", "#{myEfsID}", "0", "4"],
  ...
},
```

- Update `FinalizeBackup` activity and add the new backup activity to the `dependsOn` list (`BackupPart4` in this case).

```
{
  "id": "FinalizeBackup", "name": "FinalizeBackup", "runsOn": { "ref": "EC2Resource1" },
  "command": "wget https://raw.githubusercontent.com/awslabs/data-pipeline-samples/master/samples/EFSBackup/efs-backup-end.sh\nchmod a+x efs-backup-end.sh $1 $2", "scriptArgument": ["#{myInterval}",
    "#{myEfsID}"], "type": "ShellCommandActivity", "dependsOn": [ { "ref": "BackupPart1" },
```

```
{ "ref": "BackupPart2" }, { "ref": "BackupPart3" }, { "ref": "BackupPart4" } ], "stage": "true"
```

Adding additional restoration instances

You can add nodes to the restoration templates used in this walkthrough. To add a node, modify the following sections of the `2-Node-EFSRestorePipeline.json` template.

- Create an additional EC2Resource for each additional node you want to create (in this case, a third EC2 instance called `EC2Resource3`).

```
{
  "id": "EC2Resource3",
  "terminateAfter": "70 Minutes",
  "instanceType": "#{myInstanceType}",
  "name": "EC2Resource3",
  "type": "Ec2Resource",
  "securityGroupIds": [ "#{mySrcSecGroupID}", "#{myBackupSecGroupID}" ],
  "subnetId": "#{mySubnetID}",
  "associatePublicIpAddress": "true"
},
```

- Create an additional data pipeline activity for each additional node (in this case, `Activity RestorePart3`). Make sure to configure the following sections:
 - Update the `runsOn` reference to point to the EC2Resource created previously (in this example, `EC2Resource3`).
 - Increment the last two `scriptArgument` values to equal the backup part that each node is responsible for and the total number of nodes. For "2" and "3" in the example following, the backup part is "3" for the fourth node because in this example our modulus logic needs to count starting with 0.

```
{
  "id": "RestorePart3",
  "name": "RestorePart3",
  "runsOn": {
    "ref": "EC2Resource3"
  },
  "command": "wget https://raw.githubusercontent.com/awslabs/data-pipeline-samples/master/samples/EFSBackup/efs-restore-rsync.sh\nchmod a+x efs-restore-rsync.sh\n./efs-backup-rsync.sh $1 $2 $3 $4 $5 $6 $7",
  "scriptArgument": ["#{myEfsSource}", "#{myEfsBackup}", "#{myInterval}",
    "#{myBackup}", "#{myEfsID}", "2", "3"],
  "type": "ShellCommandActivity",
  "dependsOn": {
    "ref": "InitBackup"
  },
  "stage": "true"
},
```

- Increment the last value in all existing `scriptArgument` values to the number of nodes (in this example, "3").

```
{
  "id": "RestorePart1",
  ...
  "scriptArgument": ["#{myEfsSource}", "#{myEfsBackup}", "#{myInterval}",
    "#{myBackup}", "#{myEfsID}", "1", "3"],
  ...
},
```

```
{  
  "id": "RestorePart2",  
  ...  
  "scriptArgument": ["#{myEfsSource}", "#{myEfsBackup}", "#{myInterval}",  
    "#{myBackup}", "#{myEfsID}", "0", "3"],  
  ...  
};
```

Hosting the rsync scripts in an Amazon S3 bucket

This backup solution is dependent on running rsync scripts that are hosted in a GitHub repository on the internet. Therefore, this backup solution is subject to the GitHub repository being available. This requirement means that if the GitHub repository removes these scripts, or if the GitHub website goes offline, the backup solution as implemented preceding doesn't function.

If you'd prefer to eliminate this GitHub dependency, you can choose to host the scripts in an Amazon S3 bucket that you own instead. Following, you can find the steps necessary to host the scripts yourself.

To host the rsync scripts in your own Amazon S3 bucket

1. **Sign Up for AWS** – If you already have an AWS account, go ahead and skip to the next step. Otherwise, see [Sign up for AWS \(p. 12\)](#).
2. **Create an AWS Identity and Access Management User** – If you already have an IAM user, go ahead and skip to the next step. Otherwise, see [Create an IAM User \(p. 12\)](#).
3. **Create an Amazon S3 bucket** – If you already have a bucket that you want to host the rsync scripts in, go ahead and skip to the next step. Otherwise, see [Create a Bucket](#) in the *Amazon Simple Storage Service User Guide*.
4. **Download the rsync scripts and templates** – Download all of the rsync scripts and templates in the [EFSBackup folder](#) from GitHub. Make a note of the location on your computer where you downloaded these files.
5. **Upload the rsync scripts to your S3 bucket** – For instructions on how to upload objects into your S3 bucket, see [Add an Object to a Bucket](#) in the *Amazon Simple Storage Service User Guide*.
6. Change the permissions on the uploaded rsync scripts to allow **Everyone to Open/Download** them. For instructions on how to change the permissions on an object in your S3 bucket, see [Editing Object Permissions](#) in the *Amazon Simple Storage Service User Guide*.

The screenshot shows the AWS S3 Object details page for an object named 'efs-backup.sh'. The object is located in a bucket with the same name. The details include:

- Bucket:** [REDACTED]
- Name:** efs-backup.sh
- Link:** [https://s3-us-west-2.amazonaws.com/\[REDACTED\]/efs-backup.sh](https://s3-us-west-2.amazonaws.com/[REDACTED]/efs-backup.sh)
- Size:** 3065
- Last Modified:** Wed Dec 02 14:30:20 GMT-800 2015
- Owner:** [REDACTED]
- ETag:** [REDACTED]
- Expiry Date:** None
- Expiration Rule:** N/A

Below the details, there are two sections: **Details** (expanded) and **Permissions** (collapsed). The **Permissions** section states: "You can control access to the bucket and its contents using access policies. [Learn more.](#)" It shows two entries in the access policy:

Grantee:	Open/Download	View Permissions	Edit Permissions
Everyone	<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
[REDACTED]	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>

At the bottom right are **Save** and **Cancel** buttons.

7. **Update your templates** – Modify the `wget` statement in the `shellCmd` parameter to point to the Amazon S3 bucket where you put the startup script. Save the updated template, and use that template when you're following the procedure in [Step 3: Create a data pipeline for backup \(p. 389\)](#).

Note

We recommend that you limit access to your Amazon S3 bucket to include the IAM account that activates the AWS Data Pipeline for this backup solution. For more information, see [Editing Bucket Permissions](#) in the *Amazon Simple Storage Service User Guide*.

You are now hosting the `rsync` scripts for this backup solution, and your backups are no longer dependent on GitHub availability.

Mounting file systems without the EFS mount helper

Note

In this section, you can learn how to mount your Amazon EFS file system without the `amazon-efs-utils` package. To use encryption of data in transit with your file system, you must mount your file system with Transport Layer Security (TLS). To do so, we recommend using the `amazon-efs-utils` package. For more information, see [Using the amazon-efs-utils Tools \(p. 54\)](#).

Following, you can learn how to install the Network File System (NFS) client and how to mount your Amazon EFS file system on an Amazon EC2 instance. You also can find an explanation of the `mount`

command and the available options for specifying your file system's Domain Name System (DNS) name in the `mount` command. In addition, you can find how to use the file `fstab` to automatically remount your file system after any system restarts.

Note

Before you can mount a file system, you must create, configure, and launch your related AWS resources. For detailed instructions, see [Getting started with Amazon Elastic File System \(p. 14\)](#).

Note

Prior to mounting your file system, you need to create VPC security groups for your Amazon EC2 instances and mount targets with the required inbound and outbound access. For more information, see [Using VPC security groups for Amazon EC2 instances and mount targets \(p. 218\)](#).

Topics

- [NFS support \(p. 398\)](#)
- [Installing the NFS client \(p. 399\)](#)
- [Recommended NFS mount options \(p. 400\)](#)
- [Mounting on Amazon EC2 with a DNS name \(p. 401\)](#)
- [Mounting with an IP address \(p. 403\)](#)

NFS support

Amazon EFS supports the Network File System versions 4.0 and 4.1 (NFSv4) protocols when mounting your file systems on Amazon EC2 instances. Although NFSv4.0 is supported, we recommend that you use NFSv4.1. Mounting your Amazon EFS file system on your Amazon EC2 instance also requires an NFS client that supports your chosen NFSv4 protocol. Amazon EC2 Mac instances running macOS Big Sur only support NFS v4.0.

Amazon EFS does not support the `nconnect` mount option.

Note

For Linux kernel versions 5.4.*, the Linux NFS client uses a default `read_ahead_kb` value of 128 KB. We recommend increasing this value to 15 MB. For more information, see [Optimizing the NFS read_ahead_kb size \(p. 136\)](#).

For optimal performance and to avoid a variety of known NFS client bugs, we recommend working with a recent Linux kernel. If you are using an enterprise Linux distribution, we recommend the following:

- Amazon Linux 2
- Amazon Linux 2017.09 or newer
- Red Hat Enterprise Linux (and derivatives such as CentOS) version 7 and newer
- Ubuntu 16.04 LTS and newer
- SLES 12 Sp2 or later

If you are using another distribution or a custom kernel, we recommend kernel version 4.3 or newer.

Note

RHEL 6.9 might be suboptimal for certain workloads due to [Poor performance when opening many files in parallel \(p. 242\)](#).

Note

Using Amazon EFS with Amazon EC2 instances running Microsoft Windows is not supported.

Troubleshooting AMI and kernel versions

To troubleshoot issues related to certain AMI or kernel versions when using Amazon EFS from an EC2 instance, see [Troubleshooting AMI and kernel issues \(p. 245\)](#).

Installing the NFS client

To mount your Amazon EFS file system on your Amazon EC2 instance, first you need to install an NFS client. To connect to your EC2 instance and install an NFS client, you need the public DNS name of the EC2 instance and a user name to log in. That user name for your instance is typically ec2-user.

To connect your EC2 instance and install the NFS client

1. Connect to your EC2 instance. Note the following about connecting to the instance:
 - To connect to your instance from a computer running macOS or Linux, specify the .pem file to your Secure Shell (SSH) client with the `-i` option and the path to your private key.
 - To connect to your instance from a computer running Windows, you can use either MindTerm or PuTTY. If you plan to use PuTTY, you need to install it and use the following procedure to convert the .pem file to a .ppk file.

For more information, see the following topics in the *Amazon EC2 User Guide for Linux Instances*:

- [Connecting to Your Linux Instance from Windows Using PuTTY](#)
- [Connecting to Your Linux Instance Using SSH](#)

The key file cannot be publicly viewable for SSH. You can use the `chmod 400 filename.pem` command to set these permissions. For more information, see [Create a Key Pair](#).

2. (Optional) Get updates and reboot.

```
$ sudo yum -y update  
$ sudo reboot
```

3. After the reboot, reconnect to your EC2 instance.
4. Install the NFS client.

If you're using an Amazon Linux AMI or Red Hat Linux AMI, install the NFS client with the following command.

```
$ sudo yum -y install nfs-utils
```

If you're using an Ubuntu Amazon EC2 AMI, install the NFS client with the following command.

```
$ sudo apt-get -y install nfs-common
```

5. Start the NFS service using the following commands. For RHEL 7:

```
$ sudo service nfs start
```

For RHEL 8:

```
$ sudo service nfs-server start
```

6. Verify that the NFS service started, as follows.

```
$ sudo service nfs status
Redirecting to /bin/systemctl status nfs.service
# nfs-server.service - NFS server and services
   Loaded: loaded (/usr/lib/systemd/system/nfs-server.service; disabled; vendor preset: disabled)
     Active: active (exited) since Wed 2019-10-30 16:13:44 UTC; 5s ago
       Process: 29446 ExecStart=/usr/sbin/rpc.nfsd $RPCNFSDARGS (code=exited, status=0/SUCCESS)
      Process: 29441 ExecStartPre=/bin/sh -c /bin/kill -HUP `cat /run/gssproxy.pid` (code=exited, status=0/SUCCESS)
      Process: 29439 ExecStartPre=/usr/sbin/exportfs -r (code=exited, status=0/SUCCESS)
    Main PID: 29446 (code=exited, status=0/SUCCESS)
      CGroup: /system.slice/nfs-server.service
```

If you use a custom kernel (that is, if you build a custom AMI), you need to include at a minimum the NFSv4.1 client kernel module and the right NFS4 userspace mount helper.

Note

If you choose **Amazon Linux AMI 2016.03.0** or **Amazon Linux AMI 2016.09.0** when launching your Amazon EC2 instance, you don't need to install `nfs-utils` because it's already included in the AMI by default.

Next: Mount your file system

Use one of the following procedures to mount your file system.

- [Mounting on Amazon EC2 with a DNS name \(p. 401\)](#)
- [Mounting with an IP address \(p. 403\)](#)
- [Mounting your Amazon EFS file system automatically \(p. 79\)](#)

Recommended NFS mount options

We recommend the following default values for mount options on Linux:

- `rsize=1048576` – Sets the maximum number of bytes of data that the NFS client can receive for each network READ request. This value applies when reading data from a file on an EFS file system. We recommend that you use the largest size possible (up to 1048576) to avoid diminished performance.
- `wszie=1048576` – Sets the maximum number of bytes of data that the NFS client can send for each network WRITE request. This value applies when writing data to a file on an EFS file system. We recommend that you use the largest size possible (up to 1048576) to avoid diminished performance.
- `hard` – Sets the recovery behavior of the NFS client after an NFS request times out, so that NFS requests are retried indefinitely until the server replies. We recommend that you use the hard mount option (`hard`) to ensure data integrity. If you use a soft mount, set the `timeo` parameter to at least 150 deciseconds (15 seconds). Doing so helps minimize the risk of data corruption that is inherent with soft mounts.
- `timeo=600` – Sets the timeout value that the NFS client uses to wait for a response before it retries an NFS request to 600 deciseconds (60 seconds). If you must change the timeout parameter (`timeo`), we recommend that you use a value of at least 150, which is equivalent to 15 seconds. Doing so helps avoid diminished performance.
- `retrans=2` – Sets to 2 the number of times the NFS client retries a request before it attempts further recovery action.
- `noresvport` – Tells the NFS client to use a new Transmission Control Protocol (TCP) source port when a network connection is reestablished. Doing this helps make sure that the EFS file system has uninterrupted availability after a network recovery event.

- `_netdev` – When present in `/etc/fstab`, prevents the client from attempting to mount the EFS file system until the network has been enabled.
- `nofail` – If your EC2 instance needs to start regardless of the status of your mounted EFS file system, add the `nofail` option to your file system's entry in your `/etc/fstab` file.

If you don't use the preceding defaults, be aware of the following:

- In general, avoid setting any other mount options that are different from the defaults, which can cause reduced performance and other issues. For example, changing read or write buffer sizes or disabling attribute caching can result in reduced performance.
- Amazon EFS ignores source ports. If you change Amazon EFS source ports, it doesn't have any effect.
- Amazon EFS does not support the `nconnect` mount option.
- Amazon EFS doesn't support any of the Kerberos security variants. For example, the following mount command fails.

```
$ mount -t nfs4 -o krb5p <DNS_NAME>:/ /efs/
```

- We recommend that you mount your file system using its DNS name. This name resolves to the IP address of the Amazon EFS mount target in the same Availability Zone as your Amazon EC2 instance. If you use a mount target in an Availability Zone different from that of your Amazon EC2 instance, you incur standard EC2 charges for data sent across Availability Zones. You also might see increased latencies for file system operations.
- For more mount options, and detailed explanations of the defaults, see the [man fstab](#) and [man nfs](#) pages in the Linux documentation.

Mounting on Amazon EC2 with a DNS name

Note

Prior to mounting your file system, you need to add a rule to the mount target security group that allows inbound NFS access from the EC2 security group. For more information, see [Using VPC security groups for Amazon EC2 instances and mount targets \(p. 218\)](#).

- **File system DNS name** – Using the file system's DNS name is your simplest mounting option. The file system DNS name automatically resolves to the mount target's IP address in the Availability Zone of the connecting Amazon EC2 instance. You can get this DNS name from the console, or if you have the file system ID, you can construct it using the following convention.

```
file-system-id.efs.aws-region.amazonaws.com
```

Note

DNS resolution for file system DNS names requires that the Amazon EFS file system has a mount target in the same Availability Zone as the client instance.

- Using the file system DNS name, you can mount a file system on your Amazon EC2 Linux instance with the following command.

```
sudo mount -t nfs -o  
nfsvers=4.1,rsize=1048576,wszie=1048576,hard,timeo=600,retrans=2,noresvport file-  
system-id.efs.aws-region.amazonaws.com:/ /efs-mount-point
```

- Using the file system DNS name, you can mount a file system on your Amazon EC2 Mac instance running macOS Big Sur with the following command.

```
sudo mount -t nfs -o
  nfsvers=4.0,rsize=65536,wszie=65536,hard,timeo=600,retrans=2,noresvport,mountport=2049 file-
system-id.efs.aws-region.amazonaws.com:/ /efs
```

Important

You must use `mountport=2049` in order to successfully connect to the EFS file system when mounting on EC2 Mac instances running macOS Big Sur.

- **Mount target DNS name** – In December 2016, we introduced file system DNS names. We continue to provide a DNS name for each Availability Zone mount target for backward compatibility. The generic form of a mount target DNS name is as follows.

```
availability-zone.file-system-id.efs.aws-region.amazonaws.com
```

Note


Mount target DNS name resolution across Availability Zones is supported.

In some cases, you might delete a mount target and then create a new one in the same Availability Zone. In such a case, the DNS name for that new mount target in that Availability Zone is the same as the DNS name for the old mount target.

You can view and copy the exact commands to mount your file system in the **Attach** dialog box.

To view the mount commands for your file system

1. In the Amazon EFS console, choose the file system that you want to mount to display its details page.
2. To display the mount commands to use for this file system, choose **Attach** in the upper right.



The **Attach** screen displays the exact commands to use for mounting the file system.

3. The default **Mount via DNS** view displays the command to mount the file system using the file system's DNS name when mounting with the EFS mount helper or an NFS client.

For a list of AWS Regions that support Amazon EFS, see [Amazon Elastic File System](#) in the *AWS General Reference*.

To be able to use a DNS name in the mount command, the following must be true:

- The connecting EC2 instance must be inside a VPC and must be configured to use the DNS server provided by Amazon. For information about Amazon DNS server, see [DHCP Options Sets](#) in the [Amazon VPC User Guide](#).
- The VPC of the connecting EC2 instance must have both **DNS Resolution** and **DNS Hostnames** enabled. For more information, see [Viewing DNS Hostnames for Your EC2 Instance](#) in the [Amazon VPC User Guide](#).
- The connecting EC2 instance must be inside the same VPC as the EFS file system. For more information on accessing and mounting a file system from another location or from a different VPC, see [Walkthrough: Create and mount a file system on-premises with AWS Direct Connect and VPN \(p. 173\)](#) and [Walkthrough: Mount a File System from a Different VPC \(p. 180\)](#).

Note

We recommend that you wait 90 seconds after creating a mount target before you mount your file system. This wait lets the DNS records propagate fully in the AWS Region where the file system is.

Mounting with an IP address

As an alternative to mounting your Amazon EFS file system with the DNS name, Amazon EC2 instances can mount a file system using a mount target's IP address. Mounting by IP address works in environments where DNS is disabled, such as VPCs with DNS hostnames disabled.

You can also configure mounting a file system using the mount target IP address as a fallback option for applications configured to mount the file system using its DNS name by default. When connecting to a mount target IP address, EC2 instances should mount using the mount target IP address in the same Availability Zone as the connecting instance.


You can view and copy the exact commands to mount your file system in the **Attach** dialog box.

Note

Prior to mounting your file system, you need to add a rule for the mount target security group to allow inbound NFS access from the EC2 security group. For more information, see [Using VPC security groups for Amazon EC2 instances and mount targets \(p. 218\)](#).

To view and copy the exact commands to mount your EFS file system using the mount target IP address

1. Open the Amazon Elastic File System console at <https://console.aws.amazon.com/efs/>.
2. In the Amazon EFS console, choose the file system that you want to mount to display its details page.
3. To display the mount commands to use for this file system, choose **Attach** in the upper right.



4. The **Attach** screen displays the exact commands to use for mounting the file system.

Choose **Mount via IP** to display the command to mount the file system using the mount target IP address in the selected Availability Zone with an NFS client.

- Using the IP address of a mount target in the mount command, you can mount a file system on your Amazon EC2 Linux instance with the following command.

```
sudo mount -t nfs -o  
nfsvers=4.1,rsize=1048576,wsize=1048576,hard,timeo=600,retrans=2,noresvport mount-  
target-IP:/ /efs
```

- Using the IP address of a mount target in the mount command, you can mount a file system on your Amazon EC2 Mac instance running macOS Big Sur with the following command.

```
sudo mount -t nfs -o  
nfsvers=4.0,rsize=65536,wsize=65536,hard,timeo=600,retrans=2,noresvport,mountport=2049 mount-  
target-IP:/ /efs
```

Important

You must use `mountport=2049` in order to successfully connect to the EFS file system when mounting on EC2 Mac instances running macOS Big Sur.

Mounting with an IP address in AWS CloudFormation

You can also mount your file system using an IP address in an AWS CloudFormation template. For more information, see [storage-efs-mountfilesystem-ip-addr.config](#) in the [awsdocs/elastic-beanstalk-samples](#) repository for community-provided configuration files on GitHub.

Document History

- **API version:** 2015-02-01
- **Latest documentation update:** October 17, 2022

The following table describes important changes to the *Amazon Elastic File System User Guide* after July 2018. For notifications about documentation updates, you can subscribe to the RSS feed.

Change	Description	Date
Additional AWS Region support added (p. 405)	Amazon EFS is now available to all users in the Middle East (UAE) Region.	October 17, 2022
Support added for EFS Replication (p. 405)	Amazon EFS has removed a previous limit where EFS replication does not support sockets and named pipes, or FIFOs.	September 15, 2022
The limit for the number of file locks per connection has increased (p. 405)	The number of file locks per connection has increased from 8192 to 65,536. For more information, see Quotas for NFS clients .	May 4, 2022
Limit for processes using file locks removed (p. 405)	Amazon EFS has removed a previous limit where a maximum of 256 processes on a single instance could use file locks at the same time. For more information, see Quotas for NFS clients .	May 4, 2022
Additional AWS Region support added (p. 405)	Amazon EFS is now available to all users in the Asia Pacific (Jakarta) AWS Region.	January 27, 2022
Support added for EFS Replication (p. 405)	Use EFS Replication to replicate the data and metadata on an EFS file system to another EFS file system in the AWS Region of your choice. For more information, see Amazon EFS replication .	January 25, 2022
File system and mount target resources use 17-character resource ID format (p. 405)	New Amazon EFS file system and mount target resources are now assigned 17-character IDs. For more information, see Resource IDs .	October 22, 2021
Support added for EFS Intelligent-Tiering (p. 405)	EFS Intelligent-Tiering uses EFS Lifecycle Management to monitor file access patterns and	September 2, 2021

	<p>is designed to automatically transition files to and from your corresponding Infrequent Access (IA) storage classes. For more information, see EFS Intelligent-Tiering and Lifecycle Management</p>	
Support added for testing 17-character resource ID format (p. 405)	<p>Amazon EFS is transitioning from using 8-character IDs to 17-character IDs for file systems and mount targets on October 1, 2021. During this transition, you can opt-in and start using 17-characters resource IDs on a per AWS Region basis. For more information, see Resource IDs.</p>	May 5, 2021
Support added for mounting One Zone file systems from a different Availability Zone using Amazon EFS mount helper (p. 405)	<p>You can now use the EFS mount helper to mount an Amazon EFS file system that uses One Zone storage classes to an EC2 instance that is in a different Availability Zone by using the new az option to specify the Availability Zone of the Amazon EFS file system. For more information, see Mounting file systems with One Zone storage classes.</p>	April 6, 2021
Support added for EFS One Zone storage classes (p. 405)	<p>Amazon EFS One Zone storage classes store data redundantly within a single Availability Zone in an AWS Region. EFS One Zone and One Zone-Infrequent Access (One Zone-IA) storage classes are a cost effective option for storing data that doesn't require the multi-AZ resilience of EFS Standard and Standard-IA storage classes. For more information, see Using EFS storage classes.</p>	March 9, 2021
Additional AWS Region support added (p. 405)	<p>Amazon EFS is now available to all users in the Asia Pacific (Osaka) AWS Region.</p>	March 3, 2021

Support added for Amazon EC2 Mac instances running macOS Big Sur (p. 405)	You can now mount your Amazon EFS file system from EC2 Mac instances running macOS Big Sur using the EFS mount helper or using the NFS mount command. For more information, see Mounting with the EFS mount helper or Mounting file systems without the EFS mount helper .	February 23, 2021
New Amazon EFS management console is available in AWS GovCloud (US) Region (p. 405)	The new Amazon EFS management console is now available in the AWS GovCloud (US) AWS Region	February 10, 2021
Support added for new Amazon EFS CloudWatch metric MeteredIOBytes (p. 405)	You can use MeteredIOBytes to measure the number of metered bytes for each file system operation, including data read, data write, and metadata operations, with read operations metered at one-third the rate of other operations. For more information, see Amazon CloudWatch metrics for Amazon EFS .	January 28, 2021
Amazon EFS increases file system read throughput by 300% (p. 405)	Amazon EFS file systems now meter read requests at one-third the rate of other requests. For more information, see Understanding metered throughput .	January 28, 2021
Support added for new Amazon EFS CloudWatch metric StorageBytes (p. 405)	You can use StorageBytes to measure and monitor the size of the file system in bytes, including the amount of data stored in the Standard and Infrequent Access storage classes. For more information, see Amazon CloudWatch metrics for Amazon EFS .	January 11, 2021
Use AWS Transfer Family to access Amazon EFS file systems (p. 405)	You can use AWS Transfer Family to transfer files into and out of your Amazon EFS file systems. For more information, see Using AWS Transfer Family to access files in your EFS file system .	January 6, 2021

Use AWS Systems Manager to manage Amazon EFS client (amazon-efs-utils) (p. 405)	You can use AWS Systems Manager to automatically install or update the Amazon EFS clients (amazon-efs-utils) on your EC2 instances. For more information, see Using AWSSystems Manager to automatically install or update Amazon EFS clients .	September 29, 2020
Enforce the creation of encrypted EFS file systems (p. 405)	You can use the elasticfilesystem:Encrypted IAM condition key to enforce that users create Amazon EFS file systems that are encrypted at rest. For more information, see Enforcing the Creation of Amazon EFS File Systems Encrypted at Rest .	September 16, 2020
Amazon EFS per-client throughput increased 100% (p. 405)	EFS now supports up to 500 MB/s of per-client throughput, a 100% increase from the previous limit of 250 MB/s. For more information, see Quotas for Amazon EFS file systems .	July 23, 2020
Support added for automatic daily backups of Amazon EFS file systems (p. 405)	Automatic daily backups are now enabled by default when creating a file system using the EFS console. For more information, see Using AWS Backup with Amazon EFS .	July 16, 2020
New Quick Create workflow simplifies creating Amazon EFS file systems (p. 405)	Using the Quick Create option in the EFS console, you can create an EFS file system using service recommended settings with a single button. For more information, see CreateYour Amazon EFS file system .	July 16, 2020
New Amazon EFS management console is now available (p. 405)	The new EFS console makes it easier for you to use Amazon EFS and simplifies the management of your EFS file systems.	July 16, 2020
Amazon EFS increases file system minimum throughput (p. 405)	Amazon EFS file systems using the default bursting throughput mode now have a minimum throughput of 1 MiB/s. For more information, see Throughput Modes .	June 30, 2020

Performance of General Purpose Mode file systems increased (p. 405)	Amazon EFS General Purpose mode file systems now support up to 35,000 read operations per second, a 400% increase from the previous limit of 7,000. For more information, see Quotas for Amazon EFS File Systems .	April 1, 2020
Additional AWS Region support added (p. 405)	Amazon EFS is now available to all users in the Beijing and Ningxia AWS Regions.	January 22, 2020
Support added for IAM authorization for NFS clients (p. 405)	You can now use AWS Identity and Access Management (IAM) to manage NFS access to an Amazon EFS file system. For more information, see Using AWS IAM to Control NFS Access to Amazon EFS .	January 13, 2020
Support added for EFS Access Points (p. 405)	Amazon EFS access points are application-specific entry points into an Amazon EFS file system that make it easy to manage application access to shared datasets. For more information, see Working with Amazon EFS Access Points .	January 13, 2020
Support added for AWS Backup partial restore. (p. 405)	You can now restore specific files and directories using a partial restore, in addition to restoring a complete recovery point. For more information, see Using AWS Backup with Amazon EFS .	January 13, 2020
Support added for IAM service-linked roles (p. 405)	Amazon EFS now uses a service-linked role based on IAM, making it easier to set up EFS by automatically adding the necessary permissions. For more information, see Using Service-Linked Roles for Amazon EFS .	December 10, 2019
Additional AWS Region support added (p. 405)	Amazon EFS is now available to all users in the Europe (Stockholm) AWS Region.	November 20, 2019
Additional AWS Region support added (p. 405)	Amazon EFS is now available to all users in the Asia Pacific (Hong Kong) AWS Region.	November 20, 2019
Additional AWS Region support added (p. 405)	Amazon EFS is now available to all users in the South America (São Paulo) AWS Region.	November 20, 2019
Additional AWS Region support added (p. 405)	Amazon EFS is now available to all users in the Middle East (Bahrain) AWS Region.	November 20, 2019

New 7 day Lifecycle management policy added (p. 405)	Lifecycle management now has an additional policy to move data to the cost-effective Infrequent Access storage class after 7 days. For more information, see EFS Lifecycle Management .	November 6, 2019
Support added for Interface VPC Endpoints (p. 405)	You can establish a private connection between your virtual private cloud and Amazon EFS to call the EFS API. For more information, see Working with VPC Endpoints .	October 22, 2019
Mount an EFS file system when launching a new EC2 instance. (p. 405)	You can now configure new Amazon EC2 instances to mount your EFS file systems at launch in the EC2 Launch Instance Wizard. For more information, see Step 2. Create Your EC2 Resources and Launch Your EC2 Instance .	October 17, 2019
Support for Service Quotas added (p. 405)	You can now view all Amazon EFS limits in the Service Quotas console. For more information, see Amazon EFS Limits .	September 10, 2019
New lifecycle management policies added (p. 405)	When using Lifecycle Management, you can now choose from one of four lifecycle policies to define when files are transitioned into the cost-effective Infrequent Access storage class. For more information, see EFS Lifecycle Management .	July 9, 2019
EFS Lifecycle Management now available on all EFS file systems. (p. 405)	The EFS Lifecycle Management feature is now available on all EFS file systems. A previous restriction based on when a file system was created is now removed. For more information, see EFS Lifecycle Management .	July 9, 2019
Additional AWS Region support added (p. 405)	Amazon EFS is now available to all users in the Europe (Paris) AWS Region.	June 12, 2019
Additional AWS Region support added (p. 405)	Amazon EFS is now available to all users in the Asia Pacific (Mumbai) AWS Region.	June 5, 2019
Additional AWS Region support added (p. 405)	Amazon EFS is now available to all users in the Canada (Central) AWS Region.	May 1, 2019

API Update: Tags are now part of the CreateFileSystem operation payload (p. 405)	You can now include tags when using the AWS API and CLI CreateFileSystem operation to create an Amazon EFS file system. For more information, see CreateFileSystem and Creating a File System Using the AWS CLI .	February 19, 2019
New features: EFS Infrequent Access storage class and EFS lifecycle management (p. 405)	Amazon EFS Infrequent Access is a cost-optimized storage class for infrequently accessed files. EFS lifecycle management automatically transitions files from Standard to Infrequent Access storage. For more information, see EFS Storage Classes .	February 13, 2019
Additional AWS Region support added (p. 405)	Amazon EFS is now available to all users in the Europe (London) AWS Region.	January 23, 2019
AWS Backup Service integration with Amazon EFS (p. 405)	Amazon EFS file systems can be backed up using AWS Backup, a fully managed, centralized, automated backup service for backing up data across AWS services in the cloud and on premises. For more information, see AWS Backup and Amazon EFS .	January 16, 2019
Transit Gateway connection support to on-premises storage systems added. (p. 405)	Amazon EFS file systems are now accessible using Transit Gateway connections to on-premises storage systems. For more information, see Mounting from Another Account or VPC and Walkthrough: Mount a File System from a Different VPC .	December 6, 2018
EFS File Sync is now part of the new AWS DataSync service. (p. 405)	AWS DataSync is a managed data transfer service that simplifies synchronizing large amounts of data between on-premises storage systems and AWS storage services. For more information, see Transfer Files from On-Premises File Systems to Amazon EFS Using AWS DataSync .	November 26, 2018

VPN and inter-region VPC peering connection support added (p. 405)	Amazon EFS are now accessible over VPN connections and inter-region VPC peering connections. For more information, see Transfer Files from On-Premises File Systems to Amazon EFS Using AWS DataSync .	October 23, 2018
VPN and Inter-region VPC Peering connection support added (p. 405)	Amazon EFS file systems are now accessible over VPN connections and inter-region VPC peering connections. For more information, see Mounting from Another Account or VPC and How Amazon EFS Works with Direct Connect and VPNs .	October 23, 2018
Additional AWS Region support added (p. 405)	Amazon EFS is now available to all users in the Asia Pacific (Singapore) AWS Region.	July 13, 2018
Introducing Provisioned Throughput mode (p. 405)	You can now provision throughput for new or existing file systems with the new Provisioned Throughput mode. For more information, see Throughput Modes .	July 12, 2018
Additional AWS Region support added (p. 405)	Amazon EFS is now available to all users in the Asia Pacific (Tokyo) AWS Region.	July 11, 2018

The following table describes important changes to the *Amazon Elastic File System User Guide* before July 2018.

Change	Description	Date Changed
Additional AWS Region support added	Amazon EFS is now available to all users in the Asia Pacific (Seoul) AWS Region.	May 30, 2018
Added CloudWatch metric math support	Metric math enables you to query multiple CloudWatch metrics and use math expressions to create new time series based on these metrics. For more information, see Using metric math with Amazon EFS (p. 116) .	April 4, 2018
Added the amazon-efs-utils set of open-source tools, and added encryption in transit	<p>The amazon-efs-utils tools are a set of open-source executable files that simplifies aspects of using Amazon EFS, like mounting. There's no additional cost to use amazon-efs-utils, and you can download these tools from GitHub. For more information, see Using the amazon-efs-utils Tools (p. 54).</p> <p>Also in this release, Amazon EFS now supports encryption in transit through Transport Layer Security (TLS) tunneling. For more information, see Data encryption in Amazon EFS (p. 189).</p>	April 4, 2018

Change	Description	Date Changed
Updated file system limits per AWS Region	Amazon EFS has increased the limit on the number of file systems for all accounts in all AWS Regions. For more information, see Amazon EFS resource quotas that you cannot change (p. 237) .	March 15, 2018
Additional AWS Region support added	Amazon EFS is now available to all users in the US West (N. California) AWS Region.	March 14, 2018
Data encryption at rest	Amazon EFS now supports data encryption at rest. For more information, see Data encryption in Amazon EFS (p. 189) .	August 14, 2017
Additional region support added	Amazon EFS is now available to all users in the Europe (Frankfurt) region.	July 20, 2017
File system names using Domain Name System (DNS)	Amazon EFS now supports DNS names for file systems. A file system's DNS name automatically resolves to a mount target's IP address in the Availability Zone for the connecting Amazon EC2 instance. For more information, see Mounting on Amazon EC2 with a DNS name (p. 401) .	December 20, 2016
Increased tag support for file systems	Amazon EFS now supports 50 tags per file system. For more information on tags in Amazon EFS, see Tagging Amazon EFS resources (p. 50) .	August 29, 2016
General availability	Amazon EFS is now generally available to all users in the US East (N. Virginia), US West (Oregon), and Europe (Ireland) Regions.	June 28, 2016
File system limit increase	The number of Amazon EFS file systems that can be created per account for each AWS Region increased from 5 to 10.	August 21, 2015
Updated Getting Started exercise	The Getting Started exercise has been updated to simplify the getting started process.	August 17, 2015
New guide	This is the first release of the <i>Amazon Elastic File System User Guide</i> .	May 26, 2015