Editor Settings Reference

This document is the complete reference for the editor's own settings in FemboyEngine2D 0.4.0-alpha.1: every key, its type, its default, its clamp, what it changes and where it is stored. It covers the `[editor]` table of `project.femproj`, the single `[render]` key that the editor owns, and the `[FemboyEditor]` mirror in `editor.ini`.

The settings are environment preferences, not gameplay. They are stored next to the project so a team reproduces the same authoring environment, they are mirrored to the editor INI for humans and legacy readers, and they never change how a shipped game behaves. No shipped runtime reads them.

1. One struct, one file

Every editor setting lives in one struct:

File	Role
`Source/Editor/Infrastructure/EditorSettings.hpp`	The `EditorSettings` struct: the field list, the defaults and the types. This is the single settings file; a new setting starts here.
`Source/Editor/Infrastructure/ProjectConfig.cpp`	The `[editor]` TOML codec: `EncodeProjectToml` writes the table, `DecodeProjectToml` reads it and applies the clamps
`Source/Editor/Infrastructure/EditorSettings.cpp`	The `AppendEditorSettingsIni` mirror that rewrites the `[FemboyEditor]` section of `editor.ini`
`Source/Editor/Panels/SettingsPanels.cpp`	The Editor Settings panel: the widgets, their panel ranges and their tooltips
`Source/Engine/UI/Accessibility.hpp`	`AccessibilityEditorSettings`, the eight `ide_*` keys that the editor window also owns

The struct is trivially copyable and standard layout, and it has a defaulted `operator==`, so the store can detect that something changed without a hand-written comparison per field. That is what makes "save on commit" cheap.

Two persistence surfaces exist and they are not equal:

Surface	Written by	Read back	Role
`project.femproj`, `[editor]` table	`EncodeProjectToml`	`DecodeProjectToml`	The source of truth
`editor.ini`, `[FemboyEditor]` section	`AppendEditorSettingsIni`	Not read by the editor	A human-readable and legacy-reader mirror

Because the project file is the source of truth, editing `editor.ini` by hand does not change the editor's behaviour on the next start: the next save rewrites the section from the decoded project values. Edit the project file, or use the panel.

Decoding is defensive. Every value is clamped to its documented range, an unreadable value falls back to the default, an out-of-range view mode becomes Standard, and an

unknown key is ignored. Encoding writes every known key and nothing else, so an unknown key is dropped on the next save and a save normalises the file.

2. The complete key table

Types are the TOML types written by the encoder and accepted by the decoder. "Default" is the value in `EditorSettings.hpp` and therefore the value a new project starts with. "Clamp" is the range that `DecodeProjectToml` enforces on read.

TOML key	Field	Editor INI key	Type	Default	Clamp	Meaning
`[editor] ui_scale`	`uiScale`	`ui_scale`	float	1.0	0.5 through 3.0	Scale of the whole editor UI, including panels, toolbars and tooltips
`[editor] font_panel_title`	`fontPanelTitle`	`font_panel_title`	float	24.0	16 through 48 px	Font size of panel and window titles
`[editor] font_panel_body`	`fontPanelBody`	`font_panel_body`	float	18.0	16 through 40 px	Font size of ordinary panel text; 18 px is the readable floor on a 1080p panel
`[editor] font_tooltip`	`fontTooltip`	`font_tooltip`	float	18.0	16 through 40 px	Font size of tooltips and the viewport help card
`[editor] font_script_node_title`	`fontScriptNodeTitle`	`font_script_node_title`	float	21.0	16 through 40 px	Font size of a script graph node title
`[editor] font_script_pin_input`	`fontScriptPinInput`	`font_script_pin_input`	float	18.0	16 through 40 px	Font size of an input pin label
`[editor] font_script_pin_output`	`fontScriptPinOutput`	`font_script_pin_output`	float	18.0	16 through 40 px	Font size of an output pin label
`[editor] font_scene_text`	`fontSceneText`	`font_scene_text`	float	18.0	16 through 64 px	Font size of text drawn in the scene view
`[editor] log_max_files`	`logMaxFiles`	`log_max_files`	int	20	1 through 512	Newest journal files kept per log category; older files are deleted when the sink opens or the setting is

						applied
[editor] log_max_lines	logMaxLinesPerFile	log_max_lines	int	50000	1000 through 2000000	Line count at which a journal file is compacted in place; the newest 90 percent are kept
[editor] show_demo	showDemoWindow	show_demo	bool	false	true or false	Shows the Dear ImGui demo window; a development aid, not a shipping feature
[editor] auto_refresh_browser	autoRefreshBrowser	auto_refresh_browser	bool	true	true or false	Refreshes the Content Browser when the asset database changes
[editor] watch_assets	watchAssets	watch_assets	bool	true	true or false	Runs the OS file watcher and the hot-reload path
[editor] show_grid	showGrid	show_grid	bool	true	true or false	Draws the scene grid
[editor] viewport_view_mode	viewportViewMode	viewport_view_mode	int	0	0 through 5; invalid values become 0	The active viewport diagnostic mode; see section 4
[editor] viewport_complexity_budget	viewportComplexityBudget	viewport_complexity_budget	int	8	1 through 64	Normalisation reference of the Shader Complexity heat ramp; see section 4
[editor] window_mode	windowMode	window_mode	int	1	0 through 2	0 windowed, 1 borderless fullscreen, 2 exclusive fullscreen
[editor] window_width	windowWidth	window_width	int	1600	320 through 16384	Windowed width in pixels, used by modes 0 and 1
[editor] window_height	windowHeight	window_height	int	900	240 through 16384	Windowed height in pixels, used by modes 0 and 1
[editor] save_ini_o	saveEditorIniOnCommi	save_ini_on_commit	bool	true	true or false	Rewrites the [FemboyEdi

n_commit	t					tor] section of editor.ini after a settings commit
[editor] theme	theme	theme	string	"graphite"	Up to 31 bytes	Preset name of the editor palette
[editor] text_color	textColor	text_color	int	0xF2F2F2	0 through 0xFFFFFF	Authored sRGB colour of editor text
[editor] text_opacity	textOpacity	text_opacity	float	1.0	0.2 through 1.0	Alpha of editor text
[editor] text_contrast	textContrast	text_contrast	float	1.0	0.5 through 2.0	Contrast multiplier against the panel background
[editor] text_outline	textOutline	text_outline	bool	false	true or false	Draws an outline around glyphs
[editor] text_outline_color	textOutlineColor	text_outline_color	int	0x000000	0 through 0xFFFFFF	Outline colour
[editor] text_outline_size	textOutlineSize	text_outline_size	float	1.0	0.5 through 4.0	Outline width in logical pixels
[editor] panel_glow	panelGlow	panel_glow	float	0.15	0.0 through 1.0	Accent glow around panels; 0 disables it
[editor] custom_symbol_colors	customSymbolColors	custom_symbol_colors	bool	false	true or false	Enables the per-symbol colour overrides
[editor] symbol_*	symbolColors.*	symbol_*	int	0	0 through 0xFFFFFF	One override per symbol; 0 follows the theme
[editor] symbol_plot_0 … symbol_plot_3	symbolColors.Plot	symbol_plot_*	int	0	0 through 0xFFFFFF	Plot series colours
[editor] ide_blind_mode	-	ide_blind_mode	bool	false	true or false	Keyboard navigation, always-visible focus and the narration sink for the editor window
[editor]	-	ide_deaf_m	bool	false	true or false	Visual

ide_deaf_mode		ode				status cues only; no editor audio alerts
[editor] ide_flash_guard	-	ide_flash_guard	bool	true	true or false	FlashGuard on the editor background
[editor] ide_high_contrast	-	ide_high_contrast	bool	false	true or false	High-contrast palette at a 4.5:1 minimum contrast ratio
[editor] ide_reduce_motion	-	ide_reduce_motion	bool	false	true or false	Removes blinking and other repeated motion
[editor] ide_color_vision	-	ide_color_vision	int	0	0 through 3	0 none, 1 protanopia, 2 deuteranopia, 3 tritanopia
[editor] ide_color_vision_strength	-	ide_color_vision_strength	float	1.0	0.0 through 1.0	Strength of the colour-vision correction
[editor] ide_flash_threshold	-	ide_flash_threshold	float	0.20	0.02 through 1.0	Largest luminance change per frame that FlashGuard allows
[render] vsync	vsync	vsync	bool	true	true or false	Vertical sync of the editor window; the only editor key that lives outside [editor]

Three details that are easy to miss:

- vsync is encoded into the [render] table, next to texture_format and max_texture_size. It is still an editor setting, it still has a struct field, and it is still mirrored into [FemboyEditor]; only its TOML home is different.
- The eight ide_* keys belong to AccessibilityEditorSettings, not to EditorSettings, because the accessibility profile is shared with the game. The editor owns only the editor sub-profile of that structure.
- theme is a fixed 32-byte buffer, so a decoded value is truncated to 31 bytes and a longer string never overflows. The 1.0 editor paints one built-in dark palette and persists the name for compatibility; other values are carried forward but do not repaint the editor yet.

3. Groups in reading order

3.1 Display

Key	Notes
`ui_scale`	Applies to the whole editor UI. The panel slider covers 0.75 through 2.0, while the file clamp allows 0.5 through 3.0, so a hand-edited extreme value is accepted and a normal value is easy to reach with the slider
`window_mode`	1 is the default because borderless fullscreen gives stable frame pacing without a display mode switch; 2 is for latency and performance measurements
`window_width`, `window_height`	The windowed size. They are ignored by exclusive fullscreen, which uses the display mode
`vsync`	On by default. Turn it off only while measuring latency or tearing, because an unlocked editor frame rate makes profiling noisy

3.2 Typography

The typography block is a readability contract: 18 px body text is the floor on a 1080p panel, titles and node captions default larger, and the clamps refuse anything below 16 px.

Key	Default	Panel slider	Why
`font_panel_title`	24	16 through 36	A title must separate from body text at a glance
`font_panel_body`	18	16 through 30	The readable floor; raising it is the first accessibility fix
`font_tooltip`	18	16 through 30	Tooltips carry the same load as body text
`font_script_node_title`	21	16 through 32	Node titles sit on a busy canvas
`font_script_pin_input`	18	16 through 28	Pin labels are dense; keep them at or above the floor
`font_script_pin_output`	18	16 through 28	Same as input pins
`font_scene_text`	18	16 through 40	Scene text is read against art, so it needs more headroom
`text_line_spacing`	0	-4 through 24	Extra space between lines; 0 keeps the font metrics
`text_letter_spacing`	0	-2 through 12	Extra space after every glyph; useful for dense UI fonts
`text_word_spacing`	0	-4 through 24	Extra space after a space glyph; does not change the space character width

The panel ranges are narrower than the file clamps: the panel keeps a safe band, the file accepts an extreme for a specific display.

A legacy migration is part of the decoder. A project that still carries exactly the old combination (20 px title, 16 px body, 16 px tooltip, 18 px node title, 16 px pins, 16 px scene text) is upgraded once to the 24/18/18/21/18/18/18 defaults and the migration is logged. A project that changed any single value keeps its authored sizes, so the migration can never overwrite a deliberate choice.

Font size changes take effect when the font atlas is reloaded, which is the next launch or a hot reload. Line, letter and word spacing are applied by the text renderer immediately; they do not require an atlas rebuild.

3.3 Viewport diagnostics

These are the two keys introduced with the diagnostic viewport modes. Both are described in full in section 4.

3.4 Authoring

Key	Default	Notes
`watch_assets`	true	The OS watcher plus hot reload. Keep it on in a team so an import by a colleague reaches you without a restart
`auto_refresh_browser`	true	Refreshes the Content Browser on a database change. A very large project can turn it off and refresh by hand
`show_grid`	true	The scene grid. Turn it off for screenshot passes
`save_ini_on_commit`	true	Rewrites the INI mirror after a commit. Turning it off leaves the mirror stale while the project file stays current
`show_demo`	false	The ImGui demo window. Useful when building editor UI, noise otherwise

3.5 Logs

Key	Default	Notes
`log_max_files`	20	The newest files of each category are kept; older files are deleted when the sink opens or the setting is applied
`log_max_lines`	50000	A file that reaches this many lines is compacted in place: the oldest lines are dropped and the newest 90 percent stay

The panel exposes the same ranges as the file codec: a slider from 1 through 512

files and a numeric field from 1,000 through 2,000,000 lines. The recommended

20 files by 50,000 lines is roughly 6 MB per file. The live retention is applied

to the engine sink on commit; the project file remains the source of truth.

3.6 Theme

`theme` stores the palette preset name. The 1.0 editor ships the built-in `graphite` palette; the value is persisted and mirrored so a future palette set can read it without a format change.

3.7 Editor accessibility

The eight `ide_*` keys configure the editor window only; the game's own profile is a separate part of the project file.

Key	Default	Effect
`ide_blind_mode`	false	Keyboard navigation with an always-visible focus ring and a narration sink that a screen reader can drain
`ide_deaf_mode`	false	Visual status cues replace editor audio alerts
`ide_flash_guard`	true	Limits the luminance change of the editor background per frame
`ide_high_contrast`	false	High-contrast palette at a 4.5:1 minimum
`ide_reduce_motion`	false	Removes the blinking caret and similar repeated motion
`ide_color_vision`	0	0 none, 1 protanopia, 2 deuteranopia, 3 tritanopia
`ide_color_vision_strength`	1.0	Blend of the correction; the panel slider is disabled when the deficiency is none
`ide_flash_threshold`	0.20	Largest allowed luminance change per frame; the panel slider covers 0.02 through 0.45 and the file clamp allows up to 1.0

`ide_flash_threshold` is the only accessibility key with a conditional widget: the slider is disabled while `ide_flash_guard` is off, because the threshold has no meaning without the guard.

3.8 Text appearance and symbol colours

Text styling is independent of the panel palette: the colour is authored in

sRGB, the opacity and the contrast multiplier are applied against the selected

panel background, and the outline is drawn over the glyph coverage. The symbol

table is an override layer: `customSymbolColors` enables it, and a stored zero

always means "follow the selected theme".

Key	Default	Effect
`text_color`	0xF2F2F2	Base text colour
`text_opacity`	1.0	Text alpha; the clamp keeps the value at or above 0.2
`text_contrast`	1.0	Multiplier against the panel background
`text_outline`	false	Enables the outline pass

`text_outline_color`	0x000000	Outline colour
`text_outline_size`	1.0	Outline width in logical pixels
`panel_glow`	0.15	Accent glow around panels; 0 disables it
`custom_symbol_colors`	false	Enables the overrides below
`symbol_axis_x`, `symbol_axis_y`	0	Axis colours
`symbol_grid`	0	Grid colour
`symbol_play`, `symbol_pause`, `symbol_step`, `symbol_stop`	0	Playback bar glyphs
`symbol_rotate`	0	Rotate gizmo glyph
`symbol_multiplayer`	0	Play (Multiplayer) glyph
`symbol_plot_0` through `symbol_plot_3`	0	Plot series colours

The panel exposes the same ranges as the file codec for opacity, contrast, outline size and glow, so section 6 lists no divergence for them. The three spacing keys (`text_line_spacing`, `text_letter_spacing`, `text_word_spacing`, fields `textLineSpacing`, `textLetterSpacing` and `textWordSpacing`) exist only in `project.femproj`: the INI mirror described in section 5 is never read back, and the renderer takes them from `EditorSettings` directly.

4. The two viewport keys

4.1 viewport_view_mode

Property	**Value**
TOML	`[editor] viewport_view_mode`
INI	`viewport_view_mode`
Field	`viewportViewMode`
Type	int, stored as a uint32 in the struct
Default	0
Clamp	0 through 5, and any invalid value becomes 0
Persisted by	The view mode dropdown in the viewport toolbar and the combo in the Editor Settings panel

The value is the `Rhi::ViewportMode` enumeration:

Value	**Mode**	**Short name**	**What it is for**
0	Standard (Lit)	Standard	The shipped image
1	Unlit / Wireframe	Unlit	Art, UV and pivot checks
2	Collision Overlap	Collision	Collision participation mask
3	Shader Complexity / Overdraw	Overdraw	Fill and light cost
4	Light Complexity	Lights	Number of lights per sprite

5	SDF Visualizer	SDF	Baked distance field agreement

The clamp exists twice on purpose. `ClampViewportViewMode` in `EditorSettings.cpp` is the one helper that knows the valid range, and both the TOML decoder and the INI writer call it, so the project file and the mirror cannot disagree. The `Rhi` enumeration is append-only, so the number keeps its meaning across engine versions.

4.2 viewport_complexity_budget

Property	Value
TOML	`[editor] viewport_complexity_budget`
INI	`viewport_complexity_budget`
Field	`viewportComplexityBudget`
Type	int, stored as a uint32 in the struct
Default	8
Clamp	1 through 64
Panel widget	Slider 1 through 64

The budget is the denominator of the Shader Complexity heat ramp: a sprite whose overlap count times its light count reaches the budget is drawn fully red. It is a diagnostic reference, not a quality setting. Lower it to expose heavy sprites earlier, raise it on a dense scene, and keep one value per project so two screenshots are comparable.

A zero budget would divide by zero, which is why the clamp starts at one, and the presenter additionally treats a zero as one before dividing.

5. The editor.ini mirror

`editor.ini` is written next to the project file. The writer keeps every other section intact, removes the previous `[FemboyEditor]` section, and appends a fresh one, so the section is always complete and never duplicated.

A default project produces this section:

```
[FemboyEditor]
ui_scale = 1.000000
font_panel_title = 24.000000
font_panel_body = 18.000000
font_tooltip = 18.000000
font_script_node_title = 21.000000
font_script_pin_input = 18.000000
font_script_pin_output = 18.000000
font_scene_text = 18.000000
log_max_files = 20
log_max_lines = 50000
vsync = true
show_demo = false
auto_refresh_browser = true
watch_assets = true
show_grid = true
```

```
window_mode = 1
window_width = 1600
window_height = 900
viewport_view_mode = 0
viewport_complexity_budget = 8
save_ini_on_commit = true
ide_blind_mode = false
ide_deaf_mode = false
ide_flash_guard = true
ide_high_contrast = false
ide_reduce_motion = false
ide_color_vision = 0
ide_color_vision_strength = 1.000000
ide_flash_threshold = 0.200000
theme = "graphite"
text_color = 15921906
text_opacity = 1.000000
text_contrast = 1.000000
panel_glow = 0.150000
text_outline = false
text_outline_color = 0
text_outline_size = 1.000000
custom_symbol_colors = false
symbol_axis_x = 0
symbol_axis_y = 0
symbol_grid = 0
symbol_play = 0
symbol_pause = 0
symbol_step = 0
symbol_stop = 0
symbol_rotate = 0
symbol_multiplayer = 0
symbol_plot_0 = 0
symbol_plot_1 = 0
symbol_plot_2 = 0
symbol_plot_3 = 0
```

Floats are written with six decimal places by the string conversion used for the mirror, booleans as `true` and `false`, and the theme as a quoted string. The mirror reflects the clamped values: `window_mode` is written as at most 2 and `viewport_view_mode` goes through `ClampViewportViewMode`, so the mirror can never advertise a value the editor would refuse.

The key names in the mirror match the TOML key names for everything except `vsync`, whose TOML home is `[render]` but whose INI home is `[FemboyEditor]`. That single divergence is deliberate: the INI is a flat editor-environment dump, the project file groups the render keys together.

6. Panel ranges versus file clamps

Where the panel is narrower than the file, the file is the authority and the panel is the safe path. This is the complete list of divergences:

Key	File clamp	Panel widget
`ui_scale`	0.5 through 3.0	Slider 0.75 through 2.0
`font_panel_title`	16 through 48	Slider 16 through 36
`font_panel_body`	16 through 40	Slider 16 through 30
`font_tooltip`	16 through 40	Slider 16 through 30
`font_script_node_title`	16 through 40	Slider 16 through 32
`font_script_pin_input`	16 through 40	Slider 16 through 28
`font_script_pin_output`	16 through 40	Slider 16 through 28
`font_scene_text`	16 through 64	Slider 16 through 40
`ide_flash_threshold`	0.02 through 1.0	Slider 0.02 through 0.45, disabled when the guard is off

A hand-edited file value above the panel maximum is honoured on load and shown in the panel at its own maximum, so opening the panel and moving the slider pulls the value back into the panel band. That is intentional: the panel is an authoring tool, not a validator.

7. Changing a setting correctly

The struct is the single file, so a new setting has one route. In order:

1. Add the field to `EditorSettings` in `EditorSettings.hpp`, with its default and a short comment that states the unit or the meaning of the value.
2. Add the key to the encoder in `EncodeProjectToml` and the matching read plus clamp to `DecodeProjectToml`, in the same order as the struct.
3. Add the key to `AppendEditorSettingsIni` so the mirror stays complete.
4. Add the widget to the Editor Settings panel and choose its panel range; keep it inside the file clamp.
5. Add the field to the infrastructure test that round-trips the project file and checks the INI mirror.
6. Add a row to this reference, then run the drift check.

The drift check is part of the documentation generator:

```
python Documentation/Tools/GenerateReferenceDocs.py --check
```

It reads the `[editor]` table from `ProjectConfig.cpp` and the members of `EditorSettings`, and fails with the exact missing key or field when this reference or the Russian edition falls behind the struct. Run it after every settings change; it is the cheapest way to keep the documentation honest.

8. Recommended values

Situation	Suggested values
Default workstation, 1080p	`ui_scale` 1.0, typography defaults, `viewport_view_mode` 0
1440p or 4K editor, small UI	`ui_scale` 1.25 through 1.5, `font_panel_body` 18 through 20
Accessibility review	`ui_scale` 1.25 or more, `font_panel_body` 20, `font_tooltip` 20, `ide_high_contrast` on, `ide_blind_mode` on
Performance profiling	`vsync` off, `window_mode` 2, `viewport_view_mode`

	3 or 4, `viewport_complexity_budget` at the per-project reference
Screenshot or trailer pass	`show_grid` off, `viewport_view_mode` 0, `ui_scale` back to the team default
Shared team project	Keep `watch_assets` and `auto_refresh_browser` on, and commit the project file rather than the INI mirror

9. Related documents

- [Viewport Display Modes](ViewportModes_EN.md): what each view mode shows, the exact colour legend, the collision ladder, render masks, lights and time stop.
- [Project Settings Recommendations](ProjectSettingsRecommendations_EN.md): the project keys that sit beside these editor keys.
- [Application Guide](FemboyEngineApplicationGuide_EN.md): the editor workflow these settings affect.
- [Accessibility](../../design/accessibility.md): the shared profile and the frame path that consume the `ide_*` and accessibility keys.
- [Lighting](../../design/lighting.md): the solver whose cost the viewport modes measure.