Enterprise Transport API C Edition 3.8.2.L1

ANSI LIBRARY

Document Version: 3.8.2.L1 Date of issue: September 2024 Document ID: ETAC382REANS.240



| Legal Informat | |
|----------------|--|

© LSEG 1991, 1993, 1995, 2010, 2015, 2017-2024. All rights reserved.

Republication or redistribution of LSEG Data & Analytics content, including by framing or similar means, is prohibited without the prior written consent of LSEG Data & Analytics. 'LSEG Data & Analytics' and the LSEG Data & Analytics logo are registered trademarks and trademarks of LSEG Data & Analytics.

Any software, including but not limited to: the code, screen, structure, sequence, and organization thereof, and its documentation are protected by national copyright laws and international treaty provisions. This manual is subject to U.S. and other national export regulations.

LSEG Data & Analytics, by publishing this document, does not guarantee that any information contained herein is and will remain accurate or that use of the information will ensure correct and faultless operation of the relevant service or equipment. LSEG Data & Analytics, its agents, and its employees, shall not be held liable to or through any user for any loss or damage whatsoever resulting from reliance on the information contained herein.

Contents

| 1 | | Introduction | 1 |
|-----|----------------|-------------------------------|-----|
| | 1.1 | Overview | 1 |
| 1.2 | | ANSI Attributes and Features | 2 |
| | 1.2.1 | About the ANSI Library | 2 |
| | 1.2.2 | Characters | 2 |
| | 1.2.3 | Graphic Sets Attribute | 2 |
| | 1.2.4 | Mono/Color Attrbitues | 3 |
| | 1.2.5 | Fading Mono/Color Attributes | 3 |
| | 1.2.6 | Undefined Color Default Value | 3 |
| | 1.2.7 | Scrolling | 4 |
| | 1.2.8 | Unsupported ANSI Features | |
| | 1.3 | Organization of Manual | 4 |
| | 1.4 | Typographic Conventions | 4 |
| | 1.5 | Glossary | 5 |
| | 1.6 | Related Documents | 5 |
| | | | |
| 2 | | Data Structures | 6 |
| | 2.1 | Data Structures | 6 |
| | 2.1.1 | Character Data Structure | 6 |
| | 2.1.2 | Page Data Structure | 6 |
| | 2.1.3 | Update List Data Structure | 7 |
| | 2.2 | Using Data Structures | 8 |
| | 2.2.1 | ANSI Decode | |
| | 2.2.2 | ANSI Encode | S |
| _ | | | 4.0 |
| 3 | | Function Descriptions | |
| | 3.1 | Overview | |
| | 3.2 | qa_decode() | |
| | 3.2.1 | Synopsis | |
| | 3.2.2 | Description | |
| | 3.2.3 | Return Value | |
| | 3.3 | qa_encode() | |
| | 3.3.1 | Synopsis | |
| | 3.3.2 | Description | |
| | 3.3.3 | Return Value | |
| | 3.4 3.4.1 | qa_reset() | |
| | 3.4.1 3.4.2 | Description | |
| | 3.4.2 3.4.3 | Return Value | |
| | 3.4.3 3.5 | qa set rows() | |
| | 3.5.1 | Synopsis | |
| | 3.5.2 | Description | |
| | 3.5.3 | Return Value | |
| | 3.6 | qa set columns() | |
| | 3.6.1 | Synopsis | |
| | 3.6.2 | Description | |
| | 3.6.3 | Return Value | |
| | 3.0.3 | qa_page_rows() | |
| | 3.7.1 | Synopsis | |
| | 3.7.1 | Description | |
| | | • | |
| | 3.7.3 | Return Value | 7 - |

| 3.8 3.8.1 3.8.2 3.8.3 | Description | |
|--------------------------------|--|----|
| 4 | Hints, Tips, and Examples | 15 |
| 4.1 4.2 | Programming Hints and Tips Examples | |
| Appendix A | A ANSI Include File - q_ansi | 19 |
| Appendix I | B Installation Instructions | 23 |
| B.1 | Hardware Requirements | 23 |
| B.2 | Software Requirements | |
| B.3 | Installing the Software | |
| B.4 | Compiling | |
| B.5 | Troubleshooting: Copying the Library | 24 |
| Appendix (| C ANSI Page Data Formats | 25 |
| C.1 | Overview | |
| C.2 | Introducer Sequence | |
| C.3 | Cursor Control Sequences | 26 |
| C.4 | Scrolling Sequences | |
| C.4.1 | Margins | |
| C.4.2 | Movement | |
| C.5 | Mode Control Sequences | 28 |
| C.6 | Display Editing Control Sequences | |
| C.7 | Graphic Selection Sequences | 30 |
| C.8 | Character Attribute Sequences | 31 |
| C.9 | Character and Line Sizing | 32 |
| C.9.1 | DEC Private Sequences | |
| C.9.2 | | |
| C.10 | Miscellaneous Sequences | |
| C.10. | 1 Control Characters | 33 |
| C.10. | 2 Controls | 33 |

1 Introduction

1.1 Overview

The LSEG Real-Time Distribution System ANSI Library (referred to throughout this manual simply as the ANSI Library) provides functions to both interpret and generate ANSI character sequences.

The ANSI Library provides an easy to use programming interface to handle data received from the LSEG Real-Time Distribution System ANSI page (referred to simply as ANSI page) sources as well as an interface for constructing page data that can be published on the LSEG Real-Time Distribution System.

Pages on LSEG Real-Time Distribution System normally have 25 rows of 80 columns of ASCII characters. Each position on a page, in addition to the character displayed, may have the following values associated with it:

- Character-set indicators
- Monochrome attributes (bold, blink, underscore, inverse)
- Color attributes (foreground, background)

Pages must also support cursor-positioning controls so that updates may be applied to a page without retransmitting the entire page. Pages and updates are assembled from characters plus escape sequences and control characters in a format that conforms to the ISO 2022 or ANSI X3.64 standard. This library interprets the ANSI described in the *DEC VT220 Reference Manual* with additions for special character sets and attributes. For further detail on page data formats, refer to Appendix C, "ANSI Page Data Formats."

The qa_decode(), qa_encode(), and qa_reset() functions, along with their associated data structures, represent the heart of the ANSI Library. The qa_decode() function accepts an ANSI string and applies it to a data structure that contains the page image. The qa_encode() function accepts a data structure containing a page image along with a list of page regions that have changed and generates an ANSI string containing the appropriate update sequence. The qa_reset() function resets a page image to its blank screen state.

Four additional functions complete the Library. These functions allow the user to set and retreive the number of rows and the number of columns comprising the user's page of information. (The Library defaults to a 25 row by 80 column page.) The functions to set the page size attributes are qa_set_rows() and qa_set_columns(). One may retrieve the page size using the qa_page_rows() and qa_page_columns() functions.

The Library's C-language source code is supplied along with the Library object. The header file **q_ansi.h** declares the ANSI Library's functions and defines the data structures used to interfacie with the library.

If color and monochrome character attributes are not required by an application, the ANSI Library may be rebuilt to exclude this information. The manifest definition **ATTRIBUTES** made in the header file **q_ansi.h** controls inclusion of this information. Remove this definition to create a version without color and monochrome attributes.

1.2 ANSI Attributes and Features

1.2.1 About the ANSI Library

The ANSI Library was developed as a value-added set of functions for handling page-formated data on the LSEG Real-Time Distribution System.

1.2.2 Characters

This is represented internally as an ASCII value in the range 0x20 to 0x7E, together with a byte representing the graphic set.

1.2.3 Graphic Sets Attribute

The different graphic sets mean that the interpretation of characters is not trivial, except in the case of Sources which use only the US or UK ASCII character sets (Reuter Monitor, Telerate SOP etc.).

```
/*Character set defines*/
#define US ASCII 'B'
#define UK ASCII
                'A'
':' /*chapdelaine ascii */
#define RMJ_SPEC ';' /*rmj ascii*/
#define GARBAN S'<' /*garban ascii*/
#define MABON SP'=' /*mabon ascii*/
#define MOSAIC G
                '>' /*mosaic graphic set */
#define FBI ASCI '?' /*fbi special ascii */
#define FBI_SPEC 'f' /* " graphics */
#define TOPIC CS 't' /*topic character set */
#define GENERL G 'g' /*general graphics */
#define VIEW MOS
                'v' /*viewdata mosaics */
                's' /*sop ascii*/
#define SOP ASCI
#define SEPR MOS'w' /*view separated mosaics */
```

1.2.4 Mono/Color Attrbitues

Each cell has "Attributes", which represent the color, highlighting, blinking, and underline state of the character in the cell.

The prefix **F**_ specifies the foreground color; the prefix **B**_, the background color.

```
/* ATTRIBUTE BYTE definitions */
#define _PLAIN
               0x00
#define BLINK
                0x01
#define REVVID
                    0x02
#define DIM
#define UNDLN
                    0x08
#define BRIGHT
                    0x10
/* definitions for color */
#define F BLACK 0x00
#define F RED
                 0x01
                 0x02
#define F GREEN
#define F YELLOW 0x03
#define F BLUE 0x04
#define F MAGENTA0x05
#define F CYAN
                 0x06
#define F WHITE
                  0 \times 07
#define B BLACK
                  0x00
#define B RED
                     0x10
#define B GREEN 0x20
#define B YELLOW 0x30
#define B BLUE
                  0x40
#define B MAGENTA
                   0x50
#define B CYAN
                  0x60
#define B WHITE
                  0x70
```

1.2.5 Fading Mono/Color Attributes

Each cell has "Attributes", which represent the fading *c*olor, highlighting, blinking, and underline state of the character in the cell. The attribute values are the same as the normal attributes. The timing associated with the fading attribute must be done by the application. Fading is explained in the glossary.

1.2.6 Undefined Color Default Value

The default color and the color of erased characters is not defined by the ANSI standard. LSEG Real-Time Distribution System applications normally display this as black. It is represented in the data structure by the special value 0x0F. The default monochrome color follows:

1.2.7 Scrolling

Only vertical scrolling of entire lines (up or down) is supported. There is provision to avoid more than one set of entries in the update list if an update causes multiple scroll operations.

There is no attempt to optimize the handling of multiple scrolling operations.

There is support for the DEC escape sequences to restrict the scrolling region.

1.2.8 Unsupported ANSI Features

Double Height and Double Width character formats are NOT supported.

1.3 Organization of Manual

This manual is organized into the following sections:

| CHAPTER | CONTENTS | | | |
|--|--|--|--|--|
| Chapter 2 Describes ANSI Library data structures. | | | | |
| Chapter 3 | Chapter 3 Presents function calls with an explanation of correct syntax and return values. | | | |
| Chapter 4 Provides programming tips and examples of code using ANSI Library functions. | | | | |
| Appendix A Contains a listing of the q_ansi.h header file. | | | | |
| Appendix B Details on how to install ANSI Library software. | | | | |
| Appendix C Discusses ANSI Page Data Formats. | | | | |

Table 1: Manual Overview

1.4 Typographic Conventions

- Directories, filenames, parameters, and list entries appear in bold, e.g.: q_ansi.h
- When in text, function names, code snippets, and structures appear in black, Courier New font.
- Document titles appear in italics, e.g.: Transport API C Edition Developers Guide
- Code samples appear in a Courier New font with a grey background, e.g.:

```
typedef struct
{
   unsigned char flags;
   unsigned char code;
} SSL_STATUS_CODE;
```

1.5 Glossary

Below is a list of terms and definitions which are used frequently throughout this document.

| TERM | DEFINITION |
|--|---|
| ANSI (American National Standards Institute) This agency develops standards widely used as guidelines by US firms. Data produced developed from ANSI range from the definition of ASCII to the determination of a system performance. | |
| ANSI Sequence A string of characters which invokes a mode or status change in the display system. A start with an ESC character (033 octal) and then follow one of several patterns. The rumust recognize these patterns and act upon the supported sequences while ignoring sequences. | |
| Consumer Application | A program, compiled and linked with the LSEG Real-Time Distribution System, whose main function is to retrieve market data from the Enterprise Platform. |
| Fading A feature that many users and sources require, where an area of updated text must be hig a short time to draw attention to it. After the end of the fade period, the text returns to its or Applications implement fading as follows: when a character is changed, it is displayed inithe "Fading" set of attributes. After a fixed period of time, it is re-displayed with the defaul | |
| Image | An image is the complete data representation of an item. |
| Item | An item is a named data entity. There are two types of items: pages and records. They are identified by the name of the source which supplies them, and the name of the individual item within that source. |
| Page | A page is a type of item formatted for distribution to display systems. The data includes text and control information in accordance with ANSI X3.64 and X3.41 (plus various extensions and private sequences). |
| Page-Oriented Source A source that organizes information in logical pages. Logical pages are of variable di typically displayed in 80 columns and 24 or 25 rows. | |
| Record | A record is a type of item presented in a form which is convenient for use by computer applications. The data is presented in the Marketfeed format. |
| Source | Any application or server capable of supplying or transmitting information to the LSEG Real-Time Distribution System. |
| Update An update is a modification to the contents of an item. A source sends updates a the contents of the item change. | |

Table 2: Glossary of Terms

1.6 Related Documents

- ANSI X3.64 Protocol Specification, New York, N.Y. 1979
- DEC VT220 Programmers Reference Manual, Digital Equipment Corporation, 1984
- The <u>LSEG Developer Community</u>

2 Data Structures

2.1 Data Structures

The following descriptions summarize the data structures used to interface with the ANSI Library. The structure definitions are taken from the **q_ansi.h** header file.

2.1.1 Character Data Structure

A data structure is used to describe each character on the page. The structure contains the character attributes described in the previous section. The **CHARTYP** data structure follows:

2.1.2 Page Data Structure

The central data structure **PAGETYP** points to an array of character "cells" corresponding to the matrix of characters comprising the screen. The **PAGETYP** data structure follows:

Status information is kept in the PAGETYP structure because the decode function may be called repeatedly for the same page.

The page structure should be initialized with the ANSI reset string (ESC c).

The page structure should not be altered between calls to the decode routine.

2.1.3 Update List Data Structure

The **LISTTYP** data structure provides a mechanism to communicate which character cells have changed. It contains an array of **upd_type** structures, each comprising the row, start, and end columns of cells which have been affected by an update. A description of the **upd_type** structure follows:

If more than one row was affected by the message, many of these structures must be provided for each area of change. The **LISTTYP** structure provides a length and pointer to an array of **upd_type** structures. The user must provide the space for the array. The **LISTTYP** structure follows:

2.2 Using Data Structures

2.2.1 ANSI Decode

The function **qa_decode()** is used to decode an ANSI string into the **PAGETYP** structure. The function is passed an ANSI update string, plus pointers to a **PAGETYP** structure and **LISTTYP** structure. After the ANSI update string has been processed, the **LISTTYP** structure holds a list of all the fields which have been updated, and the **PAGETYP** structure contains the correct attributes for those fields.

The **qa_decode()** function allows for multiple "passes" over a single string of update information. This allows the Update List to be sized without knowledge of the maximum amount of update information that a source communicates. A call to **qa_decode()** returns the number of characters parsed from the update string. This value is less than the update string length when the Update List size was not sufficient. The application can make subsequent calls to **qa_decode()** to parse the remainder of the update string.

2.2.1.1 Interpreting the Update List

On return from qa_decode (), the Update List data structure contains an entry for each area updated. A descriptions of the list follows:

- max_updt number of entries in the list; it is supplied by the user
- index array offset of last entry (starting at 0); it is 1 less than number of entries in list and is set by the library
- upd_type upd_list array of update entries of length [max_updt 1]

The description of each update entry follows:

- row the row (e.g. 1 to 25) in which the data has changed
- upd_beg the column (e.g. 1 80) in which the change starts
- **upd_end** the column (e.g. 1 80) where the change ended. This is 1 beyond the last character that has changed so the total number of characters that have changed in a row is (**upd_end upd_beg**). Zero length updates should be ignored.

An entry is added to the list for the following reasons:

- For each repositioning of the cursor, an entry with zero length is generated for that point. A Carriage Return plus Line Feed is treated as a single sequence.
- Each character written increases the length of the current entry by one. If it wraps around at the end of a line, that is treated as cursor movement, and a new entry added as above.
- Scrolling generates an entry for each row scrolled, and one for the new cursor position following the scroll.

2.2.1.2 Initialization

Only one Update List data structure is required, since this is used only as a means of returning information from **qa_decode()**. One **PAGETYP** data structure is required for each page on display - it contains all of the static information for a page representation. These may be allocated dynamically or created statically.

The size of the **CHARTYP** buffer pointed to by the **PAGETYP** data structure (i.e. the page size that the Triarch ANSI Library function operates on) is communicated to the ANSI Library by the functions **qa_set_rows()** and **qa_set_columns()**. These functions define the user application's page size in rows and columns. The **CHARTYP** buffer referenced by **qa_decode()** (as well as **qa_encode()** and **qa_reset()**) must correspond to this page size.

Page size is maintained statically by the ANSI library. Once the page size has been set, one need only call <code>qa_set_rows()</code> and <code>qa_set_columns()</code> when the page size changes. The default page size is 25 rows by 80 columns. If a user's page size is always 25 rows by 80 columns, the <code>qa_set_rows()</code> and <code>qa_set_columns()</code> functions need not be called.

The update list must have the field **max_updt** initialized to the number of **upd_type** elements in the array. Note that this field is not modified by **qa_decode()**.

Each **PAGETYP** structure is best initialized by calling **qa_decode()** passing the ANSI initialize sequence (*ESC c*) which resets the entire data structure without reference to the original contents. In addition, if **qa_encode()** is to be used, the **last_mod** field must be set to the value (-1). Example initialization code follows:

```
void InitializePage( PAGEPTR page, LISTPTR u_list )
{
/* max_updt must be set and the array size > 30 */
        (void)qa_decode( page, "\033c", 2, u_list );
        page->last_mod = -1;
}
```

2.2.2 ANSI Encode

When the content of one or more regions of a page change, the application updates the page image directly, keeping track of the positions changed in the update list. The application then calls the <code>qa_encode()</code> function with the <code>PAGETYP</code> and <code>LISTTYP</code> data structures that reflect the current state of the page and the areas which were updated. <code>qa_encode()</code> generates a string containing the ANSI sequences required to communicate the changes to an LSEG Real-Time Distribution System consumer application.

The function permits multiple "passes" to manage updates that exceed the size of the update string buffer. It uses a field within the **PAGETYP** structure, **last_mod**, to save the state between passes. This field must be reset to the value **-1** before the function is called with a new update.

The size of the **CHARTYP** buffer pointed to by the **PAGETYP** data structure (i.e. the page size that the ANSI Library function operates on) is communicated to the ANSI Library by the functions **qa_set_rows()** and **qa_set_columns()**. These functions define the user application's page size in rows and columns. The **CHARTYP** buffer referenced by **qa_encode()** (as well as **qa_decode()** and **qa_reset()**) must correspond to this page size.

Page size is maintained statically by the ANSI library. Once the page size has been set, one need only call <code>qa_set_rows()</code> and <code>qa_set_columns()</code> when the page size changes. The default page size is 25 rows by 80 columns. If a user's page size is always 25 rows by 80 columns, the <code>qa_set_rows()</code> and <code>qa_set_columns()</code> functions need not be called.

3 Function Descriptions

3.1 Overview

This section contains the description and syntax for the Triarch ANSI LIbrary functions:

- qa decode(): Decodes an ANSI character sequence.
- qa encode (): Encodes an ANSI character sequence.
- qa reset(): Resets a page image.
- qa set rows() and qa set columns(): Informs the Library of the user's page size.
- qa_page_rows() and qa_page_columns(): Retrieves the Library's user page size settings.

Data structures used by these functions are described in Chapter 2.

3.2 qa_decode()

3.2.1 Synopsis

3.2.2 Description

Decoding an ANSI string is accomplished using a finite state machine. Each of the ANSI escape sequences is parsed according to the state into which the previous characters have the machine.

As the sequences are recognized, the page image is modified.

3.2.3 Return Value

Qa_decode () returns the number of characters in text it has successfully parsed. It does not return a length which would cause an escape sequence to be broken. Qa_decode () may be called as many times as necessary until all the text is parsed.

If qa decode () has completed, the length which was passed to it is returned.

3.3 qa_encode()

3.3.1 Synopsis

```
#include "q ansi.h"
int qa encode(
                                     /*pointer to the stored page image*/
     PAGEPTR page,
      unsigned char *text,
                                     /*pointer to buffer for ANSI text*/
                                     /*size of text buffer*/
      long maxstrlen,
      long *length,
                                     /*offset in text after encoding*/
      short fade enable,
                                     /*flag to enable fading*/
      LISTPTR u list)
                                     /*update list pointer whose data
                                     structure contains a list of all the
                                     blocks that need to be encoded*/
```

3.3.2 Description

This routine takes a stored page image along with a list of regions that the application has changed and encodes it into an ANSI string containing the appropriate update sequence. This function is useful when creating pages to publish on the LSEG Real-Time Distribution System network via the platform when displaying the output of an application on an ANSI terminal.

The qa_encode () function processes each entry in the update list up to the index. For the row and start column specified in the update list up to (but not including) the end column, the corresponding characters and attributes in the page image are added to text.

3.3.3 Return Value

If qa_encode () is able to encode all of the data regions defined by the update list into text, it returns DONE.

If qa_encode() runs out of room in text before the image is completely encoded, it returns NOT_DONE, and last_mod in the page image is set to the entry in the update list where qa_encode() will resume encoding the next time it is called. qa_encode() may be called as many times as necessary to completely encode all the regions defined in the update list.

The memory pointed to by length contains the length of text in either case.

3.4 qa_reset()

3.4.1 Synopsis

```
#include "q_ansi.h"
short qa_reset(
    PAGEPTR page,     /* pointer to the page image to be cleared */
    char *not_used,/* char pointer not effected by the library */
    LISTPTR u_list)/* pointer to update list to be reset */
```

3.4.2 Description

This routine takes a pointer to a page image and an update list that the user wishes to be reset.

The qa_reset() function resets the page image to the blank screen state (i.e. a page of space characters with _PLAIN attributes. qa reset() also resets the update list passed to the function.

3.4.3 Return Value

If qa reset() returns 1.

3.5 qa set rows()

3.5.1 Synopsis

```
#include "q_ansi.h"
void qa_set_rows(short rows)/* no. of rows in user's page */
```

3.5.2 Description

This routine takes the number of rows in a user's page. qa_set_rows() is used in conjunction with qa_set_columns() to tell the library the size of the CHARTYP buffer being passed in subsequent qa_encode(), qa_decode(), and qa_reset() function calls.

The Triarch ANSI Library uses the page size information during processing of page images in **qa_encode()**, **qa_decode()**, and **qa_reset()**.

Page size is maintained statically by the Triarch ANSI library. Once the page size has been set, one need only call <code>qa_set_rows()</code> and <code>qa_set_columns()</code> when the page size changes. The default page size is 25 rows by 80 columns. If a user's page size is always 25 rows by 80 columns, the <code>qa set_rows()</code> and <code>qa set_columns()</code> functions need not be called.

3.5.3 Return Value

This function has no return value.

3.6 qa_set_columns()

3.6.1 Synopsis

```
#include "q_ansi.h"
void qa_set_columns(
    short cols) /* no. of columns in user's page */
```

3.6.2 Description

This routine takes the number of columns in a user's page. qa_set_columns() is used in conjunction with qa_set_rows() to tell the library the size of the CHARTYP buffer being passed in subsequent qa_encode(), qa_decode(), and qa_reset() function calls.

The Triarch ANSI Library uses the page size information during processing of page images in qa_encode(), qa_decode(), and qa_reset().

Page size is maintained statically by the Triarch ANSI library. Once the page size has been set, one need only call **qa_set_rows()** and **qa_set_columns()** when the page size changes. The default page size is 25 rows by 80 columns. If a user's page size is always 25 rows by 80 columns, the **qa_set_rows()** and **qa_set_columns()** functions need not be called.

3.6.3 Return Value

This function has no return value.

3.7 qa_page_rows()

3.7.1 Synopsis

```
#include "q_ansi.h"
short qa_page_rows(void)
```

3.7.2 Description

Page size (in rows and columns) is maintained statically by the Triarch ANSI Library. (It can be set using the **qa_set_rows()** and **qa_set_columns()** function calls.) **qa_page_rows()** returns the current number of rows in a page.

The Triarch ANSI Library uses the statically maintained number of rows in a page to process page images during the qa_encode(), qa_decode(), and qa_reset() function calls. The information is used to determine the size of the CHARTYP buffer being passed to those functions.

3.7.3 Return Value

This function returns the current Triarch ANSI Library setting for the number of rows in a page.

3.8 qa_page_columns()

3.8.1 Synopsis

#include "q_ansi.h"
short qa_page_columns(void)

3.8.2 Description

Page size (in rows and columns) is maintained statically by the Triarch ANSI library. (It can be set using the qa_set_rows() and qa_set_columns() function calls.) qa_page_columns() returns the current number of columns in a page.

The Triarch ANSI Library uses the statically maintained number of columns in a page to process page images during the <code>qa_encode()</code>, <code>qa_decode()</code>, and <code>qa_reset()</code> function calls. The information is used to determine the size of the <code>CHARTYP</code> buffer being passed to those functions.

3.8.3 Return Value

This function returns the current Triarch ANSI Library setting for the number of columns in a page.

4 Hints, Tips, and Examples

4.1 Programming Hints and Tips

Programmers should be aware of the following:

- The function qa_decode() displays an error message when it encounters an invalid sequence. This feature may be excluded by
 undefining the manifest parameter QA_DISPLAY_ERR in q_ansi.h and rebuilding the library.
- The LISTTYP structure member index starts at zero. Thus a value of 4 indicates 5 update entries.
- It is recommended that the update list passed to qa_decode() be made large enough to handle likely Triarch message updates (see the next comment).
- The number of update list entries generated by a complex update can be very large, and sufficient space should be allowed to avoid
 overflow. An update list buffer offering 1000 entries would not be excessive for handling Telerate pages, where the drawing of vertical
 columns on a row by row basis can produce hundreds of individual updates.

4.2 Examples

The following code gives examples of routines which call the ANSI qa decode () and qa encode () functions.

```
/***************
* NAME:
             main
^{\star} DESCRIPTION: This example program demonstrates the
  use of the ANSI Library functions. The program:
  clear initializes the page and update structures
  decodes two siple strings and checks to see if an
  update was generated in a certain range
  prints out a block of the modified page to stdout.
#include <stdio.h>
#include "q ansi.h"
/*define initialization and example strings used in program*/
#define INIT STRG"\033c\033(B\033[0;47;30m\033[1;1H"
#define CHG 15"\033[1;20Hwrite on line one\
         \033[5;40Hwrite on line five"
#define CHG 48 "\033[4;10Hwrite on line three \
         \033[8;30Hwrite on line eight"
#define poffset(pageptr,row,col) &(pageptr->page [((((row) - 1) * PAGECOLS)+((col) - 1))])
#define MY ROWS 25
#define MY COLS 80
main()
{
```

```
void EncodeAnsi();/*declare lower routine*/
   PAGETYP qa page; /*page structure*/
   CHARTYP pageImage[MY ROWS*MY COLS];
   LISTTYP *qa ulist;/*pointer to update struc*/
   char qa list sp[sizeof(LISTTYP) +
      sizeof(struct upd type) * 1000];
                   /*space for update*/
   int retv,cnt;
   struct upd type *1 ptr;
   /* set up the page structure */
   qa page.page = pageImage;
   qa set rows(MY ROWS);
   qa set columns (MY COLS);
   /* set up update list area*/
   ga ulist = (LISTTYP *)ga list sp;
   qa ulist->max updt = 1000;
   /* clear data area */
   qa decode(&qa page, INIT STRG, sizeof(INIT STRG),qa ulist);
   /*run decode test with samples*/
   retv = DecodeAnsi(1,80,7,10, CHG 15, qa ulist, &qa page);
   printf("decode test 1 returned %d\n", retv);
   retv = DecodeAnsi(1,80,7,10, CHG 48, qa ulist, &qa page);
   printf("decode test 2 returned %d\n",retv);
   /*print out columns 15 to 35 for rows 4 to 9
     set up update structure*/
   qa ulist->index = -1;
   for(cnt=4,1 ptr=qa ulist->upd list;cnt <=9;cnt++,1 ptr++) {</pre>
      1 ptr->row = cnt;
      l ptr->upd beg = 15;
      1 ptr->upd end = 35;
      (qa_ulist->index)++;
   EncodeAnsi(qa_ulist, &qa_page);
   exit(0);
/************
* Name: DecodeAnsi
* Description: processes ANSI code and determines if a
* change was made in columns x1 to x2, rows y1 to y2
* it returns TRUE if an update was made in that region
* it also returns the updated PAGETYP structure and the
* last list of updates in the LISTTYP structure
* Parameters: range to check x1, x2, y1, y2
  pointer to null terminated update string *sText
  pointer to LISTTYP structure *u ptr
  pointer to PAGETYP structure *pg ptr
************************************
DecodeAnsi(x1,x2,y1,y2,sText,u ptr,pg ptr)
int x1, x2, y1, y2;
```

```
char *sText;
LISTTYP *u ptr;
PAGETYP *pg ptr;
   long text len, ch p;
   int retv, ucnt;
   struct upd_type *l_ptr;
   retv = 0; ch p = 1;
   text len = strlen(sText);
   for(;text len >0 && ch p > 0;text len -= ch p,sText += ch p){
      ch p = qa decode(pg ptr, sText, text len, u ptr);
      /*check all updates for range*/
      for(ucnt = (u ptr->index +1),1 ptr =
          u ptr->upd list;ucnt;ucnt--,l ptr++) {
         if(!retv && 1 ptr->row >= y1 && 1 ptr->row <= y2){
             if((l ptr->upd beg >= x1 \&\&
                1 ptr->upd beg <= x2) ||
               (1 ptr->upd end >= x1 \&\&
               l ptr->upd end <= x2))</pre>
                retv = 1;
          }
   return (retv);
/**************
* Name: EncodeAnsi
* Description: processes PAGETYP and LISTTYP structures
* and produce an ANSI string that will be written to
* stdout
* Parameters: pointer to LISTTYP structure *u ptr
* pointer to PAGETYP structure *pg_ptr
*********************************
void EncodeAnsi(u ptr,pg ptr)
LISTTYP *u ptr;
PAGETYP *pg ptr;
   unsigned char tmp_buf[1000];
   int retv;
   long len;
   short last_mod;
   last_mod = pg_ptr->last_mod = 0;
   do {
      last mod = pg ptr->last mod;
      retv = qa encode(pg ptr,tmp buf,1000,&len,0,u ptr);
      tmp buf[len] = ' \setminus 0';
   /*while not done and progress is being made*/
```

```
} while(last_mod != pg_ptr->last_mod && retv != DONE);
}
```

Appendix A ANSI Include File - q_ansi

```
/*|-----
 *| This source code is provided under the Apache 2.0 license --
 *| and is provided AS IS with no warranty or guarantee of fit for purpose. --
     See the project's LICENSE.md for details. Copyright (C) 1995,2019 LSEG. All rights reserved.
 *|-----
#ifndef Q ANSI H
#define Q ANSI H
#include "rtr/platform.h"
     /* define return values for qa encode */
#define DONE 0
#define NOT DONE 1
/\star define ATTRIBUTES when monochrome, color, and fading attributes are
   needed. Leaving ATTRIBUTES undefined saves space. \star/
#define ATTRIBUTES
struct upd_type { /* structure for incoming updates */
short row; /* row on which the update appears */
short upd_beg; /* beginning column of update */
short upd_end; /* ending column of update */
typedef struct list_type {
     short max_updt; /* size of upd_list */
short index; /* num of entries in upd_list */
struct upd_type upd_list[1]; /* this structure is overlaid on
                      the space the caller provides */
} LISTTYP, *LISTPTR;
typedef struct status {
    short row;
                            col;
    short col;
unsigned char cur_attr; /* monochrome attribute */
unsigned char c_attr; /* color attribute */
unsigned char c_fade_attr; /* color fading attr */
unsigned char fading; /* mono fading attr */
unsigned char gr_set; /* flag to select GO or G1 */
unsigned char GO_set; /* GO graphics set */
unsigned char G1_set; /* G1 graphics set */
short wrap_on; /* flag for line wrap */
short vem; /* flag for vert editing mode */
short hem; /* flag for horiz edit mode */
     short
} STATUSTYP, *STATUSPTR;
typedef struct char type {
    char ch;
     unsigned char gs; /* graphic set */
#ifdef ATTRIBUTES
     unsigned char attr; /* mono attrib */
```

```
unsigned char fade_attr; /* mono fading */
unsigned char c_attr; /* color attrib */
unsigned char c_fade_attr; /* color fading */
#endif
} CHARTYP, *CHARPTR;
typedef struct page type {
    CHARTYP *page; /* size of [PAGEROWS * PAGECOLS] */
    STATUSTYP
                  status;
    STATUSTYP
                  save;
                                     /* for cursor save/restore */
                                    /* top of scrolling region */
              scroll_top;
scroll_bot;
last_mod;
    short
                                    /* bottom of scrolling reg */
/* qa_encode marks last entry in u_list it was able to encode */
    short
    short
} PAGETYP, *PAGEPTR;
#define PAGELENGTH sizeof(PAGETYP)
#define CHARLENGTH sizeof(CHARTYP)
/* ATTRIBUTE BYTE definitions */
#define PLAIN 0x00
#define _BLINK
#define _REVVID
#define _DIM
                         0x01
                         0x02
                         0x04
#define _DIM 0x04

#define _UNDLN 0x08

#define _BRIGHT 0x10
/* definitions for color */
0x00
#define F BLACK
#define F_RED 0x01
#define F_GREEN 0x02
#define F YELLOW 0x03
#define F BLUE 0x04
#define F_MAGENTA 0x05
#define F_CYAN 0x06
#define F_WHITE 0x07
#define B_BLACK 0x00
#define B_RED 0x10
#define B_GREEN 0x20
#define B YELLOW 0x30
#define B BLUE 0x40
#define B MAGENTA 0x50
#define B_CYAN 0x60
#define B_WHITE 0x70
/* definitions for character size */
/* Modes for encoding ansi
   UPDATE mode adds fading blink */
#define NO_FADE 0
#define NORM 1
#define UPDATE
#define ISSUPDT
```

```
/* define character set selection parameters for use with encode ansi
     routine. These parameters are to be used to indicate character set
     or sets being used to create the page image.
#define US ASCII
                              'B'
#define UK ASCII
                              'A'
                                     /* vt100 graphics */
#define VT100 GS
                              '0'
#define CHAP SPC ':'
                                    /* chapdelaine special ascii */
#define CHAP_SPC ':' /* chapdelaine special ascii
#define RMJ_SPEC ';' /* rmj " " */
#define GARBAN_S '<' /* garban " " */
#define MABON_SP '=' /* mabon " " */
#define MOSAIC_G '>' /* mosaic graphic set */
#define FBI_ASCI '?' /* fbi special ascii */
#define FBI_SPEC 'f' /* " " graphics */
#define TOPIC_CS 't' /* topic character set */
#define GENERL_G 'g' /* general graphics */
#define VIEW_MOS 'v' /* viewdata mosaics */
/* escape sequence number and out sequence table offsets*/
#define DBH_TP 1 /*double high top*/
#define DBH_BT 2 /*double high bottom*/
#define DBHW_TP 3 /*double high/wide top*/
#define DBHW_BT 4 /*double high/wide bottom*/
#define DB_OFF 5 /*double off*/
#define DBWD 6 /*double wide single high*/
#define DBWD
                           6 /*double wide single high*/
#define DB MIN
                           1
#define DB MAX
/*masks for bits in attribute sequence
     where f is 1 when double is active
     where d is the double attribute info
     where a is the normal attribute info
#define BACK COL MASK 0xf0
#define FORG COL MASK 0x0f
#ifdef __cplusplus
extern "C"
{
#endif
extern short PAGECOLS;
extern short PAGEROWS;
extern short END OF ROW;
extern short SCROLL BOT;
#define SCROLL TOP
extern CHARTYP null char;
#if defined( cplusplus) || defined( STDC )
```

```
extern int qa decode( PAGEPTR, char*, int, LISTPTR);
extern int qa encode( PAGEPTR, unsigned char*, long, long*, short, LISTPTR);
extern short qa_page_rows();
extern short qa_page_columns();
extern short qa end of row();
extern short qa scroll bot();
extern void qa set rows ( short );
extern void qa set columns ( short );
extern void qa_set_end_of_row( short );
extern void qa_set_scroll_bot( short );
extern short qa reset(PAGEPTR, char*, LISTPTR);
#else
extern int qa_decode();
extern int qa_encode();
extern short qa page rows();
extern short qa page columns();
extern short qa end of row();
extern short qa scroll bot();
extern void qa set rows();
extern void qa_set_columns();
extern void qa set end of row();
extern void qa set scroll bot();
extern short qa reset();
#endif
#ifdef cplusplus
#endif
```

#endif

Appendix B Installation Instructions

This Appendix provides the information necessary to install and set up the ANSI Library for use in application development. It lists the hardware and software requirements for ANSI Library use and gives instructions for loading the ANSI Library software from the release media. Also included are explanations about incorporating the library in application code, and an installation troubleshooting guide.

B.1 Hardware Requirements

A Sun Microsystems Series 4 SPARC processor with a minimum of 8 megabytes of RAM memory is required to use this product. Approximately 70 kilobytes of hard disk space is required to load the ANSI Library software. At run time, the ANSI Library must have additional memory passed to it in the form of the **PAGETYP** data structure, the update list, and the ANSI string. That memory must be allocated by the user's application.

B.2 Software Requirements

The ANSI Library running on the SPARC platform requires that the Sun Operating System must be SunOS Version 4.0.3 or higher.

B.3 Installing the Software

The ANSI Library load consists of all the files needed to incorporate the ANSI Library as a set of library functions into client application programs. The Sun SPARCstation load is distributed on a Sun cartridge tape in "tar" format. To load the software, follow the instructions below.

After any step that requires you to type, press ENTER (or RETURN).

To install the ANSI Library:

- 1. Place the ANSI Library load tape on a SPARCstation streaming tape drive.
- 2. At the UNIX prompt (\$ in this example), change directories to the target directory in which you wish the ANSI Library to reside.
- 3. Type: \$ cd /target.dir
- **4.** Copy the source files from the tape into your directory.
- 5. Type: \$ tar -xvf device_name, where device_name is the device name of the streaming tape drive, usually /dev/rst0.

The files listed and described below are supplied on the tape and should now be in your directory.

- libansi.a: This is the library file of ANSI Library functions that must be linked with any application using the ANSI Library.
- q_ansip.h: You must insert this include file at the beginning of any source code using the ANSI Library functions.
- **README**: This file describes the contents of the tape.
- CHECKSUM: This file can be used to check for file transfer errors in the files that are downloaded from tape. The following command runs the standard checksum utility sum on the file named on the command line (shown in the example as filename). You can use the checksum utility to check the header files listed in this section and the libansi.a file.
- 6. Load CHECKSUM from tape
- 7. At the UNIX prompt (\$ in this example), type: \$ sum filename

B.4 Compiling

For application programs using the ANSI Library, you must add a path element to the developer's **.profile** that points to the directory in which you want the ANSI Library installed (**targetdirectory** in the following example). To the developer's **.profile**, add:

```
PATH=$PATH:/targetdirectory; export PATH
```

For any program that uses the ANSI Library (ansitest.c in this example), create an executable file (ansitest in this example) using the compiling command. At the UNIX prompt (\$ in the example) enter:

```
$ cc ansitest.c libansi.a -o ansitest
```

Alternatively, if **ansitest.o** is placed in **\$OBJS** of a **makefile**, the following **makefile** entries can be used to create an executable called **ansitest**:

```
ansitest:$(OBJS) libansi.a
cc $(OBJS) libansi.a $ (CFLAGS) -o ansitest
```

B.5 Troubleshooting: Copying the Library

If libansi.a is copied using the cp command before its use, then ranlib must be executed. At the UNIX prompt (\$ in this example) enter:

```
$ ranlib -t libansi.a
```

If you do not execute ranlib, you will see the following error message:

```
"ld: libppp.a: warning: table of contents for archive is out of date; rerun ranlib (1)."
```

There is no limit to the number of times ranlib can be applied to the library.

Appendix C ANSI Page Data Formats

C.1 Overview

Each position on a page, in addition to the character displayed, may have the following values associated with it:

- Character-set indicators
- Attributes (dim, bold, blink, underscore, reverse-video)
- Foreground and background color attributes

A complete page image consists of a full page of data and control codes. Updates can be broadcast as cursor controls followed by data or attributes. Pages must support cursor-positioning controls to make efficient use of screen-display capabilities, such as when updates to specific parts of a page are being transmitted.

RMTES describes the encoding of graphical character sets and control functions. It gives standards for selecting character sets and switching between character sets in use. The LSEG-supported character sets and control functions are defined in the text encoding standard as well. For example, the Basic Character Set is essentially ASCII. ASCII is a national variant of the ISO 646 standard for character sets. LSEG Real-Time Distribution System also supports the UK national variant of ISO 646 (the main difference being the national version of the 'pound' sign).

LSEG Real-Time Distribution System supports a subset of the LSEG standard as defined in this appendix. While an attempt is being made to conform to the international Unicode Standard, there are cases in LSEG Real-Time Distribution System where inheritance of private character sets clashes with the international standard for control sequences.

The private escape sequence SFR is used to control fading. Fading is a feature of LSEG Real-Time Distribution System display systems which allows the presentation software to enhance the display of recently modified data for a specified period of time. This is most typically used for real-time updates.

A full list of control functions and escape sequences supported by LSEG Real-Time Distribution System is given in this appendix. Supported commands consist of ANSI sequences for information exchange, DEC private sequences, and Rich private sequences. The definitions that follow are used in the transmission of information in the **Data** portion of the **SSL_ET_ITEM_IMAGE** and **SSL_ET_ITEM_UPDATE** events. All references to these command sequences refer explicitly to the use of 7-bit character encoding.

C.2 Introducer Sequence

The following control sequence introducer is supported.

| MNEMONIC | ANSI SEQUENCE | OPTIONAL CODE(S) | DESCRIPTION |
|----------|---------------|---------------------|---|
| CSI | ESC[| 1B 5B | Control sequence introducer. The optional code sets the hex values for control sequence introducer. |

Table 3: Introducer Sequences

C.3 Cursor Control Sequences

The following cursor control sequences are supported.

| MNEMONIC | ANSI SEQUENCE | OPTIONAL CODE(S) | DESCRIPTION |
|----------|------------------|------------------|--|
| BS | ^h | 0/8 | The cursor is moved one space to the left, but not past the beginning of the line. |
| HT | ^i | 0/9 | The cursor is moved to the next tab stop (default is set to 8-column tabs) or to the right margin if no more tabs exist on the line. |
| LF | ^j | 0/10 | The cursor is moved down one position, scrolling if necessary. |
| CR | ^m | 0/13 | The cursor is moved to the left margin of current line. |
| DECSC | ESC 7 | | This command is a DEC private request used to store the current cursor position and attribute for later use. |
| DECRC | ESC 8 | | This command is a DEC private request used to restore cursor position and attribute from the values saved by DECSC request. |
| IND | ESC D | | The cursor is moved to the next lower line (without changing column position), scrolling if necessary. |
| NEL | ESC E | | The cursor is moved to the first position of the next lower line, scrolling if necessary. |
| RI | ESC M | | The cursor is moved to the preceding line (without changing column position), scrolling down if necessary. |
| HVP | CSI PI; Pc f | | The cursor is moved to the screen position on line PI and column Pc. Lines and columns are numbered starting at 1. A parameter value of zero or null is interpreted as a value of one. An HVP command with no parameters has the same effect as a home command. Parameter values are tested to restrict the cursor location to the current screen. |
| CUU | CSI Pn A | | The cursor is moved upwards Pn positions, stopping at the top line. The default is set to one position and moves one position if Pn = 0. |
| CUD | CSI Pn B | | The cursor is moved down Pn positions, stopping at the last line. The default is set to one position and also moves one position if Pn = 0. |
| CUF | CSI Pn C | | The cursor is moved forward Pn positions, stopping at right margin. The default is set to one position and also moves one position if Pn = 0. |
| CUB | CSI Pn D | | The cursor is moved backward Pn positions, stopping at left margin. The default is set to one position and also moves one position if Pn = 0. |
| CUP | CSI PI ; Pc H | | The cursor is moved to position PI,Pc. This is the same as HVP control sequence. |

Table 4: Cursor Control Sequences

C.4 Scrolling Sequences

The following scrolling sequences are supported.

C.4.1 Margins

| MNEMONIC | ANSI SEQUENCE | OPTIONAL CODE(S) | DESCRIPTION |
|----------|---------------|---------------------|---|
| DECSTBM | CSI Pt; Pb r | | This command selects the top and bottom margins defining the scrolling region. Pt is the top line and Pb is the bottom line. Lines are numbered starting at 1. The default state is (1;24). |

Table 5: Scrolling Sequences: Margins

C.4.2 Movement

| MNEMONIC | ANSI SEQUENCE | OPTIONAL CODE(S) | DESCRIPTION |
|----------|---------------|---------------------|-----------------------|
| SU | CSI Pn S | | Scroll up Pn lines. |
| SD | CSI Pn T | | Scroll down Pn lines. |

Table 6: Scrolling Sequences: Movement

C.5 Mode Control Sequences

The following control sequences control the type or mode of the ANSI Page Data Format.

| MNEMONIC | ANSI SEQUENCE | OPTIONAL CODE(S) | DESCRIPTION |
|----------|------------------|--|--|
| SM | | Commands of this type set (enable) modes as requested by the | |
| | CSI ? Ps h | | parameter Ps. The ? character after the CSI defines the sequence to be a DEC private sequence |
| RM | CSI Ps I | | Commands of this type reset (disable) modes as requested by the |
| | CSI ? Ps I | | parameter Ps. The ? character after the CSI defines the sequence to be a DEC private sequence. |
| | | | NOTE: The last character in this sequence is a lower case L. |

Table 7: Mode Control Sequence Types

The following are supported mode control sequences.

| MNEMONIC | ANSI SEQUENCE | OPTIONAL CODE(S) | DESCRIPTION |
|------------------|--|--|--|
| DECCOLM | CSI ? 3 h | | These DEC private sequences control the number of columns |
| | CSI ? 3 I | | displayed on the terminal. When this mode is set, the terminal displays 132 columns. When reset, only 80 columns are displayed. |
| DECSCLM | CSI ? 4 h | | These DEC private sequences control the scrolling mechanism used |
| | by the terminal. When this mode is set, smooth scrolling is used. When eset, jump scrolling is used. | | |
| DECAWM CSI ? 7 h | CSI ? 7 h | | These DEC private sequences control the auto wrap feature. When |
| | CSI ? 7 I | ? 7 I the right margin of the display area. When | invoked, auto wrap performs a new line upon an attempt to write past the right margin of the display area. When disabled, an attempt to write past the right margin causes the right most character of the display to be replaced with the current character. |
| DECTCEM | CSI ? 25 h | | These DEC private sequences control the display status of the |
| | CSI ? 25 I | | terminal's cursor. When this mode is set, the cursor is displayed. When reset, the cursor becomes invisible. |

Table 8: Mode Control Sequences

C.6 Display Editing Control Sequences

The following sequences are used to alter or edit the visual display.

| MNEMONIC | ANSI SEQUENCE | OPTIONAL CODE(S) | DESCRIPTION |
|----------|------------------|------------------|--|
| ED | CSI Ps J | | This command erases some or all of the image according to value of Ps. |
| | | | • Ps = 0, from cursor to end inclusive |
| | | | Ps = 1, from start to cursor inclusive |
| | | | • Ps = 2, all of display |
| | | | The value of Ps Defaults to 0. |
| EL | CSI Ps K | | This command erases some or all of the current line according to value of Ps. |
| | | | • Ps = 0, from cursor to end inclusive |
| | | | • Ps = 1, from start to cursor inclusive |
| | | | • Ps = 2, all of line |
| | | | The value of Ps Defaults to 0. |
| IL | CSI Pn L | | This command inserts Pn erased lines starting at the active line and working downward. The remainder of the page is moved downward Pn lines, and the last Pn lines are discarded. The default is set to one line. One line is also inserted if Pn = 0. |
| DL | CSI Pn M | | This command deletes Pn lines starting at the active line and working downward. The remainder of the page is shifted to begin at the active line. The default is set to one line. One line is also deleted if Pn = 0. |
| DCH | CSI Pn P | | This command deletes Pn characters starting at the active position and working to the right. The remainder of the line is moved to the left of the active position. The default is set to one character. One character is also deleted if Pn = 0. The deletion of characters is restricted to the active line exclusively. |
| ICH | CSI Pn @ | | This command inserts Pn erased positions starting at the cursor and working to the right. The remainder of the line is moved Pn positions to the right and the last Pn positions are discarded. The default is set to one erased position. One erased position is also inserted if Pn = 0. The insertion of the erased characters is limited to the active line. |

Table 9: Display Editing Control Sequences

C.7 Graphic Selection Sequences

The following graphic control sequences are supported on LSEG Real-Time Distribution System. Refer to the RMTES for the Basic Character Sets 1 and 2.

A character set is mapped to a "working character set" in the range G0, G1, G2, or G3.

| MNEMONIC | ANSI SEQUENCE | OPTIONAL CODE(S) | DESCRIPTION | | |
|----------|------------------|------------------|---|---|--|
| SO | ^n | 0/14 | This command shifts out the current working graphics set and 0/14 invokes the G1 graphics set. | | |
| SI | ^0 | 0/15 | This command shifts in the current G0 graphics set as the working graphics set. | | |
| | ESC (Pf | | This command designates the G0 graphics set as the primary graphics set. The physical character set associated with the selection character Pf is invoked whenever G0 is invoked. The supported parameter values of Pf corresponding to the character set indicators are as follows: | | |
| | | | Pf Value | Description of Parameter Value | |
| | | | В | ASCII (U.S. national variant of ISO 646) | |
| | | | А | U.K. national variant of ISO 646 | |
| | | | 0 | VT100 special graphics (e.g., diamond) | |
| | | | : | Chapdelaine special set (e.g., fractions, superscripts, arrows) | |
| | | | , | RMJ special set (e.g., checkmark) | |
| | | | < | Garban character set | |
| | | | m | Mabon special character set | |
| | | | > | Mosaic graphics set (e.g., solid block) | |
| | | | ? | FBI special character set (e.g., down arrow, subscript 6) | |
| | | | f | FBI special graphics set (e.g., yen, subscript 2, 4 and 8) | |
| | | | g | General graphics set | |
| | | | S | SOP Telerate ASCII set | |
| | | | V | Viewdata mosaic set | |
| | ESC) Pf | | This command designates the G1 graphics set as the primary graphics set. The parameter values of Pf are identical to the G0 case. | | |

Table 10: Graphic Selection Sequences

C.8 Character Attribute Sequences

The following character attribute sequences are supported.

| MNEMONIC | ANSI SEQUENCE | OPTIONAL CODE(S) | DESCRIPTION | N |
|----------|---------------|------------------|------------------------------|--|
| SGR | CSI Ps m | | More than one page sequence. | ndition (SGR) sets display attributes. Defaults to Ps = 0 . parameter, separated by semicolons, can appear in this meter values of Ps include: |
| | | | Ps Value | Description of Parameter Value |
| | | | 0 | All attributes off |
| | | | 1 | High-intensity (bold) |
| | | | 2 | Half-intensity (dim) |
| | | | 4 | Underscore on |
| | | | 5 | Bblink on |
| | | | 7 | Reverse video on |
| | | | 8 | Concealed on |
| | | | 22 | Bold off |
| | | | 24 | Underscore off |
| | | | 25 | Blinking off |
| | | | 27 | Reverse video off |
| | | | 30 | Black foreground |
| | | | 31 | Red foreground |
| | | | 32 | Green foreground |
| | | | 33 | Yellow foreground |
| | | | 34 | Blue foreground |
| | | | 35 | Magenta foreground |
| | | | 36 | Cyan foreground |
| | | | 37 | White foreground |
| | | | 40 | Black background |
| | | | 41 | Red background |
| | | | 42 | Green background |
| | | | 43 | Yellow background |
| | | | 44 | Blue background |
| | | | 45 | Magenta background |
| | | | 46 | Cyan background |
| | | | 47 | White background |

Table 11: Character Attribute Sequences

| MNEMONIC | ANSI SEQUENCE | OPTIONAL CODE(S) | DESCRIPTION |
|----------|---------------|------------------|--|
| SFR | CSI > Ps m | | The private sequence Set Fading Rendition (SFR) specifies that a single attribute or several attributes are invoked in addition to the base attributes defined by the standard ANSI video attribute sequence Set Graphic Rendition (SGR). The display of recently updated fields may thus be enhanced in order to bring the user's attention to the modified area of the display. |
| | | | The added attributes are cleared after a short period of time (usually 5 seconds). The length of application of these additional attributes is controlled by the display device. Specifically, fading allows the addition of any combination of the monochrome attributes normally supported by the display system. For color displays, fading also allows the modification of both the foreground and the background color. |
| | | | Attributes are only added during the fade enhanced period. For example, a base attribute of UNDERSCORE may be enhanced by a fading BLINK. The result would be to display a blinking underscored character for the enhanced period and replace it with a steady underscored character when the enhanced period ends. |
| | | | The foreground and the background colors may be individually replaced for the fade period. If a color is not modified by SFR, then the base color or colors is in effect. If either is replaced, even in the absence of a fading monochrome attribute, fading is invoked. |
| | | | Thus, if base colors are set to blue foreground on a red background and a sequence is received to fade a white foreground, the display is white on red during the enhanced period. At the end of the enhanced period, the display returns to blue on red. |
| | | | The supported parameter values of Ps are the same those listed in the preceding table for SGR. The default is $Ps = 0$. |
| | | | NOTE: More than one parameter may appear in this sequence, in which case they are separated by semicolons. |

Table 11: Character Attribute Sequences(Continued)

C.9 Character and Line Sizing

The following escape sequences to alter character cell dimensions are supported.

C.9.1 DEC Private Sequences

| MNEMONIC | ANSI SEQUENCE | OPTIONAL CODE(S) | DESCRIPTION |
|----------|---------------|---------------------|---|
| DECDHL | ESC # 3 | | This command changes the current line to double-height/ double-width top half. |
| DECDHL | ESC # 4 | | This command changes the current line to double-height/ double-width bottom half. |
| DECSWL | ESC # 5 | | This command changes the current line to single-height/singlewidth. |
| DECDWL | ESC # 6 | | This command changes the current line to single-height/doublewidth. |

Table 12: DEC Private Sequences

C.9.2 Rich Private Sequences

The following sequences are NOT supported by DEC compatible terminals. These sequences have historically been called Rich Private Sequences. While they may still be in use, they are not consistent with the newer LSEG text encoding standards.

| SEQUENCE | DESCRIPTION |
|-----------|--|
| CSI > 1 Z | This Rich private sequence invokes double-height/single-width top half mode for all succeeding characters until modified by another character size command. |
| CSI > 2 Z | This Rich private sequence invokes double-height/single-width bottom half mode for all succeeding characters until modified by another character size command. |
| CSI > 3 Z | This Rich private sequence invokes double-height/double-width top half mode for all succeeding characters until modified by another character size command. |
| CSI > 4 Z | This Rich private sequence invokes double-height/double-width bottom half mode for all succeeding characters until modified by another character size command. |
| CSI > 5 Z | This Rich private sequence invokes single-height/single-width mode for all succeeding characters. |
| CSI > 6 Z | This Rich private sequence invokes single-height/double-width mode for all succeeding characters. |

Table 13: Rich Private Sequences

C.10 Miscellaneous Sequences

The following subsections define all other LSEG Real-Time Distribution System supported sequences not grouped in the previous sections.

C.10.1 Control Characters

| MNEMONIC | ANSI SEQUENCE | OPTIONAL CODE(S) | DESCRIPTION |
|----------|---------------|------------------|--|
| BELL | ^g | 0/7 | Generates the bell tone on the terminal keyboard if the bell is enabled. |
| DEL | | 7/15 | Delete characters are ignored when received. |

Table 14: Control Characters

C.10.2 Controls

| MNEMONIC | ANSI SEQUENCE | OPTIONAL CODE(S) | DESCRIPTION |
|----------|---------------|---------------------|---|
| RIS | ESC c | | This command resets a device to its initial state, i.e., the state it has after it has been switched on. The screen (25 lines) and fading status is cleared, and the control structure is reset to its initial state (e.g., resets attributes, modes, etc). The scrolling region is reset to the default rows (1;24). |

Table 15: Controls

LSEG 1991, 1993, 1995, 2010, 2015, 2017-2024. All rights reserved.

Republication or redistribution of LSEG Data & Analytics content, including by framing or similar means, is prohibited without the prior written consent of LSEG Data & Analytics. 'LSEG Data & Analytics' and the LSEG Data & Analytics logo are registered trademarks and trademarks of LSEG Data & Analytics.

Any third party names or marks are the trademarks or registered trademarks of the relevant third party.

Document ID: ETAC382REANS.240 Date of issue: September 2024

