

Startup Parameters – Arma Reforger

Category: [Arma Reforger/Support](#)

Startup parameters are command line interface(CLI) arguments that go after the executable's name in order to set options; e.g `ArmaReforgerSteam.exe -window` to start the game in windowed # mode.



- Startup parameters' *names* are case-insensitive - e.g `-logstats` and `-LogSTATS` are identical.
- Spaces in parameter values must be wrapped in quotations - e.g. `-addonDownloadDir "E:\Arma Addons"`

Contents

- | | |
|--|---|
| 1. General | 7. Workbench - ResourceManager Module |
| 2. Window | 8. Workbench - ScriptEditor Module |
| 3. Workbench | 9. Workbench - WorldEditor Module |
| 4. Workbench - AnimationEditor Module | 10. Hosting |
| 5. Workbench - LocalizationEditor Module | 11. Network Tuning |
| 6. Workbench - NavmeshGeneratorMain Module | 12. Debug |
| | 13. Profiling |

General

addons

`-addons` takes a list of mod IDs (specified in their `gproj` files, without brackets) to be loaded on game start, separated by a comma `,`.

Mods are searched in `profile/addons`, in `<executableDir>/addons` and in directories specified by `-addonsDir` (see [below #](#)).

Mod IDs can be:



- GUIDs (**preferred** - found in `.gproj`)
- Project ID (found in `.gproj`)
- Sub-directory name (fallback solution)

Example

```
ArmaReforgerSteam.exe -addons 88037E46AD234C72,88037E46AD234C73
```

addonsDir

-addonsDir specifies additional directories in which the game must look for mods to load, separated by a comma , .

By default, the game looks into:

- Documents/My Games/ArmaReforger/profile/addons
- <executableDir>/addons



It is recommended to use *absolute* paths to Mod directories even though the provided path *can* be relative to the executable location.

Example

```
ArmaReforgerSteam.exe -addonsDir D:\DownloadedMods
```

addonDownloadDir

-addonDownloadDir specifies where the game and the Workshop should download addons. Downloaded addons will be stored in addons subfolder inside of target directory.



It is recommended to use *absolute* paths to Mod directories even though the provided path *can* be relative to the executable location.

- It is not necessary to combine this command with **addonsDir** parameter.

Example

```
ArmaReforgerSteam.exe -addonDownloadDir D:\DownloadedMods
```



1.1.0

addonTempDir

-addonTempDir specifies the directory for temporary content. The default temporary directory is:

- before  1.4.0: %localappdata%/Temp/<addon>/<temp data> on Windows or /tmp/<addon>/<temp data> on Linux
- since  1.4.0: <addonsDir>/<addon>/temp/<temp data>

Example

```
ArmaReforgerSteam.exe -addonTempDir "C:\Temp"
```

backendDisableStorage

-backendDisableStorage disables use of storage, no loads or saves can be performed both online and **local**.

Example

```
ArmaReforgerSteam.exe -backendDisableStorage
```

backendFreshSession

-backendFreshSession skips the initial load request from dedicated server's configuration file or from script - the DS Session basically starts as a brand new one, the rest of functionalities is not affected (saves, runtime loads, etc).

Example

```
ArmaReforgerSteam.exe -backendFreshSession
```

backendLocalStorage

-backendLocalStorage forces Save & Load of player and general data normally sent to/received from the backend to work with local JSON files in profile folder instead.

Example

```
ArmaReforgerSteam.exe -backendLocalStorage
```



freezeCheck

1.2.0

number value, range 0..600, default 300

-freezeCheck overrides time in seconds to forcefully crash on application freeze or completely disable detection.



Workbench has default time set to 1 minute and will only generate minidump without crashing.

Example

```
ArmaReforgerSteam.exe -freezeCheck 30
```



freezeCheckMode

1.2.0

string value, default minidump (workbench) or crash

-freezeCheckMode overrides behavior which should happen when freeze is detected.

- crash - force crashes the application

- `minidump` - silently generates minidump and keeps application running until it unfreezes or is terminated by user
-  `kill` - will force kill the application - is more reliable than `{hl|crash}` but does not provide any data about the freeze



Option `minidump` is supported only on Windows.

Example

```
ArmaReforgerSteam.exe -freezeCheckMode crash
ArmaReforgerSteam.exe -freezeCheckMode minidump
```

cfg

-`cfg` forces to load specific user engine settings config (things like graphics settings, window position and size etc).

GPUAdapter

-`GPUAdapter` forces to use the graphic card at the provided index. GPU index can be found using [DxDiag \(http://support.microsoft.com/en-us/windows/open-and-run-dxdiag-exe-dad7792c-2ad5-f6cd-5a37-bf92228dfd85\)](http://support.microsoft.com/en-us/windows/open-and-run-dxdiag-exe-dad7792c-2ad5-f6cd-5a37-bf92228dfd85).

Example

```
ArmaReforgerSteam.exe -GPUAdapter 0
```

language

-`language` sets the game language by language code - supported language codes depends on StringTable which is set in `gproj`. Arma Reforger supported languages are:

- | | | | |
|---|--|---|--|
| ▪  <code>en_us</code> - English | ▪  <code>es_es</code> - Spanish | ▪  <code>ja_jp</code> - Japanese | ▪  <code>zh_cn</code> - Mandarin |
| ▪  <code>fr_fr</code> - French | ▪  <code>cs_cz</code> - Czech | ▪  <code>ko_kr</code> - Korean | ▪   <code>uk_ua</code> - Ukrainian |
| ▪  <code>it_it</code> - Italian | ▪  <code>pl_pl</code> - Polish | ▪  <code>pt_br</code> - Portuguese | |
| ▪  <code>de_de</code> - German | ▪  <code>ru_ru</code> - Russian | | |

Example

```
ArmaReforgerSteam.exe -language cs_cz
```

noBackend

-`noBackend` disables backend-related http communication.

Example

```
ArmaReforgerSteam.exe -noBackend
```

noSound

-noSound disables the sound system processing.

Example

```
ArmaReforgerSteam.exe -noSound
```

noSplash

-noSplash skips splash screens on game load.

Example

```
ArmaReforgerSteam.exe -noSplash
```

noThrow

-noThrow disables all kinds of error message dialogs. (VMEs, asserts, crashes, ...).

Example

```
ArmaReforgerSteam.exe -noThrow
```

profile

-profile defines the path to the `profile` directory to be used, either by parent directory name or by path.

Example

```
ArmaReforgerSteam.exe -profile "David Armstrong" // ta
\My Documents\My Games\David Armstrong\profile
ArmaReforgerSteam.exe -profile "C:\Users\MyUserName\Documents\ArmaReforgerDir" // ta
\Users\MyUserName\Documents\ArmaReforgerDir\profile"
```

singleThreadedUpdate

-singleThreadedUpdate disables multithreaded update.

Example

```
ArmaReforgerSteam.exe -singleThreadedUpdate
```

world

`-world` defines the world file to be loaded on startup, both absolute and relative paths are supported although it is recommended to use path relative to created filesystems (eg. `worlds/myworld.ent`). Workbench ignores this parameter - for that, use `-load #` parameter instead.

Example

```
ArmaReforgerSteam.exe -world worlds/myworld.ent
```

Window

window ___

`-window` starts the game windowed (fullscreen by default).

Example

```
ArmaReforgerSteam.exe -window
```

posX ___

posY ___

`-posX` and `-posY` define the initial window position. They must be used with `-window`.
`posX 0` is left of the screen,
`posY 0` is top of the screen.

Example

```
ArmaReforgerSteam.exe -window -posX 0 -posY 64
```

screenWidth ___

screenHeight ___

`-screenWidth` and `-screenHeight` define the window's size (and not its render *resolution*). They must be used with `-window`.

Example

```
ArmaReforgerSteam.exe -window -screenWidth 1024 -screenHeight 578
```

forceUpdate ___

`-forceUpdate` forces the application to render and update even when the window is out of focus.



Previously known as `-noPause` in earlier titles.

Example

```
ArmaReforgerSteam.exe -forceUpdate
```

noFocus

-noFocus prevents window focus stealing on game initialization.

Example

```
ArmaReforgerSteam.exe -noFocus
```

Workbench



These parameters apply to the Workbench executable.

forceSettings

-forcesettings forces to use the specified Workbench settings from a file instead of the usual settings stored in Windows registry which will be entirely ignored. The settings in a file will be used for reading and also writing. This functionality is compatible with wbSettingsDump.ini files being attached to crash reports.



It is possible to export Workbench settings to an .ini file from [Workbench options](#).

gproj

-gproj defines the addon project to be loaded - it can be used to skip the Workbench's addon selection screen.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -gproj "C:\Program Files (x86)\Steam\steamapps\com
```



gprojConfig

-gprojConfig forces loading the provided configuration e.g PC , HEADLESS etc.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -gprojConfig PC
```

wbModule

-wbModule specifies which [Workbench](#) module must be launched (with [-run #](#)):

Editor	Entry (case-insensitive)	Additional Information
Resource Manager	resourceManager	
World Editor	worldEditor	See also Workbench - WorldEditor Module # below
Particle Editor	particleEditor	
Animation Editor	animEditor	
Script Editor	scriptEditor	
Audio Editor	audioEditor	See also Workbench - ScriptEditor Module # below
Behavior Editor	behaviorEditor	
Procedural Animation Editor	procAnimEditor	
String Editor	localizationEditor	See also Workbench - LocalizationEditor Module # below
Navmesh Generator	navmeshGeneratorMain	See also Workbench - NavmeshGeneratorMain Module # below

- 
 - wbmodule requires an equal sign = to work.
 - Parameters specified after the module name are considered to be parameters to the module specifically.
 - The [-run #](#) parameter must be added after each instance of -wbModule for them to launch.

Example

ArmaReforgerWorkbenchSteamDiag.exe -wbModule=WorldEditor -run

plugin

-plugin specifies which [Workbench](#) plugin must be launched (WorldTestPlugin, TextureImportTool, MaterialImportTool, WorldDataExport etc).

- 
 - Parameters specified after the plugin are considered to be parameters to the plugin specifically.
 - Plugins are loaded for specific modules. Before loading a plugin specify the appropriate [wbModule #](#).

Example

ArmaReforgerWorkbenchSteamDiag.exe -wbModule=ResourceManager -plugin=ResavePlugin pl

run

-run tells the executable to open the designated Workbench module (specified by [-wbModule #](#) usage).

Example


```
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=WorldEditor -run
```

load ____

-load tells the executable to open selected file in the designated Workbench module (specified by -wbModule # usage). The file path can be specified either by absolute path, relative path, exact path or by resource name.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=WorldEditor -run -load "world/myworld.ent"
```

This will open up the World Editor and load the `myworld.ent` file.

packAddon ____

-packAddon is the main parameter used for addon packing.

When no directory is specified (by using packAddonDir #), the directory from the last session is used.

When packing an addon for the first time, a new directory is automatically created in the same dir as `profile`.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=ResourceManager -packAddon
```

packAddonDir ____

-packAddonDir specifies the output directory where resulting PAKs will be saved.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=ResourceManager -packAddon -packAddonDir
```

publishAddon ____

-publishAddon is main parameter used for addon publishing.

It should be used only for publishing addon updates, and not for the initial publish because data from last session are used to fill in the blanks.

It can be used on its own, in combination with **packAddon** or in combination with parameters starting with "publishAddon".

When no directory is specified (by using **publishAddonDir**) a directory from last session is used.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=ResourceManager -publishAddon
```

publishAddonDir

`-publishAddonDir` specifies the pre-packed data directory (obtained by the `-packAddon` parameter above). When not specified, directory from the last session is used.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=ResourceManager -publishAddon -publishAc
```

publishAddonVersion

`-publishAddonVersion` specifies the mod's version number. When not specified, newest version found on back-end is used and it's last digit is automatically incremented.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=ResourceManager -publishAddon -publishAc
```

publishAddonChangeNote

`-publishAddonChangeNote` is an optional parameter that specifies a note to the provided update.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -publishAddonChangeNote "Fix shading"
```

publishAddonChangeNoteFile

`-publishAddonChangeNoteFile` is an optional parameter which is used to specify this update's change note.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -publishAddonChangeNoteFile "C:\Addon\changelog.txt"
```

publishAddonPreviewImage

`-publishAddonPreviewImage` is an optional parameter which you can use to specify the preview image file's path.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -publishAddonPreviewImage "z:/mymod/my_preview_image.png"
```

publishAddonScreenshots

-publishAddonScreenshots is an optional parameter that specifies the directory from where the screenshots should be taken. It is then automatically scanned for all valid image file types (jpg, png, bmp).

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -publishAddonScreenshots "Z:/mymod/screenshots"
```

rebuild-database-only

-rebuild-database-only makes Workbench automatically exit when the database file is refreshed. This is useful for creating game packages which should be distributed with the latest database file.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -rebuild-database-only
```

scrDefine

-scrDefine allows to determine a script preprocessor definition. Multiple ones can be chained using multiple -scrDefine.

 This parameter also works for Client and Server executables.

```
#ifdef TAG_DEBUG
    Print("The TAG_DEBUG flag is defined.");
#else
    Print("The TAG_DEBUG flag is not defined.");
#endif
```

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -scrDefine TAG_DEBUG -scrDefine OTHER_FLAG
ArmaReforgerSteam.exe -scrDefine TAG_DEBUG -scrDefine OTHER_FLAG
ArmaReforgerServer.exe -scrDefine TAG_DEBUG -scrDefine OTHER_FLAG
```



scrNoInline

1.1.0



This parameter only works on **diag exe**!

-scrNoInline disables inline optimisation for debug purposes.

Example

```
ArmaReforgerSteamDiag.exe -scrNoInline
```

wbBackendLogin

-wbBackendLogin enforces a specific account to log in. Password is hidden console log.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -wbBackendLogin myEmail@bistudio.com myPassword
```

noGameScriptsOnInit

-noGameScriptsOnInit skips game scripts compilation on Workbench initialisation. This results in a faster startup but with the need to recompile scripts before using any script-dependent elements (prefabs, configs, etc).



Game scripts can be compiled in Script Editor using **F7**.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -noGameScriptsOnInit
```

enableWARP

-enableWARP allows [DirectX WARP](https://docs.microsoft.com/en-us/windows/win32/direct3darticles/directx-warp) (<https://docs.microsoft.com/en-us/windows/win32/direct3darticles/directx-warp>) (Windows Advanced Rasterization Platform) to create a virtual device for computers without a DirectX 12 device.



This parameter does not force WARP, only allows it.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -enableWARP
```



clearSettings

0.9.7

-clearSettings, as its name suggests, clears all Workbench user preference - window positions, preview settings, last opened files etc.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -clearSettings
```



exitAfterInit

1.1.0

-exitAfterInit makes Workbench automatically exit once it is completely initialised and all startup parameters are executed.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -exitAfterInit
```



diagMenu

1.1.0

-diagMenu overrides where diagnostic menu saved settings are stored (see hints section of [Arma Reforger:Diag Menu](#)).

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -diagMenu "file.txt"
```

Workbench - AnimationEditor Module

animDebugger



This parameter only works on **diag exe**!

-animDebugger enables animation debugging.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -animDebugger
```

Workbench - LocalizationEditor Module

build

-build creates runtime string tables from the opened string table.

Example

```
-wbModule=LocalizationEditor -run -load {C014582791ECBF24}Language/localization.st -build -  
saveDir C:\tmp\
```

For building also hidden items from the localisation database, use -scrDefine LOCALIZATION_BUILD_HIDDEN :

```
ArmaReforgerWorkbenchSteamDiag.exe -scrDefine LOCALIZATION_BUILD_HIDDEN -wbModule=Loc
```



saveDir

-saveDir specifies the (absolute) save directory for the module's build command.

Example

```
see above
```

Workbench - NavmeshGeneratorMain Module

autogenerate

-autogenerate generates the provided world's navmesh.

Example

```
// This opens up the World Editor with myworld.ent loaded, connects Navmesh Editor to  
// Navmesh Editor generates the navmesh and saves it to the path originally held by f  
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=NavmeshGeneratorMain -run -autogenerate
```



navmesh projects are optional and can be ALL to generate all projects.

saveDir

-saveDir is an optional parameter that defines in which directory the data will be exported.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=NavmeshGeneratorMain -run -autogenerate
```



logNavmeshGen

-logNavmeshGen logs output from changing states of the navmesh generator state machine.



This parameter does nothing at the moment as it is always enabled.

Workbench - ResourceManager Module

buildData

-buildData builds all data of one addon in a specified directory. Without addon specification, it builds data of the current addon (usually a game). There are two mandatory parameters: PlatformName and TargetFolder. The third parameter, AddonName, is not mandatory.

Example 1

This builds data of a current addon

```
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=ResourceManager -bulddata PC "C:\Data\I
```

Example 2

This builds data of a specific addon called "ArmaReforger"

```
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=ResourceManager -bulddata PC "C:\Data\I
```

This will build PC data to the provided directory. Possible options for the platform name are PC, PC_WB, XBOX_ONE, XBOX_SERIES, PS4, HEADLESS.

Resource database cache file resourceDatabase.rdb is being saved after build too. It contains only the files which are part of the build.

State of the incremental build progress is being continuously saved every 60 seconds into LastBuildInfo.binfo file. After an unexpected crash, the next build will continue from this last saved state.

Note that entire workbench application will be exited when build is completed.

metaFiles

-metaFiles is an optional parameter which may be used together with -buildData # - it copies .meta files to the built data.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=ResourceManager -buildData PC "C:\Data\I
```

loadBuiltData

-loadBuiltData is an optional parameter which may be used together with -buildData # - built resource is loaded into memory and possible errors are printed into the log. Useful for identifying broken resources.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -wbmodule=ResourceManager -buildData PC "C:\Data\l
```

includeTypes

-includeTypes is an optional parameter which may be used together with -buildData # - it specifies a list of file types (separated by a comma) that will be included in data build. Can be combined together with -excludeTypes #

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -wbmodule=ResourceManager -bulddata PC "c:\Data\l
```

excludeTypes

-excludeTypes is an optional parameter which may be used together with -buildData # - it specifies a list of file types (separated by a comma) that will not be included in data build. Can be combined together with -includeTypes #

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -wbmodule=ResourceManager -bulddata PC "C:\Data\l
```

filterPath

-filterPath is an optional parameter which may be used together with -buildData # - it allows to limit data build to only a single folder or file.

Example 1

```
ArmaReforgerWorkbenchSteamDiag.exe -wbmodule=ResourceManager -buildData -filterPath {
```

This limits that only data from this specific folder will go to data build

Example 2

```
ArmaReforgerWorkbenchSteamDiag.exe -wbmodule=ResourceManager -buildData -filterPath {
```

This limits that only data that belong to `Arland.ent` will go to data build (ent, smap, smd, ...)

filterTags

-filterTags is an optional parameter which may be used together with -buildData # - it can be used to exclude/include particular files and folders from/to data build. It is based on tagging files and folders through the "Build Tags" property which is part of file/folder import settings. This parameter has a form of a C++ expression where can be used only string tags and these three operators:

- `&` - logical AND

- | - logical OR
- ! - logical NOT

Examples

```
ArmaReforgerWorkbenchSteamDiag.exe -filterTags "!wbOnly & !testOnly & !consolesOnly"
```

This includes to build everything except files and folders tagged as wbOnly or testOnly or consolesOnly

```
ArmaReforgerWorkbenchSteamDiag.exe -filterTags "wbOnly"
```

This includes to build only files and folders tagged as wbOnly

```
ArmaReforgerWorkbenchSteamDiag.exe -filterTags "wbOnly & !testOnly"
```

This includes to build only files and folders tagged as wbOnly but without those of them that are tagged as testOnly

```
ArmaReforgerWorkbenchSteamDiag.exe -filterTags "wbOnly | testOnly"
```

This includes to build only files and folders tagged as wbOnly or testOnly

```
ArmaReforgerWorkbenchSteamDiag.exe -filterTags "(!wbOnly & !testOnly) | alwaysInclude"
```

This includes to build everything except files and folders tagged as wbOnly or testOnly. If some file or folder is tagged with alwaysIncluded it will be included even though it's located inside a wbOnly folder for example

wbSilent

-wbsilent initialises the engine, workbench modules and exit without opening any windows; it can be used to validate engine/game initialisation and script compilation.

Workbench - ScriptEditor Module

validate

string value, default ALL

-validate checks if the game scripts are compilable and returns Workbench application return code of "-1" when compilation failed and "0" when compilation was successful. Value is optional and script configuration name is expected (Configurations can be found in project settings, it is usually PC, XBOX_SERIES, etc).

Workbench - WorldEditor Module



forceSaveAll

1.1.0

-forceSaveAll

- **Normal edit mode:** re-saves all entity layers of opened map (.ent file + its .layer files) and also all prefabs and configs that are used in the opened map.
- **Prefab edit mode:** re-saves only opened prefab and also all other prefabs and configs that are used in the opened prefab.

Example 1 (normal edit mode)

```
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=WorldEditor -run -load "world/myworld.ent"
```

Example 2 (prefab edit mode)

```
ArmaReforgerWorkbenchSteamDiag.exe -wbModule=WorldEditor -run -load "Prefabs/Structure.ent"
```

Hosting



These parameters apply to the Server executable.

a2sIpAddress

-a2sIpAddress sets Steam Query Protocol's Bind IP address.

Example

```
ArmaReforgerServer.exe -a2sIpAddress 192.168.1.10
```

a2sPort

-a2sPort sets Steam Query Protocol's Bind port.

Example

```
ArmaReforgersServer.exe -a2sPort 7777
```

autoreload

-autoreload reloads the scenario when the session ends after the provided delay, without shutting down the server. Value is in seconds.

 the disabled value makes the server restart and relaunch as the same instance.

Example

```
ArmaReforgersServer.exe -autoreload 10
```

autosutdown

-autosutdown ensures the correct server shutdown process.

To give 30 seconds post game and then shutdown:

Example

```
ArmaReforgersServer.exe -autoreload 30 -autosutdown
```

 To circumvent 1.3.0's server restart issue, make sure to use this command and configure the server to automatically restart on failure or shutdown.

bindIP

-bindIP can be used to override both gameHostBindAddress and gameHostRegisterBindAddress values present in server config.

Example

```
ArmaReforgersServer.exe -bindIP 192.168.1.42
```

bindPort

-bindPort can be used to override both gameHostBindPort and gameHostRegisterBindPort values present in server config.

Example

```
ArmaReforgersServer.exe -bindPort 2302
```

config

-config is used by servers to point to a JSON server configuration.



See [Server Hosting](#) for more information.

Example

```
ArmaReforgerServer.exe -config myConfigFile.json
```



enableNightGrain

1.6.0

was forceDisableNightGrain in 1.6.0.54, changed in 1.6.0.76

-enableNightGrain enables night grain in multiplayer (dedicated or hosted).



Single player always has night grain disabled.

Example

```
ArmaReforgerServer.exe -enableNightGrain
```

listScenarios

-listScenarios prints to game logs the scenario .conf file paths.



- Workshop scenarios will only be listed if no scenario is being loaded (through e.g a [config #](#)).
- A list of official scenarios can be found on [Server Config - scenariold](#).

Example

```
ArmaReforgerServer.exe -listScenarios
```



loadSessionSave

1.0.0 1.6.0

-loadSessionSave allows the game to load a previous game session.

It can be used alone to load the latest save, or with a specific save file name. When left empty, it will attempt to locate the latest save game data for the current scenario on launch. Optionally, as a parameter, the UUID of a specific save can be passed, which is found inside each save point's `meta-info.json` file.

Examples

```
ArmaReforgerSteam.exe -loadSessionSave
ArmaReforgerSteam.exe -loadSessionSave 07e8fa26-d5b6-47f6-a19b-641c72ab05bc
ArmaReforgerServer.exe -loadSessionSave
ArmaReforgerServer.exe -loadSessionSave 0d51b792-2a66-47d2-b71a-09086cffba3a
```



keepSessionSave

1.6.0

-keepSessionSave keeps any save data for completed playthroughs on the game's end screen.

Example

```
ArmaReforgerSteam.exe -keepSessionSave
```

logStats

-logStats allows to log performance statistics every (optionally) defined interval (in milliseconds).

Example

```
ArmaReforgerServer.exe -logStats - logs every seconds
```

```
ArmaReforgerServer.exe -logStats 10000 - only logs every 10s
```

Result

```
FPS: 60.0, frame time (avg: 16.7 ms, min: 9.3 ms, max: 23.7 ms), Mem: 3291106 kB
```

- FPS: <float> = Current server FPS value
- frame time (avg: <float> ms, min: <float> ms, max: <float> ms) = The average, minimum, & maximum server frame times
- Mem: <int> = The current memory usage in kilobytes as reported internally by the server
- Player: <int> = Number of current players
- AI: <int> = Number of current AI spawned on the server
- Veh <int> (<int>) = The value inside the parentheses is the current number of vehicles spawned on the server
- Proj:
 - S: <int> = Number of active **s**hells
 - M: <int> = Number of active **m**issiles
 - G: <int> = Number of active **g**renades
 - | <int> = Total projectiles
- RplItemsS: <int> = The number of dynamic (spawned during game) streams on the server
- RplItemsC0: <int> = The number of streams open to the client



The memory usage reported by -logStats is a server approximation and is therefore not 100% accurate when compared with the operating system values.



logVoting

-logVoting adds logging info to the voting system with information about who created, voted, and against whom the vote was created.

Example

```
ArmaReforgerServer.exe -logVoting
```

maxFPS

-maxFPS sets max FPS limit - useful for a server, or to force a client's max FPS.



Also works on clients, even though the Video Settings FPS limitation option is preferred.

Example

```
ArmaReforgersServer.exe -maxFPS 30
```



playerLimits

1.7.0

-playerLimits sets the maximum players count per faction. The format is FactionKey:Number, multiple entries are separated by a comma.

Example

```
ArmaReforgersServer.exe -playerLimits "FIA:3"
ArmaReforgersServer.exe -playerLimits "US:1,USSR:1,FIA:62"
```

server

This parameter instructs the executable to launch **local** server and **load selected world**. When this parameter is used, config is ignored. Server parameter can be combined with addons# & addonsDir# parameters to start a server with local mods, which can be useful when testing addon before uploading it Workshop.

```
ArmaReforgersServer.exe -server "worlds/MP/MPTTest.ent" -addonsDir "C:\MyModsDir" -addo
```



These parameters apply to the Game executable.

client

-client starts up an RplSession in local client mode. The session tries to connect to the provided IP.

Example #1

```
ArmaReforgersSteam.exe -client 127.0.0.1
```

Example #2

This will connect the game to a locally hosted dedicated server and load the local MyCustomMod addon:

```
ArmaReforgersSteam.exe -client -addonsDir "C:\MyModsDir" -addons MyCustomMod
```



worldSystemsConfig

1.6.0



This parameter only works on **diag exe**!

-worldSystemsConfig allows setting a world systems config file (of type **SystemSettings**) when starting a mission directly (not via MissionHeader.conf).

Example

```
ArmaReforgerSteamDiag.exe -worldSystemsConfig "{C50579A2EC48E8EF}Configs/Systems/Mis
```



1.3.0

addonsVerify



This parameter only works on **dedicated server**!

Verifies the integrity of all installed addons. If any corrupted addons are found, the server will shut down and log the corrupted files. The verification may take some time depending on the size of the addons.



1.3.0

addonsRepair



This parameter only works on **dedicated server**!

Verifies the integrity of all installed addons. If any corrupted addons are found, they will be repaired automatically. If the repair fails, the server will shut down. The repair duration depends on the addons size and the amount of data which needs to be repaired.

Network Tuning



These parameters apply to the Server executable.

nds

number value, default 2

-nds Network Dynamic Simulation (nds) is a server feature that only streams in relevant replicated entities for each client. The provided value stands for diameter, or the number of cells which are being replicated. To turn the feature off use -nds 0. A higher diameter will result in a bigger networked view range, lower server performance.

Example

```
ArmaReforgerServer.exe -nds 1
```

nwkResolution

-nwkResolution defines what resolution Spatial Map cells should be set at in a 100..1000m range. Smaller resolution will result in less "pop-in" but lower networked view range. For high view range use high resolution, but small diameter.

Example

```
ArmaReforgerServer.exe -nwkResolution 500
```

rpl-timeout-ms

-rpl-timeout-ms sets the client/server timeout's value, in milliseconds.

Example

```
ArmaReforgerServer.exe -rpl-timeout-ms 10000
```

rpl-timeout-disable



This parameter only works on **diag exe**!

-rpl-timeout-disable disables the client/server timeout.



If a connection stops responding, the server's performance will deteriorate until it eventually runs out of memory and crash. This parameter is strictly for debugging purposes.

Example

```
ArmaReforgerSteamDiag.exe -rpl-timeout-disable
```

rpl-reconnect



This parameter only works on **diag exe**, on **client**!

The replication tries to reconnect instead of immediately raising connection.

Example

```
ArmaReforgerSteamDiag.exe -rpl-reconnect
```

rpl-vcons

number value, range 0..200, default 0



This parameter only works on **diag exe**!

-rpl-vcons sets the number of virtual connections.

Example


```
ArmaReforgerSteamDiag.exe -rpl-vcons 5
```

rpl-validation-rdb-disable



This parameter only works on **diag exe**!

`-rpl-validation-rdb-disable` disables the validation of clients resource database.



Make sure you know what you are doing first before disabling the validation as data mismatch may bring undefined behaviour!

Example

```
ArmaReforgerSteamDiag.exe -rpl-validation-rdb-disable
```

rpl-validation-scr-disable



This parameter only works on **diag exe**!

`-rpl-validation-scr-disable` disables the validation of clients scripts checksum.



Make sure you know what you are doing first before disabling the validation as script mismatch may bring undefined behaviour!

Example

```
ArmaReforgerSteamDiag.exe -rpl-validation-scr-disable
```

rpl-validation-version-disable



This parameter only works on **diag exe**!

`-rpl-validation-version-disable` disables the validation of clients executable version.



Make sure you know what you are doing first before disabling the validation as version mismatch may bring undefined behaviour!

Example

```
ArmaReforgerSteamDiag.exe -rpl-validation-version-disable
```

rpl-validation-devbin-disable



This parameter only works on **diag exe**!

-rpl-validation-devbin-disable disables the validation of developer binary flag, allowing mixing developer and non-developer binaries in the same multiplayer session.

staggeringBudget

-staggeringBudget defines how many stationary spatial map cells are allowed to be processed in one tick in 1..10201 range. If not set it uses "-nds #" diameter. A lower number will limit how many cells the server has to process per tick, but increase the time it takes for a client to have all relevant entities streamed in. If the server experiences significant performance drops on spawning/teleporting then the number is set too high, if the client experiences "pop-in" of replicated items then the number is set too low.

Example

```
ArmaReforgersServer.exe -staggeringBudget 5000
```

streamingBudget

-streamingBudget is the global streaming budget that is equally distributed between all connections. To decrement the budget, it uses the replicated hierarchy size of each entity that needs to be streamed in. It cannot go under 100 to prevent the system stalling. A lower number will limit how many entities the server has to process per tick, but increase the time it takes for a client to have that entity streamed in, if the server experiences significant performance drops on spawning/teleporting then the number is set too high, if the client experiences "pop-in" of replicated items then the number is set too low.

Example

```
ArmaReforgersServer.exe -streamingBudget 500
```

streamsDelta

number value, range 1..1000, default 100

-streamsDelta is a tool to limit the amount of streams being opened for a client. If the difference between 'the number of streams the server has open' and 'the number of streams the client has open' is larger than the NUMBER then the server will not open any more streams this tick. To be adjusted based on average client networking speed.

Example

```
ArmaReforgersServer.exe -streamsDelta 200
```

Debug



AI Limit

-aiLimit sets the top limit of AIs. No systems will be able to spawn any AIs when this ceiling is reached (through `aiWorld.CanAICharacterBeAdded()` - see also `SCR_AIGroup` (enfusion://ScriptEditor/scripts/Game/Entities/SCR_AIGroup.c;74) and `SCR_ChimeraAI Agent` (enfusion://ScriptEditor/scripts/Game/AI/SCR_ChimeraAI Agent.c;5)).

 A value less than or equal to zero simply disables any possible AI.

 This parameter applies to both hosted and singleplayer scenarios; while it can save performance, it can also break the experience!

Example

```
ArmaReforgersServer.exe -AILimit 32
ArmaReforgersServer.exe -AILimit 0
ArmaReforgersSteam.exe -AILimit 100
ArmaReforgersSteam.exe -AILimit 0
```

AIPartialSim 1.0.0 ---

number value, default: 4

-aiPartialSim sets in how many batches all simulable AIs will be divided and processed.
e.g: 150 AIs, 100 simulable AIs (100 in LOD0, 50 in LOD 10), these 100 AIs divided by 4 will make four batches of 25 AIs each.

Example

```
ArmaReforgersSteam.exe -aiPartialSim 5
```

autodeployFaction 1.0.0 ---

alias: *tdmf*

-autodeployFaction overrides respawn faction (e.g US, USSR, FIA etc).

 This parameter only works on **diag.exe**!

Example

```
ArmaReforgersSteamDiag.exe -autodeployFaction US
```

autodeployLoadout 1.0.0 ---

alias: *tdml*

 This parameter only works on **diag.exe**!

-autodeployLoadout overrides respawn role (using role name from scenario's LoadoutManager).

Example

```
ArmaReforgerSteamDiag.exe -autodeployLoadout #AR-Role_Driver
```

createDB

-createDB forces database file's regeneration. Useful after file directories changes, when some resources were moved elsewhere. Takes a few seconds upon start.

Example

```
ArmaReforgerServer.exe -createDB
```

debugger

string value, default localhost

-debugger sets the script debugger to a specific address.

Example

```
ArmaReforgerServer.exe -debugger 192.168.0.5
```

debuggerPort

number value, default 1000

-debuggerPort sets the script debugger to a specific port.

Example

```
ArmaReforgerServer.exe -debuggerPort 1040
```

disableAI

1.1.0

-disableAI disables AIWorld initialisation and ticking.

disableCrashReporter

0.9.7

-disableCrashReporter disables the Crash Reporter from appearing/sending reports automatically.

Example

```
ArmaReforgerSteam.exe -disableCrashReporter
```

disableNavmeshStreaming

1.1.0

-disableNavmeshStreaming disables navmesh streaming on all navmesh worlds.

 added navmesh projects list support ("BTRlike" for vehicles, "Soldiers" for characters), separated by commas.

1.2.0

Example

```
ArmaReforgerSteam.exe -disableNavmeshStreaming  
ArmaReforgerSteam.exe -disableNavmeshStreaming NAVMESH_PROJECT1,NAVMESHPROJECT2,etc ,
```

disableShadersBuild

-disableShadersBuild disables shaders generation.

Example

```
ArmaReforgerServer.exe -disableShadersBuild
```

generateShaders

-generateShaders forces shaders generation.

Example

```
ArmaReforgerServer.exe -generateShaders
```



rplEncodeAsLongJobs

1.1.1.0

-rplEncodeAsLongJobs makes replication use long encoding jobs instead of short ones.

Example

```
ArmaReforgerServer.exe -rplEncodeAsLongJobs
```



jobsysShortWorkerCount

1.1.1.0

-jobsysShortWorkerCount sets the number of threads working on short jobs (jobs that must finish in one update loop). Value is limited to the number of CPUs or 16, whichever is the lowest.

Example

```
ArmaReforgerServer.exe -jobsysShortWorkerCount 4
```



jobsysLongWorkerCount

1.1.1.0

number value, range 1..CPUCount, default *jobsysShortWorkerCount* # / 2

-jobsysLongWorkerCount sets the number of threads working on long jobs (jobs that can span multiple iterations of update loop).

Example

```
ArmaReforgerServer.exe -jobsysLongWorkerCount 4
```

keepNumOfLogs 0.9.8 ---

number value, default: 10

-keepNumOfLogs sets the maximum amount of logs to keep.

Example

```
ArmaReforgerServer.exe -keepNumOfLogs 3
```

log-rdb-checksum ---

-log-rdb-checksum enables logging detailed information about RDB checksum computation (GUID and path in order in which they are added to checksum) for RDB checksum issues debugging.

Example

```
ArmaReforgerSteam.exe -log-rdb-checksum
```

log-scr-checksum ---

-log-scr-checksum enables the logging of all script files used in compilation and their checksums.

Example

```
ArmaReforgerSteam.exe -log-scr-checksum
```

logAppend ---

-logAppend makes logs to not be emptied on game start, keeping the history.

Example

```
ArmaReforgerSteam.exe -logAppend
```

logFS ---

-logFS logs every *F*ile *S*ystem's read/write operation in `filesystem.log`. This option is very demanding and can produce a big file in a short time, so it is to be used with caution for debug purpose only.

Example

```
ArmaReforgerSteam.exe -logFS
```

logLevel ---

`-logLevel` allows for different log levels. Each level includes the ones below it (e.g `error` includes `error` and `fatal`). Possible values range from `normal` (where everything is logged) to `fatal` (where only extreme issues are logged):

- `normal`
- `warning`
- `error`
- `fatal`

Example

```
ArmaReforgerSteam.exe -logLevel warning
```



logTime

1.3.0

string value, default time

`-logTime` sets log line time's format; can be one of:

- `none`
- `time` (default)
- `datetime`

Example

```
ArmaReforgerServer.exe -logTime datetime
```



logsDir

0.9.8

`-logsDir` defines the directory by name (located in the `profile#` directory) or  by path, in which game instance specific data are stored like logs, memory dumps, temporary files etc.

Examples

```
ArmaReforgerSteam.exe -logsDir "DebugSession1337" // to store logs in the profile directory
\logs\DebugSession1337
ArmaReforgerSteam.exe -logsDir "C:\Users\MyUserName\Documents\ArmaReforgerDir" // to store logs
\Users\MyUserName\Documents\ArmaReforgerDir" directly
```

keepCrashFiles

`-keepCrashFiles` prevents Crash Reporter from cleaning crash files on successful crash sending.

Example

```
ArmaReforgerSteam.exe -keepCrashFiles
```

minidump

-minidump allows minidump generation to include additional data; possible values:

Value	Microsoft Equivalent (see minidump API documentation (https://learn.microsoft.com/en-us/windows/win32/api/minidumpapiset/ne-minidumpapiset-minidump_type#constants))
normal	MiniDumpNormal
dataSegs	MiniDumpWithDataSegs
fullMemory	MiniDumpWithFullMemory

Example

```
ArmaReforgerSteam.exe -minidump fullMemory
```

scriptAuthorizeAll

-scriptAuthorizeAll disables the security popup about RunCmd, RunProcess, KillProcess and (outside of profile directory) FileIO operations.

Example

```
ArmaReforgerSteam.exe -scriptAuthorizeAll
```

silentCrashReport

-silentCrashReport suppresses the Crash Reporter's dialog and automatically sends the report without any user input or message.

Example

```
ArmaReforgerWorkbenchSteamDiag.exe -silentCrashReport
```

was *noCrashDialog* before 1.0.0

VMErrorMode

-VMErrorMode sets script VM's error reporting mode; possible values are:

- silent - silently continues
- log_only - logs the error then continues
- full - shows the VME dialog, logs the error, then clicking "ignore" continues execution
- fatal - logs the error then exits the game

Profiling

checkInstance

- checkInstance turns on script VM's memory allocations logging - see [Script Profiling](#).

Example

ArmaReforgerSteam.exe -checkInstance

Retrieved from "https://community.bistudio.com/wiki?title=Arma_Reforger:Startup_Parameters&oldid=378693"