RENASCENCE

Karak Native Restaking Audit Report

Version 2.0

Audited by:

MiloTruck

alexxander

marchev

July 16, 2024

Contents

1	Intr	oduction	2
	1.1	About Renascence	2
	1.2	Disclaimer	2
	1.3	Risk Classification	2
2	Exe	cutive Summary	3
	2.1	About Karak Native Restaking	3
	2.2	Overview	3
	2.3	Issues Found	3
3	Find	lings Summary	4
4	Find	linas	6

1 Introduction

1.1 About Renascence

Renascence Labs was established by a team of experts including HollaDieWaldfee, MiloTruck, alexxander and bytes032.

Our founders have a distinguished history of achieving top honors in competitive audit contests, enhancing the security of leading protocols such as Reserve Protocol, Arbitrum, MaiaDAO, Chainlink, Dodo, Lens Protocol, Wenwin, PartyDAO, Lukso, Perennial Finance, Mute and Taurus.

We strive to deliver tailored solutions by thoroughly understanding each client's unique challenges and requirements. Our approach goes beyond addressing immediate security concerns; we are dedicated to fostering the enduring success and growth of our partners.

More of our work can be found here.

1.2 Disclaimer

This report reflects an analysis conducted within a defined scope and time frame, based on provided materials and documentation. It does not encompass all possible vulnerabilities and should not be considered exhaustive.

The review and accompanying report are presented on an 'as-is' and 'as-available' basis, without any express or implied warranties.

Furthermore, this report neither endorses any specific project or team nor assures the complete security of the project.

1.3 Risk Classification

	Impact: High	Impact: Medium	Impact: Low
Likelihood: High	High	High	Medium
Likelihood: Medium	High	Medium	Low
Likelihood: Low	Medium	Low	Low

1.3.1 Impact

- · High Funds are directly at risk, or a severe disruption of the protocol's core functionality
- Medium Funds are indirectly at risk, or some disruption of the protocol's functionality
- · Low Funds are **not** at risk

1.3.2 Likelihood

- · High almost certain to happen, easy to perform, or not easy but highly incentivized
- · Medium only conditionally possible or incentivized, but still relatively likely
- · Low requires stars to align, or little-to-no incentive

2 Executive Summary

2.1 About Karak Native Restaking

Ethereum native restaking on Karak utilizes a continual balance snapshot system combined with an ERC4626 vault where the users are allocated share tokens to handle their stake. The users can restake the Ethereum staked on their Beacon Chain validators to Karak Operators, which serve as validators for the Karak Distributed Secure Services (DSS). Users will continue to earn yields from their beacon chain validators which are also immediately restakable to the respective Karak Operators. Additionally, they will earn rewards from the Operators they choose to restake into proportional to the restaked amount.

2.2 Overview

Project	Karak Native Restaking
Repository	karak-restaking
Commit Hash	8ff20479b531
Mitigation Hash	d928a0803b62
Date	2 July 2024 - 6 July 2024

2.3 Issues Found

Severity	Count
High Risk	10
Medium Risk	7
Low Risk	5
Informational	6
Total Issues	28

3 Findings Summary

ID	Description	Status
H-1	Unsafe cast from int256 to uint256 in NativeVaultupdateBalance() will overflow	Resolved
H-2	Increasing self.totalAssets before share calculation in Native-VaultincreaseBalance() mints less shares	Resolved
H-3	Missing increment for node.activeValidatorCount in NativeVault.validateWithdrawalCredentials()	Resolved
H-4	NativeVault.validateExpiredSnapshot() cannot be called on a node owner with no active validators	Resolved
H-5	NativeVaultstartSnapshot() reverts with an arithmetic underflow when a native node's balance decreases	Resolved
H-6	<pre>assets > withdrawableWei() check in _decreaseBalance() could DOS NativeVaultupdateSnapshot()</pre>	Resolved
H-7	Calling validateWithdrawalCredentials() followed by startSnapshot()/validateExpiredSnapshot() will permanently DOS snapshots	Resolved
H-8	Specifying validatorIndex as uint64 allows BeaconProofsLib.validateValidatorProof() to pass with incorrect proofs	Resolved
H-9	Wrong withdraw address verification in NativeVaultLib.validateWithdrawalCredentials()	Resolved
H-10	Wrong use of the beacon block root instead of the beacon state root in NativeVault.validateWithdrawalCredentials().	Resolved
M-1	NativeVault.finishWithdrawal() doesn't reset withdrawalMap[withdrawalKey] after executing the withdrawal	Resolved
M-2	${\tt Native.startWithdrawal()} \ can \ be \ called \ repeatedly \ to \ queue \ an \ infinite \ number \ of \ withdrawals$	Resolved
M-3	assets > withdrawableWei() check in _decreaseBalance() causes NativeVault.finishWithdrawal() to revert when slashing occurs	Resolved
M-4	$\begin{tabular}{ll} \textbf{Missing validatorProof.length Check in BeaconProofsLib.validate-ValidatorProof()} \\ \end{tabular}$	Resolved
M-5	Function $_getParentBlockRoot()$ limits the beacon roots lookback window	Resolved
M-6	${\tt Native Vault Lib.validate With drawal Credentials () \ should \ return \ the actual \ balance \ of \ the \ validator }$	Acknowledged
M-7	Inability to update node implementation in NativeVault	Resolved
L-1	NativeVault.slashAssets() could incorrectly return 0	Resolved

ID	Description	Status
L-2	A node owner's totalRestakedETH and shares will lag behind his actual restaked balance	Resolved
L-3	NativeVault.startWithdrawal() should ensure the node owner's last snapshot has not expired	Resolved
L-4	The operator of NativeVault is not stored in NativeVaultLib.Storage	Resolved
L-5	Redundant pausing modifier in NativeVault.createNode()	Resolved
I-1	NativeVault.validateWithdrawalCredentials() should call _in-creaseBalance() to avoid an unsafe int256 cast	Resolved
I-2	${\tt STATE_ROOT_IDX} \ and \ {\tt BEACON_STATE_ROOT_IDX} \ can \ be \ combined \ in \ a \ single \ constant$	Resolved
I-3	Unused NativeNode pause functions by NativeVault	Acknowledged
I-4	Reverting receive() function in NativeNode is redundant	Resolved
I-5	Missing reentrancy guards for functions in NativeVault, NativeNode and SlashStore	Resolved
I-6	Code improvements	Resolved

4 Findings

High Risk

[H-1] Unsafe cast from int256 to uint256 in NativeVault._updateBalance() will overflow

Context: NativeVault.sol#L482-L487

Description: In NativeVault._updateBalance(), assets is cast from int256 to uint256 directly as such:

```
function _updateBalance(address _of, int256 assets) internal {
   if (assets > 0) {
        _increaseBalance(_of, uint256(assets));
   } else if (assets < 0) {
        _decreaseBalance(_of, uint256(assets));
   } else {</pre>
```

However, if assets is negative, casting it to uint256 directly will cause assets to overflow into a huge value. This will cause _updateBalance() to revert whenever it is called to decrease a user's balance, making it impossible to withdraw from the protocol.

Recommendation: Multiply assets by -1 first before casting to uint256:

```
} else if (assets < 0) {
-    __decreaseBalance(_of, uint256(assets));
+    __decreaseBalance(_of, uint256(-assets));
} else {</pre>
```

Note that this method of converting int256 to uint256 does not work if assets happens to be type(int256).min. However, assets should never reach that value under normal conditions.

Karak: Fixed in PR 341.

Renascence: Verified, the recommended fix was implemented.

[H-2] Increasing self.totalAssets before share calculation in NativeVault._increaseBalance() mints less shares

Context: NativeVault.sol#L464-L466

Description: In NativeVault._increaseBalance(), self.totalAssets is increased by assets before calculating the amount of shares to mint to the receiver:

```
self.totalAssets += assets;
uint256 shares = convertToShares(assets);
_mint(_of, shares);
```

However, increasing self.totalAssets first causes convertToShares() to calculate less shares to be minted than expected, since totalAssets() is increased beforehand.

A naive example:

· Assume the following:

```
- self.totalAssets = 100e18
- totalSupply = 100e18
```

• _increaseBalance() is called with assets = 100e18:

```
- self.totalAssets = 100e18 + 100e18 = 200e18
```

• convertToShares() calculates shares as 50e18 as:

```
assets * (totalSupply + 1) / (totalAssets + 1) = 100e18 * (100e18 + 1) / (200e18 + 1)
= 50e18
```

• However, 50e18 shares is only worth roughly 66.6e18 of assets as:

```
shares * (totalAssets + 1) / (totalSupply + 1) = 50e18 * (200e18 + 1) / (150e18 + 1) = ~66.6e18
```

In the example above, the user loses around 33.3e18 assets.

Recommendation: The correct order of operator would be to increase self.totalAssets after calling convertToShares():

```
- self.totalAssets += assets;
  uint256 shares = convertToShares(assets);
  _mint(_of, shares);
+ self.totalAssets += assets;
```

Karak: Fixed in PR 325.

[H-3] Missing increment for node.activeValidatorCount in NativeVault.validateWithdrawal-Credentials()

Context: NativeVault.sol#L182-L189

Description: Node owners call NativeVault.validateWithdrawalCredentials() to add active validators to their native node:

```
for (uint256 i = 0; i < validatorFieldsProofs.length; i++) {
   totalRestakedWei += self.validateWithdrawalCredentials(
        nodeOwner,
        beaconStateRootProof.timestamp,
        _getParentBlockRoot(beaconStateRootProof.timestamp),
        validatorFieldsProofs[i]
   );
}</pre>
```

However, after calling NativeVaultLib.validateWithdrawalCredentials() to add all active validators in the loop above, the function does not increment node.activeValidatorCount (ie. the number of active validators in a native node) by the number of new validators added.

This makes it impossible to update the validator's balance in future snapshots as the number of active validators for all native nodes will always remain at 0.

Recommendation: Increment node.activeValidatorCount by the number of active validators added as such:

Karak: Fixed in PR 323.

Renascence: Verified, the issue was fixed by incrementing activeValidatorCount in NativeVaultLib.validateWithdrawalCredentials() each time it is called.

[H-4] NativeVault.validateExpiredSnapshot() cannot be called on a node owner with no active validators

Context: NativeVault.sol#L210-L215

Description: NativeVault.validateExpiredSnapshot() contains the following checks:

```
NativeVaultLib.ValidatorDetails memory validatorDetails =
node.validatorPubkeyHashToDetails[validatorPubkey];

if (beaconStateRootProof.timestamp < validatorDetails.lastBalanceUpdateTimestamp +
Constants.SNAPSHOT_EXPIRY) {
    revert SnapshotNotExpired();
}
if (validatorDetails.status != NativeVaultLib.ValidatorStatus.ACTIVE) revert
ValidatorNotActive();</pre>
```

As seen from above, validateExpiredSnapshot() can only be called when an active validator's last-BalanceUpdateTimestamp is more than 7 days ago. As such, it is not possible to call validateExpiredSnapshot() when a user has no active validators, even if his last snapshot has expired.

When slashing occurs, this would make it impossible to forcefully update a node owner's snapshot. As a result, the node owner's balance will never be updated and slashStore might never receive the slashed funds.

For example:

- Node owner has one active validator with 32 ETH.
- Node owner performs a full withdrawal for his validator. Its status is now WITHDRAW and the 32 ETH is moved into his native node.
- Karak operator calls slashAssets() to perform slashing, which reduces his balance to 31 ETH.
- Since the node owner has no more active validators, validateExpiredSnapshot() cannot be called.

In this scenario, it is impossible to forcefully move 1 ETH from the node owner's native node into slashStore and update his balance. If the node owner chooses to withdraw his remaining 31 ETH and never calls startSnapshot(), slashStore will never receive the 1 ETH that was slashed.

Recomendation:

Consider checking if a node owner's last snapshot has expired with node.lastSnapshotTimestamp instead:

```
function validateExpiredSnapshot(
   address nodeOwner,
) external nodeExists(nodeOwner)
whenFunctionNotPaused(Constants.PAUSE_NATIVEVAULT_VALIDATE_EXPIRED_SNAPSHOT) {
   NativeVaultLib.Storage storage self = _state();
   NativeVaultLib.NativeNode storage node = self.ownerToNode[nodeOwner];

   if (block.timestamp < node.lastSnapshotTimestamp + Constants.SNAPSHOT_EXPIRY) {
      revert SnapshotNotExpired();
   }

   _startSnapshot(node, false, nodeOwner);
}</pre>
```

Karak: Fixed in PR 335. The earlier design was supposed to check if the validator has been slashed on the beacon chain as well. However, based on this issue we realized introducing that check would complicate our flow and just allowing anyone to start a snapshot after an expiry period seemed the better way to go.

Renascence: Verified, the recommended fix was implemented.

 $[H-5] {\tt Native Vault._startSnapshot()} \ reverts \ with \ an \ arithmetic \ underflow \ when \ a \ native \ nodes \ balance \ decreases$

Context:

- NativeVault.sol#L448
- NativeVault.sol#L422-L423

Description: node.creditedNodeETH stores the cumulative amount of ETH ever held by the native node as it is increased in _updateSnapshot() by nodeBalanceWei:

```
node.creditedNodeETH += snapshot.nodeBalanceWei;
```

Note that node.creditedNodeETH is not modified anywhere else in the code.

node.creditedNodeETH is used in $_startSnapshot()$ to calculate the amount of ETH gained by the native node since the last snapshot:

```
// Calculate unattributed node balance
uint256 nodeBalanceWei = node.nodeAddress.balance - node.creditedNodeETH;
```

However, when the native node transfers ETH out, its ETH balance will become smaller than node.creditedNodeETH. Afterwards, when _startSnapshot() is called, node.nodeAddress.balance - node.creditedNodeETH will revert with an underflow.

For example:

- Assume a native node holds 2 ETH. Both nodeAddress.balance and creditedNodeETH are 2e18.
- The node owner withdraws 1 ETH, which transfers 1 ETH out from the native node.

- When _startSnapshot() is called afterwards:
 - nodeAddress.balance creditedNodeETH = 1e18 2e18, which reverts with an underflow

This makes it impossible for the node owner's snapshot to ever be updated. As such, his number of shares will never increase even if his total restaked balance increases from ETH rewards.

Recommendation: creditedNodeETH should store the native node's ETH balance during the last snapshot.

In _updateSnapshot(), consider removing the line adding nodeBalanceWei to creditedNodeETH:

```
- node.creditedNodeETH += snapshot.nodeBalanceWei;
```

Instead, set creditedNodeETH to the node's current balance in _startSnapshot(). Additionally, node-BalanceWei should be 0 when the native node's ETH balance decreases:

```
// Calculate unattributed node balance
- uint256 nodeBalanceWei = node.nodeAddress.balance - node.creditedNodeETH;
+ uint256 nodeBalanceWei;
+ if (node.nodeAddress.balance > node.creditedNodeETH) {
+ nodeBalanceWei = node.nodeAddress.balance - node.creditedNodeETH;
+ }
+ node.creditedNodeETH = node.nodeAddress.balance;
```

This ensures nodeBalanceWei will always be the amount of ETH received by the native node after the last snapshot.

Karak: Fixed in PR 330.

Renascence: Verified, the issue has been fixed by subtracting from node.creditedNodeETH on withdrawal and reducing it to the balance of the native node in _transferToSlashStore().

[H-6] assets > withdrawableWei() check in _decreaseBalance() could DOS NativeVault._up-dateSnapshot()

Context:

- NativeVault.sol#L454
- NativeVault.sol#L473

Description: Whenever a snapshot is completed, NativeVault._updateSnapshot() calls to update the node owner's balance:

```
_updateBalance(nodeOwner, totalDeltaWei);
```

If totalDeltaWei happens to be negative, _updateBalance() calls _decreaseBalance(), which checks that totalDeltaWei is not greater than withdrawableWei():

```
if (assets > withdrawableWei(_of)) revert WithdrawMoreThanMax();
```

Note that withdrawableWei() returns the minimum between the node owner's native node balance and the assets equivalent of his shares.

However, this check could cause _updateSnapshot() to incorrectly revert when completing a snapshot. For example:

- · Assume a node owner has 32 ETH in a validator and no ETH in his native node.
- The following events occur:
 - His native node receives 0.3 ETH from validator rewards.
 - The beacon chain slashes his validator for 1 ETH, leaving 31 ETH remaining.
- He calls startSnapshot(), which sets nodeBalanceWei = 0.3 ether as his native node gained 0.3 ETH.
- He calls validateSnapshotProofs(), which sets balanceDeltaWei = -1 ether as his validator lost 1 ETH.
- When _updateSnapshot() is called:
 - totalDeltaWei = 0.3 ether 1 ether = -0.7 ether
 - _decreaseBalance() is called with assets = 0.7 ether.
 - withdrawableWei() returns his native node's balance, which is 0.3 ETH.
 - Since assets > withdrawableWei(), the function reverts.

As seen from above, if a node owner's validators are slashed for more than his native node's current balance, _updateSnapshot() will always revert when called. This makes it impossible to update his snapshot, even after it expires.

Recommendation: Consider removing the assets > withdrawableWei(_of) check from _decreaseBalance():

```
function _decreaseBalance(address _of, uint256 assets) internal {
    NativeVaultLib.Storage storage self = _state();
    if (assets > withdrawableWei(_of)) revert WithdrawMoreThanMax();
```

This check should be moved into finishWithdrawal() instead to ensure the user cannot withdraw assets than he should be able to.

Karak: Fixed in PR 342.

Renascence: Verified, the check was removed from _decreaseBalance().

[H-7] Calling validateWithdrawalCredentials() followed by startSnapshot()/validateExpiredSnapshot() will permanently DOS snapshots

Context:

- NativeVault.sol#L172-L175
- NativeVaultLib.sol#L179
- NativeVault.sol#L145-L147

Description: NativeVaultLib.validateWithdrawalCredentials() has the following checks for beaconStateRootProof.timestamp:

```
if (
    beaconStateRootProof.timestamp < node.lastSnapshotTimestamp
    || beaconStateRootProof.timestamp < node.currentSnapshotTimestamp
) revert BeaconTimestampTooOld();</pre>
```

As seen from above, only restriction on beaconStateRootProof.timestamp is that it cannot be older than the last/ongoing snapshot. This makes it possible for beaconStateRootProof.timestamp to be block.timestamp.

Later on in the function, the newly added validator's lastBalanceUpdateTimestamp is set to beacon-StateRootProof.timestamp in NativeVaultLib.validateWithdrawalCredentials():

```
validatorDetails.lastBalanceUpdateTimestamp = updateTimestamp;
```

However, if startSnapshot() or validateExpiredSnapshot() is called after validateWithdrawal-Credentials() in the same block, the newly added validator cannot be proven with validateSnapshotProofs() due to the following check:

```
if (validatorDetails.lastBalanceUpdateTimestamp >= node.currentSnapshotTimestamp) {
    revert ValidatorAlreadyProved();
}
```

This will make it impossible to complete the snapshot as the newly added validator can never be proven, so snapshot.remainingProofs will never reach 0. For example:

- · Assume a node owner has no validators.
- In the block where block.timestamp = 1000:
 - validateWithdrawalCredentials() is called:
 - * Assume beaconStateRootProof.timestamp = block.timestamp.
 - * validator.lastBalanceUpdateTimestamp = 1000.
 - * node.activeValidatorCount is incremented to 1.
 - startSnapshot() is called to start a new snapshot:
 - * snapshot.remainingProofs = 1

- * node.currentSnapshotTimestamp = 1000
- When attempting to prove the validator with validateSnapshotProofs():
 - Both validatorDetails.lastBalanceUpdateTimestamp and node.currentSnapshotTimestamp are 1000, so the check shown above reverts.
- As such, the validator can never be proven and snapshot.remainingProofs is forever stuck at 1.

If this occurs, snapshots will be forever DOSed for the node owner.

Recommendation: Ensure that validateWithdrawalCredentials() cannot be called with beacon-StateRootProof.timestamp as block.timestamp by adding the following check:

```
if (beaconStateRootProof.timestamp == block.timestamp) {
    revert BeaconTimestampIsCurrent();
}
```

Note that even without this check, it is unlikely for validateWithdrawalCredentials() to be called with block.timestamp as it is difficult to generate proofs for a block root returned by _getParent-BlockRoot() in a future block.

Karak: Fixed in PR 341.

Renascence: Verified, the recommended fix was implemented.

[H-8] Specifying validatorIndex as uint64 allows BeaconProofsLib.validateValidatorProof() to pass with incorrect proofs

Context:

- BeaconProofsLib.sol#L74-L75
- BeaconProofsLib.sol#L83

Description: In BeaconProofsLib.validateValidatorProof(), validatorIndex is declared as uint64:

```
function validateValidatorProof(
   uint64 validatorIndex,
```

However, validatorIndex should be uint40 instead as the maximum length of validators in BeaconState is 2 ** 40. Any index greater than type(uint40).max is invalid.

This becomes a problem as validatorIndex is OR-ed with the other bits in index:

```
uint256 index = (CONTAINER_IDX « (VALIDATOR_HEIGHT + 1)) | uint256(validatorIndex);
```

Assuming the rightmost bit in index is bit 0, an attacker can set bits 41 to 45 of validatorIndex to switch from the validators field to certain fields after it in BeaconState. You can think of it

as modifying CONTAINER_IDX to a different value, which would end up proving a different field in BeaconState.

For example, assume CONTAINER_IDX = 15 and validatorIndex = 0. index would be:

```
(15 « (VALIDATOR_HEIGHT + 1)) | uint256(0) = 0x1e0000000000
```

The same value can be reached with CONTAINER_IDX = 12 and validatorIndex = 0x1e0000000000, since:

```
(12 « (VALIDATOR_HEIGHT + 1)) | uint256(0x1e0000000000) = 0x1e0000000000
```

If validateValidatorProof() was called with validatorIndex = 0x1e0000000000, the function would end up validating validatorFields against the field at index 15 in BeaconState, which is previous_epoch_participation. This makes it possible for validateValidatorProof() to pass with an invalid validatorFields.

Recommendation: Declare validatorIndex as uint40 instead:

```
function validateValidatorProof(
- uint64 validatorIndex,
+ uint40 validatorIndex,
    bytes32[] calldata validatorFields,
```

This change should be reflected throughout the codebase - any variable that represents the validator's index in the beacon chain should be changed to uint40:

- · BeaconProofsLib.sol#L33-L34
- NativeVaultLib.sol#L20-L22

The unsafe cast from uint64 to uint40 at NativeVaultLib.sol#L120 can then be removed.

Karak: Fixed in PR 341 and PR 348.

[H-9] Wrong withdraw address verification in NativeVaultLib.validateWithdrawalCredentials()

Context:

NativeVaultLib.sol#L162-L167

Description: In NativeVaultLib.validateWithdrawalCredentials() the withdraw credential verification is the following:

```
if (
    BeaconProofs.getWithdrawalCredentials(validatorFieldsProof.validatorFields)
    != bytes32(abi.encodePacked(bytes1(uint8(1)), bytes11(0), address(this)))
) {
    revert WithdrawalCredentialsMismatchWithNode();
}
```

First two parameters supplied to abi.encodePacked() are the prefix 0x01 and 11 zeros bytes as per the withdrawal credential spec, however, the last parameter is the withdrawal address which should be the Native Node, not the Native Vault. **Recommendation:**

```
@@ -161,7 +164,7 @@ library NativeVaultLib {
    // Construct beacon chain withdraw address with current node's payable
    address
    if (
        BeaconProofs.getWithdrawalCredentials(validatorFieldsProof.validatorFiel]
        ds)
-        != bytes32(abi.encodePacked(bytes1(uint8(1)), bytes11(0),
address(this)))
+        != bytes32(abi.encodePacked(bytes1(uint8(1)), bytes11(0),
self.ownerToNode[nodeOwner].nodeAddress))
```

Karak: Fixed in PR 324.

Renascence: Verified, the recommended fix was implemented.

[H-10] Wrong use of the beacon block root instead of the beacon state root in NativeVault.validateWithdrawalCredentials().

Context:

NativeVault.sol#L186

Description: NativeVaultLib.validateWithdrawalCredentials() expects the parameter bytes32 beaconStateRoot. In NativeVault.validateWithdrawalCredentials(), beaconStateRootProof.beaconStateRoot is verified, however, It is the beacon block root that is passed to NativeVaultLib.validateWithdrawalCredentials(), which is incorrect. The beacon state root should be supplied instead.

Recommendation:

Karak: Fixed in PR 336.

Medium Risk

[M-1] NativeVault.finishWithdrawal() doesnt reset withdrawalMap[withdrawalKey] after executing the withdrawal

Context: NativeVault.sol#L261-L262

Description: In NativeVault.finishWithdrawal(), the withdrawal to execute is fetched with withdrawalMap[withdrawalKey]:

```
NativeVaultLib.Storage storage self = _state();
NativeVaultLib.QueuedWithdrawal memory startedWithdrawal =
self.withdrawalMap[withdrawalKey];
```

However, after the pending withdrawal is executed, self.withdrawalMap[withdrawalKey] isn't reset in storage. This allows a user to call finishWithdrawal() repeatedly with the same withdrawalKey to withdraw all his assets, effectively bypassing MIN_WITHDRAWAL_DELAY.

Recommendation: Consider clearing withdrawalMap[withdrawalKey] as such:

```
NativeVaultLib.Storage storage self = _state();
NativeVaultLib.QueuedWithdrawal memory startedWithdrawal =
  self.withdrawalMap[withdrawalKey];
+ delete self.withdrawalMap[withdrawalKey];
```

Karak: Fixed in PR 327.

Renascence: Verified, the recommended fix was implemented.

[M-2] Native.startWithdrawal() can be called repeatedly to queue an infinite number of withdrawals

Context: NativeVault.sol#L238

Description: The maximum amount of ETH a node owner can withdraw through NativeVault.startWithdrawal() is limited by withdrawableWei():

```
if (weiAmount > withdrawableWei(msg.sender)) revert WithdrawMoreThanMax();
```

withdrawableWei(msg.sender) is the minimum between the amount of ETH in the caller's native node and the asset equivalent of his shares, so it doesn't exclude the amount of ETH that are currently in pending withdrawals.

As such, users can queue an infinite amount of ETH for withdrawals by repeatedly calling startWithdrawal() with weiAmount = withdrawableWei(msg.sender). This allows them to bypass MIN_WITHDRAWAL_DELAY for withdrawals in the future as they have an infinite number of pending withdrawals, and can call finishWithdrawal() anytime to instantly perform a withdrawal.

Recommendation: Consider tracking the amount of ETH in pending withdrawals and subtracting it from withdrawableWei() in startWithdrawal().

In NativeVaultLib, add a new mapping in Storage named nodeOwnerToWithdrawAmount, which represents the total amount of assets in pending withdrawals for each node owner:

```
// mapping of node owner to their withdraw nonce
mapping(address nodeOwner => uint256 withdrawNonce) nodeOwnerToWithdrawNonce;
+ // mapping of node owner to their total pending withdrawal amount
+ mapping(address nodeOwner => uint256 withdrawAmount) nodeOwnerToWithdrawAmount;
// mapping of owners' withdraw nonce to pending withdrawals
mapping(bytes32 ownerWithdrawNonce => QueuedWithdrawal withdrawal) withdrawalMap;
```

In startWithdrawal(), subtract nodeOwnerToWithdrawAmount from withdrawableWei(). Additionally, nodeOwnerToWithdrawAmount should be increased by weiAmount whenever a new withdrawal is started:

```
- if (weiAmount > withdrawableWei(msg.sender)) revert WithdrawMoreThanMax();

NativeVaultLib.Storage storage self = _state();
+ if (weiAmount > withdrawableWei(msg.sender) -
self.nodeOwnerToWithdrawAmount[msg.sender]) {
+    revert WithdrawMoreThanMax();
+ }
+ self.nodeOwnerToWithdrawAmount[msg.sender] += weiAmount;
```

In finishWithdrawal(), whenever a withdrawal is finished, subtract the amount of assets withdrawn from nodeOwnerToWithdrawAmount:

```
if (startedWithdrawal.start == 0) revert WithdrawalNotFound();
if (startedWithdrawal.start + Constants.MIN_WITHDRAWAL_DELAY > block.timestamp) {
    revert MinWithdrawDelayNotPassed();
}

+ self.nodeOwnerToWithdrawAmount[startedWithdrawal.nodeOwner] -=
    startedWithdrawal.assets;
```

Karak: Fixed in PR 342.

[M-3] assets > withdrawableWei() check in _decreaseBalance() causes NativeVault.finish-Withdrawal() to revert when slashing occurs

Context:

- NativeVault.sol#L269
- NativeVault.sol#L473

Description: When finishing a withdrawal, NativeVault.finishWithdrawal() calls _decreaseBalance() to decrease the node owner's asset balance:

```
_decreaseBalance(startedWithdrawal.nodeOwner, startedWithdrawal.assets);
```

_decreaseBalance() checks that startedWithdrawal.assets is not greater than withdrawableWei():

```
if (assets > withdrawableWei(_of)) revert WithdrawMoreThanMax();
```

Note that withdrawableWei() returns the minimum between the node owner's native node balance and the assets equivalent of his shares.

However, if Karak operator or the beacon chain slashes the node owner's ETH balance before a withdrawal is finished, it might become impossible for the withdrawal to be executed using finish-Withdrawal() due to this check.

For example:

- · Assume that:
 - A node owner holds 32e18 shares that corresponds to 32 ETH.
 - He is the only node owner in the entire protocol, so totalSupply and totalAssets are both 32e18 as well.
- Node owner calls startWithdrawal() with weiAmount = 32e18 to withdraw his entire balance.
- Karak operator calls slashAssets() to slash 1 ETH, so totalAssets = 31e18.
- Node owner calls finishWithdrawal() to finish the withdrawal. In _decreaseBalance():
 - withdrawableWei() returns 31 ETH.
 - startedWithdrawal.assets = 32e18 is greater than withdrawableWei(), so the check reverts.

If a withdrawal can never be completed using finishWithdrawal(), as demonstrated above, the node owner will have to go through the full MIN_WITHDRAWAL_DELAY period again to withdraw his assets.

Recommendation: Consider removing the assets > withdrawableWei(_of) check from _decreaseBalance():

```
function _decreaseBalance(address _of, uint256 assets) internal {
   NativeVaultLib.Storage storage self = _state();
-   if (assets > withdrawableWei(_of)) revert WithdrawMoreThanMax();
```

In finishWithdrawal(), consider limiting the amount of assets withdrawn to withdrawableWei() instead of reverting:

```
+ uint256 withdrawableAssets = withdrawableWei(startedWithdrawal.nodeOwner);
+ if (startedWithdrawal.assets > withdrawableAssets) {
+    startedWithdrawal.assets = withdrawableAssets;
+ }
    _decreaseBalance(startedWithdrawal.nodeOwner, startedWithdrawal.assets);
    INativeNode(self.ownerToNode[startedWithdrawal.nodeOwner].nodeAddress).withdraw(
        startedWithdrawal.to, startedWithdrawal.assets
);
```

Karak: Fixed in PR 342.

Renascence: Verified, the recommended fix was implemented.

[M-4] Missing validatorProof.length check in BeaconProofsLib.validateValidatorProof()

Context: BeaconProofsLib.sol#L74-L88

Description: In BeaconProofsLib.validateValidatorProof(), there no is check on the length of validatorProof, which allows an attacker to freely specify the number of proof hashes to be used in verifyInclusionSha256().

If it is shorter than it should be, the number of times validatorRoot is hashed will be less. This could potentially cause validatorProof() to pass with an invalid validatorRoot.

Recommendation: The length of validatorProof should be the height of the merkleized Validator list + the height of the merkleized BeaconState container. Consider adding the following check:

```
- if (!Merkle.verifyInclusionSha256(validatorProof, beaconStateRoot, validatorRoot, index)) {
+ if (
+ validatorProof.length != 32 * ((VALIDATOR_HEIGHT + 1) + BEACON_STATE_HEIGHT) ||
+ !Merkle.verifyInclusionSha256(validatorProof, beaconStateRoot, validatorRoot, index)
+ ) {
    revert InvalidValidatorFieldsProof();
}
```

Karak: Fixed in PR 342.

[M-5] Function _getParentBlockRoot() limits the beacon roots lookback window

Context:

NativeVault.sol#L384

Description: Since timestamps are 12 seconds apart, the check on line L384 should be block.timestamp - timestamp >= Constants.BEACON_ROOTS_RING_BUFFER * 12. Currently, this would limit the _getParentBlockRoot() to return only 683 of the latest stored beacon block roots, while the beacon roots contract accommodates 8191.

Recommendation: Change the code on line 384 to Constants.BEACON_ROOTS_RING_BUFFER * 12. The check could also be entirely removed since the beacon roots contract will also revert on a query that is more than 8191 roots old.

```
# Pseudo code of the beacon roots contract
def get():
    if len(evm.calldata) != 32:
        evm.revert()

if to_uint256_be(evm.calldata) == 0:
    evm.revert()

timestamp_idx = to_uint256_be(evm.calldata) % HISTORY_BUFFER_LENGTH
    timestamp = storage.get(timestamp_idx)

if timestamp != evm.calldata:
    evm.revert()

root_idx = timestamp_idx + HISTORY_BUFFER_LENGTH
    root = storage.get(root_idx)

evm.return(root)
```

Karak: Fixed in PR 342.

Renascence: Verified, the check was removed.

[M-6] NativeVaultLib.validateWithdrawalCredentials() should return the actual balance of the validator

Context:

NativeVaultLib.sol#L169

Description: The effective balance of a validator is capped at 32 ETH. If a validator has more than 32 ETH, such as 64 ETH, getEffectiveBalanceWei() will return 32 ETH while its balance in Beacon-ProofsLib.validateBalance() would be 64 ETH.

As such, if NativeVault.validateWithdrawalCredentials() is called to register a validator that holds more than 32 ETH, only 32 ETH worth of shares will be minted to the nodeOwner and added to totalRestakedETH. The remaining shares will only be minted in the next snapshot.

This causes the number of shares held by the nodeOwner to be temporarily lower than their actual ETH balance until the next snapshot. Additionally, the shares that have not been minted cannot be slashed.

Recommendation: Consider specifying restakedBalanceWei as the validator's actual balance here, using validateBalance().

Karak: Acknowledged. The excess ETH balance isn't restaked so node owners won't be getting rewards for them, so it's fine if it can't be slashed.

Renascence: Acknowledged.

[M-7] Inability to update node implementation in NativeVault

Context: NativeVault.sol#L85

Description: NativeVault acts as a beacon for any node deployed through. The function Native-Vault#changeNodeImplementation() that is used to update the beacon proxy implementation is restricted to the contract owner, which is the Core contract. However, the Core contract does not include any functionality to invoke changeNodeImplementation(). As a result, once a NativeVault is deployed, there's no way to update the nodeImpl for nodes that rely on NativeVault as a beacon.

Recommendation: Depending on the intended behavior, make sure the NativeNode#changeNodeImplementation() can be called by the respective role within the project, e.g. MANAGER_ROLE.

Karak: Fixed in PR 322.

Renascence: Verified, the issue was fixed by allowing the MANAGER_ROLE to call changeNodeImplementation().

Low Risk

[L-1] NativeVault.slashAssets() could incorrectly return 0

Context: NativeVault.sol#L293-L298

Description: In NativeVault.slashAssets(), if the amount of assets to slash is greater than the total amount of assets, totalAssets is set to 0:

```
// avoid negative totalAssets if slashing amount is greater than totalAssets
if (totalAssetsToSlash > self.totalAssets) {
   emit Slashed(self.totalAssets);
   self.totalAssets = 0;
   return self.totalAssets;
}
```

However, since self.totalAssets is set to 0 before the return statement, it will always return 0 in the block shown above.

Recommendation: Consider modifying the logic as such:

```
// avoid negative totalAssets if slashing amount is greater than totalAssets
if (totalAssetsToSlash > self.totalAssets) {
    emit Slashed(self.totalAssets);
    self.totalAssets = 0;
    return self.totalAssets;
    totalAssetsToSlash = self.totalAssets;
}
```

Karak: Fixed in PR 338.

Renascence: Verified, the recommended fix was implemented.

[L-2] A node owners totalRestakedETH and shares will lag behind his actual restaked balance

Context: NativeVault.sol#L422-L425

Description: Due to the following check in _startSnapshot(), NativeVault.startSnapshot() can only be called by a node owner when his native node's ETH balance has increased since the last snapshot:

```
// Calculate unattributed node balance
uint256 nodeBalanceWei = node.nodeAddress.balance - node.creditedNodeETH;
if (throwIfNoBalanceChange && nodeBalanceWei == 0) revert NoBalanceUpdateToSnapshot();
```

However, a node owner might want to start a snapshot even if his native node's balance hasn't changed since the last snapshot. For example, if his validator's balance on the beacon chain increased, starting a snapshot would increase totalRestakedETH and mint more shares to him to reflect this change.

startSnapshot() cannot be called by the node owner until either:

- 1. 7 days has passed, causing his last snapshot to expire.
- 2. A partial withdrawal is executed on the beacon chain to withdraw his validator's excess balance to the native node.

Note that the duration of (2) depends entirely on the state of the beacon chain, and can take up to multiple days to occur.

Therefore, since the node owner has to wait for a period of time before startSnapshot() can be called, his totalRestakedETH value and number of shares will temporarily lag behind the actual amount of ETH he has restaked.

Recommendation: Consider removing this check from _startSnapshot():

Karak: Fixed in PR 338. Instead of deciding on our own, we can take this from the user itself. So, if they don't want to go ahead with a snapshot with 0 node balance update, they can pass in the option.

Renascence: Verified, the issue was fixed by allowing the user to specify throwIfNoBalanceChange when calling NativeVault.startSnapshot().

$\hbox{[$L$-3]$ Native Vault. start Withdrawal() should ensure the node owners last snapshot has not expired}$

Context: NativeVault.sol#L237

Description: In the current implementation of the code, NativeVault.startWithdrawal() can be called by the node owner to start a withdrawal regardless of when his last snapshot was taken.

This seems to be known by the team in the following TODO:

```
// TODO: make recent snapshot compulsory
```

However, at the very least, startWithdrawal() should ensure that the node owner's last snapshot isn't expired. In the event where slashing occurs and the node owner wishes to withdraw all his funds, he can just call startWithdrawal() to withdraw his entire balance without updating his snapshot.

This forces the protocol to call validateExpiredSnapshot() on his behalf to transfer the remaining funds left behind from slashing to the slashStore.

Recommendation: Add the following check to startWithdrawal():

```
NativeVaultLib.Storage storage self = _state();
+ NativeVaultLib.NativeNode storage node = self.ownerToNode[msg.sender];
+
+ if (block.timestamp >= node.lastSnapshotTimestamp + Constants.SNAPSHOT_EXPIRY) {
+    revert SnapshotNotExpired();
+ }
```

Karak: Fixed in PR 338.

Renascence: Verified, the recommended fix was implemented.

[L-4] The operator of NativeVault is not stored in NativeVaultLib.Storage

Context:

NativeVault

Description: In NativeVault.initialize(), the operator is stored only in VaultLib.Config, self.operator is not assigned and remains address(0) inside NativeVaultLib.Storage. The parts of the code that become affected are:

- 1. NativeVaultLib.deployNode(): The calculation of the salt for the same msg.sender will be the same across Native Vaults even if the operator is different. This does not seem to lead to anything major.
- 2. NativeVault.startWithdrawal() and NativeVault.finishWithdrawal() functions will emit events with address(0) as the operator.

Recommendation: Assign self.operator to the operator in NativeVault.initialize(), the name and symbol variables of the Vault in NativeVaultLib.Storage can be assigned as well.

```
+ self.name = _name;
+ self.symbol = _symbol;
+ self.operator = _operator;
```

Karak: Fixed in PR 338.

Renascence: Verified, the issue was fixed by removing name, symbol and operator from Native-VaultLib.Storage and can be accessing them from VaultLib.Config through the _config() function.

[L-5] Redundant pausing modifier in NativeVault.createNode()

Context: NativeVault.sol#L97-L99

Description: The createNode() function uses both whenNotPaused() and whenFunctionNot-Paused(Constants.PAUSE_NATIVEVAULT_CREATE_NODE), leading to redundancy. If createNode() should be paused when any function in the protocol is paused, remove whenFunctionNotPaused, as whenNotPaused covers this. If it should only be paused for PAUSE_NATIVEVAULT_CREATE_NODE, remove whenNotPaused.

Recommendation: Depending on the intended behavior, remove either the whenNotPaused or when-FunctionNotPaused modifier from the createNode() function.

Karak: Fixed in PR 338.

Renascence: Verified, the whenNotPaused modifier was removed.

Informational

[I-1] NativeVault.validateWithdrawalCredentials() should call_increaseBalance() to avoid an unsafe int256 cast

Context: NativeVault.sol#L191

Description: In NativeVault.validateWithdrawalCredentials(), totalRestakedWei (which is a uint256) is cast directly to int256 and passed to _updateBalance():

```
_updateBalance(nodeOwner, int256(totalRestakedWei));
```

However, since totalRestakedWei can never be negative, _increaseBalance() should be used directly instead of _updateBalance() to avoid casting to int256.

Recommendation: Consider calling _increaseBalance() instead:

```
_updateBalance(nodeOwner, int256(totalRestakedWei));
+ _increaseBalance(nodeOwner, totalRestakedWei);
```

Karak: Fixed in PR 337.

Renascence: Verified, the recommended fix was implemented.

[I-2] STATE_ROOT_IDX and BEACON_STATE_ROOT_IDX can be combined in a single constant

Context:

- BeaconProofsLib.sol#L9
- · BeaconProofsLib.sol#L11

Description: STATE_ROOT_IDX and BEACON_STATE_ROOT_IDX both represent the same value, which is the index of state_root in BeaconBlockHeader.

Recommendation: Consider removing STATE_ROOT_IDX and using BEACON_STATE_ROOT_IDX in BeaconProofsLib.validateBalanceContainer().

Karak: Fixed in PR 337.

[I-3] Unused NativeNode pause functions by NativeVault

Context:

• NativeNode.sol#L37-L45

Description: The functions NativeNode.pause() and NativeNode.unpause() are never called by the owner of the contract, which is NativeVault.

Recommendation: Consider including the following functions in NativeVault if pausing and unpausing of NativeNode is intended behavior.

```
function pauseNode(INativeNode node, uint256 map) external
onlyRolesOrOwner(Constants.MANAGER_ROLE) {
    node.pause(map);
}

function unpauseNode(INativeNode node, uint256 map) external
onlyRolesOrOwner(Constants.MANAGER_ROLE) {
    node.unpause(map);
}
```

Karak: Acknowledged. We don't need NativeNode to be pausable since the only function it has is withdraw(), and that too can be only called by the owner which will always be the NativeVault. If the withdraw function in NativeVault is paused, then it implies that the native node's withdraw is paused.

Renascence: It's fine to not have NativeNode be pausable, but the MANAGER_ROLE would have to pause finishWithdrawal(), alongside startSnapshot() and validateExpiredSnapshot() as well since _startSnapshot() also withdraws from the native node for slashing.

[I-4] Reverting receive() function in NativeNode is redundant

Context:

NativeNode.sol#L48-L50

Description: If NativeNode doesn't have a receive() function, attempts to transfer ETH, that are not coming from the BeaconChain, will fail. The inclusion of a reverting receive() function is redundant.

Recommendation:

```
- /// @notice Direct deposit to NativeNode address is not allowed to limit sources of
unattributed ETH
- receive() external payable {
- revert DirectDepositToNode();
- }
```

Karak: Fixed in PR 337.

[I-5] Missing reentrancy guards for functions in NativeVault, NativeNode and SlashStore

Context:

- NativeVault.sol#L113
- NativeVault.sol#L127
- NativeVault.sol#L164
- NativeVault.sol#L200
- NativeNode.sol#L56
- SlashStore.sol#L32

Description: The functions NativeVault.startSnapshot(), NativeVault.validateSnapshot-Proofs(), NativeVault.validateWithdrawalCredentials(), NativeVault.validateExpiredSnapshot(), NativeNode.withdraw(), and SlashStore.withdraw() could benefit from reentrancy guards as protective measures.

Recommendation: Add nonReentrant modifiers to the listed functions.

Karak: Fixed in PR 337 and PR 346.

Renascence: Verified, the nonReentant modifier was added to the functions listed above.

[I-6] Code improvements

Description / Recommendation

1. Pauser.sol#L76

The line of code can be simplified to:

```
- if (((~self._paused) & (~map)) != (~self._paused)) revert
AttemptedPauseWhileUnpausing();
+ if (self._paused & map != map) revert AttemptedPauseWhileUnpausing();
```

2. Pauser.sol#L36-L42

Consider using the names $_Pauser_init()$ and $_Pauser_init_unchained()$ to be consistent with the upgradeable contracts' init function name pattern and avoid confusion in child contracts that use it. The init functions in upgradeable contracts normally follow the pattern $_\{ContractName\}_init$ and $_\{ContractName\}_init_unchained$.

Karak: Fixed in PR 337.