

## CHAPTER 4: DEALING WITH TEXT OUTPUT


In Windows programming, the **client area** is the part of the application window that is not taken up by the title bar, window-sizing border, and other elements.



### What is the Client Area?

The **client area** is the part of the window where your app does the actual drawing — think of it as your painting canvas.

It's everything **except** the title bar, borders, and scroll bars.



### What is Painting?

The process of displaying text or graphics in a Windows program's client area is called "**painting**".

We don't draw whenever we want — Windows controls **when** we're allowed to paint, by sending us a message: [WM\\_PAINT](#).

Windows programs must be able to handle client areas of varying sizes, from very small to very large.

Windows provides a [Graphics Device Interface \(GDI\)](#) for painting, but in this chapter, we will focus on displaying simple lines of text.

Windows programs should use the [system font as the default font](#), as this ensures consistent appearance across different systems.

```
case WM_PAINT:  
{  
    PAINTSTRUCT ps; // Struct to hold paint info.  
  
    // Start painting: Gets a device context (HDC) for drawing.  
    // This HDC is specific to the current paint operation.  
    HDC hdc = BeginPaint(hwnd, &ps);  
  
    // --- Your Drawing Commands Go Here ---  
    // Example: Display "Hello WinAPI!" text at (10, 10).  
    TextOut(hdc, 10, 10, TEXT("Hello WinAPI!"), 13);  
  
    // End painting: Releases the HDC and validates the update region.  
    // Crucial for telling Windows you're done and preventing endless WM_PAINTs.  
    EndPaint(hwnd, &ps);  
}  
break;
```

**HDC (Device Context):** Think of this as your canvas. All GDI (Graphics Device Interface) drawing functions need an HDC to know where to draw.

- Always use `BeginPaint()` / `EndPaint()` inside `WM_PAINT`.

## Device-Independent Programming

**Device-independent programming** is the practice of writing software that can run on a variety of hardware and software configurations. Different screens, resolutions, DPI settings... your code needs to adapt.

### Tips:

- Use system font (`GetStockObject(SYSTEM_FONT)`)
- Use window metrics (`GetClientRect`, `GetDeviceCaps`) to stay responsive
- Avoid hardcoded positions and sizes

The **size of the client area** can change at any time, so Windows programs need to be able to react to these changes.

Windows programs can use a **variety of techniques** to make their output look good on different screen sizes.

In Windows, programs can only draw text and graphics in the client area of their window.

```
LRESULT CALLBACK WndProc(HWND hwnd, UINT message, WPARAM wParam, LPARAM lParam)
{
    switch (message)
    {
        case WM_PAINT:
        {
            PAINTSTRUCT ps;
            HDC hdc = BeginPaint(hwnd, &ps);

            // Paint the client area of the window here
            EndPaint(hwnd, &ps);
            return 0;
        }
        default:
            return DefWindowProc(hwnd, message, wParam, lParam);
    }
}
```

## ◆ HWND hwnd

Handle to the window that got the message. Think of this as the *unique ID* for your window.

## ◆ UINT message

Tells you *what happened*. Could be:

- WM\_PAINT → Time to redraw
- WM\_KEYDOWN → Key pressed
- WM\_MOUSEMOVE → Mouse moved

## ◆ WPARAM wParam & LPARAM lParam

Extra info, depending on the message:

- If it's a keypress, wParam might be the key code.
  - If it's mouse movement, lParam might pack the (x, y) coords.
-



## Message Handling Logic

You handle these messages using a switch (message) block:

```
switch (message)
{
    // You can comment out this part because PlaySound requires the winmm.lib library,
    // which is not linked by default in most Windows projects.
    // Unlike kernel32.lib, user32.lib, and gdi32.lib (which are included automatically),
    // winmm.lib is an external multimedia library that handles sounds and music.
    // If you don't link winmm.lib, calling PlaySound will cause linker errors.
    // So, unless you explicitly link winmm.lib in your project settings,
    // it's safer to comment out PlaySound to avoid build problems.
    case WM_CREATE:
        //PlaySound(TEXT("hellowin.wav"), NULL, SND_FILENAME | SND_ASYNC);
        return 0;

    case WM_PAINT:
    {
        PAINTSTRUCT ps; // Struct to hold paint info.

        // Start painting: Gets a device context (HDC) for drawing.
        // This HDC is specific to the current paint operation.
        HDC hdc = BeginPaint(hwnd, &ps);

        // --- Your Drawing Commands Go Here ---
        // Example: Display "Hello WinAPI!" text at (10, 10).
        TextOut(hdc, 10, 10, TEXT("Hello WinAPI!"), 13);

        // End painting: Releases the HDC and validates the update region.
        // Crucial for telling Windows you're done and preventing endless WM_PAINTs.
        EndPaint(hwnd, &ps);
        return 0;
    }

    case WM_DESTROY:
        PostQuitMessage(0);
        return 0;
}
```

## WM\_PAINT – Drawing Time

When your window needs to update its client area (the drawable part), Windows sends WM\_PAINT.

### What Triggers WM\_PAINT?

- Window is resized.
- A covered section becomes visible.
- A tooltip disappears.
- You manually request repainting (InvalidateRect).

### The Painting Steps (explained line-by-line)

#### PAINTSTRUCT ps;

This holds data about the area that needs to be redrawn.  
Windows fills this when you call BeginPaint().

#### BeginPaint(hwnd, &ps);

Starts the painting.  
Returns an HDC (Handle to Device Context) — this is your *drawing tool*.  
You'll use it to draw text, shapes, etc.

#### Draw Your Content

Between BeginPaint() and EndPaint(), do things like:

```
TextOut(hdc, 20, 20, TEXT("Hello World!"), 12);
```

#### EndPaint(hwnd, &ps);

Always call this when you're done.  
It releases the HDC and tells Windows: "I'm done painting."

---



## DefWindowProc – The Default Handler

Not every message is one **you** need to handle yourself.

If your window gets a message you **don't explicitly process**, you need to *pass it along* to DefWindowProc(). This function is built into Windows — it knows how to handle the boring but critical stuff like:

- Moving the window around.
- Resizing.
- Clicking the close button.
- Minimizing/maximizing.
- System commands (like Alt+F4).

If you don't call it for unhandled messages, weird stuff happens — your window might stop behaving like a normal window. It won't close right, it won't respond to default key combos, and users will think it's broken .

### What You're Passing In:

```
return DefWindowProc(hwnd, message, wParam, lParam);
```

This ensures default behavior (like dragging, closing, etc.) still works.

- **hwnd:** Which window this is about
- **message:** The type of message (e.g. WM\_CLOSE, WM\_MOVE, etc.)
- **wParam / lParam:** Any extra info tied to the message — depends on the message type.

Basically, you're saying:

"Hey Windows, I don't know what to do with this message, so *you* deal with it."


---

## Real Example

1. User clicks the **X (close)** button on your app window.
  2. Windows **sends a WM\_CLOSE message** to your window procedure (WndProc).
  3. Now you have two choices in your WndProc function:
    - ✓ **Handle WM\_CLOSE yourself** (maybe ask "Are you sure?" with a message box, or save work).
    - ✓ **Or if you don't care to do anything special, pass it to DefWindowProc.**
- 

## What happens if you do *not* pass WM\_CLOSE to DefWindowProc?

If your WndProc looks like this:



```
case WM_CLOSE:  
    // Do nothing  
    break;
```

Then Windows will NOT close your window. Your app stays open, but you can't interact with it. It's now a **zombie window** — looks alive, but it doesn't respond or close.

## Correct Way (if you don't want to do anything special):



```
case WM_CLOSE:  
    DefWindowProc(hWnd, message, wParam, lParam);  
    break;
```

Or, more commonly, let it fall through to the default handler:

```
default:  
    return DefWindowProc(hWnd, message, wParam, lParam);
```


This ensures Windows does its job: destroying the window, sending WM\_DESTROY, and eventually posting a WM\_QUIT to end the message loop.

### **Bottom Line**

**Yes — if you don't handle WM\_CLOSE, and you don't pass it to DefWindowProc, your window won't close. Always call DefWindowProc for messages you don't explicitly handle.**

## CLIENT AREA PAINTING

Back in the day — in good old DOS or other character-mode environments — you could draw *anywhere* on the screen.



The entire display was yours: a giant grid of characters or pixels. You could scribble on it, and whatever you wrote stayed put until you changed it.

## Total control. No rules.

In traditional character-based environments, programs had direct control over the entire video display.

They could write text and graphics anywhere on the screen, and the modifications will remain visible until [explicitly overwritten](#).

This [simplicity](#) allows programs to manage the screen contents without worrying about external factors.

Windows is much complex, so programs can only draw on the client area of their own [window](#), a designated rectangular region within the overall window frame.

This restriction is primarily due to the [multitasking](#) nature of Windows, where multiple programs share the screen space.




Additionally, the content of the client area is not guaranteed to persist indefinitely.

**There are several scenarios where the client area may need to be repainted:**

**Revealing Previously Hidden Areas:** When a hidden portion of the window is brought into view, either by moving the window or uncovering it from behind another window, Windows will send a WM\_PAINT message to the window procedure. This message signals the need to redraw the exposed area.

Windows tells your program:


"Hey, that section was in the shadows, now it's in the light — redraw it."



**Window Resizing:** If the user resizes the window, and the window class style has the CS\_HREDRAW and CW\_VREDRAW bits set, Windows will again send a WM\_PAINT message. This ensures that the client area adapts to the new window size.




**Scrolling:** When a program uses the ScrollWindow or ScrollDC functions to scroll part of the client area, Windows will generate a WM\_PAINT message to update the visible portion of the client area.



**Explicit Invalidations:** Programs can explicitly request a repaint of specific areas of the client area using the InvalidateRect or InvalidateRgn functions.

- Use InvalidateRect(hwnd, NULL, TRUE) — to redraw everything
- Or use InvalidateRgn() for custom shapes

This is great when your internal data changes and the screen needs to match.



**Temporary Overwriting:** In some cases, Windows may attempt to save and restore an area of the display when it is temporarily overwritten, such as when a [dialog box](#) or a [popup menu](#) is displayed over the client area.

However, this process is not always reliable, and Windows may sometimes send a WM\_PAINT message even when the client area was not actually altered.

In short, paint [repaint the area after the overlay is gone](#), restore the visuals beneath, just to make sure.

## Mouse Cursor and Icon Dragging:

This is one of the rare "**clean**" **overwrite cases**.

When the mouse or an icon drags over your client area:

- ⌚ Windows **always saves and restores** the bits underneath — *no repaint needed*.
- 🧠 Unless something actually changed, no WM\_PAINT is fired. Efficient and smart.



### ⚠️ Final Pro Tip

Always assume a WM\_PAINT could hit **any time**.

Be ready to redraw *everything needed*, even if you just painted it a second ago.

That's the **Windows way**.

## DEALING WITH WM\_PAINT MESSAGES

### 🎯 Understanding How to Handle WM\_PAINT Properly

#### 🧠 It's Not About Drawing Whenever You Want

In older systems (think DOS or bare metal), if you wanted something on screen — you drew it *right then and there*.

✍️ You directly touched the screen memory and said:

“Put this text here. Draw that shape there.”

Done.

But in **Windows**, you **don't control the screen** like that anymore.

You're playing in a **multitasking, window-sharing, constantly redrawing OS**.


---

### 🎬 In Windows: You Wait For the WM\_PAINT Signal

When your app wants to update the visuals:

✗ **Don't draw right away.**

✓ **Instead, mark the area as needing a repaint.**



⌚ Then, when Windows sends a WM\_PAINT message, *that's your green light*. That's when you actually do the drawing.

## **Real-World:**

Think of it like a **traffic system**. When cars approach an **intersection** (like your application windows), they wait for the green light (the WM\_PAINT message). The green light signals that it's their turn to move.

You don't let each car move whenever it feels like it—you wait for a **coordinated signal** (like the WM\_PAINT message), and only then do you allow all the cars (representing drawing operations) to proceed in an organized, synchronized way.

Just like traffic lights control the flow of cars, **WM\_PAINT** controls the flow of painting operations.

Windows doesn't start rendering (or painting) until it's **explicitly told** to do so, ensuring everything is done at the right time and in the right order.

This keeps the process smooth and avoids chaos, making sure that multiple requests don't interfere with each other.

## **Why This Weird Flow?**

Because Windows is juggling tons of things:

- Other apps
- Minimizing and restoring windows
- Moving stuff around
- Tooltips, dialogs, drag-drops — all fighting for screen space

So, it's **Windows** that controls **when** something is drawn.

## **You just tell it:**

"Hey, I changed something—next time you're redrawing, include this region I've marked for repaint," says the program.

## **And how fast does Windows handle these repaints?**

"Fast enough that we hardly even notice them. It's so seamless that the updates often feel instant, and we're rarely aware of the precise moment the screen refreshes."

## **Do all Windows apps, even those written in other languages and frameworks like Qt, C#, Tkinter, and Electron, rely on WinAPI concepts, just in a higher-level way?**

Yes! All Windows apps, whether using low-level WinAPI (like in Charles Petzold's examples) or high-level frameworks like C#, Qt, Tkinter, or Electron, are ultimately built on WinAPI concepts.

These frameworks abstract the complexity but still depend on Windows' core system calls for window creation, message handling, painting, and user input.

- **WinAPI (C, Petzold):** Direct interaction with the Windows message loop and handling events like WM\_PAINT yourself.
- **C# (WinForms, WPF):** Handles high-level UI details but still relies on Windows' message system for painting and event dispatching.
- **Qt:** Cross-platform but on Windows, it still uses WinAPI behind the scenes.
- **Tkinter:** Python's Tk toolkit wraps around WinAPI for window management and events.
- **Electron:** Runs on Chromium and Node.js, but for windowing and events, it depends on WinAPI concepts on Windows.

In short, even though these frameworks make things easier, they all tap into the same underlying Windows mechanisms.

## **InvalidateRect**

A function in Windows programming that adds a rectangle to a window's update region, signaling that the **specified area needs to be redrawn**. It doesn't immediately trigger a repaint, but rather **accumulates changes** to be processed later when a **WM\_PAINT message** is sent or when **ValidateRect** is called. The **ValidateRect function** removes a rectangle from the update region, essentially marking it as already redrawn.

```
BOOL InvalidateRect(
    [in] HWND      hWnd,
    [in] const RECT *lpRect,
    [in] BOOL      bErase
);
```

#### ➊ Key parameters:

- ✓ **hWnd:** A handle to the window to invalidate.
- ✓ **lpRect:** A pointer to a RECT structure defining the rectangle to invalidate, or NULL to invalidate the entire client area.
- ✓ **bErase:** A boolean indicating whether to erase the background of the invalidated area.

#### ➋ Return value:

```
// Example usage:  
RECT rectToInvalidate = {10, 10, 50, 50};  
InvalidateRect(hwnd, &rectToInvalidate, TRUE); // Invalidate the rectangle and erase the background
```

This doesn't paint instantly — it **adds a WM\_PAINT to the message queue**. Windows will call you back soon to handle it. This may feel like you're giving up control — but trust, it's for the better.

You're now coding in a way that's clean, predictable and works with the OS, not against it.

Structured drawing = stable apps.

Let the OS decide **when** to paint. You (your program) just decides **what** to paint.

## ❖ Valid vs Invalid Regions — What's Dirty?

### ▀ Invalid Region

An **invalid region** is just a part of your window that needs to be redrawn because something changed there.

Windows keeps track of it silently in the background.

The moment you:

- *Resize your window*
- *Uncover a hidden section e.g. previously covered by dialog boxes and other windows.*
- *Invalidate a rectangle yourself, Boom — that region becomes "invalid."*

As soon as one of these things happens, Windows immediately marks that region as "invalid" — meaning it needs to be redrawn.

 You don't need to memorize this. Just remember:

**No WM\_PAINT = No invalid region = No redrawing.**

*That means, If Windows doesn't send a WM\_PAINT message, it means nothing needs to be redrawn, because no invalid regions have been marked.*

---

### **Valid Region**

After you **handle the WM\_PAINT message** (which means you've drawn the content that needed updating), you **call EndPaint()** to tell Windows that you're done with the drawing.

When you do that, **the invalid region is cleared** — meaning the part of the window that needed a redraw is now considered **valid** again.

- **Valid region** = No more painting needed for this part until something changes again (like resizing or uncovering it).
  - When you finish painting, your window has a **clean slate**: everything that needed updating is now updated, so there's nothing left for the system to redraw until something changes again.
- 

### **In simpler terms:**

- **Before you paint:** The area of the window that needs updating is marked as **invalid** (it needs to be redrawn).
- **After you paint:** Once you finish drawing and call EndPaint(), the system **clears the invalid region**, and that part of the window is now considered **valid** again. Windows won't ask you to repaint that area until the next time it needs to change.

So after handling WM\_PAINT and calling EndPaint(), **there's no more redrawing needed until something else happens** to make the window "invalid" again.

## ⚠️ Forcing Repaints (When You Gotta Break the Flow)

Sometimes, you can't wait for Windows to decide when to repaint — you need an immediate update to reflect some change in your UI, like when a button changes state or something dynamic happens that needs to be shown right away.

You can:

1. Invalidate the entire client area (the whole window):

```
InvalidateRect(hwnd, NULL, TRUE); // Mark the entire client area as dirty
```

OR

2. Invalidate just a specific region that needs to change:

```
// Example usage:  
RECT rectToInvalidate = {10, 10, 50, 50};  
InvalidateRect(hwnd, &rectToInvalidate, TRUE); // Invalidate the rectangle and erase the background
```

## 🎨 The Paint Information Structure: Windows' Dirty Canvas Tracker

Whenever Windows tells you "Hey! Redraw this area!" via WM\_PAINT, it's not just shouting into the void —

It quietly hands you a **little bundle of info** behind the scenes: the PAINTSTRUCT.

This structure is what Windows uses to manage repainting — it's like a "painting invoice" saying:

*"Here's what needs redrawing. Here's the rectangle. Go crazy, but only inside this box."*

## PAINTSTRUCT — The Real Deal Struct

Here's what it looks like under the hood (from <windows.h>):

```
typedef struct tagPAINTSTRUCT {
    HDC hdc;           // Handle to device context for painting
    BOOL fErase;       // Non-zero if background should be erased
    RECT rcPaint;     // The smallest rectangle that needs to be painted (invalid area)
    BOOL fRestore;     // Reserved; used internally
    BOOL fIncUpdate;   // Reserved; used internally
    BYTE rgbReserved[32]; // Reserved
} PAINTSTRUCT;
```

### HDC hdc

Handle to Device Context — this is your **drawing tool**.

Comes from BeginPaint() and lets you draw directly onto the window.

### BOOL fErase

Tells you whether Windows wants the **background cleared** before drawing.

If TRUE, you might want to call FillRect() to repaint the background.

Windows often sets this to TRUE if it thinks leftover graphics are around.

### RECT rcPaint

The **exact rectangle** that Windows has marked as invalid. This is the region your app *should* repaint. Ignore the rest. This is your **scope**, your **mission zone**, your **red zone**. Don't go repainting the entire window unless this says so.

### BOOL fRestore, fIncUpdate, BYTE rgbReserved[32]

**Ignore these.** They're internal stuff for the OS.

Legacy or reserved — don't touch unless you're writing your own OS (and if you are, I bow to you 😊).

## Real-World Use

In practice, this is how you use PAINTSTRUCT:

```
case WM_PAINT:  
{  
    PAINTSTRUCT ps;  
    HDC hdc = BeginPaint(hwnd, &ps); // Starts painting, gives you HDC and rcPaint  
  
    // Use ps.rcPaint to know what part to update  
    FillRect(hdc, &ps.rcPaint, (HBRUSH)(COLOR_WINDOW+1)); // Just a simple fill example  
  
    EndPaint(hwnd, &ps); // Clean up. Mark area as valid again.  
    return 0;  
}
```

This is **how you stay efficient**.

No wasted redraws. Just precision.

---

## Recap Time

- PAINTSTRUCT holds everything you need during a repaint.
  - You get it from BeginPaint(), and pass it to EndPaint().
  - Its rcPaint member tells you *exactly* what needs redrawing.
  - Only repaint that region — keeps your app responsive and slick.
- 

This paint pipeline is foundational in **any GUI Windows app** — get this down, and the rest builds on it.

Hit me with the next part. We're moving like pros now. 🔥💻

## ❌ Invalid Rectangle Updates — No Duplicate Paint Chaos

### What Happens If New Damage Occurs Before You Paint?

Imagine this:

1. A part of your window becomes “damaged” — say, something was moved, resized, or revealed.
2. Windows sends you a WM\_PAINT, saying: “Yo, redraw this bit here.”
3. **But you haven’t handled that paint message yet.**

Then boom — **another part** of the client area gets damaged **before you even start painting**.

### ❗ So... What Does Windows Do?

Instead of flooding your message queue with **multiple WM\_PAINTs**, Windows gets slick:

- It **combines** all the damaged regions into a single **invalid region**.
- It recalculates the **invalid rectangle (rcPaint)** to cover **both areas**.
- The original paint info (PAINTSTRUCT) is updated to reflect the **new, larger zone**.
- Still **just one WM\_PAINT** message in the queue for your window.

## Efficient Like a Pro

This is done to **optimize performance** and reduce flickering or redundant painting.

Even if more parts get messed up while you’re procrastinating the WM\_PAINT, Windows patiently waits, **bundles all the junk**, and **sends one big cleanup mission** when you’re finally ready to paint.

## Real World Analogy

Think of it like a housekeeper:

If they see one cup on the floor, they’re about to clean it... but before they do, someone knocks over a plate too.


Rather than running back and forth for each mess, they wait, see it all, and **clean everything in one go**. That’s Windows.

## Gotchas and Tips

- **Never assume** `rcPaint` only covers the original damage. Always check it fresh when handling `WM_PAINT`.
- **Don't try to queue multiple `WM_PAINTs`** — Windows *won't* let you. Just use `InvalidateRect()` again, and it'll expand the region.
- **Efficiency is the name of the game** — only paint the invalid region, not the whole window, unless needed.

---

This is **paint region management 101** — it's all about letting Windows juggle those rectangles so you don't have to.



## Invalidating Rectangles — Manually Saying “Repaint This!”

### What's the Deal?

Sometimes your app changes something — maybe some data updates, or a UI element needs refreshing — but **Windows doesn't know that**. So, **you** have to tell Windows:

“Hey, this rectangle right here? It's dirty. Needs repainting.”

You do that with:

```
InvalidateRect(hwnd, &rect, TRUE);
```



## What It Does

- Marks the specified rect in the **client area** as invalid (or the **entire client area**, if rect is NULL).
- Doesn't immediately redraw.
- Instead, it **queues a WM\_PAINT message** — but **only if** one isn't already waiting.

If there's already a WM\_PAINT in the queue?

Windows just updates the invalid region — no duplicate message. Efficient AF.

---



## Example

Say your app has a button that changes text on the screen. You'd do something like:

```
InvalidateRect(hwnd, NULL, TRUE); // Repaint the whole client area
```

Or target a specific zone:

```
RECT updateArea = { 20, 20, 200, 50 };
InvalidateRect(hwnd, &updateArea, TRUE);
```

Boom 💥 — the system goes:

“Okay, I'll send WM\_PAINT soon — this region needs some fresh perfume.”

---

## Retrieving the Invalid Rectangle Coordinates

So now you get WM\_PAINT — how do you know **which part** to repaint?

### 1. Inside the WM\_PAINT handler

When you do:

```
PAINTSTRUCT ps;  
HDC hdc = BeginPaint(hwnd, &ps);
```

You get ps.rcPaint — that's your **invalid rectangle**. That's what you repaint.

### 2. Outside WM\_PAINT? Use GetUpdateRect()

Maybe you're not inside WM\_PAINT, but you're curious what needs repainting.

You can call:

```
RECT rect;  
BOOL hasInvalid = GetUpdateRect(hwnd, &rect, FALSE);
```

- If hasInvalid is TRUE, there's a region that needs repainting.
- rect will hold its coordinates.

**Don't use this during actual painting though** — just a heads-up check.

## Final Thoughts

In summary:

**InvalidateRect:** This function manually marks part or all of the window as "dirty" (i.e., needing to be redrawn).

**Windows queues a WM\_PAINT message:** If there isn't already a WM\_PAINT message queued, it adds one. If there's already a queued WM\_PAINT, it simply updates the invalid region.

**BeginPaint()**: When handling the WM\_PAINT, BeginPaint() provides you with rcPaint, which tells you the exact region that needs to be repainted.

**GetUpdateRect()**: This function gives you the invalidated region outside of the painting process — helpful if you need to know what needs repainting without triggering the paint cycle.

---

## Real World Analogy

Think of it like telling a janitor:

*"This aisle is dirty — add it to your list." (InvalidateRect)*

If he's already planning to clean it, just update his list.

When he shows up to clean (WM\_PAINT), he brings a clipboard (rcPaint) to show exactly what areas need to be cleaned.

## Validating Rectangles — Marking Areas as "All Good"

Windows sends a WM\_PAINT message when it thinks a part of your window needs to be redrawn.

But what if your app's like:

*"Yo, I'm good. No need to repaint this."*

That's where ValidateRect() comes in.

```
ValidateRect(hwnd, &rect);
```

## This tells Windows:

"This rectangle? It's already fresh. No need to send a WM\_PAINT for it."

- If you pass **NULL** as the rect, it means you're telling Windows that **the entire client area** is valid and doesn't need any redrawing.
  - If a **WM\_PAINT** message is already in the queue and the validated area fully covers the invalid region, Windows will **cancel** that WM\_PAINT because it thinks everything is good now. It's like telling Windows, "Forget that repaint request; everything's fine."
- 

## When Does This Happen?

### 1. Automatically after BeginPaint():

When you call `BeginPaint()`, Windows automatically marks the invalid region as valid.

```
PAINTSTRUCT ps;  
HDC hdc = BeginPaint(hwnd, &ps);
```

**What happens:** You start painting, and Windows automatically assumes the invalid region is taken care of. It's like saying:

- **You:** "I'm painting now."
- **Windows:** "Okay, I'll consider that area cleaned up, no need to worry about it anymore."

You usually **don't need to manually validate** inside the WM\_PAINT message because `BeginPaint()` already does this for you.

## Manually with ValidateRect():

If you want to skip repainting or let Windows know that **nothing needs to be redrawn**, you can use ValidateRect() manually.

For example:

- To validate the whole window (mark it all as good):

```
ValidateRect(hwnd, NULL); // The entire client area is now valid
```

- Or to validate a specific region (like part of the window):

```
RECT cleanZone = {100, 100, 200, 200};  
ValidateRect(hwnd, &cleanZone);
```

## Why would you do this?

You might want to do this if there's a **false alarm** (like an event that looks like it needs repainting but doesn't) or if the **visuals didn't actually change**. This can **stop a pending WM\_PAINT** or **prevent a new one from being queued**.

---

## Summary:


- *ValidateRect() tells Windows, "This area is fine, no need for repainting".*
- *After BeginPaint(), Windows automatically validates the region you're painting, so no need to call ValidateRect() in most cases.*
- *You can manually call ValidateRect() to stop or clear a WM\_PAINT if you don't actually need to redraw anything.*

This section is about **telling Windows to stop worrying about certain parts of the window**, so it doesn't waste time or resources sending unnecessary WM\_PAINT messages.

## INTRODUCTION TO GDI

The **Graphics Device Interface (GDI)** is a set of functions provided by Windows for drawing text, graphics, and other visual elements on the screen.

To paint the client area of your window, you'll utilize these GDI functions (text, lines, shapes, even bitmaps).



**(Read this carefully, you'll meet these everywhere!)**

**HWND: Handle to a Window (Your Window's ID Tag)**

In the world of WinAPI, HWND is your **window's unique identity**.

Think of it like:

- *A username for your window.*
- *Or better — a pointer to your window's profile in memory.*



Whenever you create a window, Windows gives you an HWND —

This is a **handle** — or a **number-like ID** that points to an internal structure inside the OS containing:

-  Size
-  Position
-  Visibility
-  Styles
-  Input
-  Owner relationships
-  ...and more

That **structure tracks everything** about your window: size, position, visibility, input, styles, ownership... the whole deal.

### Easy Analogy: The “Human Hand” Metaphor

HWND = "hand to the window"

- Want to **move** the window? Use MoveWindow(hwnd, ...)
- Want to **resize**? SetWindowPos(hwnd, ...)
- Want to **show or hide** it? ShowWindow(hwnd, SW\_SHOW)
- Want to **send a message**? SendMessage(hwnd, WM\_CLOSE, ...)

If you don't have the HWND, you've got **no way to talk to the window**.

### How Windows Thinks Behind the Scenes

Every window lives somewhere in memory.

The HWND is like a **map pin** that tells the OS,


*“Yo, that window you created earlier? Yeah, it lives here.”*

 When you drag, resize, or close a program like Word:

- You're interacting with a GUI layer.
- Under the hood, the OS uses the HWND to locate that window's internal data.
- That data includes instructions (from your program's code) on how it should react.

## So Why Do We Care?

Every serious WinAPI function starts by asking:



It's like showing your ID card at the door. **No HWND? No access.**

- *Draw inside the window?*
- *Resize it?*
- *Send it a message?*

You better have that HWND — it's your ID badge.

Even message processing (WndProc) is tied to your HWND — Windows routes messages to the correct window **using its HWND**.

### TLDR:

- *HWND is the handle (ID) that uniquely represents a window. It's the address of the house.*
- *The OS uses it to find and manage that window's memory and behavior.*
- *Without it, you can't interact with the window using WinAPI.*

## 🟡 🟢 **HDC: Handle to Device Context (Your Drawing Toolkit)**

**Meet HWND's younger brother: HDC** - He's the artist, the technician, the graffiti guy painting walls all day, while HWND handles the business side of windows things.

If HWND is the **address of a house**, then HDC is your **access pass** to paint the walls inside it, to the **drawing tools** and **space** inside that window.



**HDC stands for Handle to Device Context.**

It's the **identifier** you use when you want to draw on the window.

It gives you access to a **drawing environment**:

- Text
- Shapes
- Lines
- Bitmaps
- Anything GUI-related

Think of it as a "**key**" that **unlocks the drawing surface**, allowing your program to interact with the graphical environment of that window.

## How Windows Thinks About HDC:

- ◆ “Okay, Nick made a window — here’s the HWND.”
- ◆ “Oh he wants to draw now? He called GetDC()? Cool.”
- ◆ “Here’s an HDC for that window’s drawable surface.”
- ◆ “But he better return it later... GDI is *not* unlimited.”

## HDC = Surface + Settings

It’s not just a canvas — it’s the full drawing setup:

-  Target: screen, printer, bitmap, etc.
-  State: pen, brush, font, color
-  Transform: where/how drawings appear

Windows tracks this under the hood — and HDCs are not cheap.

That’s why functions like BeginPaint() or GetDC() give you one, and **you must release it** when done:

```
HDC hdc = GetDC(hwnd); // Step 1: Get access to the window's drawing surface  
// ... perform drawing operations ...  
ReleaseDC(hwnd, hdc); // Step 2: Release the access to the drawing surface
```

- *Give me access to the drawing surface for this window.*
- *The OS provides you with an HDC, which represents the drawing environment for that window.*
- *It’s like receiving an access pass to interact with the window’s graphical content.*
- *With this HDC, you can start using various drawing functions (like TextOut(), MoveToEx(), LineTo(), etc.) to draw on the window.*
- *Once you’re done with the drawing operations, you call ReleaseDC(hwnd, hdc) to release the HDC back to the operating system.*
- *You’re telling the operating system, “I’m done using the drawing surface for this window.”*

## What Actually Happens When a Window is Created?

When you launch your app and create a window, the OS does **not** draw your content for you. Here's what really goes down:

---

### Step 1: The Shell is Born

When you call something like CreateWindowEx():

- Windows allocates memory and resources.
- It builds the *structure* of the window (size, borders, style, etc.).
- It gives you back the HWND.

But that's it.

Your window now **exists...**

*...but it's empty inside. Blank. A white void.*

Think of it as: An apartment with walls, doors, and lighting, but no furniture, no paint, no posters — just a shell.

---

### Step 2: You (the Program) Must Do the Painting

Now Windows says:

*"Hey, this window needs something to show — I'll send a WM\_PAINT message."*

At that point:

- You handle WM\_PAINT in your WndProc.
- You call BeginPaint() to get an HDC.
- Now you have access to **drawing tools**: pens, brushes, fonts, etc.

Your program is now responsible for:

- Painting text with TextOut()
- Drawing shapes
- Rendering bitmaps
- Laying out UI elements

Nothing shows up unless **you** draw it with GDI.

## The OS Just Gives You Tools — You Do the Work

Let's reframe the big picture:

 The OS is like a huge construction company.  
It builds the **outer frame** of your app window (via HWND).  
But when it comes to **furnishing and decorating** (what the user sees inside),  
That's your job — and the only way in is through HDC.

You don't draw stuff **anytime** you want — you draw **when Windows tells you**, during the WM\_PAINT cycle. And you use the HDC it hands you.

---

### TLDR Recap:

- *When a window is created (via HWND), it starts off completely blank.*
- *The OS gives you access to the drawable surface (via HDC).*
- *Your program draws the actual GUI using GDI functions like TextOut(), Rectangle(), etc.*
- *Nothing visible happens unless you handle painting during WM\_PAINT.*

 This is critical background that makes the **entire paint cycle** make sense. Leave this in your notes exactly where it is — just tighten the formatting, and maybe even call it:

### Common Misunderstanding:

"I created a window... why isn't anything showing up?"

→ Because you haven't painted anything yet, chief. Windows gave you the space — now pick up the brush.

**Whenever you're ready, we can dive into:**

- WM\_PAINT lifecycle
- PAINTSTRUCT
- BeginPaint vs GetDC
- and how GDI fits into all of it like clockwork.

*Finally, let's close out this discussion on HWND and HDC.*



## HWND vs HDC — Brothers From the WinAPI Womb

- **HWND = the handle to your window.**  
It's like a **home address**. It tells the OS, "Yo, this is where the window lives." It identifies *what* you want to draw on, manage, move, minimize, etc.
  - **HDC = the handle to device context.**  
It's like a **toolbox + canvas**. Once you have the window (HWND), HDC is how you say,  
*"Okay, give me the brush and let's start painting."*
- 



## Under the Hood (How Windows Thinks)

Windows separates the *what* (the window itself) from the *how* (the tools used to draw into it):

- The **OS gives you the HWND** so it can manage windows, events, messages, and layout.
- The **OS gives you HDCs** so you can draw to surfaces — whether that's a screen, a printer, or an in-memory bitmap.

This separation is deliberate and powerful. Imagine HWND as the **body** and HDC as the **painted clothes, tattoos, or makeup** you apply with care.

---



## True Statement Recap

**"While HWND is the handle that identifies your window, HDC is the handle that provides the drawing tools and the canvas inside that window."**

That's **absolutely correct** and beautifully put. Keep that line — it slaps both technically and poetically.

---

## Final Reminder: Don't Be this Guy

Once you're done with drawing, release stuff:

```
EndPaint(hwnd, &ps); // Or ReleaseDC(hwnd, hdc);
```

Because...

### Forget to release? You leak GDI objects. Windows *will* retaliate.

- **HWND** → The **address** of the window (the "building").
- **HDC** → The **drawing tools and surface** inside the window (your "blueprint & brushes").
- You get an HDC via GetDC() or BeginPaint().
- You release it via ReleaseDC() or EndPaint().

**We're done with HDC and HWND, now we head back to GDI topic.**

## TextOut: A Versatile Text Output Function

Windows offers several GDI functions for writing text to the client area, but the most commonly used is undoubtedly TextOut.

```
BOOL TextOut(
    HDC hdc,          // device context (where to draw)
    int x, int y,     // position on screen (in pixels)
    LPCSTR psText,   // pointer to the text string
    int iLength       // number of characters to draw
);
```

or

```
BOOL TextOut(HDC hdc, int x, int y, LPCSTR psText, int iLength);
```

The function prints a string of text at position (x, y) in the client area.

### Simple enough — just give it:

- A valid DC (handle to a drawing surface) - that just means asking Windows for the tools (pens, brushes, etc.) and the surface (where to draw) so your app can actually put pixels on the screen."
- The coordinates (where the text begins),
- A string to draw, and
- How many characters to draw.

## Pro Tip:

If you pass **strlen(yourString)** as **iLength**, you won't need to count chars manually. I know that's sorcery, you didn't hear nothing. 😎 Welcome to C.



That line's a **mic-drop tip** for using text functions like `TextOut()` or `DrawText()` in WinAPI where you have to **tell Windows how many characters you're printing**.

Say you've got this:

```
char* myMessage = "Hello, Windows!";
TextOutA(hdc, 10, 10, myMessage, ???);
```

That last parameter is asking:

*"How many characters should I draw?"*

You **could** count manually like a caveman:

```
TextOutA(hdc, 10, 10, myMessage, 15); // hardcoded 💀
```

But then you change the message... and forget to change the length... and now your app is drawing random garbage or cuts off early.

### Pro tip to the rescue:

```
TextOutA(hdc, 10, 10, myMessage, strlen(myMessage));
```

Now C counts the characters **automatically**, right before passing it to TextOutA() — no typos, no mental math, no pain.

---

### Gotchas:

- Make sure the string is **null-terminated** (\0), or strlen() might run off into memory madness.
- Don't use strlen() if you're drawing only **part of the string** (like just the first 5 letters). Use 5 directly in that case.

**strlen(yourString)** = C doing the counting for you

 Clean, automatic, no guesswork

---

### Bonus bar for our notes:

```
// Pass strlen(msg) to Textout() if you want C to count the characters for you.  
// No need to hardcode lengths manually.  
// Just make sure msg is null-terminated.
```

Don't count characters manually — just pass `strlen(yourText)` for `iLength`.

```
TextOut(hdc, x, y, psText, iLength);
```

- **psText:**  Pointer to the string you wanna draw.
- **iLength:**  How many characters to draw (not bytes, chars).
- **x, y:**  Where to start drawing (top-left of the text).

 **Pro Tip:** Don't count characters manually — just pass `strlen(yourText)` for `iLength`.

## **The Device Context (DC): Your Drawing License**

- `hdc` stands for **Handle to Device Context** ([We discussed this in great depth](#)).
- It's your *entry ticket* to draw on screen.
- Without it? You're basically drawing in the void — Windows won't know where, how, or even **why** you're drawing.

## **What is a Handle?**

A handle is just an ID — like a number — that Windows gives you to represent a GDI object (in this case, the DC).

## 💡 What is the DC?


Think of the **Device Context** as a *temporary canvas* managed by GDI.

It's a **data structure** maintained internally by GDI.

It's associated with a **specific display device**, such as a monitor or a printer.

For a **video display**, the DC is typically linked to a particular window on the screen.

- It knows where you're drawing (your app's window).
- It tracks drawing settings: pens, brushes, fonts, colors, etc.
- It's specific — could be the screen, a printer, or even a bitmap in memory.



## 🧠 Analogy Time:

Imagine you walk into a **government office (Windows)**. You want to paint something. You have to:

1. Ask permission (BeginPaint()).
2. Get a painting license (hdc).
3. Use the license to draw on the assigned wall (your window).
4. Return the license when done (EndPaint()).

If you forget to return it?

💣 You're leaking GDI objects and Windows **will get mad**.

## **Bottom Line**



## **Always:**

- Get a valid hdc before calling any GDI drawing function.
- Use TextOut() with valid strings and positions.
- Return the hdc if you got it from BeginPaint() or GetDC().

*Boom. That whole section is now screen-friendly, visually layered, and stupidly readable for anyone — even if they're running on 2 hours of sleep and 3 cups of tea.*



## 💡 GRAPHICS ATTRIBUTES: DEFINING THE LOOK AND FEEL

The DC contains various values known as graphics attributes, which determine how GDI drawing functions operate.

In the past, we said the DC is just a **permission slip** or **ID** to draw, but:

- ❖ ***it's also a whole profile of how your drawings will look.***

For instance, in the case of TextOut, these attributes specify the text color, background color, font to use, and how the x and y coordinates from the function are mapped to the client area.

### 💡 The DC holds "graphics attributes"—

These are basically **style settings** for everything you draw.

When you call TextOut(...), GDI checks these attributes to decide:

- What **color** the text should be
- What **background** (if any) to fill behind it
- Which **font** to use
- And how **your (x, y) coordinates** map to the actual screen area

You don't pass these in directly each time—they're baked into the DC.

If you want to change how text or shapes appear, you update these **DC attributes** first.



## Acquiring and Releasing the Device Context Handle

Before any drawing happens, your app must **request a handle** to the device context. This is the **hdc**—your VIP pass into the GDI club.

❖ When you request it (e.g. via BeginPaint() or GetDC()),

Windows initializes the DC with **default settings** like:

- Black text
- White background
- System default font

You can override any of these defaults using GDI functions:

```
SetTextColor(hdc, RGB(255, 0, 0));      // Red text
SetBkMode(hdc, TRANSPARENT);           // No background fill
SelectObject(hdc, hFont);              // Use a custom font
```

## 🔒 Releasing the Handle: Clean-Up Matters

Once you're done drawing, **you must release the DC handle**.

Failing to do this is like leaving your brush in the paint can—messy and bad practice.

⌚ Releasing the DC:

- Frees up system resources
- Marks the handle as invalid so it can't be reused accidentally
- Prevents **resource leaks**, especially in loops or frequent messages

## 💥 Golden Rule:

Unless you're using a *persistent* DC from CreateDC() (advanced stuff), you should **acquire and release the handle within the same message cycle**.

 **OK:**

```
case WM_PAINT:  
    hdc = BeginPaint(hWnd, &ps);  
    TextOut(hdc, 10, 10, "Hello", 5);  
    EndPaint(hWnd, &ps);  
    break;
```

*In this example, you only use the HDC within the scope of the WM\_PAINT message. This means the HDC is created and released inside the same block of code where it's needed, so it's managed properly.*

*EndPaint(hWnd, &ps) automatically cleans up and releases the HDC after painting is done. No HDC is left hanging around, and memory/resources are freed correctly after painting.*

*Releasing the handle `invalidates` it and prevents its further use.*

*The program should acquire and `release the handle` within the processing of a single message.*

*With the exception of a DC created using the `CreateDC` function, which is beyond the scope of this chapter, you should not maintain a DC handle between messages.*

 **Bad:**

```
// Global hdc retained between messages – DO NOT DO THIS  
hdc = GetDC(hWnd); // Called once, never released
```

*Global or persistent use of an HDC (like keeping it across multiple messages or function calls) is a bad idea because you never release the HDC with `ReleaseDC`.*

*The HDC represents a drawing surface that can be tied to OS resources. If you don't release it properly, those resources remain allocated or held, causing performance and memory issues.*

### Summary (Sticky Notes Style):

- DC holds *style info* (color, font, etc.)
- Get a DC → draw → release it (cleanly!)
- Don't hoard DC handles between messages—only use them while painting
- Use SelectObject, SetTextColor, etc., to *customize the DC*

## COMMON METHODS FOR OBTAINING A DEVICE CONTEXT HANDLE

Windows applications generally employ two methods to obtain a DC handle for screen painting.

### Using BeginPaint:

To draw on a window, you need a Device Context (DC) — like getting a brush and canvas before painting.

The BeginPaint function **retrieves the DC handle** for the window and prepares it for painting. This function should be called at the beginning of the WM\_PAINT message processing.

```
hdc = BeginPaint(hwnd, &ps);
```

- It prepares the drawing surface (the device context (HDC)) for your program to use.
- It validates the "dirty area" (called the invalid region) of the window that needs repainting. This tells Windows that you're handling the WM\_PAINT request and you're ready to paint.

### Think of it as:

*"Hey Windows, I'm ready to repaint the part you said needs redrawing!"*

 Always pair it with:

```
EndPaint(hwnd, &ps);
```

## 🟡 Using GetDC — For Anytime Drawing

```
hdc = GetDC(hwnd);  
...  
ReleaseDC(hwnd, hdc);
```

✓ You can use this **anywhere**, not just inside WM\_PAINT.

✓ Use **anytime** (e.g. mouse clicks, timers).

Perfect for drawing things when **you decide**, like during a mouse event or button press.

🧠 Think of it as:

*"I want to draw now — hand me the brush!"*

## ⚠️ Important Tips

- ⚡ Always release the DC after you're done, or you'll leak GDI resources — like leaving a paintbrush stuck in a wall.
- ❌ Never hold onto a DC handle across multiple messages unless you created it with CreateDC (advanced stuff).

```
ReleaseDC(hwnd, hdc);
```

## Method One: Acquiring a Device Context Handle with BeginPaint and EndPaint

### Painting with BeginPaint and EndPaint – The **WM\_PAINT** Ritual

When your window needs a fresh coat of pixels, Windows doesn't just guess — it **sends a WM\_PAINT message**. That's your cue to step in and repaint the damaged (invalid) portion of your window.

And the *only* legit way to respond to this sacred call is by using BeginPaint and EndPaint.

---

### **BeginPaint** – Enter the Drawing Arena

**BeginPaint:** Preparing for Painting

```
PAINTSTRUCT ps;  
HDC hdc = BeginPaint(hwnd, &ps);
```

The program utilizes various GDI functions, such as TextOut, to draw on the client area using the acquired device context handle.

What it does:

-  **Erases the background** if necessary. If CS\_HREDRAW or CS\_VREDRAW is set in your window class, the area gets wiped clean before your brush hits it.
-  **Fills a PAINTSTRUCT** which includes:
  - ✓ The HDC (device context handle).
  - ✓ The rectangle that needs repainting (rcPaint).
  - ✓ Some extra state info (like whether background erasure was done).
-  **Returns a valid HDC**, scoped only for this paint cycle.

**Note:** This HDC is **only valid within WM\_PAINT**, and only between BeginPaint and EndPaint.

## Use That HDC to Paint Stuff

Once you've got the HDC, let the art begin:

```
TextOut(hdc, 10, 10, TEXT("Hello WinAPI"), 12);
Rectangle(hdc, 20, 40, 150, 100);
// Or any other GDI function
```

This is your moment. Draw only what's in ps.rcPaint, if you want optimal performance. Don't repaint the whole window unless you really must.

---

## EndPaint – Close the Ceremony

```
EndPaint(hWnd, &ps);
```

It validates the previously invalid region, indicating to Windows that the repainting is complete.

## What If You Skip BeginPaint/EndPaint?

Bad things happen:

-  You **don't get a valid HDC** → GDI functions may fail or act weird.
-  **WM\_PAINT keeps firing in a loop**, because Windows thinks the area is still dirty.
-  Your app becomes a CPU-burning mess.

 If you're using GetDC() inside WM\_PAINT — **that's wrong**. That's not the proper ritual. Only BeginPaint prepsthe right context for this scenario.



## Real-World Flow: WM\_PAINT Handler

```
case WM_PAINT: {
    PAINTSTRUCT ps;
    HDC hdc = BeginPaint(hWnd, &ps);

    // ✓ Drawing using GDI
    TextOut(hdc, 10, 10, TEXT("WM_PAINT in action!"), 21);

    EndPaint(hWnd, &ps);
    return 0;
}
```



## Summary – Respect the Painting Ritual

Step	Purpose
BeginPaint	Erases background, gives you HDC
GDI drawing	You do your magic
EndPaint	Validates region, releases HDC

👉 This pattern is non-negotiable. It's how you stay in harmony with the message loop gods.

## DEFAULT WM\_PAINT HANDLING: WHO PAINTS IF YOU DON'T?

If your window procedure doesn't handle the WM\_PAINT message, Windows ain't just gonna sit and cry — it passes the torch to the **default window procedure**, DefWindowProc.

### What does DefWindowProc do?

It calls BeginPaint and EndPaint internally, making sure the invalid region is validated.

It takes care of basic cleanup, but won't draw custom stuff for you.

So yeah, your fancy rectangle won't draw unless you step in.

---

### Your Job: Handle WM\_PAINT Properly

Use this standard pattern inside WndProc when uMsg == WM\_PAINT:

```
case WM_PAINT:  
{  
    PAINTSTRUCT ps;  
    HDC hdc = BeginPaint(hWnd, &ps); // ↗ Get a valid device context (DC)  
  
    // ✓ You now have permission to draw on the window's client area  
    // Let's draw something basic, like a rectangle  
  
    Rectangle(hdc, 10, 10, 110, 110); // Draw a 100x100 black rectangle  
  
    EndPaint(hWnd, &ps); // ↗ Must call this! Releases the DC and validates region  
    return 0;  
}
```

## Breakdown of the Flow:

- **BeginPaint()**
    - 👉 Gives you a special HDC that's valid only during WM\_PAINT
    - 👉 Also erases background automatically (unless you tweak it)
  - **GDI Drawing (like Rectangle, TextOut, etc.)**
    - 👉 Now you can do your painting magic here
  - **EndPaint()**
    - 👉 Closes the painting session
    - 👉 If you don't call it, **you're leaking GDI objects** (and Windows *will* throw shade eventually)
- 

## Pro Tip:

If you're inside WM\_PAINT, **always use BeginPaint**, not GetDC.

Why? Because GetDC doesn't handle invalid regions or cleanup properly in this context.

## PAINTSTRUCT STRUCTURE IN DEPTH

The PAINTSTRUCT structure, referred to as "**paint information structure**".

It holds essential information about the painting process and is populated by Windows when the BeginPaint function is called.

```
typedef struct tagPAINTSTRUCT {  
    HDC hdc;           // Handle to the device context  
    BOOL fErase;       // Did Windows erase the background?  
    RECT rcPaint;     // Area that needs repainting (dirty rect)  
    BOOL fRestore;     // Reserved  
    BOOL fIncUpdate;   // Reserved  
    BYTE rgbReserved[32]; // Reserved  
} PAINTSTRUCT;
```

Whenever your **window needs repainting**, BeginPaint() returns more than just an HDC. It fills out a full PAINTSTRUCT — a structure with the info you need to paint smart, not dumb.

## Key Fields You Actually Use

```
ps.hdc      // the drawing canvas (device context)
ps.fErase   // true if Windows erased the background (rarely used)
ps.rcPaint  // RECT of the area needing a repaint
```

**hdc:** This field holds the handle to the device context (DC), which is a unique identifier for the window's drawing context.

**fErase:** This Boolean flag indicates whether Windows has already erased the background of the invalid rectangle. If TRUE (nonzero), the background has been erased.

**rcPaint:** This field is a RECT structure that defines the boundaries of the invalid rectangle. The values represent pixel coordinates relative to the client area's top-left corner.

## Where It Comes From

When you call BeginPaint(hWnd, &ps);, Windows:

- **Fills ps.rcPaint** with the dirty area (what needs redrawing).
- **Provides ps.hdc**, a special DC just for painting.
- Optionally **sets ps.fErase** if background erase was needed.

You then use this data to repaint **only what's needed**. It's efficient and avoids flicker.

## Real World Tip

 Check rcPaint to avoid repainting the whole window every time. Only redraw what's dirty.

## Example (Just the Paint Part)

```
case WM_PAINT:  
{  
    PAINTSTRUCT ps;  
    HDC hdc = BeginPaint(hWnd, &ps);  
  
    // Only redraw inside ps.rcPaint  
    Rectangle(hdc, ps.rcPaint.left, ps.rcPaint.top,  
               ps.rcPaint.right, ps.rcPaint.bottom);  
  
    EndPaint(hWnd, &ps);  
}  
return 0;
```

## Key Fields of PAINTSTRUCT

When the BeginPaint function is called, Windows fills in the relevant fields of the PAINTSTRUCT structure:

### Programmatic Access to PAINTSTRUCT Fields

## Programmatic Access to PAINTSTRUCT

The PAINTSTRUCT structure holds critical info Windows feeds you during a WM\_PAINT message. But guess what? Only **3 fields actually matter** for your program:

- **hdc** – the device context (DC) handle you'll use for drawing.
- **fErase** – tells you if Windows *wants you* to erase the background.
- **rcPaint** – the rectangle that needs repainting (in client-area pixels).

The rest? Internal Windows stuff. Don't touch it. Don't look at it. Don't even *breathe* on it.



## fErase: Should You Wipe the Background?

The **fErase** flag = background erasing helper.

This flag tells Windows whether to clear the background of a window before drawing new content.

- **TRUE (any non-zero value):** Windows says, "Hey, clean up this background for me." This means Windows will automatically erase the previous content, preparing a clean slate for your new drawing.
- **FALSE (0):** "No background erase needed, I got this." This tells Windows not to erase the background. You'll then be responsible for clearing or drawing over the old content yourself before painting new visuals.

```
InvalidateRect(hWnd, NULL, FALSE);
```

This line of code is telling Windows to mark a window (or part of it) as needing to be redrawn, but without erasing its background first.

**You'd use this when you want more control over how things are drawn, esp. for:**

- **Custom visuals:** When you're drawing something intricate and want to manage every pixel.
- **Faster redraws:** Skipping the background erase can sometimes make your application feel snappier, as it's one less step for Windows to perform.
- **Manual double-buffering:** This is a technique where you draw to an off-screen image first and then quickly display the complete image to avoid flickering. When doing this, you usually don't need Windows to erase the background, as you're replacing the entire content at once.

*In short, setting fErase to FALSE means you take on the responsibility of ensuring the window's background is correctly handled (e.g., drawing over it or clearing it) before you paint new elements.*



## rcPaint: What Area Needs a Fresh Coat of Paint?

**rcPaint** is a rectangle that Windows gives you. It marks the specific area of your window that is "dirty" and needs to be redrawn or "repainted."

- **It's a Rectangle:** This rcPaint is always a rectangular shape.
- **Pixel Coordinates:** The numbers defining this rectangle are in pixels.
- **Relative to Your Window:** These pixel coordinates are measured from the top-left corner of the *inside* part of your window (the "client area"), not the entire window including borders and title bar.
- **Your "Dirty Zone":** Think of rcPaint as your window's "dirty zone." It's the area Windows says, "Hey, this part changed, go update it!" Your job is to draw the correct content within this rectangle.

**This rectangle is also the clipping region:**

*Even if the actual invalid region is oddly shaped, Windows only lets you draw inside the rcPaint box. It's your drawing sandbox. If you try to draw outside it, Windows will cut off your drawing at the edges of rcPaint.* 

---



## Forcing a Full Repaint?

Need to repaint **everything**, not just a slice? This is how you tell Windows to do that:

```
InvalidateRect(hwnd, NULL, TRUE);
```

Let's look at what each part of that line means:

- **hwnd:** This is just the "handle" or ID for your specific window.
- **NULL:** When you put NULL here, it tells Windows: "Invalidate (mark as needing redraw) the entire inside area of my window, from top to bottom, left to right."
- **TRUE:** This tells Windows: "Before you redraw, please erase the background of the window first." This gives you a completely clean slate to draw on.

## When to use this (draw everything, erase background):

You'd use InvalidateRect(hwnd, NULL, TRUE); when:

- **The entire content of your window has changed.**
- **You want a completely fresh, clean canvas** to draw on, removing anything that was there before.
- **Something major happened, like the window was resized significantly or a large element moved**, and it's easier to just redraw everything than figure out specific "dirty" areas.

## What if you want to redraw everything but *keep the background as is?*

If you want to redraw the whole window but *don't* want Windows to erase the background for you (maybe because you're doing your own custom drawing/clearing), simply change TRUE to FALSE:

```
InvalidateRect(hwnd, NULL, FALSE); // Redraw everything, but DON'T erase background
```

## Summary:

When handling WM\_PAINT, PAINTSTRUCT gives you:

- **hdc** – your drawing tool
- **fErase** – erase or not
- **rcPaint** – where to draw (and only there!)

With these, you're painting like a pro. 

In summary, the PAINTSTRUCT structure serves as a vital information carrier during the painting process. It provides access to the device context handle, indicates whether background erasing is necessary, and defines the boundaries of the invalid rectangle, ensuring that your program paints efficiently and accurately.





Figure 4–1. The boundaries of the invalid rectangle.

**💡 Clipping Region Alert:** Even if the actual invalid region is complex or non-rectangular, Windows will still restrict your painting logic to the rectangle in rcPaint. Nothing gets drawn outside it.



## Pro Tip: To Redraw or Not to Redraw?

In theory, rcPaint lets you **only redraw what's "dirty"** — saving performance.

 **But in real-world GUIs?**  *Sometimes it's simpler and safer to just repaint the whole client area.*

 **Example:** *Let's say you're drawing a circle. If only half of it falls inside rcPaint, it's better to redraw the whole circle, not just the slice.*

 **Why?** *Because Windows will clip your drawing anyway — you don't have to worry about painting "too much." - It won't show outside the bounds.*

---

## Performance Consideration:

- For simple GUIs:  full repaint = easy + fast enough
- For complex UIs or disk-loaded content (like BMPs)?  
 You *should* respect rcPaint to avoid overdraw or file access. **Try to only redraw the rcPaint area.** This prevents wasting power by drawing things that are already visible or repeatedly loading large files.

## UNDERSTANDING DEVICE CONTEXT ATTRIBUTES

The **Device Context (HDC)** you get in WM\_PAINT or BeginPaint() isn't just a **drawing tool** — it's loaded with **style settings** that affect how text and graphics appear.

Let's cover the **main text-specific attributes** one by one:

### SetTextColor(hdc, COLORREF color);

- **Default:** Black
- **What it does:** Sets the color of the actual text glyphs.

```
SetTextColor(hdc, RGB(255, 0, 0)); // Red text
```

### **SetBkColor(hdc, COLORREF color);**

- **Default:** White
- **What it does:** Sets the **background color behind each character**, also called the "**character cell box**."
- **Only applies** if background mode is **OPAQUE** (default).

```
SetBkColor(hdc, RGB(255, 255, 0)); // Yellow background behind text
```

### **SetBkMode(hdc, TRANSPARENT or OPAQUE);**

- **OPAQUE (default):** Fills in the character box with the background color
- **TRANSPARENT:** Doesn't draw any background behind text — useful when drawing over complex backgrounds or images.

```
SetBkMode(hdc, TRANSPARENT); // No background fill behind text
```

## **Selecting Fonts with SelectObject()**

If you want to ditch the default system font and use your own:

1. You first **create a font object** using CreateFont() or CreateFontIndirect().
2. Then you **select it into the DC** using SelectObject().

```
HFONT hFont = CreateFont(
    20, 0, 0, 0, FW_BOLD, FALSE, FALSE, FALSE,
    ANSI_CHARSET, OUT_DEFAULT_PRECIS, CLIP_DEFAULT_PRECIS,
    DEFAULT_QUALITY, DEFAULT_PITCH | FF_DONTCARE,
    TEXT("Consolas")
);
SelectObject(hdc, hFont);
```

Boom — now your text is in **20pt bold Consolas**. Don't forget to delete the font later using `DeleteObject()` to avoid memory leaks.

### Pro Insight: Why This Matters

- Without setting these attributes, **all your text looks default**, basic, and identical.
  - Once you **start drawing dynamic content** (like syntax-highlighted code or UI widgets), styling becomes everything.
  - This is also **how themes and skinning** are built in GUIs — colors, fonts, modes... all via the DC.
- 

### Common Gotchas

Don't forget to **restore the old font** if you change it:


```
HFONT hold = SelectObject(hdc, hFont);
// ...
SelectObject(hdc, hold);
DeleteObject(hFont);
```

`SetBkColor()` won't *visually* do anything if `SetBkMode()` is `TRANSPARENT`.

## COORDINATE SYSTEM AND MAPPING MODES

### Logical vs. Physical Coordinates

When you tell Windows to draw something, like text at a certain spot, you might think you're picking an exact pixel on the screen. But you're usually not!



You're **NOT** saying: "Put 'Hello' exactly at screen pixel 50 across and 100 down."

Instead, you're saying: "**Place this text at logical coordinate (50, 100).**"

### So, what's a "logical coordinate?"

Think of logical coordinates as your *abstract drawing units*. They're like measurements on a blueprint, not the actual physical dimensions of the final product.


### Mapping Mode: The Translation Guide

The "mapping mode" is the crucial setting that decides how your "**logical units**" (like that '50' or '100') get translated into actual "**physical pixels**" on your screen, or dots on a printer, or whatever device you're drawing to.

- **It's like a scale:** If your mapping mode says "1 logical unit = 1 pixel," then (50, 100) *will* be pixel (50, 100).
- **But it can change:** If your mapping mode says "1 logical unit = 2 pixels" (e.g., for scaling up), then logical (50, 100) would end up at physical pixel (100, 200)!

This allows your **drawings to adapt** to different screen resolutions or printers without you having to change all your drawing coordinates manually. You draw in your logical world, and the mapping mode handles the real-world translation.

 **Mapping mode** = how logical units translate into actual device pixels (screen dots, printer dots, etc.)



## ⚙️ MM\_TEXT — The Default & Simple One

This is the mode Windows uses by default. It's like:

"Hey man, no need for translation, logical == physical. Just draw at (x, y) as pixels."

### Behavior of MM\_TEXT:

- (0, 0) is top-left of client area
- +X moves right
- +Y moves **down**
- Each logical unit = **1 pixel**

So this:

```
TextOut(hdc, 50, 100, L"Nick Was Here", 13);
```

↓ Literally means:

Draw the text starting **50 pixels from the left, 100 pixels down** from top.

```
// MM_TEXT is the default, but we can still be explicit:  
SetMapMode(hdc, MM_TEXT);  
TextOut(hdc, 100, 200, L"MM_TEXT mode", 12);
```

## Other Mapping Modes — Scaling Comes In

If you're printing, drawing in inches/mm, or zooming? You'll want other modes.

Here's some spicy ones:

Mapping Mode	Logical Units	Origin	Y Axis	Use Case
MM_TEXT	1 unit = 1 pixel	Top-Left	Down	Default screen drawing
MM_LOENGLISH	0.01 inch (low res)	Bottom-Left	Up	Inches, low precision
MM_HIENGLISH	0.001 inch (high res)	Bottom-Left	Up	Fine print graphics
MM_LOMETRIC	0.1 mm	Bottom-Left	Up	Metric stuff
MM_HIMETRIC	0.01 mm	Bottom-Left	Up	High-res metric
MM_TWIPS	1/1440 inch	Bottom-Left	Up	Typography, publishing

 In all modes *except MM\_TEXT*, the origin is **bottom-left**, and Y increases **upwards**.

- **Mapping Mode:** This is the specific setting you tell Windows to use. Each mode changes how your drawing commands (like TextOut(X, Y...)) are interpreted.
- **Logical Units:** This is the key! It tells you what one "unit" in your drawing code (e.g., if you draw at X=100, that 100 represents this many units) translates to in real-world measurements.

### MM\_TEXT (Default for Screens):

- This is the simplest and most common mode, especially for drawing directly on your computer screen. In MM\_TEXT, **1 unit in your drawing code is exactly equal to 1 pixel** on the screen.
- So, if you tell your program to draw a line 100 units long, it will be 100 pixels long. This makes it very easy to position things precisely on a pixel grid for typical screen-based applications.

### **MM\_LOENGLISH (Low-Res Inches):**

- Imagine you're designing something where you want to specify sizes in inches, but without needing super tiny precision. In MM\_LOENGLISH, **1 unit in your drawing code represents one-hundredth of an inch (0.01 inches)**.
- This means if you want to draw a shape that is exactly 1 inch wide, you would tell your program to draw it 100 units wide (because  $100 \text{ units} * 0.01 \text{ inches/unit} = 1 \text{ inch}$ ). It's great for drawings where general inch measurements are useful, like simple diagrams.

### **MM\_HIENGLISH (High-Res Inches):**

- This mode is similar to MM\_LOENGLISH, but it offers much finer detail when you're working with inches. In MM\_HIENGLISH, **1 unit in your drawing code represents one-thousandth of an inch (0.001 inches)**.
- So, to draw something exactly 1 inch wide, you'd specify 1000 units in your code (because  $1000 \text{ units} * 0.001 \text{ inches/unit} = 1 \text{ inch}$ ). This precision is crucial for professional graphics, detailed architectural plans, or when sending designs to high-resolution printers where every tiny fraction of an inch matters.

### **MM\_LOMETRIC (Low-Res Millimeters):**

- This is the metric version of MM\_LOENGLISH. If you prefer to work with millimeters, this mode is for you. In MM\_LOMETRIC, **1 unit in your drawing code represents one-tenth of a millimeter (0.1 mm)**.
- Therefore, if you want to draw an object that is exactly 10 millimeters (which is 1 centimeter) wide, you would tell your program to draw it 100 units wide (because  $100 \text{ units} * 0.1 \text{ mm/unit} = 10 \text{ mm}$ ). It's good for general metric designs.

### **MM\_HIMETRIC (High-Res Millimeters):**

- This is the high-precision metric mode, mirroring MM\_HIENGLISH. In MM\_HIMETRIC, **1 unit in your drawing code represents one-hundredth of a millimeter (0.01 mm)**.
- To draw something that is 10 millimeters (1 cm) wide, you would need to specify 1000 units in your code. This mode is excellent for very detailed technical drawings, engineering designs, or for precise output on high-resolution metric printers.

## **MM\_TWIPS (Tiny Typography Units):**

- This mode uses a very specific unit called a "twip," which is commonly found in older desktop publishing and word processing applications. In MM\_TWIPS, **1 unit in your drawing code is equal to 1/1440th of an inch.**
- This might sound odd, but it comes from the fact that there are 72 "points" in an inch (a common unit for font sizes), and there are 20 twips in a single point. So,  $72 \text{ points/inch} * 20 \text{ twips/point} = 1440 \text{ twips/inch}$ .
- This extremely small unit allows for incredibly fine and consistent control over text placement and layout, regardless of the screen's or printer's resolution. It ensures your text looks exactly the same size and spacing when printed as it does on screen, even across different devices.

**Origin:** This tells you where the (0,0) point of your drawing coordinate system is located within the window or page.

**Top-Left:** (0,0) is at the top-left corner.

**Bottom-Left:** (0,0) is at the bottom-left corner. (This is typical for print-oriented modes, like graphing).

**Y Axis:** This describes the direction of the Y-axis (vertical axis).

**Down:** As Y values increase, you move downwards on the screen (common for screen drawing).

**Up:** As Y values increase, you move upwards (common for graphing and print, where (0,0) is bottom-left).

**Use Case:** This gives you typical scenarios where each mapping mode would be beneficial.

In essence, these mapping modes give you the flexibility to draw in units that make sense for your output, whether it's pixels on a screen, inches for print, or tiny twips for precise text layout, letting Windows handle the conversion to actual physical dots.

## Real-World Use Case: When Does This Matter?

You might think, "Why bother with logical coordinates if MM\_TEXT (1 logical unit = 1 pixel) is the default and works fine for screens?"

This system becomes super useful when:

- **Print Previews:** You're showing how something will look on a printer. Printers have different resolutions (DPI - Dots Per Inch) than screens. Using modes like MM\_HIENGLISH (which defines units in thousandths of an inch) or MM\_TWIPS (1/1440 of an inch) lets you draw in real-world measurements (like inches or millimeters) so your design prints correctly, no matter the printer's DPI.
- **Multiple DPI Screens:** Your app needs to look good on screens with different pixel densities (e.g., a standard monitor vs. a high-resolution Retina display). Drawing in logical units ensures your elements scale properly.

## Tip: Combine Mapping + Viewport for Advanced Control

Mapping modes set the *scale* (how big a logical unit is) and *direction* (e.g., is Y-axis up or down?). But you can also use these two functions to further manipulate your drawing space:

```
// Shift the origin (0,0) of your *physical* drawing area.  
SetViewportOrgEx();  
// Shift the origin (0,0) of your *logical* drawing area.  
SetWindowOrgEx();
```

- **SetViewportOrgEx()**: Moves where your logical (0,0) point *appears* on the physical screen. Good for panning your view.
- **SetWindowOrgEx()**: Moves what logical coordinates correspond to the physical (0,0) point. Good for offsetting your drawing.

**Why use these?** You can combine these to easily **pan, zoom, and scale your drawings** without having to rewrite all your drawing code or recalculate every single coordinate. It lets you create complex viewing features (like in a CAD program) with relative ease.

---

## Summary Wrap-up: Quick Recap

- *TextOut and similar drawing functions use logical coordinates, not exact screen pixels.*
- *The mapping mode tells Windows how to convert your logical 'X' and 'Y' values into actual screen or printer pixels.*
- *MM\_TEXT is the simplest mapping mode; 1 logical unit equals 1 pixel. Great for basic screen drawing.*
- *Other mapping modes (like MM\_HIENGLISH or MM\_TWIPS) let you draw using real-world units (inches, mm) or scalable units, which is vital for printouts or high-DPI displays.*
- *Always choose your mapping mode based on what you're drawing for (screen, printer) and whether you need automatic scaling.*

## UNICODE SUPPORT

### TextOut: Text and Unicode – A Quick Guide

Yes, TextOut can draw text with all sorts of characters, including international ones (Unicode). But there's a small detail based on how you call it:

- **TextOutA:** This is for "ANSI" text, the **older, simpler text** where each character typically takes up only **1 byte** of memory. It's usually limited to characters from a specific language or region.
- **TextOutW:** This is for "Unicode" text, the **modern way** to handle text, where each character often uses **2 or more bytes** (called "wide characters"). Unicode can represent almost every character from every language in the world, including emojis and special symbols.

*TextOut supports Unicode character strings, allowing for the display of multilingual text. The number of bytes in a Unicode string is double the iLength value, and the string should not contain any ASCII control characters.*

*We looked at unicode in-depth in chapter 1.*

If you're writing C/C++ code and using TextOut to display Unicode text (which is highly recommended for modern apps):

- **iLength (the length parameter):** When you tell TextOut how long your text is, this iLength value should *still be the number of characters, NOT the number of bytes*. Even though Unicode characters might take 2 bytes each, Windows automatically handles this detail for you.
- **For C/C++ users:** Because of this, when you're calculating the length of a Unicode string in C/C++, **don't use strlen()** - counts bytes (good for ANSI), **use wcslen()** correctly counts wide characters (good for Unicode).



### 💡 Important Note on Formatting:

- Characters like \n (new line), \r (carriage return), or \t (tab) **will NOT create line breaks or tabs** when you draw them with TextOut. TextOut just draws them as literal characters (sometimes as little squares) or simply ignores them.
- If you need **multi-line text**, you'll have to handle line breaks yourself by calling TextOut multiple times for each line.

### 🔗 Clipping Region and Its Impact on Text Rendering

The **clipping region** is one of those invisible superheroes in GDI — you usually don't see it, but it's protecting your graphics from chaos.

### 💡 What's the Clipping Region?

It's a **boundary** that Windows uses to say:

*"You can only draw inside this area. Everything outside? Nope, not allowed."*

This applies to **everything**, including:

- TextOut
- DrawText
- Rectangle, Ellipse, BitBlt...

The device context, which serves as the drawing context for a window, [also defines](#) a clipping region.

This region determines the area within which graphical elements, including text, will be rendered.

By default, the clipping region is set to the [entire client area for a device context handle](#) obtained using GetDC and to the invalid region for a device context handle obtained using BeginPaint.

When the TextOut function is called to display text, Windows will [only render](#) the portions of the character string that fall within the clipping region.

Any part of a character that [lies outside the clipping region](#) will not be displayed. Similarly, if a character partially overlaps the clipping boundary, only the portion of the character inside the region will be rendered.

This clipping mechanism ensures that text is displayed only within the visible boundaries of the window, [preventing it from extending beyond the client area](#) or [overlapping](#) with other graphical elements.

## Two Main Scenarios for Clipping:

Function	What It Gives You
BeginPaint()	A drawing area <b>limited only to what's damaged</b> (the invalidated rectangle). Great for efficient repainting during <code>WM_PAINT</code> .
GetDC()	A drawing area that covers the <b>entire window's client area</b> . Use this for real-time or user-triggered drawing (like mouse moves).

BeginPaint() says: "**Just repaint the broken part; I got you covered.**"

GetDC() says: "**Here's the whole canvas — you do your thing, but clean up after.**"

## ⌚ Two Ways to Get a Device Context — and What You Can Draw

When you want to draw **anything** in WinAPI, you first need a **Device Context (DC)** — your window's personal canvas 🎨.

But *how* you get that DC? That changes **where** Windows *lets* you draw.

FunctionFlags	What It Gives You Access To	Used During	Default Clipping Region	Must Pair With
BeginPaint()	DC <i>only for the dirty area</i> (what needs redraw)	WM_PAINT	🚫 Only the invalid rectangle	<input checked="" type="checkbox"/> EndPaint()
GetDC()	DC for the <i>entire client area</i>	Outside WM_PAINT	🟢 Whole client area	<input checked="" type="checkbox"/> ReleaseDC()

## ⭐ Why Clipping Is Useful:

- *Keeps your UI clean — text doesn't spill over borders.*
  - *Speeds up painting — Windows can skip drawing clipped-out pixels.*
  - *Makes redraws more efficient — you can redraw only the parts that changed.*
-

 **TLDR:**

- ✓ TextOut supports Unicode — just make sure you pass wchar\_t\* strings and use iLength as **character count**, not bytes.

```
#include <windows.h>

LRESULT CALLBACK WndProc(HWND hWnd, UINT msg, WPARAM wParam, LPARAM lParam) {
    switch (msg) {
        case WM_PAINT: {
            PAINTSTRUCT ps;
            HDC hdc = BeginPaint(hWnd, &ps);

            // Unicode text
            wchar_t* text = L"Hello, 🌎 Unicode!";
            TextOutW(hdc, 50, 50, text, wcslen(text)); // Notice: character count

            EndPaint(hWnd, &ps);
            break;
        }
        case WM_DESTROY: PostQuitMessage(0); break;
    }
    return DefWindowProc(hWnd, msg, wParam, lParam);
}
```

**Clipping Region:** Draw inside it only.

The **clipping region** of an HDC controls where text and graphics can appear.

```
#include <windows.h>

LRESULT CALLBACK WndProc(HWND hWnd, UINT msg, WPARAM wParam, LPARAM lParam) {
    switch (msg) {
        case WM_PAINT: {
            PAINTSTRUCT ps;
            HDC hdc = BeginPaint(hWnd, &ps);

            // Create a tiny clipping region
            HRGN hRgn = CreateRectRgn(0, 0, 100, 100);
            SelectClipRgn(hdc, hRgn);

            // Try to draw inside and outside the region
            TextOutA(hdc, 10, 10, "Visible", 7);    // Inside: will show
            TextOutA(hdc, 200, 200, "Ignored", 7); // Outside: will not show

            DeleteObject(hRgn);
            EndPaint(hWnd, &ps);
            break;
        }
        case WM_DESTROY: PostQuitMessage(0); break;
    }
    return DefWindowProc(hWnd, msg, wParam, lParam);
}
```

Anything outside the clipping region is automatically ignored — *no need to manually crop.*

- ✓ If you use BeginPaint, you're limited to the **invalid region**.

```
#include <windows.h>

LRESULT CALLBACK WndProc(HWND hWnd, UINT msg, WPARAM wParam, LPARAM lParam) {
    switch (msg) {
        case WM_LBUTTONDOWN:
            // Force a partial redraw of the top-left only
            InvalidateRect(hWnd, &(RECT){0, 0, 100, 100}, TRUE);
            break;

        case WM_PAINT:
            PAINTSTRUCT ps;
            HDC hdc = BeginPaint(hWnd, &ps);

            // Entire screen draw attempt – but only the invalid region will show it
            for (int y = 0; y < 300; y += 20) {
                TextOutA(hdc, 10, y, "Hello", 5);
            }

            EndPaint(hWnd, &ps);
            break;
    }
    case WM_DESTROY: PostQuitMessage(0); break;
}
return DefWindowProc(hWnd, msg, wParam, lParam);
}
```

- ✓ If you use GetDC, you can draw on the **entire client area**.

```
#include <windows.h>

LRESULT CALLBACK WndProc(HWND hWnd, UINT msg, WPARAM wParam, LPARAM lParam) {
    switch (msg) {
        case WM_KEYDOWN:
            HDC hdc = GetDC(hWnd); // No clipping – full access to client area
            TextOutA(hdc, 100, 200, "Drawn with GetDC!", 18);
            ReleaseDC(hWnd, hdc);
            break;
    }
    case WM_DESTROY: PostQuitMessage(0); break;
}
return DefWindowProc(hWnd, msg, wParam, lParam);
}
```

# SYSTEM FONT

The [device context also defines](#) the default font that Windows uses when displaying text using the `TextOut` function.

This default font is known as the "system font" or, using the identifier defined in the [WINGDI.H](#) header file, `SYSTEM_FONT`.

Hi, I'm Arial!  
I'm a system font!

The system font is the font that Windows employs by default for text strings in title bars, menus, and dialog boxes.

It serves as a baseline font for text rendering and is commonly used throughout the Windows user interface.

## Evolution of the System Font: From Fixed-Pitch to Variable-Pitch

In the early versions of Windows, the system font was a [fixed-pitch font](#), meaning that all characters had the same width.

This was similar to the font used in typewriters. However, with the release of Windows 3.0, the system font transitioned to a [variable-pitch font](#).



Variable-pitch fonts allow different characters to have different widths, reflecting their natural shapes and sizes.

This change from fixed-pitch to variable-pitch fonts was driven by research indicating that text displayed in [variable-pitch fonts is more readable](#) and visually appealing.

## **Impact of Variable-Pitch Fonts on Programming**


The adoption of variable-pitch fonts necessitated adjustments in programming practices.

Developers had to adapt their code to account for the varying widths of characters and ensure proper text alignment and formatting.

## **Raster Fonts vs. TrueType Fonts: A Distinction**

The **system font** is a **raster font**, meaning that the **characters are defined as blocks of pixels**. This definition is tied to a specific resolution and **may not scale well** to different display sizes.

Play this video: 



In contrast, TrueType fonts, which we'll explore in the last Chapters, are defined by scalable outlines.

TrueType fonts are **vector-based fonts**, meaning that they are defined by mathematical formulas rather than fixed bitmaps.

They can be **rendered at various resolutions without losing quality**, making them more versatile for various display sizes and text rendering scenarios.

### **Bitmap      TrueType**



## Conclusion

The device context's clipping region and the system font play crucial roles in text rendering within Windows applications.

The clipping region ensures that text is displayed only within the visible boundaries of the window, while the system font provides a default text rendering style. Understanding these concepts is essential for creating visually appealing and user-friendly Windows applications.

The TextOut function is an essential tool for displaying text in Windows applications. Its straightforward syntax and integration with device context attributes enable programmers to create visually appealing and informative user interfaces.

Understanding the concept of mapping modes and Unicode support further enhances the versatility of this function.

Also, read the GDI documentation.

## CHARACTER DIMENSIONS AND TEXT RENDERING

When displaying multiple lines of text using the TextOut function, it is crucial to determine the dimensions of the characters in the font.

This information allows for proper spacing between lines and columns of text, ensuring a visually appealing and readable layout.

## Dynamic Character Dimensions: Impact of Display Size and Font Selection

The dimensions of characters are not static and can vary depending on the pixel size of the video display.

Windows allows a range of display resolutions, such as 640x480, 800x600, and 1024x768.



Additionally, users can choose different font sizes for the system font. These factors contribute to the dynamic nature of character dimensions.

## Determining Character Dimensions Using GetTextMetrics

To determine the character dimensions for a specific font, a program can utilize the [GetTextMetrics](#) function.

This function requires a handle to the device context, as it retrieves information about the font currently selected in that context.

The retrieved information is stored in a TEXTMETRIC structure, which contains various fields related to font metrics.

[Key Fields of the TEXTMETRIC Structure](#). Among the 20 fields in the TEXTMETRIC structure, the following seven are particularly relevant for character dimensions:

- **tmHeight:** Represents the total height of a character, including both the ascent and descent.
- **tmAscent:** Indicates the portion of the character that extends above the baseline.
- **tmDescent:** Represents the portion of the character that extends below the baseline.
- **tmInternalLeading:** Refers to the additional spacing between lines of text within the tmHeight boundary.
- **tmExternalLeading:** Represents the additional spacing between lines of text outside the tmHeight boundary.
- **tmAveCharWidth:** Indicates the average width of characters in the font.
- **tmMaxCharWidth:** Represents the width of the widest character in the font.

## Units of Measurement for Character Dimensions

The values in the **TEXTMETRIC structure** are measured in units based on the mapping mode currently selected for the device context.

In the default device context, the mapping mode is MM\_TEXT, meaning the dimensions are in pixels.

## Code Example for Retrieving Character Dimensions

The following code snippet demonstrates how to retrieve character dimensions using GetTextMetrics:

```
TEXTMETRIC tm;

// Get a handle to the device context
HDC hdc = GetDC(hwnd);

// Retrieve character metrics for the current font
GetTextMetrics(hdc, &tm);

// Examine and use the values in the text metric structure
int characterHeight = tm.tmHeight;
int averageCharacterWidth = tm.tmAveCharWidth;

// Release the device context
ReleaseDC(hwnd, hdc);
```

```

#include <windows.h>
typedef struct tagTEXTMETRIC {
    LONG tmHeight;
    LONG tmAscent;
    LONG tmDescent;
    LONG tmInternalLeading;
    LONG tmExternalLeading;
    LONG tmAveCharWidth;
    LONG tmMaxCharWidth;
    // Add other structure fields as needed
} TEXTMETRIC, *PTEXTMETRIC;

int main() {
    HDC hdc = GetDC(0); // Get the device context of the screen
    // Get the font information
    LOGFONT lf;
    GetObject(GetStockObject(DEFAULT_GUI_FONT), sizeof(LOGFONT), &lf);
    // Create a font using the information obtained
    HFONT hFont = CreateFontIndirect(&lf);
    // Select the font into the device context
    SelectObject(hdc, hFont);
    // Get the text metrics
    TEXTMETRIC tm;
    GetTextMetrics(hdc, &tm);
    // Display the text metrics
    printf("Text Metrics:\n");
    printf(" Height: %ld\n", tm.tmHeight);
    printf(" Ascent: %ld\n", tm.tmAscent);
    printf(" Descent: %ld\n", tm.tmDescent);
    printf(" Internal Leading: %ld\n", tm.tmInternalLeading);
    printf(" External Leading: %ld\n", tm.tmExternalLeading);
    printf(" Average Character Width: %ld\n", tm.tmAveCharWidth);
    printf(" Maximum Character Width: %ld\n", tm.tmMaxCharWidth);
    // Clean up
    DeleteObject(hFont);
    ReleaseDC(0, hdc);
    return 0;
}

```

This code uses the [Windows API](#) to obtain the default font on the system, [creates a font from that information, selects it into a device context, and then retrieves the text metrics](#) using `GetTextMetrics`. Finally, it prints out the various fields of the `TEXTMETRIC` structure.

Please note that this [code assumes you are working in a Windows environment](#), as it relies on Windows API functions. If you are using a different platform, you might need to use a different approach.


## Delving into the TEXTMETRIC Structure for Character Dimensions

The [TEXTMETRIC structure](#) provides comprehensive information about the font currently selected in the device context.

Among its various fields, four are particularly relevant for understanding character dimensions: tmHeight, tmAscent, tmDescent, and tmInternalLeading.

### tmHeight: Defining the Overall Character Height

The tmHeight field represents the total height of a character, encompassing both the ascent and descent. It serves as a crucial parameter for determining the vertical spacing between lines of text.



### tmAscent and tmDescent: Character Extents Above and Below the Baseline


The tmAscent field indicates the portion of the character that extends above the baseline, while tmDescent represents the portion that extends below the baseline. These values are essential for proper positioning of text relative to the baseline.

### tmInternalLeading: Accounting for Accent Marks

tmInternalLeading refers to the additional spacing between lines of text within the tmHeight boundary. This spacing typically accommodates accent marks, which are small characters placed above or below other characters.

## External Leading: An Optional Spacing Suggestion


The TEXTMETRIC structure also includes a field named **tmExternalLeading**, which represents an additional spacing suggestion from the font designer. This spacing is intended to be added between successive rows of displayed text. Programmers have the flexibility to accept or reject this suggestion based on their desired text layout.



**Figure 4–3.** Four values defining vertical character sizes in a font.

## Character Widths: Average and Maximum

Character widths are represented by two fields in the TEXTMETRIC structure: **tmAveCharWidth** and **tmMaxCharWidth**. **tmAveCharWidth** indicates the average width of lowercase characters, while **tmMaxCharWidth** represents the width of the widest character in the font.



## Calculating Uppercase Character Width

For the sample programs in this chapter, the average width of uppercase letters is required. This value can be approximated by calculating 150% of tmAveCharWidth.

## Dynamic Character Dimensions: Adapting to Display Size and Font Selection

It is crucial to recognize that the **dimensions of a system font are not static** and can vary depending on the pixel size of the video display on which Windows runs.



Additionally, some **users may have customized the system font size**, further influencing character dimensions.

## Importance of Accurate Character Dimensions

Relying on guesswork or **hard-coded values for character dimensions** can lead to inconsistent and visually unappealing text layouts across different display setups and user preferences.



## Role of GetTextMetrics in Obtaining Accurate Character Dimensions

The **GetTextMetrics** function provides a reliable and device-independent mechanism for retrieving accurate character dimensions. By utilizing this function, programmers can ensure that their text rendering adapts to various display configurations and font selections.




In summary, the **TEXTMETRIC structure** offers valuable insights into font metrics, particularly character dimensions. Understanding the significance of each field and employing the **GetTextMetrics** function empowers programmers to create visually consistent and user-friendly text layouts.

## Formatting text and optimizing GetTextMetrics usage:

### Efficient Utilization of GetTextMetrics for Text Formatting

Since the dimensions of the system font remain constant throughout a Windows session, it is unnecessary to repeatedly call **GetTextMetrics**.




A single call during program initialization is sufficient.

An ideal location for this call is within the window procedure's response to the WM\_CREATE message, the first message received by the window procedure.

## Defining Variables for Character Dimensions

Consider a Windows program that displays **multiple lines of text** within the client area.

To calculate the **appropriate spacing** between lines and characters, the average character width (`cxChar`) and total character height (`cyChar`) need to be determined.



These values can be stored in static variables defined within the window procedure:

The static **variables** `cxChar` and `cyChar` are defined within the `WM_CREATE` message handler of the window procedure.

This **message handler is executed when the window is created**, and it's an appropriate place to initialize these variables since they need to be valid for subsequent message processing, such as `WM_PAINT`.

Here's an example of how to define and initialize these variables in the `WM_CREATE` message handler:

```
case WM_CREATE:  
    hdc = GetDC(hwnd);  
    GetTextMetrics(hdc, &tm);  
    cxChar = tm.tmAveCharWidth;  
    cyChar = tm.tmHeight + tm.tmExternalLeading;  
    ReleaseDC(hwnd, hdc);  
    return 0;
```

# FORMATTING TEXT IN WINDOWS

In Windows programming, **formatting text involves** using functions like GetTextMetrics, TextOut, wsprintf, and sprintf to control the appearance of text displayed on the screen.

These functions **allow you to modify font characteristics**, line spacing, and text alignment.

## Obtaining Character Metrics

The **GetTextMetrics** function retrieves information about the system font, including character width and height.


This information is crucial for **positioning text accurately** and **ensuring proper line spacing**.

The function **takes a device context handle (HDC)** as input and returns a **TEXTMETRIC** structure containing relevant font metrics.

## Storing Character Metrics

The **cxChar** and **cyChar variables** are used to store the average character width and total character height, respectively.

These variables are defined as static to maintain their values across multiple message processing calls.



## WM\_CREATE Message Handling

The WM\_CREATE message is the first message received by a window procedure after window creation.

It's an ideal place to initialize the text formatting variables. The WM\_CREATE message handler typically performs the following steps:

### **Retrieve the device context handle (HDC) using GetDC.**

Call GetTextMetrics to obtain character metrics and store them in cxChar and cyChar.

Release the device context using ReleaseDC.

Return 0.

## **Displaying Formatted Text**

To display formatted text, you can use functions like wsprintf and TextOut.

**wsprintf** formats a string according to specified format specifiers and stores the result in a buffer.

**TextOut** then renders the formatted string to the specified coordinates on the device context.

### Example Code for Formatted Text Output

The provided code snippet demonstrates the usage of wsprintf and TextOut to display the sum of two numbers:

```
int iLength;
TCHAR szBuffer[40];

// Other program lines

iLength = wsprintf(szBuffer, TEXT("The sum of %i and %i is %i"), iA, iB, iA + iB);
TextOut(hdc, x, y, szBuffer, iLength);
```

### Concise Code Combining wsprintf and TextOut

While not as elegant, you can combine wsprintf and TextOut into a single statement:

```
TextOut(hdc, x, y, szBuffer, wsprintf(szBuffer, TEXT("The sum of %i and %i is %i"), iA, iB, iA + iB));
```

This approach directly passes the formatted string to TextOut without the need for an intermediate buffer.

## Summary

Formatting text in Windows involves using specific functions to control font characteristics, line spacing, and text alignment. The GetTextMetrics function provides character width and height information, while TextOut and wsprintf enable formatted text output. These functions empower developers to create visually appealing and informative text displays in their Windows applications.

## Creating a Header File for GetSystemMetrics Information

The provided code snippet below will introduce the concept of [creating a header file named SYSMETS.H](#) to manage the information retrieved from the GetSystemMetrics function.

This [header file defines an array of structures](#) containing both the GetSystemMetrics index identifier and the corresponding text for each value returned by the function.

## Structure Definition for GetSystemMetrics Information

The SMETRICS structure is defined to hold the GetSystemMetrics index identifier and the associated text:

```
typedef struct {
    int smIndex;
    LPCTSTR szLabel;
} SMETRICS;
```

The [smIndex member](#) stores the index identifier for GetSystemMetrics, while the [szLabel member](#) holds the corresponding text label.

## Array of SMETRICS Structures

An array of SMETRICS structures is defined to store multiple GetSystemMetrics index-text pairs:


```
SMETRICS aSMETRICS[] = {
    { SM_CXSIZE, TEXT("Width in pixels") },
    { SM_CYSIZE, TEXT("Height in pixels") },
    { SM_CXICON, TEXT("Icon width in pixels") },
    // ... Additional SMETRICS entries ...
};
```

Each structure in the array associates a GetSystemMetrics index with a descriptive text label.

## Benefits of Using a Header File

Creating a header file like SYSMETS.H offers several advantages:

**Centralized Information Management:** The header file centralizes the information about GetSystemMetrics indices and their corresponding text labels, making it easier to maintain and update.



**Improved Code Readability:** By encapsulating the index-text mapping in a separate file, the main program code becomes more readable and less cluttered with GetSystemMetrics index constants.

```
/**
 * Code Readability
 */
if (readable()) {
    be_happy();
} else {
    refactor();
}
```

**Error Reduction:** The header file serves as a single source of truth for the GetSystemMetrics index-text associations, reducing the risk of errors in the main program code.



Overall, using a header file like SYSMETS.H promotes code organization, maintainability, and readability, especially when dealing with large sets of data or complex information management.

```
/* SYSMETS.H - System metrics display structure */

#ifndef SYSMETS_H
#define SYSMETS_H

#include <tchar.h>

typedef struct {
    int iIndex;
    TCHAR* szLabel;
    TCHAR* szDesc;
} SMETRIC_ENTRY;

#define NUMLINES ((int)(sizeof(sysmetrics) / sizeof(sysmetrics[0])))

SMETRIC_ENTRY sysmetrics[] = {
    { SM_CXSCREEN, TEXT("SM_CXSCREEN"), TEXT("Screen width in pixels") },
    { SM_CYSCREEN, TEXT("SM_CYSCREEN"), TEXT("Screen height in pixels") },
    { SM_CXVSCROLL, TEXT("SM_CXVSCROLL"), TEXT("Vertical scroll width") },
    { SM_CYHSCROLL, TEXT("SM_CYHSCROLL"), TEXT("Horizontal scroll height") },
    { SM_CYCAPTION, TEXT("SM_CYCAPTION"), TEXT("Caption bar height") },
    { SM_CXBORDER, TEXT("SM_CXBORDER"), TEXT("Window border width") },
    { SM_CYBORDER, TEXT("SM_CYBORDER"), TEXT("Window border height") },
    { SM_CXFIXEDFRAME, TEXT("SM_CXFIXEDFRAME"), TEXT("Dialog window frame width") },
    { SM_CYFIXEDFRAME, TEXT("SM_CYFIXEDFRAME"), TEXT("Dialog window frame height") },
    // ... Other metric entries ...
};

#endif // SYSMETS_H
```

```

490 #include <windows.h>
491 #include "sysmets.h"
492
493 LRESULT CALLBACK WndProc(HWND, UINT, WPARAM, LPARAM);
494
495 int WINAPI WinMain(HINSTANCE hInstance, HINSTANCE hPrevInstance, PSTR szCmdLine, int iCmdShow) {
496     static TCHAR szAppName[] = TEXT("SysMets1");
497     HWND hwnd;
498     MSG msg;
499     WNDCLASS wndclass;
500
501     wndclass.style = CS_HREDRAW | CS_VREDRAW;
502     wndclass.lpfWndProc = WndProc;
503     wndclass.cbClsExtra = 0;
504     wndclass.cbWndExtra = 0;
505     wndclass.hInstance = hInstance;
506     wndclass.hIcon = LoadIcon(NULL, IDI_APPLICATION);
507     wndclass.hCursor = LoadCursor(NULL, IDC_ARROW);
508     wndclass.hbrBackground = (HBRUSH)GetStockObject(WHITE_BRUSH);
509     wndclass.lpszMenuName = NULL;
510     wndclass.lpszClassName = szAppName;
511
512     if (!RegisterClass(&wndclass)) {
513         MessageBox(NULL, TEXT("This program requires Windows NT!"), szAppName, MB_ICONERROR);
514         return 0;
515     }
516
517     hwnd = CreateWindow(szAppName, TEXT("Get System Metrics No. 1"), WS_OVERLAPPEDWINDOW,
518                         CW_USEDEFAULT, CW_USEDEFAULT, CW_USEDEFAULT, CW_USEDEFAULT,
519                         NULL, NULL, hInstance, NULL);
520
521     ShowWindow(hwnd, iCmdShow);
522     UpdateWindow(hwnd);
523
524     while (GetMessage(&msg, NULL, 0, 0)) {
525         TranslateMessage(&msg);
526         DispatchMessage(&msg);
527     }
528
529     return msg.wParam;
530 }
531
532 LRESULT CALLBACK WndProc(HWND hwnd, UINT message, WPARAM wParam, LPARAM lParam) {
533     static int cxChar, cxCaps, cyChar;
534     HDC hdc;
535     int i;
536     PAINTSTRUCT ps;
537     TCHAR szBuffer[10];
538     TEXTMETRIC tm;
539
540     switch (message) {
541     case WM_CREATE:
542         hdc = GetDC(hwnd);
543         GetTextMetrics(hdc, &tm);
544         cxChar = tm.tmAveCharWidth;
545         cxCaps = (tm.tmPitchAndFamily & 1 ? 3 : 2) * cxChar / 2;
546         cyChar = tm.tmHeight + tm.tmExternalLeading;
547         ReleaseDC(hwnd, hdc);
548         return 0;
549
550     case WM_PAINT:
551         hdc = BeginPaint(hwnd, &ps);
552         for (i = 0; i < NUMLINES; i++) {
553             TextOut(hdc, 0, cyChar * i, sysmetrics[i].szLabel, lstrlen(sysmetrics[i].szLabel));
554             TextOut(hdc, 22 * cxCaps, cyChar * i, sysmetrics[i].szDesc, lstrlen(sysmetrics[i].szDesc));
555             SetTextAlign(hdc, TA_RIGHT | TA_TOP);
556             TextOut(hdc, 22 * cxCaps + 40 * cxChar, cyChar * i, szBuffer,
557                     wsprintf(szBuffer, TEXT("%5d"), GetSystemMetrics(sysmetrics[i].iIndex)));
558             SetTextAlign(hdc, TA_LEFT | TA_TOP);
559         }
560         EndPaint(hwnd, &ps);
561         return 0;
562
563     case WM_DESTROY:
564         PostQuitMessage(0);
565         return 0;
566     }
567
568     return DefWindowProc(hwnd, message, wParam, lParam);
569 }

```

The SYSMETS1.C source code file contains the implementation of the SYSMETS program, which displays various system metrics on the screen.

The program utilizes the GetSystemMetrics function to retrieve information about various graphical elements, such as icon sizes, scroll bar dimensions, and window borders.


*The WinMain function serves as the entry point for the program. It performs the following tasks:*

**Register the window class:** This step defines the characteristics of the program's window, including its style, icon, and cursor.

**Create the window:** Using the registered window class, WinMain creates the program's window and assigns a handle to it.

**Display the window:** The window is made visible using the ShowWindow function.

**Enter the message loop:** The program enters a message loop, where it continuously processes messages received from the operating system.




*The WndProc function is responsible for handling messages sent to the program's window. It processes various messages, including:*

**WM\_CREATE:** This message is received when the window is created. The SYSMETS program uses this message to initialize the text formatting variables.

**WM\_PAINT:** This message is received when the window needs to be repainted. The SYSMETS program uses this message to retrieve system metrics using GetSystemMetrics and display the information on the screen using TextOut.

**WM\_DESTROY:** This message is received when the window is destroyed. The SYSMETS program uses this message to perform any necessary cleanup tasks.




### Relationship to Previous Code

The [WinMain function in SYSMETS1](#) is similar to the one in HELLOWIN, as both involve registering the window class, creating the window, and displaying it.

The [WndProc function in SYSMETS1](#) incorporates elements discussed in previous chapters, such as obtaining character metrics and using TextOut for formatted text output.

The [SYSMETS1 program](#) demonstrates the practical application of concepts covered in earlier chapters, including window creation, message handling, and text formatting. It showcases how to utilize the GetSystemMetrics function to retrieve system-specific information and display it in a structured manner.



The program runs well in Visual studio community 2022.

Name	Description	Value	
SM_CXSCREEN	Screen width in pixels	1280	
SM_CYSCREEN	Screen height in pixels	1024	
SM_CVSCROLL	Vertical scroll width	17	
SM_CYHSCROLL	Horizontal scroll height	17	
SM_CXBORDER	Caption bar height	23	
SM_CYBORDER	Window border width	1	
SM_CXFIXEDFRAME	Window border height	1	
SM_CYFIXEDFRAME	Dialog window frame width	3	
SM_CVTHUMB	Dialog window frame height	3	
SM_CXHTHUMB	Vertical scroll thumb height	17	
SM_CXICON	Horizontal scroll thumb width	17	
SM_CYICON	Icon width	32	
SM_CXCURSOR	Icon height	32	
HWND	Cursor width	32	
MSG	Cursor height	32	
WNDCL	Menu bar height	20	
SM_CXFULLSCREEN	Full screen client area width	1280	
SM_CYFULLSCREEN	Full screen client area height	953	
SM_CYKANJIWINDOW	Kanji window height	0	
SM_MOUSEPRESENT	Mouse present flag	1	
wndcl	Vertical scroll arrow height	17	
SM_CVSCROLL	Horizontal scroll arrow width	17	
wndcl	SM_DEBUG	0	
wndcl	SM_SWAPBUTTON	0	
wndcl	SM_CXMIN	Minimum window width	136
SM_CYMIN	Minimum window height	39	
wndcl	SM_CXSIZE	Min/Max/Close button width	36
SM_CYSIZE	Min/Max/Close button height	22	
wndcl	SM_CXSIZEFRAME	Window sizing frame width	4
SM_CYSIZEFRAME	Window sizing frame height	4	
SM_CXMINTRACK	Minimum window tracking width	136	
SM_CYMINTRACK	Minimum window tracking height	39	
SM_CXDOUBLECLK	Double click x tolerance	4	
SM_CYDOUBLECLK	Double click y tolerance	4	
SM_CXICONSPACING	Horizontal icon spacing	75	
SM_CYICONSPACING	Vertical icon spacing	75	
SM_MENUDROPALIGNMENT	Left or right menu drop	0	
SM_PENWINDOWS	Pen extensions installed	0	
SM_DBCSENABLED	Double-Byte Char Set enabled	0	
SM_CMOUSEBUTTONS	Number of mouse buttons	3	
SM_SECURE	Security present flag	0	
SM_CEDGE	3-D border width	2	

## The SYSMETS1 Window Procedure

The WndProc window procedure in the SYSMETS1.C program is responsible for handling messages sent to the window. It processes three main types of messages:

**WM\_CREATE:** This message is sent when the window is created. In response, the WndProc procedure obtains a device context for the window using the GetDC function and retrieves the text metrics for the default system font using the GetTextMetrics function. The text metrics include the average character width (stored in cxChar) and the total height of the characters (including external leading) (stored in cyChar).

**WM\_PAINT:** This message is sent when the window needs to be repainted. In response, the WndProc procedure draws the window's contents using the device context obtained in the WM\_CREATE message. The procedure uses the TextOut function to display three columns of text: the system metric identifier, the system metric description, and the system metric value. The position of each column is calculated based on the text metrics and the width of the uppercase letters (stored in cxCaps).

**WM\_DESTROY:** This message is sent when the window is destroyed. In response, the WndProc procedure cleans up any resources that were allocated in the WM\_CREATE message.

## Detailed Explanation of WM\_PAINT Processing

The WM\_PAINT message processing involves the following steps:

**BeginPaint:** The WndProc procedure obtains a handle to the device context using the BeginPaint function. The device context is used for drawing the window's contents.

**TextOut for Identifiers:** The WndProc procedure uses the TextOut function to display the uppercase identifiers in the first column. The second argument to TextOut is set to 0 to start the text at the left edge of the client area. The text is obtained from the szLabel field of the sysmetrics structure. The length of the string is calculated using the lstrlen function and passed as the last argument to TextOut.

**TextOut for Descriptions:** The WndProc procedure uses the TextOut function to display the descriptions of the system metric values in the second column. The descriptions are stored in the szDesc field of the sysmetrics structure. The second argument to TextOut is set to 22 \* cxCaps to position the start of the text to the right of the identifiers.

**TextOut for Values:** The WndProc procedure uses the TextOut function to display the numeric values obtained from the GetSystemMetrics function in the third column. To right-justify the numbers, the WndProc procedure sets the text alignment using the SetTextAlign function before calling TextOut. The position of the numbers is calculated based on the width of the digits and the width of the uppercase letters.

**EndPaint:** The WndProc procedure releases the device context obtained in the BeginPaint function using the EndPaint function.

The **cxCaps variable** is calculated to be 150% of cxChar for variable-width fonts and equal to cxChar for fixed-pitch fonts.

The **SetTextAlign function** is used to set the text alignment to right-justified for the column of numbers and then set back to the default alignment before the next iteration of the loop.

This detailed explanation provides a deeper understanding of the SYSMETS1 window procedure and its role in displaying system metric information.

## The "Not Enough Room" Problem

The **SYSMETS1** program displays a list of system metrics along with their corresponding values.

However, due to **limitations in how the program determines the available space for displaying text**, the entire list may not be visible on screens with smaller resolutions or window sizes.



The primary issue lies in the program's reliance on **the default behavior of Windows to clip text that extends beyond the client area** of the window.

This approach assumes that the program has sufficient space to display the entire list, which may not be the case on all systems or window configurations.

### Proposed Solution

To address this issue, the program needs to **explicitly determine the available space** within the client area before attempting to display the text.

This can be achieved by retrieving the dimensions of the client area using **the GetClientRect function**.

### Implementation Details

**Determining Available Space:** Before displaying the list of system metrics, the program should call the GetClientRect function to obtain the width and height of the client area.



**Adjusting Text Positioning:** Based on the available client area dimensions, the program should adjust the positioning of the text to ensure it fits within the visible area. This may involve modifying the vertical position of the text or truncating the list if necessary.



**Handling Overflow:** If the entire list cannot be displayed within the client area, the program should consider displaying a notification or implementing a [scrolling mechanism](#) to allow users to view the remaining entries.

Evolution of the Scrollbar



See more at [infomesh.org](http://infomesh.org)

Sébastien Matos, écal 2019

By incorporating these changes, the SYSMETS1 program can ensure that the system metrics list is displayed appropriately, regardless of the screen resolution or window size.

## Determining the Client Area Size

The **client area** is the portion of a window that is available for displaying application content. It excludes the title bar, menu bar, and any other non-client elements.

**Determining the size of the client area** is essential for ensuring that application content is displayed correctly and efficiently.

### Traditional Method: GetClientRect Function


The **GetClientRect** function is a traditional method for retrieving the dimensions of the client area. It takes a window handle as input and returns a **RECT structure** containing the client area's coordinates. However, calling this function repeatedly can be inefficient, especially if the client area size changes frequently.

### Efficient Method: Processing WM\_SIZE Message

A more efficient approach is to process the **WM\_SIZE** message in the window procedure. This message is sent whenever the window's size changes, providing the updated client area dimensions in the **lParam** parameter.

### Storing Client Area Dimensions

To store the client area dimensions, define static variables **cxClient** and **cyClient** in your window procedure. These variables are declared as **static** to retain their values between message processing cycles.



## Handling WM\_SIZE Message

The WM\_SIZE message is handled within the window procedure using the following code:

```
case WM_SIZE:  
    cxClient = LOWORD(lParam);  
    cyClient = HIWORD(lParam);  
    return 0;
```

The **LOWORD** and **HIWORD** macros extract the low-order and high-order words from the lParam parameter, respectively. These values represent the client area's width and height.

## Calculating Displayable Text Lines and Characters

Once the client area dimensions are known, you can calculate the number of full lines of text and lowercase characters that can be displayed:

- Number of text lines: cyClient / cyChar.
- Number of lowercase characters: cxClient / cxChar.

These calculations rely on the values of cxChar and cyChar, which represent the average character width and total character height, respectively. These values are typically determined during the WM\_CREATE message when the window is created.

## ScrollBar for Content Overflow

If the **client area is not large enough to hold all the content**, scroll bars can be implemented to provide a way for the user to view the remaining information. Scroll bars are essential for applications that handle large amounts of text or data.



## Conclusion

Determining the size of the client area is a crucial aspect of Windows programming. By utilizing the WM\_SIZE message and storing the client area dimensions efficiently, developers can ensure that application content is displayed correctly and efficiently, even when window sizes change dynamically.

# SCROLL BARS: ENHANCING USER INTERFACE INTERACTION

Scroll bars are a ubiquitous and essential component of graphical user interfaces (GUIs), enabling users to navigate through **extensive content that exceeds the visible area** of a window.

They provide a **user-friendly and intuitive way** to scroll through documents, spreadsheets, images, web pages, and other types of content.

## Types and Placement of Scroll Bars

Scroll bars come in two main types: vertical and horizontal.


**Vertical scroll bars** are used for scrolling up and down, typically found on the right side of a window.

**Horizontal scroll bars**, used for scrolling left and right, are typically positioned at the bottom of a window.


## Scroll Bar Components and Functionality

Each scroll bar comprises several key components:

**Scroll Bar Arrows:** Clicking on the arrows at either end of the scroll bar initiates scrolling in the corresponding direction (up or down for vertical scroll bars, left or right for horizontal scroll bars).



**Scroll Box (Thumb):** The scroll box, also known as the thumb, is a movable indicator that represents the approximate position of the visible content within the entire document. Dragging the scroll box allows for direct navigation to a specific location in the content.



**Scroll Bar Track:** The scroll bar track provides the area along which the scroll box can move. Clicking within the scroll bar track, either above or below the scroll box, initiates scrolling in the corresponding direction.

## Scroll Bar Integration into Windows Applications

Integrating scroll bars into Windows applications is a straightforward process.

During window creation using the [CreateWindow function](#), the desired scroll bar type can be specified by including the corresponding window style identifiers:

- **WS\_VSCROLL**: Vertical scroll bar.
- **WS\_HSCROLL**: Horizontal scroll bar.
- **WS\_VSCROLL | WS\_HSCROLL**: Both vertical and horizontal scroll bars.

Once included, scroll bars are [automatically positioned and sized](#) according to the window's client area.

Windows handles all mouse interactions with the scroll bars, providing the necessary scrolling behavior.


## Keyboard Interface for Scroll Bars

While Windows manages mouse interactions with scroll bars, it does not provide an automatic keyboard interface. If you want to enable keyboard navigation using cursor keys, you'll need to implement the necessary logic within your application.

## Enhancing Scroll Bar Usability

Scroll bars can be further enhanced to improve user experience:


**Scroll Bar Visibility:** Implement logic to hide scroll bars when the content fits within the visible area and show them only when scrolling is necessary.



**Scroll Bar Feedback:** Provide visual feedback during scrolling, such as highlighting the scroll box or changing its color, to indicate the current position within the content.



**Keyboard Navigation:** Implement keyboard shortcuts using cursor keys to provide an alternative scrolling method.



**Scroll Bar Customization:** Allow users to customize scroll bar appearance, such as color, size, and placement.




## Scroll Bar Range and Position: Controlling Scrolling Behavior

Scroll bars play a crucial role in graphical user interfaces (GUIs) by enabling users to [navigate through extensive content](#) that exceeds the visible area of a window.

They provide a visual representation of the overall content and allow users to scroll smoothly through it.

## Scroll Bar Range


The scroll bar range defines the minimum and maximum values associated with the scroll bar. These values represent the extent of the content that can be scrolled through. For instance, a scroll bar with a range of 0 to 100 indicates that the content can be scrolled from its initial position (0) to its full length (100).



## Setting Scroll Bar Range


The SetScrollRange function is used to modify the range of a scroll bar. It takes five arguments:

- **hwnd:** The window handle of the window containing the scroll bar.
- **iBar:** Specifies the scroll bar type (SB\_VERT for vertical, SB\_HORZ for horizontal).
- **iMin:** The new minimum value of the scroll bar range.
- **iMax:** The new maximum value of the scroll bar range.
- **bRedraw:** A Boolean value indicating whether to redraw the scroll bar based on the new range (TRUE for redrawing, FALSE to avoid unnecessary redraws).



## Scroll Bar Position

The scroll bar position indicates the current location of the visible content within the overall content. It corresponds to the placement of the scroll box (thumb) along the scroll bar track. When the scroll box is at the top or left, the position is the minimum value of the range. At the bottom or right, the position is the maximum value of the range.



## Setting Scroll Bar Position


The SetScrollPos function is used to set the position of the scroll box within the scroll bar range. It takes four arguments:

- **hwnd:** The window handle of the window containing the scroll bar
- **iBar:** Specifies the scroll bar type (SB\_VERT for vertical, SB\_HORZ for horizontal).
- **iPos:** The new position of the scroll box within the range (must be between the minimum and maximum values).
- **bRedraw:** A Boolean value indicating whether to redraw the scroll bar based on the new position (TRUE for redrawing, FALSE to avoid unnecessary redraws).

## Querying Scroll Bar Range and Position

The [GetScrollRange](#) and [GetScrollPos](#) functions can be used to retrieve the current range and position of a scroll bar, respectively.


These functions provide access to the [scroll bar's state](#) and allow applications to adjust scrolling behavior accordingly.




## Windows' Responsibilities for Scroll Bars

Windows handles the [low-level interactions with scroll bars](#), providing the necessary functionality and visual feedback to the user. Its responsibilities include:


**Mouse Message Processing:** Windows handles all mouse events directed towards scroll bars, interpreting clicks and drags to initiate and control scrolling.




**Reverse-Video Flash:** When the user clicks within the scroll bar track, Windows provides a visual cue by flashing the area in reverse video, indicating that scrolling action is taking place.



**Thumb Movement:** As the user drags the scroll box (thumb) within the scroll bar, Windows updates its position accordingly, reflecting the user's intent to scroll through the content.



**Scroll Bar Messages:** Windows sends scroll bar messages to the window procedure of the window containing the scroll bar. These messages inform the application about scroll bar interactions, such as clicks, drags, and changes in position.



## Your Program's Responsibilities for Scroll Bars

While Windows handles the [low-level mechanics of scroll bars](#), your program plays a crucial role in managing the overall scrolling behavior and content updates:

**Scroll Bar Range Initialization:** You are responsible for setting the initial range of the scroll bar using the [SetScrollRange function](#). The range defines the minimum and maximum values associated with the scroll bar, representing the extent of the content that can be scrolled through.

**Scroll Bar Message Processing:** Your program's window procedure needs to [process the scroll bar messages sent by Windows](#). These messages provide information about scroll bar interactions and allow your program to react accordingly.

**Scroll Bar Thumb Update:** Based on the scroll bar messages and the [current position of the scroll box \(thumb\)](#), your program should update the position of the thumb to reflect the user's scrolling actions.

**Content Area Updates:** When the scroll bar position changes, [your program should update the contents of the client area](#) to display the corresponding portion of the content. This ensures that the visible content matches the user's scrolling actions.

## Scroll Bar Messages: Communicating Scroll Bar Interactions

Scroll bars provide a crucial user interface element for navigating through extensive content that exceeds the visible area of a window.

When [users interact with scroll bars](#), Windows sends messages to the window procedure of the window containing the scroll bar to inform the application about these interactions and enable appropriate responses.

### [WM\\_VSCROLL and WM\\_HSCROLL Messages](#)

Two primary messages are used for scroll bar interactions:

- [WM\\_VSCROLL](#): This message is sent for vertical scroll bars.
- [WM\\_HSCROLL](#): This message is sent for horizontal scroll bars.

Each mouse action on the scroll bar triggers at least two of these messages: one when the mouse button is pressed and another when it is released. This allows the application to track the user's scrolling actions and update the content accordingly.

#### wParam and lParam Message Parameters


Like all Windows messages, WM\_VSCROLL and WM\_HSCROLL messages are accompanied by two additional parameters:

- **wParam:** This parameter contains the notification code, which indicates the specific action the user is performing with the scroll bar.
- **lParam:** For scroll bars created as part of the main window, lParam can be ignored. However, for scroll bars created as child windows, lParam provides additional information, typically related to the child window's position.

#### Notification Codes

Notification codes are represented by identifiers that begin with **SB**, indicating "scroll bar." These codes specify the type of action the user is performing with the scroll bar. Some of the commonly used notification codes include:

- **SB\_LINEUP:** Scrolls one line up (vertical scroll bar).
- **SB\_LINEDOWN:** Scrolls one line down (vertical scroll bar).
- **SB\_PAGEUP:** Scrolls one page up (vertical scroll bar).
- **SB\_PAGEDOWN:** Scrolls one page down (vertical scroll bar).
- **SB\_THUMBPOSITION:** Indicates the current position of the scroll box (thumb).
- **SB\_THUMBTRACK:** Indicates that the scroll box (thumb) is being dragged.
- **SB\_TOP:** Scrolls to the top (vertical scroll bar).
- **SB\_BOTTOM:** Scrolls to the bottom (vertical scroll bar).
- **SB\_LEFT:** Scrolls to the left (horizontal scroll bar).
- **SB\_RIGHT:** Scrolls to the right (horizontal scroll bar).
- **SB\_ENDSCROLL:** Indicates that the scroll bar operation has ended.



The scrollbar image you sent shows a **vertical and horizontal scrollbar** with a scroll box (thumb) positioned at the top of the scrollbar track. This indicates that the visible content is at the top of the overall content.

The **scrollbar track** is divided into a number of equal segments, each representing a specific portion of the overall content.

The **scroll box (thumb)** is sized to indicate the relative amount of visible content. For instance, a large scroll box indicates that a significant portion of the content is visible, while a small scroll box indicates that only a small portion of the content is visible.

The scrollbar arrows at either end of the scrollbar track allow users to scroll up or down through the content.

Clicking on one of the arrows **scrolls the content in the corresponding direction** by a small amount.

Alternatively, users can drag the **scroll box (thumb)** along the scrollbar track to scroll through the content more quickly.

The scrollbar image also includes a number of other elements:

- **Scroll bar track:** The vertical bar that the scroll box (thumb) moves along.
- **Scroll box (thumb):** The movable indicator that represents the approximate position of the visible content within the overall content.
- **Scroll bar arrows:** The arrows at either end of the scrollbar track that allow users to scroll up or down through the content.
- **Scroll bar range:** The minimum and maximum values associated with the scroll bar, representing the extent of the content that can be scrolled through.
- **Scroll bar position:** The current location of the visible content within the overall content, indicated by the placement of the scroll box (thumb) along the scrollbar track.

By interpreting these notification codes, the application can determine the user's scrolling intent and make the necessary changes to the visible content. This ensures that the user's scrolling actions are reflected in the displayed information.

## **SB\_THUMBTRACK and SB\_THUMBPOSITION Notification Codes**

When the user drags the scroll box (thumb), scroll bar messages with notification codes of SB\_THUMBTRACK and SB\_THUMBPOSITION are generated. These codes provide information about the current and final positions of the scroll box.

**SB\_THUMBTRACK:** The high word of wParam represents the current position of the scroll box as the user is dragging it. This position is within the minimum and maximum values of the scroll bar range.

**SB\_THUMBPOSITION:** The high word of wParam represents the final position of the scroll box when the user released the mouse button.

## **Processing SB\_THUMBTRACK or SB\_THUMBPOSITION Messages**

Your program can choose to process either SB\_THUMBTRACK or SB\_THUMBPOSITION messages, but not both. The choice depends on how you want to handle the scrolling behavior.

**Processing SB\_THUMBTRACK Messages:** If you process SB\_THUMBTRACK messages, you can update the contents of the client area as the user is dragging the thumb, providing real-time feedback. However, this approach can be more demanding on the program's resources.

**Processing SB\_THUMBPOSITION Messages:** If you process SB\_THUMBPOSITION messages, you will only update the contents of the client area when the user stops dragging the thumb. This approach is less demanding but may not provide as smooth of a scrolling experience.

## **SB\_TOP, SB\_BOTTOM, SB\_LEFT, and SB\_RIGHT Notification Codes**

The notification codes SB\_TOP, SB\_BOTTOM, SB\_LEFT, and SB\_RIGHT indicate that the scroll bar has been moved to its minimum or maximum position. However, these codes are never sent for scroll bars created as part of your application window.

## **32-bit Scroll Bar Range**

While it is possible to use 32-bit values for the scroll bar range, the high word of wParam, which is only a 16-bit value, cannot properly indicate the position for SB\_THUMBTRACK and SB\_THUMBPOSITION actions. In this case, you need to use the GetScrollInfo function to retrieve the necessary information.


## ***SYSMETS PROGRAM***

*You can find this code in the chapter 4 sysmets2 after running it, you will see the same program, but with a scroll bar that moves when clicked. In-depth explanation of the SYSMETS2.C code, with specific details and insights:*

### **Header Files and Preprocessor Directives**

**windows.h:** This header file provides essential Windows programming functionalities, including function declarations, data types, and macros. It's crucial for interacting with the Windows operating system and managing window elements.

**sysmets.h:** This custom header file presumably contains definitions and structures related to the system metrics being displayed. It serves as a local information repository for the application's specific data.



## WndProc Function: Message Handling



**WM\_CREATE Message:** This message indicates the creation of the application window. In response, the code performs essential initialization tasks:

- **Text Metrics Retrieval:** It retrieves the text metrics for the current font using GetTextMetrics. This provides information about character width and height, which is crucial for positioning text elements within the window.
- **Scroll Bar Range Setup:** It sets the scroll bar range using SetScrollRange. This defines the minimum and maximum values of the scroll bar, ensuring that the user can scroll through the entire list of system metrics.
- **Initial Scroll Position:** It initializes the current scroll position to 0 using SetScrollPos. This sets the starting point for displaying the system metrics within the visible area of the window.

**WM\_SIZE Message:** This message is triggered when the window size changes. The code simply updates the cyClient variable, which stores the client area height, to reflect the new dimensions. This information is used later for adjusting the layout of the displayed text.


**WM\_VSCROLL Message:** This message is generated when the user interacts with the scroll bar. The code handles various scroll bar actions:

- **Line Up/Down:** For line-by-line scrolling, it adjusts the iVscrollPos variable accordingly, either decreasing or increasing it by 1.
- **Page Up/Down:** For page-by-page scrolling, it adjusts the iVscrollPos variable by the height of the client area in character units. This ensures that a full page of system metrics is scrolled at a time.
- **Thumb Position:** When the user drags the scroll box (thumb), the code updates the iVscrollPos variable to the high word of wParam, which represents the new position of the thumb.
- **Invalidation and Update:** After adjusting the scroll position, the code ensures it stays within the valid range using max and min functions. If the scroll position changes, it updates the scroll bar position using SetScrollPos and invalidates the window's client area using InvalidateRect. This triggers a repaint to reflect the updated scroll position and display the corresponding system metrics.

**WM\_PAINT Message:** This message prompts the code to repaint the window's client area. The code iterates through the system metrics array and draws each metric's label, description, and corresponding value using the TextOut function. This ensures that the system metrics are presented in a clear and organized manner.

**WM\_DESTROY Message:** This message indicates the destruction of the application window. The code responds by sending a PostQuitMessage to the message queue, signaling the end of the application's execution.

## Main Function: Application Entry Point



**Window Class Registration:** The WinMain function starts by registering the window class using RegisterClass. This defines the characteristics of the window, such as its style, window procedure, instance handle, icon, cursor, background brush, and class name.

**Window Creation:** It creates the window using the CreateWindow function. This allocates memory for the window structure, establishes its position and size, and associates it with the previously registered window class.

**Window Visibility and Update:** It displays the window using the ShowWindow function, making it visible to the user. It then updates the window's layout and contents using the UpdateWindow function.

**Message Loop:** It enters a message loop using a while loop. This continuously retrieves messages from the message queue using GetMessage, translates them using TranslateMessage, and dispatches them to the WndProc callback function using DispatchMessage.

**Application Termination:** The message loop continues until a WM\_QUIT message is received. In this case, the GetMessage function returns 0, signaling the end of the message queue. The WinMain function exits the loop and returns the message parameter from GetMessage.

## Vertical Scroll Bar Integration

The CreateWindow call now includes the WS\_VSCROLL window style in the third argument, adding a vertical scroll bar to the window.

This allows users to scroll through the list of system metrics if the entire list cannot be displayed within the visible area of the window.

System Metric	Description	Value
SM_CXSCREEN	Screen width in pixels	1280
SM_CYSCREEN	Screen height in pixels	1024
SM_CXVSCROLL	Vertical scroll width	17
SM_CYHSCROLL	Horizontal scroll height	17
SM_CYCAPTION	Caption bar height	23
SM_CXBORDER	Window border width	1
SM_CYBORDER	Window border height	1
SM_CXFIXEDFRAME	Dialog window frame width	3
SM_CYFIXEDFRAME	Dialog window frame height	3
SM_CYVTHUMB	Vertical scroll thumb height	17
SM_CXHTHUMB	Horizontal scroll thumb width	17
SM_CXICON	Icon width	32
SM_CYICON	Icon height	32
SM_CXCURSOR	Cursor width	32
SM_CYCURSOR	Cursor height	32
SM_CYMENU	Menu bar height	20
SM_CXFULLSCREEN	Full screen client area width	1280
SM_CYFULLSCREEN	Full screen client area height	953
SM_CYKANJIWINDOW	Kanji window height	0
SM_MOUSEPRESENT	Mouse present flag	1
SM_CYVSCROLL	Vertical scroll arrow height	17
SM_CXHSCROLL	Horizontal scroll arrow width	17
SM_DEBUG	Debug version flag	0
SM_SWAPBUTTON	Mouse buttons swapped flag	0
SM_CXMIN	Minimum window width	136
SM_CYMIN	Minimum window height	39
SM_CXSIZE	Min/Max/Close button width	36
SM_CYSIZE	Min/Max/Close button height	22
SM_CXSIZEFRAME	Window sizing frame width	4
SM_CYSIZEFRAME	Window sizing frame height	4
SM_CXMINTRACK	Minimum window tracking width	136
SM_CYMINTRACK	Minimum window tracking height	39
SM_CXDOUBLECLK	Double click x tolerance	4
SM_CYDOUBLECLK	Double click y tolerance	4
SM_CXICONSPACING	Horizontal icon spacing	75
SM_CYICONSPACING	Vertical icon spacing	75
SM_MENUDROPALIGNMENT	Left or right menu drop	0
SM_PENWINDOWS	Pen extensions installed	0
SM_DBCSENABLED	Double-Byte Char Set enabled	0
SM_CMOUSEBUTTONS	Number of mouse buttons	3
SM_SECURE	Security present flag	0
SM_CXEDGE	3-D border width	2
SM_CYEDGE	3-D border height	2
SM_CXMINSPACING	Minimized window spacing width	160
SM_CYMINSPACING	Minimized window spacing height	28
SM_CXSMICON	Small icon width	16
SM_CYSMICON	Small icon height	16

## Setting Scroll Bar Range and Initial Position

In response to the [WM\\_CREATE message](#), the WndProc window procedure **sets the scroll bar range and initial position using the SetScrollRange and SetScrollPos functions**, respectively.

**SetScrollRange:** This function establishes the minimum and maximum values of the scroll bar, ensuring that it can cover the entire range of system metrics (0 to NUMLINES - 1).

**SetScrollPos:** This function initializes the current scroll position to 0, placing the first line of system metrics at the top of the client area.

## Scroll Position Variable

A static variable named iVscrollPos is defined within the WndProc window procedure to **track the current position of the scroll bar thumb**. This variable plays a crucial role in managing the scroll bar behavior and updating the displayed system metrics.

## Handling WM\_VSCROLL Messages

The WndProc window procedure handles various WM\_VSCROLL messages to respond to user interactions with the scroll bar:

**SB\_LINEUP and SB\_LINEDOWN:** For line-by-line scrolling, the scroll position is adjusted by 1, either decreasing or increasing it accordingly.

**SB\_PAGEUP and SB\_PAGEDOWN:** For page-by-page scrolling, the scroll position is adjusted by the height of the client area in character units (cyClient divided by cyChar). This ensures that a full page of system metrics is scrolled at a time.

**SB\_THUMBPOSITION:** When the user drags the scroll box (thumb), the new thumb position is stored in the high word of wParam. This value is then assigned to iVscrollPos to reflect the current scroll position.

**SB\_ENDSCROLL and SB\_THUMBTRACK:** These messages are ignored in this version of the program.

## Validating Scroll Position and Updating Window

After adjusting the scroll position based on the WM\_VSCROLL message type, the code ensures that the value of iVscrollPos remains within the valid range of the scroll bar using the min and max macros.

If the scroll position has changed, it is updated using SetScrollPos, and the entire window is invalidated using InvalidateRect to trigger a repaint.

## Updating Client Area

When repainting the client area in response to a WM\_PAINT message, the y-coordinate of each line is calculated using the formula  $cyChar * (i - iVscrollPos)$ .

This formula takes into account the current scroll position, ensuring that the appropriate lines of system metrics are displayed within the visible area of the window.

## *Painting in Response to WM\_PAINT*

The preferred approach in Windows programming is to handle all client area painting in response to a WM\_PAINT message.


This ensures that the entire **client area is repainted consistently** and efficiently.

Duplicating painting logic in response to other messages can lead to **redundancy** and **potential inconsistencies**.

## *Discipline of WM\_PAINT-based Painting*

While it may seem indirect, this approach offers several benefits:


**Code Clarity and Maintainability:** By centralizing painting logic in the WM\_PAINT handler, the code becomes more organized and easier to maintain.



**Consistent Repainting:** The WM\_PAINT handler should be capable of repainting the entire client area, ensuring that the window's contents are always displayed correctly.



**Efficiency:** Windows optimizes painting operations, so relying on WM\_PAINT messages for repainting can lead to better performance.



### InvalidateRect for Invalidating Client Area

When a program needs to trigger a repaint of a specific area or the entire client area, it can use the **InvalidateRect** function.

This marks the specified rectangles as invalid, prompting Windows to generate a WM\_PAINT message.

### Considerations with InvalidateRect

While InvalidateRect is useful for invalidating specific areas, it's important to note that WM\_PAINT messages are handled with **lower priority** than other messages.

This means that **if the system is busy with other tasks**, it may take some time for the WM\_PAINT message to be processed, resulting in visible "holes" in the window.

### UpdateWindow for Immediate Repainting

To address this delay, you can use the **UpdateWindow function** after calling InvalidateRect.

This causes the window procedure to be **immediately called with a WM\_PAINT message**, bypassing the message queue and ensuring immediate repainting of the invalidated area.

### UpdateWindow's Role in Window Creation

**UpdateWindow** is also used during window creation to trigger the initial painting of the client area.

When a window is first created, the entire client area is marked as invalid, and UpdateWindow directs the window procedure to paint it accordingly.

## Conclusion

SYSMETS2.C introduces vertical scrolling functionality, allowing users to navigate through the list of system metrics efficiently. The code effectively manages the scroll bar position and updates the displayed content accordingly.

However, this implementation is still wasteful and inefficient, as it renders lines of text outside the client area. Improvements will be made to address this issue in subsequent versions.

# BUILDING A BETTER SCROLLBAR

## Obsolete Scroll Bar Functions


The scroll bar functions introduced in earlier versions of Windows, including SetScrollRange, SetScrollPos, GetScrollRange, and GetScrollPos, are considered obsolete in the Win32 API.

While they are still functional and can handle 32-bit arguments, they have been superseded by newer functions that offer additional capabilities.

## New Scroll Bar Functions: SetScrollInfo and GetScrollInfo

The Win32 API introduced two new scroll bar functions: [SetScrollInfo](#) and [GetScrollInfo](#). These functions provide all the functionality of the older functions and add two significant enhancements:

**Thumb Size Control:** The size of the scroll bar thumb can now be **dynamically adjusted** based on the page size, which represents the portion of the document displayed in the window. This allows for a more **visually intuitive representation** of the document's size and scroll position.



**32-bit Thumb Position Retrieval:** The GetScrollInfo function provides access to the actual 32-bit value of the thumb position, even if the range exceeds 65,536. This addresses a limitation of the older functions, which only provided 16 bits of thumb position information.

***Benefits of SetScrollInfo and GetScrollInfo. These new functions offer several advantages over the obsolete ones:***

**Enhanced Functionality:** They provide greater control over the appearance and behavior of scroll bars, including thumb size adjustment and accurate thumb position retrieval.



**Future-Proofing:** They are designed to handle larger ranges and provide more flexibility for future scroll bar implementations.



**Improved User Experience:** By enabling dynamic thumb sizing and accurate position tracking, they contribute to a more intuitive and responsive user experience.



*Here is an in-depth explanation of the syntax and usage of the SetScrollInfo and GetScrollInfo functions:*

### Function Syntax

```
SetScrollInfo(hwnd, iBar, &si, bRedraw);
GetScrollInfo(hwnd, iBar, &si);
```

### Parameters

**hwnd:** Handle of the window that contains the scroll bar.

**iBar:** Specifies which scroll bar to set or get information for. It can be SB\_VERT for a vertical scroll bar, SB\_HORZ for a horizontal scroll bar, or SB\_CTL for a scroll bar control.

**&si:** A pointer to a SCROLLINFO structure that contains the scroll bar information to set or get.

**bRedraw:** (For SetScrollInfo only) A Boolean value indicating whether to redraw the scroll bar after applying the changes. TRUE to redraw, FALSE to skip redrawing.

### SCROLLINFO Structure

The SCROLLINFO structure, defined as follows, holds the scroll bar information:

```
typedef struct tagSCROLLINFO {
    UINT cbSize; // Size of the SCROLLINFO structure
    UINT fMask; // Flags indicating which fields to set or get
    int nMin; // Minimum value of the scroll bar range
    int nMax; // Maximum value of the scroll bar range
    UINT nPage; // Page size, used for proportional thumb sizing
    int nPos; // Current position of the scroll bar thumb
    int nTrackPos;
    // Current tracking position of the scroll bar thumb
    // (only valid during SB_THUMBTRACK or SB_THUMBPOSITION messages)
} SCROLLINFO, * PSCROLLINFO;
```

## Setting the cbSize Field

Before calling either SetScrollInfo or GetScrollInfo, you must initialize the cbSize field of the SCROLLINFO structure to the size of the structure:

```
si.cbSize = sizeof(si);
```

This allows for future compatibility with potential enhancements to the structure without breaking existing programs.

## Example Usage

To set the scroll bar range for a vertical scroll bar:

```
SCROLLINFO si;
si.cbSize = sizeof(si);
si.fMask = SIF_RANGE;
si.nMin = 0;
si.nMax = 100;
SetScrollInfo(hwnd, SB_VERT, &si, TRUE);
```

To retrieve the current position of a horizontal scroll bar:

```
SCROLLINFO si;
si.cbSize = sizeof(si);
si.fMask = SIF_POS;
GetScrollInfo(hwnd, SB_HORZ, &si);
int currentPos = si.nPos;
```

## *Flag Syntax and Usage*

The fMask field of the SCROLLINFO structure is used to specify which fields of the structure to set or get. The flags begin with the SIF prefix and can be combined using the bitwise OR () operator.

### SIF\_RANGE Flag

This flag is used to [set or get the scroll bar range](#).

When [used with SetScrollInfo](#), the nMin and nMax fields of the SCROLLINFO structure must be set to the desired minimum and maximum values, respectively.

When [used with GetScrollInfo](#), the nMin and nMax fields will be updated to reflect the current scroll bar range.

### SIF\_POS Flag

This flag is used to [set or get the current position of the scroll bar](#).

When [used with SetScrollInfo](#), the nPos field of the SCROLLINFO structure must be set to the desired scroll bar position.

When [used with GetScrollInfo](#), the nPos field will be updated to reflect the current scroll bar position.

### SIF\_PAGE Flag

This flag is used to [set or get the page size](#), which determines the proportional size of the scroll bar thumb.

When [used with SetScrollInfo](#), the nPage field of the SCROLLINFO structure must be set to the desired page size.

When [used with GetScrollInfo](#), the nPage field will be updated to reflect the current page size.

### SIF\_TRACKPOS Flag

This flag is used to [get the current 32-bit thumb position](#) when processing a WM\_VSCROLL or WM\_HSCROLL message with a notification code of SB\_THUMBTRACK or SB\_THUMBPOSITION.

The [nTrackPos field](#) of the SCROLLINFO structure will be updated to reflect the current thumb position.

### SIF\_DISABLENOSCROLL Flag

This flag is used with SetScrollInfo to [disable the scroll bar](#) instead of hiding it when the scroll bar arguments would normally make it invisible.

## SIF\_ALL Flag

This flag is a combination of SIF\_RANGE, SIF\_POS, SIF\_PAGE, and SIF\_TRACKPOS. It is useful for setting the scroll bar arguments during a WM\_SIZE message or processing a scroll bar message.

**SIF stands for Scroll Information Flag.** It is a bitmask used in the SetScrollInfo() and GetScrollInfo() functions to specify which fields of the SCROLLINFO structure are to be set or retrieved.

Here's a table summarizing the flag usage:

Flag	Usage
SIF_RANGE	Set or get the scroll bar range
SIF_POS	Set or get the current position of the scroll bar
SIF_PAGE	Set or get the page size
SIF_TRACKPOS	Get the current 32-bit thumb position
SIF_DISABLENOSCROLL	Disable the scroll bar instead of hiding it
SIF_ALL	Combination of SIF_RANGE, SIF_POS, SIF_PAGE, and SIF_TRACKPOS

The SetScrollInfo and GetScrollInfo functions represent a significant advancement in scroll bar control and provide a more powerful and flexible approach to managing scroll bars in Windows applications.

## Determining the Maximum Scroll Position

In SYSMETS2, the scroll bar range is unnecessarily large, extending beyond the visible area of the client area.

To address this, we can dynamically adjust the scroll bar range based on the window size and the height of the text elements.

## Calculating Scroll Bar Range Using WM\_SIZE

Instead of setting the scroll bar range during WM\_CREATE, we can defer it until the WM\_SIZE message is received, ensuring that the range is adjusted based on the actual window dimensions.

```
iVscrollMax = max(0, NUMLINES - cyClient / cyChar);
SetScrollRange(hwnd, SB_VERT, 0, iVscrollMax, TRUE);
```

In this code, NUMLINES represents the total number of lines of information, cyClient is the client area height, and cyChar is the character height. The max function ensures that the maximum scroll position (iVscrollMax) is never less than 0.

## Using Scroll Bar Page Size for Automatic Range Adjustment

The new scroll bar functions introduce the concept of scroll bar page size, which represents the portion of the document displayed in the window.

This feature simplifies the calculation of the maximum scroll position and ensures that the scroll bar thumb is sized proportionally to the visible content.

```
si.cbSize = sizeof(SCROLLINFO);
si.fMask = SIF_RANGE | SIF_PAGE;
si.nMin = 0;
si.nMax = NUMLINES - 1;
si.nPage = cyClient / cyChar;
SetScrollInfo(hwnd, SB_VERT, &si, TRUE);
```

In this code, si is a SCROLLINFO structure, NUMLINES is the total number of lines, and cyClient and cyChar are as defined earlier.

The SetScrollInfo function automatically adjusts the maximum scroll position based on the page size (si.nPage), ensuring that the scroll bar range is appropriate for the visible content.

## Handling Large Page Sizes

If the [page size is equal to or larger than the scroll bar range](#), Windows automatically hides the scroll bar. This is a convenient behavior that [eliminates unnecessary scroll bar controls](#) when the entire content is visible.

## Disabling Scroll Bar Instead of Hiding

If you prefer to keep the scroll bar visible even when the page size is large, you can use the [SIF\\_DISABLENOSCROLL flag](#) when calling SetScrollInfo.

This will [disable the scroll bar](#) instead of hiding it, allowing users to manually scroll through the content if needed.

By employing these techniques, you can [prevent excessive scrolling](#) and ensure that the scroll bar behavior is consistent with the actual amount of visible content.

I was able to run sysmets3 code. It's actually a better scrollbar with a hide feature:

Get System Metrics No. 3		
SM_CXSCREEN	Screen width in pixels	1280
SM_CYSCREEN	Screen height in pixels	1024
SM_CXVSCROLL	Vertical scroll width	17
SM_CYHSCROLL	Horizontal scroll height	17
SM_CYCAPTION	Caption bar height	23
SM_CXBORDER	Window border width	1
SM_CYBORDER	Window border height	1
SM_CXFIXEDFRAME	Dialog window frame width	3
SM_CYFIXEDFRAME	Dialog window frame height	3
SM_CYTHUMB	Vertical scroll thumb height	17
SM_CXHTHUMB	Horizontal scroll thumb width	17
SM_CXICON	Icon width	32
SM_CYICON	Icon height	32
SM_CXCURSOR	Cursor width	32
SM_CYCURSOR	Cursor height	32
SM_CYMENU	Menu bar height	20
SM_CXFULLSCREEN	Full screen client area width	1280
SM_CYFULLSCREEN	Full screen client area height	953
SM_CYKANJIWINDOW	Kanji window height	0
SM_MOUSEPRESENT	Mouse present flag	1
SM_CYSVSCROLL	Vertical scroll arrow height	17
SM_CXHSCROLL	Horizontal scroll arrow width	17
SM_DEBUG	Debug version flag	0
SM_SWAPBUTTON	Mouse buttons swapped flag	0
SM_CXMIN	Minimum window width	136
SM_CYMIN	Minimum window height	39
SM_CXSIZE	Min/Max/Close button width	36
SM_CYSIZE	Min/Max/Close button height	22
SM_CXSIZEFRAME	Window sizing frame width	4
SM_CYSIZEFRAME	Window sizing frame height	4
SM_CXMINTRACK	Minimum window tracking width	136
SM_CYMINTRACK	Minimum window tracking height	39
SM_CXDDOUBLECLK	Double click x tolerance	4
SM_CYDDOUBLECLK	Double click y tolerance	4
SM_CXICONSPACING	Horizontal icon spacing	75
SM_CYICONSPACING	Vertical icon spacing	75
SM_MENUDROPALIGNMENT	Left or right menu drop	0
SM_PENWINDOWS	Pen extensions installed	0
SM_DBCSENABLED	Double-Byte Char Set enabled	0
SM_CMOUSEBUTTONS	Number of mouse buttons	3
SM_SECURE	Security present flag	0
SM_CXEDGE	3-D border width	2

And an unhide feature, and it flows better than the former one:

Get System Metrics No. 3		
SM_CXSCREEN	Screen width in pixels	1280
SM_CYSCREEN	Screen height in pixels	1024
SM_CXVSCROLL	Vertical scroll width	17
SM_CYHSCROLL	Horizontal scroll height	17
SM_CYCAPTION	Caption bar height	23
SM_CXBORDER	Window border width	1
SM_CYBORDER	Window border height	1
SM_CXFIXEDFRAME	Dialog window frame width	3
SM_CYFIXEDFRAME	Dialog window frame height	3
SM_CYVTHUMB	Vertical scroll thumb height	17
SM_CXHTHUMB	Horizontal scroll thumb width	17
SM_CXICON	Icon width	32
SM_CYICON	Icon height	32
SM_CXCURSOR	Cursor width	32
SM_CYCURSOR	Cursor height	32
SM_CYMENU	Menu bar height	20
SM_CXFULLSCREEN	Full screen client area width	1280
SM_CYFULLSCREEN	Full screen client area height	953
SM_CYKANJIWINDOW	Kanji window height	0
SM_MOUSEPRESENT	Mouse present flag	1
SM_CVSCROLL	Vertical scroll arrow height	17
SM_CXHSCROLL	Horizontal scroll arrow width	17
SM_DEBUG	Debug version flag	0
SM_SWAPBUTTON	Mouse buttons swapped flag	0
SM_CXMIN	Minimum window width	136
SM_CYMIN	Minimum window height	39
SM_CXSIZE	Min/Max/Close button width	36
SM_CYSIZE	Min/Max/Close button height	22
SM_CXSIZEFRAME	Window sizing frame width	4
SM_CYSIZEFRAME	Window sizing frame height	4
SM_CXMINTRACK	Minimum window tracking width	136
SM_CYMINTRACK	Minimum window tracking height	39
SM_CXDOUBLECLK	Double click x tolerance	4
SM_CYDOUBLECLK	Double click y tolerance	4
SM_CXICONSPACING	Horizontal icon spacing	75
SM_CYICONSPACING	Vertical icon spacing	75
SM_MENUDROPALIGNMENT	Left or right menu drop	0
SM_PENWINDOWS	Pen extensions installed	0
SM_DBCSENABLED	Double-Byte Char Set enabled	0
SM_CMOUSEBUTTONS	Number of mouse buttons	3
SM_SECURE	Security present flag	0
SM_CXEDGE	3-D border width	2

## Reliance on Windows for Scroll Bar Management

SYSMETS3 simplifies scroll bar management by relying on Windows to handle most of the scroll bar information and boundary checking. Instead of manually tracking scroll bar positions and enforcing limits, the program retrieves the current scroll bar information at the beginning of WM\_VSCROLL and WM\_HSCROLL processing.

## Handling Scroll Bar Notifications

The program adjusts the scroll bar position based on the notification code received in these messages. For instance, if the notification code indicates that the scroll bar thumb has been moved, the program adjusts the scroll bar position accordingly.

## **Setting and Retrieving Scroll Bar Positions**

After adjusting the scroll bar position, SYSMETS3 calls SetScrollInfo to inform Windows of the new position. This allows Windows to maintain consistent scroll bar information across the system. To verify the updated position, the program calls GetScrollInfo and checks if the position was adjusted by Windows due to any boundary constraints.

## **Utilizing ScrollWindow for Efficient Scrolling**

Instead of repainting the entire client area whenever scrolling occurs, SYSMETS3 employs the ScrollWindow function to perform the scrolling operation more efficiently. This function scrolls the client area horizontally and vertically based on the specified amounts.

## **Invalidation and WM\_PAINT Message Handling**

By setting the last two arguments of ScrollWindow to NULL, the program indicates that the entire client area should be scrolled. Windows automatically invalidates the exposed rectangle in the client area, triggering a WM\_PAINT message. This eliminates the need to explicitly call InvalidateRect.

## **Ignoring SB\_THUMBTRACK for Horizontal Scrolling**

In WM\_HSCROLL processing, SYSMETS3 ignores the SB\_THUMBTRACK notification code and only responds to SB\_THUMBPOSITION. This means that the program does not scroll the window horizontally while the user is dragging the thumb on the horizontal scroll bar. Instead, it updates the scroll bar position only when the user releases the mouse button.

## **Responsive Vertical Scrolling**

In contrast to horizontal scrolling, SYSMETS3 scrolls the window vertically in real-time as the user drags the thumb on the vertical scroll bar. This is achieved by capturing SB\_THUMBTRACK messages and updating the scroll bar position accordingly.

## **Potential Performance Issues with Frequent Scrolling**

While responsive scrolling provides a more intuitive user experience, it can lead to performance issues if users rapidly drag the scroll bar thumb back and forth. This is because the program continuously updates the scroll position and repaints the client area in response to these rapid movements.

## **Considering Alternative Scrolling Strategies for Slow Machines**

To optimize performance on slower machines, SYSMETS3 could incorporate the SB\_SLOWMACHINE flag when calling GetSystemMetrics. This flag provides information about the system's processing speed and could be used to trigger less frequent scrolling updates or utilize alternative scrolling mechanisms.

## **Efficient WM\_PAINT Handling**

To optimize WM\_PAINT processing, SYSMETS3 identifies the lines within the invalid rectangle and rewrites only those lines instead of repainting the entire client area. This approach reduces the amount of repainting required and improves overall performance.

# **USERS AND SCROLLBAR**

## **User Preferences and Mouse Usage**

While mice have become the standard input device for personal computers, some users still prefer to operate their systems primarily using the keyboard. This preference may be due to familiarity, comfort, or accessibility considerations.

## **Early Windows and Mouseless Operation**

In the early versions of Windows, a significant portion of users relied solely on the keyboard for navigation and interaction. This was reflected in the design of the operating system and many applications, which were designed to be fully functional without mouse input.

**Providing keyboard alternatives for scroll bar operations offers several advantages:**

**Accessibility:** Users with limited hand mobility or dexterity may find it easier to use keyboard shortcuts rather than relying on a mouse.



**Consistency:** Keyboard shortcuts provide a consistent and predictable way to interact with scroll bars, regardless of the user's preference or ability to use a mouse.



**Efficiency:** Experienced users can often navigate through scroll bars more quickly using keyboard shortcuts than with a mouse.



#### Maintaining Compatibility with Older Windows Behavior

The inclusion of code that handles WM\_VSCROLL messages with notification codes SB\_TOP and SB\_BOTTOM in SYSMETS3 is likely intended to **maintain compatibility** with older versions of Windows, where these messages were sent for scroll bar operations.

#### Future Enhancements with Keyboard Interface

In the next chapter, you'll **explore techniques for implementing a keyboard interface for scroll bar operations**, allowing users to navigate through the content using keyboard shortcuts. This will enhance the program's accessibility and provide alternative input methods for those who prefer or require them.