Ant Tasks

# **Table of Contents**

| S] | LEE Management Task                         | . 2 | ) |
|----|---------------------------------------------|-----|---|
|    | Install Deployable Unit Sub-Task            | . 2 | ) |
|    | Uninstall Deployable Unit Sub-Task          | . 2 | ) |
|    | Activate Service Sub-Task                   | . 2 | ) |
|    | Deactivate Service Sub-Task                 | . 3 | 3 |
|    | Create Resource Adaptor Entity Sub-Task     | . 3 | 3 |
|    | Remove Resource Adaptor Entity Sub-Task     | . 3 | 3 |
|    | Activate Resource Adaptor Entity Sub-Task   | . 3 | 3 |
|    | Deactivate Resource Adaptor Entity Sub-Task | . 4 | Į |
|    | Bind Resource Adaptor Link Sub-Task         | . 4 | Į |
|    | Unbind Resource Adaptor Link Sub-Task       | . 4 | l |

JAIN SLEE includes some tasks for Apache Ant, which can be used for common management tasks done through , when the container is running. The tasks come bundled in *\$JBOSS\_HOME/server/default/deploy/restcomm-slee/lib/ant-tasks.jar*. To use these, the Ant script must include the following code:

```
cproperty environment="system" />
<property name="node" value="default" />
<property name="jboss.deploy" value="${system.JBOSS_HOME}/server/${node}/deploy" />
<path id="project.classpath">
    <fileset dir="${jboss.deploy}/restcomm-slee/lib">
        <include name="*.jar" />
    </fileset>
    <fileset dir="${system.JBOSS_HOME}/client">
        <include name="*.jar" />
    </fileset>
</path>
<property name="project.classpath" refid="project.classpath" />
<property name="jnpHost" value="127.0.0.1" />
cproperty name="jnpPort" value="1099" />
<taskdef name="slee-management"
    classname="org.mobicents.ant.MobicentsManagementAntTask"
    classpath="${project.classpath}" />
```

It is important to understand some properties set by the code above:

#### node

This property defines the server configuration profile to be used, for further information about those refer to [\_server\_profiles].

#### inpHost

The host/ip which Restcomm JAIN SLEE is bound.

#### jnpPort

The port which the JMX Agent is listening.



The property values can be overridden when invoking the Ant script. To do this, use the parameter - DpropertyName=propertyValue. For example, the server profile can be changed from default to all using -Dnode=all.

## **SLEE Management Task**

The slee-management task allows a script to manage JAIN SLEE deployable units, services and resource adapters. The operations, or sub-tasks, are done through.

```
<slee-management jnpport="${jnpPort}" host="${jnpHost}">
    <!-- sub-tasks -->
</slee-management>
```

The attributes have the same meaning as the properties listed in the script code to import the tasks here: [\_management\_tools\_ant\_tasks].

### **Install Deployable Unit Sub-Task**

The install sub-task installs JAIN SLEE the deployable unit jar pointed by the value of attribute url. Example of usage:

## **Uninstall Deployable Unit Sub-Task**

The uninstall sub-task uninstalls JAIN SLEE the deployable unit jar which was installed from the value of attribute url. Example of usage:

```
<slee-management jnpport="${jnpPort}" host="${jnpHost}">
        <uninstall url="file:///tmp/my-deployable-unit.jar" />
        </slee-management>
```

### **Activate Service Sub-Task**

The activateservice sub-task activates an already installed JAIN SLEE service, with the id specified by the value of attribute componentid. Example of usage:

### **Deactivate Service Sub-Task**

The deactivateservice sub-task deactivates an already installed JAIN SLEE service, with the id specified by the value of attribute componentid. Example of usage:

### **Create Resource Adaptor Entity Sub-Task**

The createraentity sub-task creates the resource adaptor entity with the name specified by the value of attribute entityname, for an already installed JAIN SLEE resource adaptor, with the id specified by the value of attribute componentid. Example of usage:

### Remove Resource Adaptor Entity Sub-Task

The removeraentity sub-task removes the resource adaptor entity with the name specified by the value of attribute entityname. Example of usage:

```
<slee-management host="${jnpHost}" jnpport="${jnpPort}">
    <removeraentity entityname="FooRA" />
</slee-management>
```

### **Activate Resource Adaptor Entity Sub-Task**

The activateraentity sub-task activates the resource adaptor entity with the name specified by the value of attribute entityname. Example of usage:

### **Deactivate Resource Adaptor Entity Sub-Task**

The deactivateraentity sub-task deactivates the resource adaptor entity with the name specified by the value of attribute entityname. Example of usage:

```
<slee-management host="${jnpHost}" jnpport="${jnpPort}">
     <deactivateraentity entityname="FooRA" />
</slee-management>
```

### **Bind Resource Adaptor Link Sub-Task**

The bindralinkname sub-task binds the resource adaptor link with the name specified by the value of attribute linkname, for an already active JAIN SLEE resource adaptor entity, with the name specified by the value of attribute entityname. Example of usage:

### **Unbind Resource Adaptor Link Sub-Task**

The unbindralinkname sub-task unbinds the resource adaptor link with the name specified by the value of attribute linkname. Example of usage: