Using SPECFEM3D_Cartesian-2.1 for ASKI - Analysis of Sensitivity

and Kernel Inversion, version 0.3

Florian Schumacher¹ and Wolfgang Friederich¹

¹Ruhr-Universität Bochum

September 12, 2013

Copyright ©2013 Florian Schumacher. Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

This documentation was written in the hope that it will be useful to the user, but it *cannot be assured* that it is accurate in every respect or complete in any sense.

Please do not hesitate to improve this documentation by incorporating your experiences with SPECFEM3D for ASKI and your personal experience of getting used to it.

Furthermore, my moderate experience with LATEX may well give rise to improving the document style, hence the readability of the manual as a whole, as well as the coding style of the .tex file.

The LATEX source files and all related components of this document are contained in the SPECFEM3D_Cartesian-2.1 for ASKI 0.3 package, available via http://www.rub.de/ASKI

Florian Schumacher, 2013

Guide Through This Manual

We assume that you have sufficient knowledge of how to run the regular SPECFEM3D_Cartesian code.

For details on how to extend the regularly installed $SPECFEM3D_Cartesian-2.1$ code to produce output for ASKI, please read section 8.

Before you start using the code to produce output for ASKI, please consider the general comments in section 1.

If you are going to use the automated python script

 $run_specfem3dCartesianForASKI_simulations.py$ then please start reading section 3.

If you want to conduct one single simulation producing some output for $\,\,\text{ASKI}$, please start reading section 2.

Section 7 is intened to be used as a reference section only.

Bracketed comments starting with "TODO IN THE FUTURE:" are intended to mark ideas for future work. So please ignore if you are just applying the code.

Contents

1	Gen	eral Stuff to Consider	4	
2	One Single Simulation		4	
3	Usin	g Automated Python Script for Doing Several Simulations	ons 4	
	3.1	Manually Setting Par_file_ASKI	5	
	3.2	Manually Setting FORCESOLUTION	5	
	3.3	Manually Setting CMTSOLUTION	5	
	3.4	Manually Setting STATIONS	6	
4	Imp	orting the currently inverted model for next iteration step	6	
5	Prep	Preparing Synthetic Data as Expected by ASKI		
6	Prep	paring synthetically computed "measured" data as expected by ASKI	7	
7	File	Par_file_ASKI	7	
	7.1	ASKI output	7	
	7.2	Frequency discretization	8	
	7.3	Inversion grid	8	
8	Exte	end SPECFEM3D_Cartesian-2.1 to produce output for ASKI	9	
	8.1	Download and Dependencies	10	
	8.2	Installation	10	
\mathbf{G}	NU Fı	ree Documentation License	12	

1 General Stuff to Consider

- parameters FILE_KERNEL_REFERENCE_MODEL and FILE_WAVEFIELD_POINTS of the parameter file for a specific iteration step must be set to some main ASKI output file, which is the basefile name of ASKI_outfile extendet by .main, see 7.1. Use the main ASKI output file of some arbitrary ASKI output, e.g. the kernel displacement output of the first source.
- As there is a fixed order assumed of ASKI wavefield points (by procs and local element numbering), the computation of many kernels (e.g. for many seismic paths in an inversion) can only be consistent, if the *same* mesh decomposition and the *same* number of procs is used at all times (for those kernels you want to use together, e.g. all kernels in your specific iteration step of an inversion). It may, hence, be sensible to use the same MPI Databases for all SPECFEM3D for ASKI simulations (adjust your script process.sh in such a way, that you do not always recompile and decompose MESH, but only call the solver again (with changed parameter files and source files).
- there is (probably?!) no proper support for multiple sources in case of producing output for ASKI.
- Green tensor simulations are done using value ALT in the station definition as the FORCESOLUTION depth value, in order to allow receivers to be located not only on the surface. It, hence, may be sensible to throughoutly use USE_SOURCES_RECVS_Z = .true. in SPECFEM3D/src/shared/constants.h.
- As the coordinates of wavefield points (and, hence, inversion grid coordinates) SPECFEM3D for ASK uses:

First coordinate = X, second coordinate = Y, third coordinate = Z.

• ...

2 One Single Simulation

As usual, you need to do (external or internal) meshing for the appropriate (current) background model. See section 4 for details on how to import the current model of an inversion (the model of the last iteration step) into SPECFEM3D.

Set the regular SPECFEM3D files Par_file, CMTSOLUTION / FORCESOLUTION and STATIONS (standard SPECFEM3D functionality; only if you want to record any seismograms). Additionally, you need to set file Par_file_ASKI to desired values. The file is described in detail in section 7.

After that, you are ready to run the code. As there is no ASKI dependent change of SPECFEM3D components which are sensitive to compiling, you do not need to recompile the SPECFEM3D code every time you run a SPECFEM3D simulation for ASKI.

3 Using Automated Python Script for Doing Several Simulations

As usual, you need to do (external or internal) meshing for the appropriate (current) background model. See section 4 for details on how to import the current model of an inversion (the model

of the last iteration step) into SPECFEM3D.

Python script run_specfem3dCartesianForASKI_simulations.py conducts the specified kernel simulations (as described inside the script on the top) by iteratively running SPECFEM3D simulations, using appropriate settings of the parameter files for each iteration. You need to edit the first lines of the script (above definition of class simulation) and set all variables defined there to appropriate values, as described in the comments in the script (TODO IN THE FUTURE: maybe it is better to have an input (file?) mechanism to this script. But then: more overhead/extra requirements (packages, arguments handling) to cope with on cluster machines ...)

The python script may not be suitable for the HPC system you are using! If you are not able to adapt it in a way which makes it possible to be used, you might have to figure out an analogous way yourself how to perform the tasks done by this script.

In case of using the provided python script run_specfem3dCartesianForASKI_simulations. py, some parameters in SPECFEM3D files CMTSOLUTION, FORCESOLUTION, Par_file and in file Par_file_ASKI are automatically changed, while the script iteratively conducts SPECFEM3D simulations.

In the following, only those parameters/lines are listed, which, if necessary, need to be set manually before running this python script. All other parameters are set by the script.

3.1 Manually Setting Par_file_ASKI

The following Par_file_ASKI parameters need to be set manually before running the python script, since they are not changed/set by the script.

- OVERWRITE ASKI OUTPUT
- ASKI_DFT_double
- ASKI_DFT_apply_taper, ASKI_DFT_taper_percentage
- in case of define_ASKI_output_volume_by_inversion_grid = False, you need to manually set all parameters concerning the inversion grid, i.e. ASKI_type_inversion_grid, ASKI_(cw) (xyz), ASKI_rot_(XYZ)

3.2 Manually Setting FORCESOLUTION

The python script *always* automatically sets "latitude:", "longitude:", "depth:", "factor force source:", "component dir vect source E:", "component dir vect source N:", "component dir vect source Z_UP:". In case of displ and gt simulations, additionally "hdur:" is set to "0.". So, if you wish to do a data simulation for single force sources, using a different "hdur:" value, you should conduct those in a separate run of the python script.

3.3 Manually Setting CMTSOLUTION

The python script *always* automatically sets "latitude:", "longitude:", "depth:", "Mrr:", "Mtt:", "Mpp:", "Mrt:", "Mrp:", "Mtp:". In case of displ and simulations, additionally "half duration:" is set to "0.". So, if you wish to do a data simulation for single force sources, using a different "half duration:" value, you should conduct those in a separate run of the python script.

3.4 Manually Setting STATIONS

The standard SPECFEM3D STATIONS file should contain the definition of stations as in the ASKI file file_stations_list, in consistend SPECFEM3D notation, i.e. coordinate columns being lat (= Y, third column of STATIONS and fourth column of file_stations_list) and lon (= X, fourth column of STATIONS and third column of file_stations_list) and elev (= Z, sixth column of STATIONS and fifth column of file_stations_list).

You must also assure to use the very same station names and network codes in file STATIONS as in ASKI file file_stations_list!

4 Importing the currently inverted model for next iteration step

Exported .kim files (as produced by ASKI program exportKim) may be read used as a model by SPECFEM3D for ASKI, as explained in the following:

The model values defined by the kernel inverted model will be *superimposed* onto the SPECFEM3D default model values as defined by e.g. Cubit, using a special implementation of the SPECFEM3D module model_external_values.

Set MODEL = external in Par_file. Then directory DATA must contain a file named model_external_ASKI which must contain 3 lines:

line 1 interpolation type:

The first line may be of the following formats:

- shepard_standard meaning that a standard inverse distance interpolation, respecting for direction of neighbours, after Shepard is used to interpolate model values from the inversion grid cell centers onto the new SPECFEM3D GLL points. The radii of the inversion grid cells are used to decide whether a GLL point is in range of an inversion grid cell or not.
- shepard_factor_radius FACTOR whereby FACTOR is a factor to be applied to the inversion grid cell radii before applying the same interpolation method as in case shepard_standard.

line 2 model file type:

only kim_export supported by now, meaning that the file given in line 3 must be an exported .kim file as produced by ASKI program exportKim.

line 3 name of model file:

name of model file of type as defined in line 2, which is expected to be in directory DATA

5 Preparing Synthetic Data as Expected by ASKI

Use binary createSpecfem3dSyntheticData. Calling createSpecfem3dSyntheticData -h will print a help message how to use it.

It is assumed that a copy of the OUTPUT_FILES folder (without the MPI_DATABASES files etc...) of all involved SPECFEM3D simulations (which contain the standard seismograms files) can be found at the path as choosen by the automated python script (see 3), i.e. filename of the kernel displacement file for the respective event with the extension _OUTPUT_FILES. The

synthetic data then is written in the required form to path PATH_SYNTHETIC_DATA, where the filenames are by convention synthetics_EVENTID_STATIONNAME.

The option <code>-data</code> allows you to also transform synthetically created "real" data (e.g. for a pure synthetic inversion) to the required form. Also in this case it is assumed that a copy of the <code>OUTPUT_FILES</code> folders can be found at paths as choosen by the automated python script, i.e. the base filename of the measured data for the respective event with extension <code>_OUTPUT_FILES</code>. The "real" data then is written in the required form to the measured data files with base filenames as defined in the iteration step info database.

6 Preparing synthetically computed "measured" data as expected by ASKI

You can produce ASKI files for measured data in the required form from SPECFEM3D for ASKI "data" simulations (e.g. produced by automated python script, 3). This functionality may be used for synthetic tests, in which you must produce data for some perturbed earth model, which is treated as measured data.

Use binary createSpecfem3dMeasuredData. Calling createSpecfem3dMeasuredData -h will print a help message how to use it.

It is assumed that a copy of the content of the OUTPUT_FILES folder (without the MPI_DATABASES files etc...) of the "data" simulations (which contain the standard seismograms files) can be found at directory PATH_MEASURED_DATA/data_EVENTID_OUTPUT_FILES. The measured data files then are written in the required form to path PATH_MEASURED_DATA, where the filenames are by convention data_EVENTID_STATIONNAME_COMP.

7 File Par file ASKI

File Par_file_ASKI is, just like the file Par_file, located in directory DATA/ of your current SPECFEM3D example. It basically controls ASKI functionality SPECFEM3D if used along with an ASKI extended SPECFEM3D installation. If in such an installation file Par_file_ASKI is not present, no ASKI output is produced and SPECFEM3D runs with standard functionality.

In the following, we give a short description of the functionality of parameters defined in file Par_file_ASKI.

7.1 ASKI output

COMPUTE_ASKI_OUTPUT, OVERWRITE_ASKI_OUTPUT

Parameter COMPUTE_ASKI_OUTPUT controls if any ASKI functionality is applied by SPECFEM3D and output files (i.e. kernel green tensor kernel displacement files) are produced. If true, OVERWRITE_ASKI_OUTPUT controls if those files shall be overwritten if existend or not. If false and files exist, the SPECFEM3D solver will terminate raising an error message.

ASKI_outfile, ASKI_output_ID

ASKI_outfile defines the absolute base file name of ASKI output files. ASKI_output_ ID is a character string of maximum lenght as defined by parameter length_ASKI_output_

ID in file specfem3D_par_ASKI.f90 with which all output files of a certain run will be taged, and it will be used to check consistency of the files (could be a timestamp, eventID, station name, component etc).

7.2 Frequency discretization

The double precision df [Hz] and integer values jf have the following meaning: The spectra are saved for all frequencies f = (jf) * df [Hz].

ASKI_df, ASKI_nf, ASKI_jf

ASKI_df is a predefined frequency step that is used to evaluate the spectrum. In case we want to do an inverse FT in case of time-domain sensitivity kernel computation, we need to choose ASKI_df with care as ASKI_df = $1/length_of_time_series$ and suitably high frequency indices (dependent on frequency content). Otherwise we could lose periodicity (if in $exp^(-i2pi(k)(n)/N)$ N is no integer, these are no roots of 1 anymore). The spectra are saved for frequencies $f = (ASKI_jf) *ASKI_df (ASKI_nf many)$.

ASKI_DFT_double

Choose precision of Discrete Fourier Transform. If there is enough memory available, it is highly recommended to use $ASKI_DFT_double = .true.$ in which case double complex spectra are hold in memory (single precision is written to file, though, but less roundoffs during transformation). Otherwise choose $ASKI_DFT_double = .false.$ in which case single precision spectra will be used in memory. The transformation coefficients $exp^(-i*2pi*f*t)$ are always in double complex precision!

ASKI_DFT_apply_taper, ASKI_DFT_taper_percentage

Decide whether the (oversampled, noisy, ...) time series should be tapered by a hanning taper (on tail) before (i.e. while) applying the discrete fourier transform (on-the-fly). If ASKI_DFT_apply_taper = .true., the value of ASKI_DFT_taper_percentage (between 0.0 and 1.0) defines the amount of total time for which the hanning taper will be applied at the tail of the time series.

7.3 Inversion grid

ASKI_type_inversion_grid

ASKI supports several types of inversion grids for FORWARD_METHOD = SPECFEM3D. ASKI_type_inversion_grid =

- (TYPE_INVERSION_GRID = ccsInversionGrid)
 NOT TO BE USED WITH SPECFEM3D Cartesian! NOT SUPPORTED YET ASKI internal, but SPECFEM independent spherical inversion grid
- 2. (TYPE_INVERSION_GRID = scartInversionGrid)

 ASKI internal, but SPECFEM independent cartesian inversion grid:

 The values for ASKI output are stored at all inner GLL points of spectral elements which lie inside the block volume defined below by parameters ASKI_(cw) (xyz).

ASKI loactes the coordinates of those points inside the inversion grid cells and computes integration weights for them.

- 3. (TYPE_INVERSION_GRID = ecartInversionGrid)
 - External inversion grid provided e.g. by CUBIT, which may contain tetrahedra, as well as hexahedra. As in case of ASKI_type_inversion_grid = 2, ASKI output is stored at all inner GLL points of elements which are inside the volume defined by $ASKI_(cw)(xyz)$. ASKI locates the wavefield points inside the inversion grid and computes weights.
- 4. (TYPE_INVERSION_GRID = specfem3dInversionGrid)
 Use SPECFEM elements as inversion grid:

Wavefield points are *all* GLL points of an element for elements which are (at least partly) inside the volume defined by ASKI_(cw) (xyz). Additionally store the jacobians for all wavefield points. Assume ncell = ntot_wp/(NGLLX*NGLLY*NGLLY) as the number of inversion grid cells, and the order of wavefield points accordingly (do k=1, NGLLZ; do j=1, NGLLY; do i=1, NGLLX; ip=ip+1)

ASKI_(cw) (xyz), ASKI_rot_(XYZ)

Dependent on ASKI_type_inversion_grid, (a selection of) the following parameters may be used to define a volume within which wavefield points are searched for:

First, ASKI_wx, ASKI_wy, ASKI_wz define the total width of a block which is centered in x=y=z=0 E.g. the total block extension in x-direction covers all points with $x >= -0.5*ASKI_wx$ and $x <= 0.5*ASKI_wx$.

Then, ASKI_rot_X, ASKI_rot_Y, ASKI_rot_Z define rotation angles in degrees by which the block is rotated (anti-clockwise) about the Z, Y and X coordinate axis, before ASKI_cx, ASKI_cy, ASKI_cz define a vector by which the rotated block is shifted (new center of block).

Be aware:

- the parameters for rotation angles ASKI_rot_(XYZ) *must always* be assinged to values! Set to 0. if not used.
- scartInversionGrid only supports ASKI_rot_Z and uses a different definintion of the z-coverage.
- ecartInversionGrid and specfem3dInversionGrid use *all* rotation angles ASKI_rot_(XYZ).

8 Extend SPECFEM3D_Cartesian-2.1 to produce output for ASKI

This section explains how to use the SPECFEM3D_Cartesian software http://geodynamics.org/cig/software/specfem3d as a forward method for ASKI. In general, a regularly installed SPECFEM3D_Cartesian version is extended by certain few modifications so it can produce output for ASKI. So, SPECFEM3D_Cartesian for ASKI basically has the same requirements and dependencies than the SPECFEM3D_Cartesian code, except that it needs a bit more memory and disc space. You should, therefore, have sufficient knowledge of

how to run the regular SPECFEM3D_Cartesian software. Furthermore, you need an installation of ASKI (obviously).

8.1 Download and Dependencies

The extension package SPECFEM3D_Cartesian-2.1 for ASKI can be downloaded from http://www.rub.de/ASKI.

It assumes a running version of SPECFEM3D_Cartesian on your system which must be capable of a certain functionality. If the currently available release version of SPECFEM3D_Cartesian does not have this functionality, you can download http://www.rub.de/ASKI. This is a basic extract from the SPECFEM3D_Cartesian svn-repository (svn-revision by 9 june 2013, SPECFEM3D version 2.1) which has been debugged and slightly modified such that it is capable of the required functionality. Important functionality is listed in the following, whereby the code references are related to the previously mentioned modified svn revision:

- in case of USE_FORCE_POINT_SOURCE = .true. in Par_file the sources should be interpolated inside the source array and not just set to the closest GLL point (compare src/specfem3D/locate_source.f90, comments FS FS)

 This, however, is not a strict necessity, you can also use SPECFEM3D_Cartesian codes which do not do this.
- in case of USE_FORCE_POINT_SOURCE = .true. and

 USE_RICKER_TIME_FUNCTION = .false. in Par_file, the regular Heaviside

 source time function (function comp_source_time_function) must be used (compare src/specfem3D/compute_add_sources_viscoelastic.f90, src/specfem3D/

 setup_sources_receivers.f90 comments FS FS)
- using external models (MODEL = external in Par_file), subroutine model_external_values must be passed the default model values on enter (compare src/generate_databases/get_model.f90, comments FS FS)
- the general user interface of the SPECFEM3D_Cartesian code (i.e. definition of source mechanisms and receivers, models, output files etc.) must be compatible with SPECFEM3D_Cartesian version 2.1 by june 2013.

8.2 Installation

Extract the files of the extension package SPECFEM3D_Cartesian-2.1 for ASKI into a subdirectory of your ASKI installation path, in the following refered to as SPECFEM_for_ASKI. I.e. the directory SPECFEM_for_ASKI is contained in directory ASKI. Install a SPECFEM3D_Cartesian code on your system which meets the requirements as in subsection 8.1, in the following the SPECFEM3D_Cartesian installation path is refered to as SPECFEM3D.

- Follow the 9 items in the "Installation" section of file ASKI/SPECFEM_for_ASKI/README, whereby the first one should already be completed.
- Adjust variables SHELL, BLAS, LAPACK etc. in SPECFEM_for_ASKI/Makefile in the same way as you did in ASKI/Makefile for the installation of ASKI. The same environment variables are assumed here, too.

- Run make clean and make all in ASKI/SPECFEM_for_ASKI.
- Set USE_SOURCES_RECVS_Z = .true.in SPECFEM3D/src/shared/constants. h (or wherever your constants.h is).
- Recompile your SPECFEM3D_Cartesian code by running make clean and make all in SPECFEM3D.

GNU Free Documentation License

Version 1.3, 3 November 2008 Copyright © 2000, 2001, 2002, 2007, 2008 Free Software Foundation, Inc.

<http://fsf.org/>

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

Preamble

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "**Document**", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "**you**". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "**Modified Version**" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "**Title Page**" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text. The "**publisher**" means any person or entity that distributes copies of the Document to the public.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.

- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may

include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, or distribute it is void, and will automatically terminate your rights under this License.

However, if you cease all violation of this License, then your license from a particular copyright holder is reinstated (a) provisionally, unless and until the copyright holder explicitly and finally terminates your license, and (b) permanently, if the copyright holder fails to notify you of the violation by some reasonable means prior to 60 days after the cessation.

Moreover, your license from a particular copyright holder is reinstated permanently if the copyright holder notifies you of the violation by some reasonable means, this is the first time you have received notice of violation of this License (for any work) from that copyright holder, and you cure the violation prior to 30 days after your receipt of the notice.

Termination of your rights under this section does not terminate the licenses of parties who have received copies or rights from you under this License. If your rights have been terminated and not permanently reinstated, receipt of a copy of some or all of the same material does not give you any rights to use it.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See http://www.gnu.org/copyleft/.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation. If the Document specifies that a proxy can decide which future versions of this License can be used, that proxy's public statement of acceptance of a version permanently authorizes you to choose that version for the Document.

11. RELICENSING

"Massive Multiauthor Collaboration Site" (or "MMC Site") means any World Wide Web server that publishes copyrightable works and also provides prominent facilities for anybody to edit those works. A public wiki that anybody can edit is an example of such a server. A "Massive

Multiauthor Collaboration" (or "MMC") contained in the site means any set of copyrightable works thus published on the MMC site.

"CC-BY-SA" means the Creative Commons Attribution-Share Alike 3.0 license published by Creative Commons Corporation, a not-for-profit corporation with a principal place of business in San Francisco, California, as well as future copyleft versions of that license published by that same organization.

"Incorporate" means to publish or republish a Document, in whole or in part, as part of another Document.

An MMC is "eligible for relicensing" if it is licensed under this License, and if all works that were first published under this License somewhere other than this MMC, and subsequently incorporated in whole or in part into the MMC, (1) had no cover texts or invariant sections, and (2) were thus incorporated prior to November 1, 2008.

The operator of an MMC Site may republish an MMC contained in the site under CC-BY-SA on the same site at any time before August 1, 2009, provided the MMC is eligible for relicensing.

ADDENDUM: How to use this License for your documents

To use this License in a document you have written, include a copy of the License in the document and put the following copyright and license notices just after the title page:

Copyright © YEAR YOUR NAME. Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with ... Texts." line with this:

with the Invariant Sections being LIST THEIR TITLES, with the Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.