

How to setup the ODBC driver

Copy URL Share this page

ISSUE

This article explains how to uninstall the old ODBC drivers and install new drivers for your computer to connect to the Spillman Server

ENVIRONMENT

- Windows

RESOLUTION

Click each heading to expand its contents and follow the step-by-step instructions:

▼ 1. Uninstall outdated ODBC drivers

1.
 - a. If you have ever connected to the Spillman Server using ODBC before on this computer, then you will need to follow this step. If you have never used this computer to connect to the server using ODBC, you can skip step 1 and go to step 2
 - b. On the computer that you plan to use ODBC, open the Control Panel.
 - i. You can get to the Control Panel by clicking on the Start menu, and then typing "control panel".
 - c. Click **Uninstall Program**.
 - d. Look for any listing that starts with "Faircom c-treeACE ODBC Driver."
 - i. For example, the following entries can be safely uninstalled (as well as other versions you may have on your system).
 - e. Right click the "Faircom c-treeACE ODBC Driver" entry and then click **Uninstall**. Follow the on-screen prompts to finish uninstalling

▼ 2. Download the newest ODBC driver

- a. ODBC Drivers are specific to the version of ctree running on the Spillman Server. This means that after a patch or an upgrade, you may need to reinstall the ODBC drivers. The only way to ensure you are getting the correct driver is to download it from the Spillman Server.
- b. Go to [http://\[Your Spillman Servers IP Address or hostname\]:4080/odbc](http://[Your Spillman Servers IP Address or hostname]:4080/odbc). You will see a page that looks similar to this
 - i. For instance, if the IP address of your Spillman server is 192.168.1.5 then you would go to <http://192.168.1.5:4080/odbc>.
 - ii. If you are unsure of your IP address or hostname, then open the Spillman client, and before logging in, click **detail**. The address is listed at the bottom of the Login screen.
- c. If you are an administrator, you can use your Spillman username and password to login to the ODBC page.
- d. Once logged into the webpage you will see a page that looks similar to the following.
- e. Important Versioning Information
 - i. If the Application you are using is 32-bit, then choose the first driver "c-treeACE-ODBC_Driver.Win32.msi"
 - ii. If the Application you are using is 64-bit, then choose the second driver "c-treeACE-ODBC_Driver.WinX64.msi"
 - iii. The bit version of your operating system does not matter at all.
 - iv. For example, Crystal Reports is a 32-bit application. This means you will download the first driver "c-treeACE-ODBC_Driver.Win32.msi"

▼ 3. Install the driver

- a. Run the downloaded driver installer.
- b. Accept the license agreement.
- c. Change the install path if preferred, otherwise click **Next**.
- d. Click **Install**.
- e. Click **Finish**.

4. Configure the driver

- a. After running the installer, a User DSN (Data Source Name) needs to be set up using Window's ODBC Data Source Administrator.
- b. Be aware that Windows handles 32-bit and 64-bit DSNs with separate executables:
 - i. The 64-bit Data Source Administrator is found at C:\Windows\System32\odbcad32.exe
 - ii. The 32-bit Data Source Administrator is found at C:\Windows\SysWOW64\odbcad32.exe



Both applications have the same name, and their location is somewhat counter-intuitive (SysWOW64 for the 32-bit, System32 for the 64-bit). Ensure you're using the correct one.

- c. After launching the appropriate .exe, click Add under the **User DSN** tab.
- d. Choose **c-treeACE ODBC Driver**, and then click **Finish**.
- e. Fill out the form. The following are the relevant fields:
 - i. **Data Source Name** – can be anything.
 - ii. **Description** – can be anything.
 - iii. **Host** – IP address of the Spillman Server.
 - iv. **Database** – should be *live*.
 - v. **User ID and password** – input a ctree (not a Spillman) username and password. (This will usually be odbcuser and whatever odbcuser's associated password is.
- vi. **Service** – should be 6597.
- vii. The rest of the fields should be left as their defaults.



Note: For some programs, particularly Microsoft created ones, if the password for the ODBCUSER contains an ! it needs to be entered as '!'.

i.e. ThisIsNotARealPassword!' if it was ThisIsNotARealPassword!

Testing ODBC Driver Connection with ODBCtest:

- There is a way to test the odbc driver connectivity using this tool ODBCtest
- Here's a zip file download for it [odbcetest.zip](#) Once installed and the ODBC driver is installed you can open the 32 bit or 64 bit version of the tool and go to **Conn > Full Connection > Select the Ctree ODBC driver > click OK**
- You'll see if it connects fine. It won't be useful for much more than testing connection, but that is something that can be used to further verify if the ODBC driver is in error.

Using SSL For ODBC Connection With Driver:

- This webpage from faircom explains how you can configure and setup the odbc driver with ssl encryption: <https://docs.faircom.com/doc/ctreeplus/74152.htm>
- The agency can create an SSL certificate that they then can utilize with this setup to encrypt the connection.

TECHNICAL NOTES