


**SUREN NETWORK**  
PLAY WITH TECHNOLOGIES



 HO-EDGE

```
Ethernet0/2          unassigned      YES TFTP   up          up
Ethernet0/3          unassigned      YES TFTP   up          up

HO-EDGE#config t
*Aug 27 09:09:32.141: %LINK-3-UPDOWN: Interface Ethernet0/2, changed state to do
wn
*Aug 27 09:09:32.142: %LINK-3-UPDOWN: Interface Ethernet0/3, changed state to do
wn
*Aug 27 09:09:33.142: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
2, changed state to down
*Aug 27 09:09:33.143: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
3, changed state to down
HO-EDGE#config t
Enter configuration commands, one per line.  End with CNTL/Z.
HO-EDGE(config)#int e0/0
HO-EDGE(config-if)#ip add 10.0.0.1 255.0.0.0
HO-EDGE(config-if)#no sh
HO-EDGE(config-if)#exit
HO-EDGE(config)#int e0/1
HO-EDGE(config-if)#ip add 20.0.0.1 255.0.0.0
HO-EDGE(config-if)#no sh
HO-EDGE(config-if)#exit
HO-EDGE(config)#ip route 0.0.0.0 0.0.0.0 20.0.0.2
HO-EDGE(config)#interface e0/0
HO-EDGE(config-if)#ip nat inside
HO-EDGE(config-if)#exit
HO-EDGE(config)#
*Aug 27 09:10:48.586: %LINEPROTO-5-UPDOWN: Line protocol on Interface NVI0, chan
ged state to up
HO-EDGE(config)#interface e0/1
HO-EDGE(config-if)#ip nat outside
HO-EDGE(config-if)#exit
HO-EDGE(config)#access-list 10 permit 10.0.0.0 0.255.255.255
HO-EDGE(config)#ip nat inside source list 10 interface e0/1 overload
HO-EDGE(config)#ip dhcp pool LALN
HO-EDGE(dhcp-config)#network 10.0.0.0 255.0.0.0
HO-EDGE(dhcp-config)#default-router 10.0.0.1
HO-EDGE(dhcp-config)#dns-server 8.8.8.8
HO-EDGE(dhcp-config)#lease 8
HO-EDGE(dhcp-config)#exit
HO-EDGE(config)#
```

## DC-EDGE

```
DC-EDGE#show ip int br
Interface                IP-Address      OK? Method Status      Prot
ocol
Ethernet0/0              unassigned      YES TFTP   up          up
Ethernet0/1              unassigned      YES TFTP   up          up
Ethernet0/2              unassigned      YES TFTP   down        down
Ethernet0/3              unassigned      YES TFTP   down        down
```

```
DC-EDGE#config t
Enter configuration commands, one per line.  End with CNTL/Z.
DC-EDGE(config)#int e0/0
DC-EDGE(config-if)#ip add 192.168.1.1 255.255.255.0
DC-EDGE(config-if)#no sh
DC-EDGE(config-if)#exit
DC-EDGE(config)#int e0/1
DC-EDGE(config-if)#ip add 30.0.0.2 255.0.0.0
DC-EDGE(config-if)#no sh
DC-EDGE(config-if)#exit
DC-EDGE(config)#ip route 0.0.0.0 0.0.0.0 30.0.0.1
DC-EDGE(config)#int e0/0
DC-EDGE(config-if)#ip nat inside
DC-EDGE(config-if)#exit
DC-EDGE(config)#
*Aug 27 09:40:35.162: %LINEPROTO-5-UPDOWN: Line protocol on Interface NVI0, changed state to up
DC-EDGE(config)#int e0/1
DC-EDGE(config-if)#ip nat outside
DC-EDGE(config-if)#exit
DC-EDGE(config)#ip nat inside source static 192.168.1.2 30.0.0.
*Aug 27 09:41:56.112: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
DC-EDGE(config)#ip nat inside source static 192.168.1.2 30.0.0.10
DC-EDGE(config)#ip nat inside source static 192.168.1.3 30.0.0.11
DC-EDGE(config)#ip dhcp pool DC
DC-EDGE(dhcp-config)#network 192.168.1.0 255.255.255.0
DC-EDGE(dhcp-config)#default-router 192.168.1.1
DC-EDGE(dhcp-config)#dns-server 8.8.8.8
DC-EDGE(dhcp-config)#lease 8
DC-EDGE(dhcp-config)#exit
DC-EDGE(config)#
```

