

PUBLIC

Sample Code Configuration Guide for Integration with SAP Business Network Global Track and Trace

SAP Business Network Global Track and Trace

December 2025

THE BEST RUN SAP

Contents

Document History 3

1. PREREQUISITES 5

1.1 Check the SAP Product Version 5

1.2 Log on the Development Client to Configure BTE 5

2. DOWNLOAD ABAP CODE FROM GITHUB 6

2.1 Initial Download ABAP Code from GitHub 6

2.1.1 Install ABAPGit *6*

2.1.2 Download ABAP Code from GitHub *6*

2.2 Update ABAP Code from GitHub 8

2.2.1 Update ABAP Code from GitHub *8*

3. SAP S/4HANA INTEGRATION CONFIGURATION OPTION 1 (IMPORT BC SET + MANUAL CONFIGURATION) 9

3.1 Download BC Set from GitHub 10

3.2 Import BC Set 11

3.3 Activate BC Set 12

3.4 Define RFC Connection for SAP Business Network Global Track and Trace 15

3.5 Define Ports 20

3.6 Define Partner Profiles 22

3.7 Maintain AOT Type Restriction for Cross-Processes 24

3.8 Maintain Event Type Restriction for Cross-Processes 24

3.9 Maintain Sales Order Types that will be sent to SAP Business Network Global Track and Trace 24

3.10 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace 24

3.11 Maintain Purchase Order Types that will be sent to SAP Business Network Global Track and Trace 25

3.12 TM Configurations 25

4. SAP S/4HANA INTEGRATION CONFIGURATION OPTION 2 (MANUAL CONFIGURATION) 27

4.1 Define RFC Connection for SAP Business Network Global Track and Trace 27

4.2 Define Logical System 31

4.3 Define Ports 32

4.4 Define Partner Profiles 33

4.5 Define CI tenant for SAP Business Network Global Track and Trace 35

4.6 Define GTT Extraction Functions 35

4.7 Define Used Business Process Types, Appl. Object Types and Event Types 41

4.8 Define Application Object Types for Header Level Extractor 42

4.9 Define Application Object Types for Item Level Extractor 46

4.10 Define Event Types for Header Level Extractor 49

4.11 Define Event Types for Item Level Extractor 51

4.12 Purchase Order Extractor Configuration 53

4.12.1 Define Application Object Types for Purchase Order Header *53*

4.12.2 Define Application Object Types for Purchase Order Item *53*

4.12.3 Define Event Types for Purchase Order Item *54*

4.12.4 Cross-processes for Purchase Order *55*

4.12.5 Maintain Purchase Order Types that will be sent to SAP Business Network Global Track and Trace *56*

4.13 Inbound Delivery Extractor Configuration 57

4.13.1 Define Application Object Types for Inbound Delivery Header *57*

4.13.2 Define Application Object Types for Inbound Delivery Item *58*
4.13.3 Define Event Types for Inbound Delivery Header *59*
4.13.4 Define Event Types for Inbound Delivery Item *59*
4.13.5 Cross-processes for Inbound Delivery *60*
4.13.6 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace .. *60*
4.14 Sales Order Extractor Configuration **61**
4.14.1 Define Application Object Types for Sales Order Header *61*
4.14.2 Define Application Object Types for Sales Order Item *61*
4.14.3 Cross-processes for Sales Order *62*
4.14.4 Maintain Sales Order Types that will be sent to SAP Business Network Global Track and Trace *62*
4.15 Outbound Delivery Extractor Configuration **62**
4.15.1 Define Application Object Types for Outbound Delivery Header *62*
4.15.2 Define Application Object Types for Outbound Delivery Item *63*
4.15.3 Define Event Types for Outbound Delivery Header *64*
4.15.4 Define Event Types for Outbound Delivery Item *64*
4.15.5 Cross-processes for Outbound Delivery *66*
4.15.6 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace .. *66*
4.16 Shipment Extractor Configuration **66**
4.16.1 Define Application Object Types for Shipment Header *66*
4.16.2 Define Event Types for Shipment Header *67*
4.17 Freight Unit Extractor Configuration **69**
4.17.1 Define Application Object Types for Freight Unit Header *69*
4.17.2 Define Event Types for Freight Unit Header *69*
4.18 Road Freight Order/Ocean Booking/Air Booking Extractor Configuration **75**
4.18.1 Define Application Object Types for Road Freight Order/Ocean booking/Air Booking Header *75*
4.18.2 Define Event Types for Road Freight Order/Ocean Booking/Air Booking Header *75*
4.19 TM Configurations **79**
5. CONFIGURATION AND CODING GUIDE – ADVANCED **82**
6 KNOWN ISSUES **82**
6.1 Planned Event Extension Not Enabled **82**
6.2 One-time locations Relevant **82**
APPENDIX ONE: DEFINE THE UNPLANNED EVENTS FOR AIR BOOKING **83**
APPENDIX TWO: FAQS **85**
Q1: After the configuration of GTT and SAP TM systems, we found that the freight unit / freight order / freight booking IDOC cannot be sent to SAP Business Network Global Track and Trace, how can we do the troubleshooting? **85**
Q2: How to add customized planned event and synchronize this event back to SAP TM? **89**
Q3: How to update business partner's LBN ID? **92**
Q4: How is the connection established between SAP S/4HANA and SAP Business Network Global Track and Trace? Do I need to configure PI in SAP S/4HANA? **92**
Q5: What scenarios are supported in SAP Business Network Global Track and Trace? **93**
Q6: Do sample codes support one-time locations? Where can I maintain the one-time location address? **94**
Q7: How to stop sending unnecessary IDOCs from SAP S/4HANA to the GTT system? **95**
Q8: How to deactivate or activate the application log? **95**

Document History

2512 Release:

1. Add 3.12 TM Configurations and 4.19 TM configurations
2. Update 3.3 Activate BC Set

2505 Release:

1. Update 3.4 Define RFC Connection for SAP Business Network Global Track and Trace

2408 Release:

1. Update 4.8 Define Application Object Types for Header Level Extractor
2. Update 4.9 Define Application Object Types for Item Level Extractor

2406 Release:

1. Update 3.4 Define RFC Connection for SAP Business Network Global Track and Trace
2. Update 4.1 Define RFC Connection for SAP Business Network Global Track and Trace

2403 Release:

1. Update 1.2 Log on the Development Client to Configure BTE
2. Update 3.4 Define RFC Connection for SAP Business Network Global Track and Trace
3. Update 4.1 Define RFC Connection for SAP Business Network Global Track and Trace

2307 Release:

1. Update 3.3 Activate BC Set
2. Update 5. Configuration and Coding Guide-Advanced

2306 Release:

1. Update 2.1.1 Install ABAPGit
2. Update 2.1.2 Download ABAP Code from GitHub
3. Update 3.7 Maintain AOT Type Restriction for Cross-Processes
4. Update 3.8 Maintain Event Type Restriction for Cross-Processes
5. Update 4.12.4 Cross-processes for Purchase Order
6. Update 4.13.5 Cross-processes for Inbound Delivery
7. Update 4.14.3 Cross-processes for Sales Order
8. Update 4.15.5 Cross-processes for Outbound Delivery

2305 Release:

1. Update 3.4 Define RFC Connection for SAP Business Network Global Track and Trace
2. Update 4.1 Define RFC Connection for SAP Business Network Global Track and Trace
3. Update 5.7 Enhancement Codes for Cross-processes Tracking
4. Add Q8: How to deactivate or activate the application log?

2304 Release:

1. Update prerequisites for Chapter 3 SAP S/4HANA Integration Configuration option 1 (Import BC set + Manual configuration)
2. Update 5.7 Enhancement Codes for Cross-processes Tracking
3. Add the Chapter 6 Known Issues
4. Update Q1: After the configuration of GTT and SAP TM systems, we found that the freight unit / freight order / freight booking IDOC cannot be sent to SAP Business Network Global Track and Trace, how can we do the troubleshooting?
5. Add the following FAQs:
   - Q6: Do sample codes support one-time locations? Where can we maintain the one-time location address?
   - Q7: How to stop sending unnecessary IDOCs from SAP S/4HANA system to the GTT system?

2303 Release:

1. Update 3.4 Define RFC Connection for SAP Business Network Global Track and Trace
2. Update 3.7 Maintain AOT Type Restriction for Cross-Processes
3. Update 3.10 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace
4. Add 3.11 Maintain Purchase Order Types that will be sent to SAP Business Network Global Track and Trace
5. Update 4.1 Define RFC Connection for SAP Business Network Global Track and Trace

6. Update 4.12.4 Cross-processes for Purchase Order
7. Add 4.12.5 Maintain Purchase Order Types that will be sent to SAP Business Network Global Track and Trace
8. Add 4.13.6 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace
9. Update 4.14.3 Cross-processes for Sales Order
10. Update Q2: How to add customized planned event and synchronize this event back to SAP TM?
11. Add Q4: How is the connection established between SAP S/4HANA and SAP Business Network Global Track and Trace? Do we need to configure PI in SAP S/4HANA?
12. Add Q5: What scenarios are supported in SAP Business Network Global Track and Trace?

1. PREREQUISITES


1.1 Check the SAP Product Version

Make sure that you have met the requirements for the product version mentioned in the "Prerequisites" section of *Basic Knowledge: Connect to SAP S/4HANA* in *How to Send Documents from SAP S/4HANA to SAP Business Network Global Track and Trace*. You can find this guide at http://help.sap.com/gtt.

The ABAP codes on Github to support fulfillment tracking apps for SAP Business Network Global Track and Trace shall be implemented in SAP S/4HANA 1909 SP03 on premise or higher. Please note that the codes are not validated in its lower version or other ECC series of products, so you might need to do further adaptation work or build your own extractor.

1.2 Log on the Development Client to Configure BTE

1.2.1 Ensure you have development access to the client for cross-client customizing and local development.
1.2.2 Log on to the client and enter transaction code (T-code): **BF11.**
1.2.3 Position on the Application ID: **PI-EM.** Check the field **Application Active.**



1.2.4 Click **Save.**

2. DOWNLOAD ABAP CODE FROM GITHUB


2.1 Initial Download ABAP Code from GitHub

2.1.1 Install ABAPGit


You need to install ABAPGit before downloading the codes from GitHub. To install ABAPGit, follow the instructions on https://docs.abapgit.org/user-guide/getting-started/install.html . Make sure you **Install the standalone version** in your dev system. When installation is complete, a new report is created, *ZABAPGIT_STANDALONE*.

2.1.2 Download ABAP Code from GitHub

2.1.2.1 Enter T-code *SE38* and fill in the report name from 2.1.1, *ZABAPGIT_STANDALONE. Click **Execute** to run the report.*




2.1.2.2 Click **New Online** to download the code.



2.1.2.3 Fill in the **Git Repository URL**.


https://github.com/SAP-samples/logistics-business-network-gtt-standardapps-samples.git

2.1.2.4 Fill in the **Package** where you want to create the new ABAP code. If the package does not exist yet, click **Create package** to create it. Set *Full* for **Folder Logic.** Click **Clone Online Repo** to download the code.



2.1.2.5 Assign the change to a change request. If you do not have any available change requests, you need to create a new one.

2.1.2.6 Click **Pull** to pull down the code of the latest version.




2.1.2.7 After you download the code, you can check it with T-code *SE80*.

2.2 Update ABAP Code from GitHub

In each release, there are some changes in the public sample codes. To update your local sample codes of Fulfillment Tracking apps after a future release, do the following:

2.2.1 Update ABAP Code from GitHub

2.2.1.1 Enter T-code *SE38* and fill in the report name *ZABAPGIT_STANDALONE*. Click the **Execute** icon to run the report.




2.2.1.2 To access the Fulfillment Tracking apps' repository, click the › button.


2.2.1.3 Click **Pull** to pull down the latest version code.

3. SAP S/4HANA INTEGRATION CONFIGURATION OPTION 1 (IMPORT BC SET + MANUAL CONFIGURATION)

Prerequisites:

- For this option, you must establish the system environment WITHOUT a production client for preparation. If you try to import the BC set into the system with a production client, an error will pop up.





- You must maintain the business process types used for SAP Business Network Global Track and Trace correctly. To do so, follow the steps below:
  a. In **Display IMG** page, click **Integration with Other SAP Components** -> **Interface to Global Track and Trace** -> **Define Application Interface.**
  b. Choose activity **Define Used Business Process Types, Appl. Object Types and Event Types.**
  c. Choose **Define Used Business Process Types** and click **New Entries** to maintain business process type as follows:


Business Process Type	Update Mode	BPT Processing Mode	Description
ESC_DELIV	Update Task (V1)	Active	Delivery in SAP R/3 Enterprise
ESC_MATDOC	Update Task (V1)	Active	Material Document in SAP R/3 Enterprise
ESC_PURORD	Update Task (V1)	Active	Purchase Order in SAP R/3 Enterprise

ESC_SHIPMT	Update Task (V1)	Active	Shipment (SAP R/3 Enterprise)
ESC_SORDER	Update Task (V1)	Active	Sales Order in SAP R/3 Enterprise
TMS_TOR	Update Task (V1)	Active	Transportation Order (SAP TM)


3.1 Download BC Set from GitHub

3.1.1 Navigate to BC Set in https://github.com/SAP-samples/logistics-business-network-gtt-standardapps-samples/blob/main/lbn-gtt-standard-app/BCset/ZGTT_CONF.bcs.


3.1.2 Click on “Raw” button.



3.1.3 Click **Save as** to save the configuration file to your local path.




3.1.4 Change file extension to “.bcs”.




3.2 Import BC Set

3.2.1 From SAP Easy Access Menu, **Tools** -> **Customizing** -> **Business Configuration Sets** -> **Display and Maintain BC Sets** (Transaction Code SCPR3).


3.2.2 Select **Upload BC Set**.




3.2.3 Select the file " ZGTT_CONF.bcs", then click **Open** to upload the BC set to your development system.



All of the configurations are loaded in the system.




3.2.4 Click **Save** to save the BC Set.




3.3 Activate BC Set


Please note that when the system is upgraded to a new version, the BC set ZGTT_CONF might be missing. You must follow the steps outlined in this section to reactivate the BC set.

3.3.1 From SAP Easy Access Menu, **Tools** -> **Customizing** -> **Business Configuration Sets** -> **Activation of BC Sets** (Transaction Code SCPR20).
3.3.2 Enter the name of the BC Set and select **Activate**.




3.3.3 Provide a Workbench request and a Customizing request.







3.3.4 Various activation options are available. Choose appropriate ones and click **Continue** to proceed with the activation.

The following message is displayed:
"**Caution** You have started the BC Set activation If you continue, new data records will be created and/or existing ones overwritten."






3.3.5 BC Set is activated and BC set data is stored in the customization tables.



3.3.6 Click **Activation Logs** to check the logs.



Tips:


- By default, the application log is activated for imported configurations. If you want to stop recording the application log, refer to Q8: How to deactivate or activate the application log? for detailed instructions.

3.4 Define RFC Connection for SAP Business Network Global Track and Trace


3.4.1 Log on to the business client, enter T-code *SPRO* and then click **SAP Reference IMG** to open **Display IMG page.**

3.4.2 Click **Integration with Other SAP Components** -> **Interface to Global Track and Trace** -> **Define System Configuration**. Choose activity: **Define RFC Connection for SAP GTT**

3.4.3 Choose **HTTP Connections to External Server**, click **Create** to create a new RFC connection.



3.4.4 Fill in the **Destination** and choose the **Connection Type: "G-HTTP connection to external server"**.



3.4.5 Enter a description. In the **Technical Settings** tab, fill in the **Host**, **Port** and **Path Prefix.**


For example, the URL of solution owners is as follows:

https://xxxxxx.gtt-flp-lbnplatform.cfapps.eu10.hana.ondemand.com

Host: xxxxxx.gtt-flp-lbnplatform.cfapps.eu10.hana.ondemand.com

Port: *443*

Path Prefix: */api/idoc/em/v1/TrackedProcessAndEvent*




3.4.6 In the **Logon & Security** tab, enter the Logon information.

For the basic authentication, the GTT technical user / password is needed. You can get this from your GTT administrator.

For more information about the technical user, please refer to “Create a Technical User and Assign Role Collection”. Please be noted that the technical user must be maintained in “System Connections App”, for more information, please refer to “Maintain Technical User in the System Connections App”.


Also, SSL must be **Active**. The recommended SSL Certificate is: DFAULT SSL Client (Standard).




3.4.7 Save the configuration.

3.4.8 Click **Connection Test** and check the HTTP status code in the **Test Result** tab:

- Status code “403” indicates the configuration is correct. No action is required.
- If the status code is “401” or a prompt window (as shown in the screenshot below) appears asking your username and password, there are three possibilities:



- The technical user may be locked (informed by an email received in the technical user's mailbox), you need to follow the steps in the email to unlock the technical user.
- Your username, password, or URL of **Host** and **Path Prefix** may be incorrect. You need to provide the correct ones.
- You may have used incorrect technical user in RFC connection. Use the valid one.
  A valid technical user must meet the following requirements:
  - It can successfully sign in to the site https://accounts.sap.com/ui/protected/profilemanagement with its email and password.
  - The **User ID** of the technical user must start with "P", as shown in the following screenshot. You can check this after signing in. Regarding how to create a technical user, please refer to "Create a Technical User and Assign Role Collection".



3.5 Define Ports


3.5.1 In **Display IMG** page, click **Integration with Other SAP Components** -> **Interface to Global Track and Trace** -> **IDoc Settings.** Choose activity **Define Ports.**

3.5.2 Choose **XML HTTP** folder, and click **Create** to create a new port GTTAPPPORT.

3.5.3 Fill in the **RFC Destination.**

3.5.4 Choose **Content Type** as *application/x-sap.idoc*

3.5.5 *Choose* **HTTP Version** as Version 1.0. Mark it as SOAP Protocol.




3.5.6 Save the configuration.


3.6 Define Partner Profiles

3.6.1 In **Display IMG** page, unfold **Integration with Other SAP Components -> Interface to Global Track and Trace -> IDoc Settings.** Choose activity **Define Partner Profiles.**


3.6.2 Choose **Partner Type LS** folder, and click **Create** to create a new partner profile.




3.6.3 Fill in the **Partner No.** that you created and fill in the **Processor** information.



3.6.4 Click **Add** under **Outbound** box to create a new outbound parameter.



3.6.5 Fill in the **Message Type** GTTMSG and Fill in the **Receiver Port** that you created in 3.5.



3.6.6 Save the configuration.

3.7 Maintain AOT Type Restriction for Cross-Processes

The following entries should be maintained in transaction “ZGTT_AOTYPE_RST - AOT Types Restrictions” for Cross-Processes tracking scenario.

Restr.ID	Restr.Pos	Option	Sign	Application Obj.Type
FU_TO_IDLH	001	Equal To	Include	GTT_IDLV_HD
FU_TO_IDLI	001	Equal To	Include	GTT_IDLV_IT
SH_TO_IDLH	001	Equal To	Include	GTT_IDLV_HD
SH_TO_IDLI	001	Equal To	Include	GTT_IDLV_IT
DL_TO_POIT	001	Equal To	Include	GTT_PO_IT
DL_TO_SOIT	001	Equal To	Include	GTT_SO_IT
SH_TO_ODLH	001	Equal To	Include	GTT_ODLV_HD
FU_TO_ODLH	001	Equal To	Include	GTT_ODLV_HD
FU_TO_ODLI	001	Equal To	Include	GTT_ODLV_IT
DL_TO_POHD	001	Equal To	Include	GTT_PO_HD
DL_TO_SOHD	001	Equal To	Include	GTT_SO_HD

3.8 Maintain Event Type Restriction for Cross-Processes

The following entry should be maintained in transaction “ZGTT_EVTYPE_RST – Event Types Restrictions” for Cross-Processes tracking scenario.

Restr.ID	Restr.Pos	Option	Sign	Event Type
DL_TO_POIT	001	Equal To	Include	GTT_EVT_PO_IT_CF

3.9 Maintain Sales Order Types that will be sent to SAP Business Network Global Track and Trace

Maintain the sales order type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_SOTYPE_RST - GTT Sales Doc Type Configuration”, then mark it as active.
For example:

Sales Document Type	Active
ZGTT	X

3.10 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace

Maintain the outbound and inbound delivery type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_DLVTYPE_RST - GTT Delivery Type Configuration”, then mark it as active.

For example:

Delivery Type	Active
LBNP	X
EL	X

3.11 Maintain Purchase Order Types that will be sent to SAP Business Network Global Track and Trace

Maintain the purchase order type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_POTYPE_RST - GTT Purchase Doc Type Configuration”, then mark it as active.
For example:

Purchasing Document Type	Active
NB	X

3.12 TM Configurations

You must do the following configurations in TM in SAP S/4HANA to ensure the following documents can be sent to Global Track and Trace:

- fright unit
- freight order
- freight booking

Procedure

1. Adjust the integration with TM in SAP S/4HANA and SAP EM. The Post Processing Framework (PPF) is used to trigger the communication from SAP Transportation Management (SAP TM) to SAP Event Management (SAP EM). You need to maintain the output management adapter for this communication to work.
    a. Log onto SAP, enter T-code **SPRO** and then click **SAP Reference IMG** to open the **Display IMG** page. Go to **Cross-Application Components** -> **Processes and Tools for Enterprise Applications** -> **Reusable Objects and Functions for BOPF Environment** -> **PPF Adapter for Output Management** -> **Maintain Output Management Adapter Settings**.
    b. In the **Dialog Structure** section, choose **Direct Output Agents (w/o PPF & w/o History)**.
    c. Choose the following entry and enable it.
        - Business Object: /SCMTMS/TOR
        - Node: ROOT
        - Agent Name: SEND_EM_DATA_FROM_TOR
    d. Choose **Synch/Asynch** with value "Has Critical o/p: Process during Save - before Commit". (As described in note 1842397, the Synch/Asynch setting has to be set to "Has Critical o/p: Process during Save - before Commit" in order to use the before image data in the BAdI implementations.)
    e. In the **Dialog Structure** section, choose **Nodes for Before Image**.

f. Create the following entries:

Business Object	Node	Sub Node Name
/SCMTMS/TOR	ROOT	EXECUTIONINFORMATION
/SCMTMS/TOR	ROOT	ITEM_TR
/SCMTMS/TOR	ROOT	STOP
/SCMTMS/TOR	ROOT	STOP_SUCCESSOR
/SCMTMS/TOR	ROOT	DOCREFERENCE
/SCMTMS/TOR	ROOT	EXECUTIONINFORMATION_TR
/SCMTMS/TXC	ROOT	TEXT
/SCMTMS/TXC	TEXT	TEXT_CONTENT

2. Adjust document type settings.

Note

Adjust the value of **Appl.Obj.Type** of these document types to ensure it's consistent with the following fields:

- **Appl.Obj.Type** field in **IMG** -> **Integration with Other SAP Components** -> **Interface to Global Track and Trace** -> **Define Application Interface** -> **Define Used Business Process Types, Appl. Object Types and Event Types** -> **Business Process Type TMS_TOR** -> **Define Application Object Types** -> **Interface to Global Track and Trace**
- **Application Object Type** field in the “gttft1” model (under the tab IDOC Integration) of the **Manage Models** app.

a. Adjust freight unit type settings.
   i. On the IMG, go to **Transportation Management** -> **Planning** -> **Freight Unit** -> **Define Freight Unit Types**
   ii. In the table, open the applicable freight unit type to be tracked with SAP Event Management.
   iii. In the Integration Settings, fill in the **Application Obj.Type** field with value "**GTT_FU**".
   iv. In the **Execution Settings**, the **Execution Tracking Relevance** field is set to “Execution Tracking with External Event Management”.

b. Adjust freight order type settings.
   i. On the IMG, go to **Transportation Management** -> **Freight Order Management** -> **Freight Order** -> **Define Freight Order Types**
   ii. In the table, open the applicable freight order type to be tracked with SAP Event Management.
   iii. In the **Integration Settings**, fill in the **Application Obj.Type** field with value **GTT_SHP_HD**.
   iv. In the **Execution Settings**, the **Execution Tracking Relevance** field is set to “Execution Tracking with External Event Management”.

c. Adjust the freight booking type settings.
   i. On the IMG, go to **Transportation Management** -> **Freight Booking Management** -> **Freight Booking** -> **Define Freight Booking Types**
   ii. In the table, open the applicable freight booking type to be tracked with SAP Event Management

iii. In the Integration Settings, fill in the **Application Obj.Type** field with value **GTT_SHP_HD**.
iv. In the **Execution Settings**, the **Execution Tracking Relevance** field is set to “Execution Tracking with External Event Management”


4. SAP S/4HANA INTEGRATION CONFIGURATION OPTION 2 (MANUAL CONFIGURATION)

4.1 Define RFC Connection for SAP Business Network Global Track and Trace


4.1.1 Log on to the business client, enter T-code *SPRO* and then click **SAP Reference IMG** to open **Display IMG page.**

4.1.2 Click **Integration with Other SAP Components** -> **Interface to Global Track and Trace** -> **Define System Configuration**. Choose activity: **Define RFC Connection for SAP GTT**

4.1.3 Choose **HTTP Connections to External Server**. Click **Create** to create a new RFC connection.



4.1.4 Fill in the **Destination** and choose the **Connection Type: 'G-HTTP connection to external server'**.



4.1.5 Enter a description. In the **Technical Settings** tab, fill in the **Host**, **Port** and **Path Prefix.**


For example, the URL of solution owners is as follows:

https://xxxxxx.gtt-flp-lbnplatform.cfapps.eu10.hana.ondemand.com

Host: xxxxxx.gtt-flp-lbnplatform.cfapps.eu10.hana.ondemand.com

Port: *443*

Path Prefix: */api/idoc/em/v1/TrackedProcessAndEvent*




4.1.6 In the **Logon & Security** tab, enter the Logon information.

For the basic authentication, the GTT technical user / password is needed. You can get this from your GTT administrator.

For more information about the technical user, please refer to "Create a Technical User and Assign Role Collection". Please be noted that the technical user must be maintained in "System Connections App", for more information, please refer to "Maintain Technical User in the System Connections App".


Also, SSL must be **Active**. The recommended SSL Certificate is: DFAULT SSL Client (Standard).




4.1.7 Save the configuration.

4.1.8 Click **Connection Test** and check the HTTP status code in the **Test Result** tab:

- Status code “403” indicates the configuration is correct. No action is required.
- If the status code is “401” or a prompt window (as shown in the screenshot below) appears asking your username and password, there are three possibilities:




  - The technical user may be locked (informed by an email received in the technical user’s mailbox), you need to follow the steps in the email to unlock the technical user.
  - Your username, password, or URL of **Host** and **Path Prefix** may be incorrect. You need to provide the correct ones.
  - You may have used incorrect technical user in RFC connection. Use the valid one.
    A valid technical user must meet the following requirements:
    - It can successfully sign in to the site https://accounts.sap.com/ui/protected/profilemanagement with its email and password.
    - The **User ID** of the technical user must start with “P”, as shown in the following screenshot. You can check this after signing in. Regarding how to create a technical user, please refer to “Create a Technical User and Assign Role Collection”.



4.2 Define Logical System

4.2.1 In **Display IMG** page, click **Integration with Other SAP Components** -> **Interface to Global Track and Trace** -> **Define System Configuration.** Choose activity **Define Logical System.**

4.2.2 Create **New Entries** to create a new Logical System, fill in the Logical System code and Name of the new logical system.



4.2.3 Save the configuration.

4.3 Define Ports


4.3.1 In **Display IMG** page, click **Integration with Other SAP Components** -> **Interface to Global Track and Trace** -> **IDoc Settings.** Choose activity **Define Ports.**

4.3.2 Choose **XML HTTP** folder, and click **Create** to create a new port GTTAPPPORT.

4.3.3 Fill in the **RFC Destination.**

4.3.4 Choose **Content Type** as *application/x-sap.idoc*

4.3.5 Choose **HTTP Version** as Version 1.0. Mark it as SOAP Protocol.




4.3.6 Save the configuration.


4.4 Define Partner Profiles

4.4.1 In **Display IMG** page, unfold **Integration with Other SAP Components** -> **Interface to Global Track and Trace** -> **IDoc Settings.** Choose activity **Define Partner Profiles.**


4.4.2 Choose **Partner Type LS** folder, and click **Create** to create a new partner profile.




4.4.3 Fill in the **Partner No.** that you created and fill in the **Processor** information.



4.4.4 Click **Add** under the **Outbound** box to create a new outbound parameter.



4.4.5 Fill in the Message Type GTTMSG and Fill in the Receiver Port that you created in [4.3](#).




4.4.6 Save the configuration.

4.5 Define CI tenant for SAP Business Network Global Track and Trace

4.5.1 In **Display IMG** page, click **Integration with Other SAP Components** -> **Interface to Global Track and Trace** -> **Define Application Interface.**

Choose activity **Define CI Tenant for SAP GTT**.

4.5.2 Click **New Entries** to create a new CI tenant for SAP Business Network Global Track and Trace, fill in the information for the new CI tenant. The **CI Log. System** is the logical system you created in 4.2.




4.6 Define GTT Extraction Functions


Prerequisite:
You have already installed ABAPGit and downloaded the code of Fulfillment Tracking apps in your development system.

4.6.1 In **Display IMG** page, click **Integration with Other SAP Components** -> **Interface to Global Track and Trace** -> **Define Application Interface.** Choose activity **Define SAP GTT Extraction Functions.**

4.6.2 Choose the type of extraction function you want to create from the **Dialog Structure,** and click **New entries.**



4.6.3 Input the **Function** name and **Function Module** for the newly created extraction function.



4.6.4 Click **Save.**

Hint:
After completing the configuration of 'Define GTT Extraction Functions', the configuration should be as follows:

Category	Extractor	Function Module Name	Description
Control Parameter Extractors	GTT_MIA_IDLV_HD_OTE	ZGTT_MIA_OTE_DL_HDR	Control Parameter Extractor for Inbound Delivery Header
	GTT_MIA_IDLV_IT_OTE	ZGTT_MIA_OTE_DL_ITEM	Control Parameter Extractor for Inbound Delivery Item
	GTT_MIA_SHP_HD_OTE	ZGTT_MIA_OTE_SH_HDR	Control Parameter Extractor for Shipment Header
	GTT_TS_FO_HD_OTE	ZGTT_STS_OTE_FO_HDR	Control Parameter Extractor for Freight Order and Freight Booking
	GTT_TS_FU_HD_OTE	ZGTT_STS_OTE_FO_HDR	Control Parameter Extractor for Freight Unit
	GTT_POF_PO_HD_OTE	ZGTT_SPOF_OTE_PO_HDR	Control Parameter Extractor for Purchase Order Header
	GTT_POF_PO_IT_OTE	ZGTT_SPOF_OTE_PO_ITM	Control Parameter Extractor for Purchase Order Item
	GTT_SOF_SO_HD_OTE	ZGTT_SSOF_OTE_SO_HD	Control Parameter Extractor for Sales Order Header
	GTT_SOF_SO_IT_OTE	ZGTT_SSOF_OTE_SO_ITEM	Control Parameter Extractor for Sales Order Item
	GTT_SOF_ODLV_HD_OTE	ZGTT_SSOF_OTE_DE_HD	Control Parameter Extractor for Outbound Delivery Header
	GTT_SOF_ODLV_IT_OTE	ZGTT_SSOF_OTE_DE_ITEM	Control Parameter Extractor for Outbound Delivery Item
Event Data Extractors	GTT_MIA_IDLV_HD_GR	ZGTT_MIA_EE_DL_HDR_GR	Actual event Inbound Delivery Header Goods Receipt

	GTT_MIA_IDLV_IT_PA	ZGTT_MIA_EE_DL_ITEM_PA	Actual event Inbound Delivery Item Put Away
	GTT_MIA_IDLV_IT_PKNG	ZGTT_MIA_EE_DL_ITEM_PKNG	Actual event Inbound Delivery Item Packing
	GTT_MIA_SHP_HD_ARR	ZGTT_MIA_EE_SH_HDR_ARR	Actual event Shipment Header Arrival
	GTT_MIA_SHP_HD_CI	ZGTT_MIA_EE_SH_HDR_CI	Actual event Shipment Header Check In
	GTT_MIA_SHP_HD_DEP	ZGTT_MIA_EE_SH_HDR_DEP	Actual event Shipment Header Departure
	GTT_MIA_SHP_HD_LE	ZGTT_MIA_EE_SH_HDR_LE	Actual event Shipment Header Load End
	GTT_MIA_SHP_HD_LS	ZGTT_MIA_EE_SH_HDR_LS	Actual event Shipment Header Load Start
	GTT_TS_TOR_ARRIVAL	ZGTT_STS_EE_FO_ARRIVAL	Actual Event FO/FB/FU Proof of Arrival
	GTT_TS_TOR_COUPLING	ZGTT_STS_EE_FO_COUPLING	Actual Event FO/FB/FU Coupling
	GTT_TS_TOR_DECOUPL	ZGTT_STS_EE_FO_DECOUPLING	Actual Event FO/FB/FU Decoupling
	GTT_TS_TOR_DELAY	ZGTT_STS_EE_FO_DELAY	Actual Event FO/FB/FU Delay
	GTT_TS_TOR_DEPART	ZGTT_STS_EE_FO_DEPARTURE	Actual Event FO/FB/FU Proof of Departure
	GTT_TS_TOR_FU_DELAY	ZGTT_STS_EE_FU_DELAY	Actual Event FO/FB/FU Delay
	GTT_TS_TOR_LOAD_END	ZGTT_STS_EE_FO_LOAD_END	Actual Event FO/FB/FU Loading End
	GTT_TS_TOR_LOAD_STR	ZGTT_STS_EE_FO_LOAD_START	Actual Event FO/FB/FU Loading Start
	GTT_TS_TOR_POD	ZGTT_STS_EE_FO_POD	Actual Event FO/FB/FU Proof of Delivery
	GTT_TS_TOR_POPU	ZGTT_STS_EE_FO_POPU	Actual Event FO/FB/FU Proof of Pick-Up
	GTT_TS_TOR_UNLD_END	ZGTT_STS_EE_FO_UNLOAD_END	Actual Event FO/FB/FU Unloading End
	GTT_TS_TOR_UNLD_STR	ZGTT_STS_EE_FO_UNLOAD_START	Actual Event FO/FB/FU Unloading Start
	GTT_POF_PO_IT_CF	ZGTT_SPOF_EE_PO_ITM_CONF	Actual Event PO Item Confirmation
	GTT_POF_PO_IT_DE	ZGTT_SPOF_EE_PO_ITM_DEL	Actual Event PO Item Deletion
	GTT_POF_PO_IT_GR	ZGTT_SPOF_EE_PO_ITM_GR	Actual Event PO Item Goods Receipt
	GTT_SOF_ODLV_GI	ZGTT_SSOF_EE_DE_GI	Actual Event of Outbound Delivery Goods Issue
	GTT_SOF_ODLV_IT_PA	ZGTT_SSOF_EE_DE_PACKING	Actual Event Outbound Delivery Packing
	GTT_SOF_ODLV_IT_PI	ZGTT_SSOF_EE_DE_PICKING	Actual Event Outbound Delivery Picking
	GTT_SOF_ODLV_IT_POD	ZGTT_SSOF_EE_DE_POD	Actual Event Outbound Delivery POD
Planned Event Extractors	GTT_MIA_IDLV_HD_EE	ZGTT_MIA_EE_DL_HDR	Selection of EEs for Inbound Delivery Header
	GTT_MIA_IDLV_IT_EE	ZGTT_MIA_EE_DL_ITEM	Selection of EEs for Inbound Delivery Item

	GTT_MIA_SHP_HD_EE	ZGTT_MIA_EE_SH_HDR	Selection of EEs for Shipment Header
	GTT_TS_FO_HD_EE	ZGTT_STS_EE_FO_HDR	Selection of EEs for FO/FB Header
	GTT_TS_FU_HD_EE	ZGTT_STS_EE_FO_HDR	Selection of EEs for FU Header
	GTT_POF_PO_HD_EE	ZGTT_SPOF_EE_PO_HDR	Selection of EEs for Purchase Order Header
	GTT_POF_PO_IT_EE	ZGTT_SPOF_EE_PO_ITM	Selection of EEs for Purchase Order Item
	GTT_SOF_SO_HD_EE	ZGTT_SSOF_EE_SO_HD	Selection of EEs for Sales Order Header
	GTT_SOF_SO_IT_EE	ZGTT_SSOF_EE_SO_ITM	Selection of EEs for Sales Order Item
	GTT_SOF_ODLV_HD_EE	ZGTT_SSOF_EE_DE_HD	Selection of EEs for Outbound Delivery Header
	GTT_SOF_ODLV_IT_EE	ZGTT_SSOF_EE_DE_ITM	Selection of EEs for Outbound Delivery Item
Tracking ID Extractors	GTT_MIA_IDLV_HD_TID	ZGTT_MIA_OTE_DL_HDR_TID	Tracking ID Extractor for Inbound Delivery Header
	GTT_MIA_IDLV_IT_TID	ZGTT_MIA_OTE_DL_ITEM_TID	Tracking ID Extractor for Inbound Delivery Item
	GTT_MIA_SHP_HD_TID	ZGTT_MIA_OTE_SH_HDR_TID	Tracking ID Extractor for Shipment Header
	GTT_TS_FO_HD_TID	ZGTT_STS_OTE_FO_HEADER_TID	Tracking ID Extractor for Freight Order and Freight Booking
	GTT_TS_FU_HD_TID	ZGTT_STS_OTE_FO_HEADER_TID	Tracking ID Extractor for Freight Unit
	GTT_POF_PO_HD_TID	ZGTT_SPOF_OTE_PO_HDR_TID	Tracking ID Extractor for Purchase Order Header
	GTT_POF_PO_IT_TID	ZGTT_SPOF_OTE_PO_ITM_TID	Tracking ID Extractor for Purchase Order Item
	GTT_SOF_SO_HD_TID	ZGTT_SSOF_TRACKID_OTE_SOHDR	Tracking ID Extractor for Sales Order Header
	GTT_SOF_SO_IT_TID	ZGTT_SSOF_TRACKID_OTE_SOITEM	Tracking ID Extractor for Sales Order Item
	GTT_SOF_ODLV_HD_TID	ZGTT_SSOF_TRACKID_OTE_DEHDR	Tracking ID Extractor for Outbound Delivery Header
	GTT_SOF_ODLV_IT_TID	ZGTT_SSOF_TRACKID_OTE_DEITEM	Tracking ID Extractor for Outbound Delivery Item
GTT relevance function of AOT	GTT_MIA_IDLV_HD_REL	ZGTT_MIA_OTE_DL_HDR_REL	Appl. Object Type Relevance for Inbound Delivery Header
	GTT_MIA_IDLV_IT_REL	ZGTT_MIA_OTE_DL_ITEM_REL	Appl. Object Type Relevance for Inbound Delivery Item
	GTT_MIA_SHP_HD_REL	ZGTT_MIA_OTE_SH_HDR_REL	Appl. Object Type Relevance for Shipment Header

	GTT_TS_FO_HD_REL	ZGTT_STS_OTE_FO_HDR_REL	Appl. Object Type Relevance for FO/FB Header
	GTT_TS_FU_HD_REL	ZGTT_STS_OTE_FO_HDR_REL	Appl. Object Type Relevance for FU Header
	GTT_POF_PO_HD_REL	ZGTT_SPOF_OTE_PO_HDR_REL	Appl. Object Type Relevance for Purchasing Order Header
	GTT_POF_PO_IT_REL	ZGTT_SPOF_OTE_PO_ITM_REL	Appl. Object Type Relevance for Purchasing Order Item
	GTT_SOF_SO_HD_REL	ZGTT_SSOF_OTE_SO_HDR_REL	Appl. Object Type Relevance for Sales Order Header
	GTT_SOF_SO_IT_REL	ZGTT_SSOF_OTE_SO_ITM_REL	Appl. Object Type Relevance for Sales Order Items
	GTT_SOF_ODLV_HD_REL	ZGTT_SSOF_OTE_DE_HDR_REL	Appl. Object Type Relevance for Outbound Delivery Header
	GTT_SOF_ODLV_IT_REL	ZGTT_SSOF_OTE_DE_ITM_REL	Appl. Object Type Relevance for Outbound Delivery Items
GTT relevance function of Event Type	GTT_MIA_IDLV_HD_GR	ZGTT_MIA_EE_DL_HDR_GR_REL	Relevance function for Actual event Delivery Header Goods Receipt
	GTT_MIA_IDLV_IT_PA	ZGTT_MIA_EE_DL_ITEM_PA_REL	Relevance function for Actual event Delivery Item Put Away
	GTT_MIA_IDLV_IT_PKNG	ZGTT_MIA_EE_DL_ITEM_PKNG_REL	Relevance function for Actual event Delivery Item Packing
	GTT_MIA_SHP_HD_ARR	ZGTT_MIA_EE_SH_HDR_ARR_REL	Relevance function for Actual event Shipment Header Arrival
	GTT_MIA_SHP_HD_CI	ZGTT_MIA_EE_SH_HDR_CI_REL	Relevance function for Actual event Shipment Header Check In
	GTT_MIA_SHP_HD_DEP	ZGTT_MIA_EE_SH_HDR_DEP_REL	Relevance function for Actual event Shipment Header Departure
	GTT_MIA_SHP_HD_LE	ZGTT_MIA_EE_SH_HDR_LE_REL	Relevance function for Actual event Shipment Header Load End
	GTT_MIA_SHP_HD_LS	ZGTT_MIA_EE_SH_HDR_LS_REL	Relevance function for Actual event Shipment Header Load Start
	GTT_TS_TOR_ARRIVE	ZGTT_STS_EE_FO_ARRIVAL_REL	Relevance function for Actual event FO/FB/FU Arrival
	GTT_TS_TOR_COUP	ZGTT_STS_EE_FO_COUPLING_REL	Relevance function for Actual event FO/FB/FU Coupling
	GTT_TS_TOR_DECP	ZGTT_STS_EE_FO_DECOUPLING_REL	Relevance function for Actual event FO/FB/FU Decoupling

	GTT_TS_TOR_DELAY	ZGTT_STS_EE_FO_DELAY_REL	Relevance function for Actual event FO/FB/FU Delay
	GTT_TS_TOR_DEPART	ZGTT_STS_EE_FO_DEPARTURE_REL	Relevance function for Actual event FO/FB/FU Departure
	GTT_TS_TOR_FU_DELAY	ZGTT_STS_EE_FU_DELAY_REL	Relevance function for Actual event FO/FB/FU Freight Unit Delay
	GTT_TS_TOR_LEND	ZGTT_STS_EE_FO_LOAD_END_REL	Relevance function for Actual event FO/FB/FU Loading End
	GTT_TS_TOR_LSTR	ZGTT_STS_EE_FO_LOAD_START_REL	Relevance function for Actual event FO/FB/FU Loading Start
	GTT_TS_TOR_POD	ZGTT_STS_EE_FO_POD_REL	Relevance function for Actual event FO/FB/FU Proof of Delivery
	GTT_TS_TOR_POPU	ZGTT_STS_EE_FO_POPU_REL	Relevance function for Actual event FO/FB/FU Proof of Pick Up
	GTT_TS_TOR_UEND	ZGTT_STS_EE_FO_UNLOAD_END_REL	Relevance function for Actual event FO/FB/FU Unloading End
	GTT_TS_TOR_USTR	ZGTT_STS_EE_FO_UNLOAD_STRT_REL	Relevance function for Actual event FO/FB/FU Unloading Start
	GTT_POF_PO_IT_CF_REL	ZGTT_SPOF_EE_PO_ITM_CONF_REL	Relevance function for Actual event PO Item Confirmation
	GTT_POF_PO_IT_DE_REL	ZGTT_SPOF_EE_PO_ITM_DEL_REL	Relevance function for Actual event PO Item Deletion
	GTT_POF_PO_IT_GR_REL	ZGTT_SPOF_EE_PO_ITM_GR_REL	Relevance function for Actual event PO Item Goods Receipt
	GTT_SOF_ODLV_GI_REL	ZGTT_SSOF_EE_DE_GI_REL	Relevance function for Actual event Outbound Delivery Goods Issue
	GTT_SOF_ODLV_PA_REL	ZGTT_SSOF_EE_DE_PACKING_REL	Relevance function for Actual event Outbound Delivery Packing
	GTT_SOF_ODLV_PI_REL	ZGTT_SSOF_EE_DE_PICKING_REL	Relevance function for Actual event Outbound Delivery Picking
	GTT_SOF_ODLV_POD_REL	ZGTT_SSOF_EE_DE_POD_REL	Relevance function for Actual event Outbound Delivery POD
AOID Extractor	GTT_MIA_IDLV_HD_AOID	ZGTT_MIA_AOID_DL_HDR	AOID Extractor for Inbound Delivery Header
	GTT_MIA_IDLV_IT_AOID	ZGTT_MIA_AOID_DL_ITEM	AOID Extractor for Inbound Delivery Item
	GTT_MIA_SHP_HD_AOID	ZGTT_MIA_AOID_SH_HDR	AOID Extractor for Shipment Header
	GTT_STS_AOID_TOR	ZGTT_STS_AOID_TOR	AOID Extractor for FU/FO/FB
	GTT_POF_PO_IT_AOID	ZGTT_SPOF_AOID_PO_ITM	AOID Extractor for Purchase Order Item

	GTT_POF_PO_HD_AOID	ZGTT_SPOF_AOID_PO_HDR	AOID Extractor for Purchase Order Header
	GTT_SOF_AOID	ZGTT_SSOF_AOID	AOID Extractor for Sales Order / Outbound Delivery

4.7 Define Used Business Process Types, Appl. Object Types and Event Types

4.7.1 In **Display IMG** page, click **Integration with Other SAP Components** -> **Interface to Global Track and Trace** -> **Define Application Interface.**

Choose activity **Define Used Business Process Types, Appl. Object Types and Event Types.**

4.7.2 You can create event types and application object types for each business process type.

The following sections from 4.8 to 4.11 only demonstrate how to configure relevant objects. For actual configuration, refer to the scenarios configuration listed below.
Scenarios configuration:
1) Purchase Order -> Inbound Delivery -> Shipment.
For this scenario, see the following configurations:
4.12 Purchase Order Extractor Configuration
4.13 Inbound Delivery Extractor Configuration
4.16 Shipment Extractor Configuration

2) Purchase Order -> Inbound Delivery -> Freight Unit -> Road Freight Order / Ocean booking / Air Booking.
For this scenario, see the following configurations:
4.12 Purchase Order Extractor Configuration
4.13 Inbound Delivery Extractor Configuration
4.17 Freight Unit Extractor Configuration
4.18 Road Freight Order/Ocean Booking/Air booking Extractor Configuration


3) Sales Order -> Outbound Delivery -> Shipment.
For this scenario, see the following configurations:
4.14 Sales Order Extractor Configuration
4.15 Outbound Delivery Extractor Configuration
4.16 Shipment Extractor Configuration

4) Sales Order -> Outbound Delivery -> Freight Unit -> Road Freight Order / Ocean Booking / Air Booking.
For this scenario, see the following configurations:
4.14 Sales Order Extractor Configuration
4.15 Outbound Delivery Extractor Configuration
4.17 Freight Unit Extractor Configuration
4.18 Road Freight Order/Ocean Booking/Air Booking Extractor Configuration

4.8 Define Application Object Types for Header Level Extractor

4.8.1 As an example of AOT type's header level tracking introduction, choose the business process type ESC_DELIV from the **Define Used Business Process Types** on the right side.


Double click **Define Application Object Types.**



4.8.2 Click **New Entries** to create a new Application Object Type.


4.8.3 Fill in the **Application Object Type** and **Text** fields.

4.8.4 Fill in the information required in the **General Data** tab. **CI for GTT** is the CI Tenant you created in 4.5. Check **GTT Relevant.**




Hint:

When you are creating Application Object Type for one Business Process Type, make sure the AOT name must be the same name defined in the corresponding model in the *Manage Models* app in Version 2 of SAP Business Network Global Track and Trace.



4.8.5 Fill in the **Main Object table** and **Master Table** in the **Control Tables** tab.




Note:

If the event type or application object type is on the header level, then you only need to assign the **Main Object Table**.


If the event type or application object type is on the item level, then you need to assign the **Main Object Table** and **Master Table**, and assign the reference between the **Main Object Table** and **Master Table**.

4.8.6 If there is no customized logic to determine the AOT ID, choose **Determine from Field**, and use the key field to fill the AO ID fields. When choosing **Determine by Function**, you must enter the customized information in the AOID function field.



4.8.7 In the **Global Track & Trace Relevance** tab, choose the **GTT Relevance Method** you need.

If you choose the **GTT Relevance Method** as *Check Function*, then you need to define a relevance function according to 4.6, and fill in the relevance function name here.




4.8.8 In the **Parameter Setup** tab, choose the **TrkID Method** as you need.

If you choose the **TrkID Method** as *Determine by Function*, then you need to define a tracking ID function according to 4.6, and fill in the relevance function name here.

If no customized logic exists, for **TrkID Method** choose *Determine from Field,* then you need to fill the key field and name the Code Set for the AOT.

Fill in the extractor functions for **Control Data, Info Data(optional), Planned Event.**


Click **Save**.



Hint:


In the AOT you maintained, make sure the name of Tracking ID Type is the same name defined in the corresponding process type of the model in the *Manage Models* app in Version 2 of SAP Business Network Global Track and Trace.

If the Tracking ID Type is determined by Field, input the value source field in the Tracking ID field, and the Code Set that refers to the Tracking ID Type for the AOT as below.



4.9 Define Application Object Types for Item Level Extractor


4.9.1 As an example of AOT type's item level tracking introduction, choose the business process type ESC_DELIV from the **Define Used Business Process Types** on the right side. Double click **Define Application Object Types.**




4.9.2 Click **New Entries** to create a new Application Object Type.

4.9.3 Fill in the **Application Object Type** and **Text** fields.


4.9.4 Fill in the information required in the **General Data** tab. **CI for GTT** is the CI Tenant you created in 4.5. Check **GTT Relevant.**




4.9.5 Fill in the **Main Object table** and **Master Table** in the **Control Tables** tab.




4.9.6 Fill in the **AOID method** in the **Object Identification** tab.



4.9.7 In the **Global Track & Trace Relevance** tab, choose the **GTT Relevance Method** you need.




4.9.8 In the **Parameter Setup** tab, choose the **TrkID Method** as you need.




4.10 Define Event Types for Header Level Extractor


4.10.1 As an example of event's header level tracking introduction, choose the business process type ESC_MATDOC from the **Define Used Business Process Types** on the right side. Double click **Define Event Types.**



4.10.2 Click **New Entries** to create a new event type.
4.10.3 Fill in the **Event Type** and **Text** fields.
4.10.4 Fill in the information required in the **General Data** tab. **HCI for GTT** is the CI Tenant you created in 4.5. **Event Function** is the extractor function you created in 4.6. Check **GTT Relevant.**




4.10.5 Fill in the **Main Object Table** and **Master Table** in the **Control Tables** tab.



Caution:
If the event type or application object type is on the header level, then you only need to assign the **Main Object Table**.


If the event type or application object type is on the item level, then you need to assign the **Main Object Table** and **Master Table**, and assign the reference between the **Main Object Table** and **Master Table**.

4.10.6 In the **Global Track & Trace Relevance** tab, choose the **GTT Relevance Method** you need.
If you choose the **GTT Relevance Method** as *Check Function*, then you need to define a relevance function according to 4.6, and fill in the relevance function name here. Click **Save**.




4.11 Define Event Types for Item Level Extractor


4.11.1 As an example of the event's item level tracking introduction, choose the business process type ESC_DELIV from the **Define Used Business Process Types** on the right side. Double click **Define Event Types.**



4.11.2 Click **New Entries** to create a new event type.
4.11.3 Fill in the **Event Type** and **Text** fields.
4.11.4 Fill in the information required in the **General Data** tab. **HCI for GTT** is the CI Tenant you created in 4.5. **Event Function** is the extractor function you created in 4.6. Check **GTT Relevant.**




4.11.5 Fill in the **Main Object Table** and **Master Table** in the **Control Tables** tab.



Caution:
If the event type or application object type is on the header level, then you only need to assign the **Main Object Table**.

If the event type or application object type is on the item level, then you need to assign the **Main Object Table** and **Master Table**, and assign the reference between the **Main Object Table** and **Master Table**.

4.11.6 In the **Global Track & Trace Relevance** tab, choose the **GTT Relevance Method** you need.
If you choose the **GTT Relevance Method** as *Check Function*, then you need to define a relevance function according to 4.6, and fill in the relevance function name here. Click **Save**.



4.12 Purchase Order Extractor Configuration

4.12.1 Define Application Object Types for Purchase Order Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_PURORD
	Appl. Obj. Type	GTT_PO_HD
	Description	Extract purchase order header information to SAP Business Network Global Track and Trace
	Text	Purchase Order Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	Object Type	BUS2012
	GTT Relevant	X
Control Tables	Main Obj. Table	PURCHASE_ORDER_HEADER_NEW
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_POF_PO_HD_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_POF_PO_HD_REL
Parameter Setup	TrkID Method	Determine by Function
	Tr.ID Extractor	GTT_POF_PO_HD_TID
	Ctrl Data Function	GTT_POF_PO_HD_OTE
	Planned Event Function	GTT_POF_PO_HD_EE

4.12.2 Define Application Object Types for Purchase Order Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_PURORD
	Appl. Obj. Type	GTT_PO_IT
	Description	Extract purchase order item information to SAP Business Network Global Track and Trace
	Text	Purchase Order Item
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	Object Type	BUS2012
	GTT Relevant	X
Control Tables	Main Obj. Table	PURCHASE_ITEM_NEW
	Master Table	PURCHASE_ORDER_HEADER_NEW
	Del. Obj. Table	PURCHASE_ITEM_OLD
Control Tables – Reference Between Main and Master	Uplink Field	EBELN
	Uplink Mode	R

Table – First Field Reference from Main to Master Table	Uplink Target Fld	EBELN
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_POF_PO_IT_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_POF_PO_IT_REL
Parameter Setup	TrkID Method	Determine by Function
	Trk. ID Function	GTT_POF_PO_IT_TID
	Ctrl Data Function	GTT_POF_PO_IT_OTE
	Planned Event Function	GTT_POF_PO_IT_EE

4.12.3 Define Event Types for Purchase Order Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_PURORD
	Event Type	GTT_EVT_PO_IT_CF
	Description	PO Item Confirmation Event
	Text	Confirmation Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_POF_PO_IT_CF
	GTT Relevant	X
Control Tables	Main Obj. Table	PURCHASE_ITEM_NEW
	Master Table	PURCHASE_ORDER_HEADER_NEW
	Old Main Obj. Table	PURCHASE_ITEM_OLD
	Old Master Table	PURCHASE_ORDER_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	EBELN
	Uplink Mode	R
	Uplink Target Fld	EBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_POF_PO_IT_CF_REL

Segment	Field	Value
Header	Bus. Proc. Type	ESC_PURORD
	Event Type	GTT_EVT_PO_IT_DE
	Description	PO Item Deletion Event

	Text	Deletion Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_POF_PO_IT_DE
	GTT Relevant	X
Control Tables	Main Obj. Table	PURCHASE_ITEM_NEW
	Master Table	PURCHASE_ORDER_HEADER_NEW
	Old Main Obj. Table	PURCHASE_ITEM_OLD
	Old Master Table	PURCHASE_ORDER_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	EBELN
	Uplink Mode	R
	Uplink Target Fld	EBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_POF_PO_IT_DE_REL

Segment	**Field**	**Value**
Header	Bus. Proc. Type	ESC_MATDOC
	Event Type	GTT_EVT_PO_IT_GR
	Description	PO Item Goods Receipt Event
	Text	Goods Receipt Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_POF_PO_IT_GR
	GTT Relevant	X
Control Tables	Main Obj. Table	MATERIAL_SEGMENT
	Master Table	MATERIAL_HEADER
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	MBLNR
	Uplink Mode	R
	Uplink Target Fld	MBLNR
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_POF_PO_IT_GR_REL

4.12.4 Cross-processes for Purchase Order

The following entries should be maintained in transaction “ZGTT_AOTYPE_RST - AOT Types Restrictions” for the cross-processes tracking scenario.

Restr.ID	Restr.Pos	Option	Sign	Application Obj.Type
DL_TO_POIT	001	Equal To	Include	GTT_PO_IT
DL_TO_POHD	001	Equal To	Include	GTT_PO_HD

The following entries should be maintained in transaction “ZGTT_EVTYPE_RST - Event Types Restrictions” for the cross-processes tracking scenario.

Restr.ID	Restr.Pos	Option	Sign	Event Type
DL_TO_POIT	001	Equal To	Include	GTT_EVT_PO_IT_CF

4.12.5 Maintain Purchase Order Types that will be sent to SAP Business Network Global Track and Trace

Maintain the purchase order type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_POTYPE_RST - GTT Purchase Doc Type Configuration”, then mark it as active.
For example:

Purchasing Document Type	Active
NB	X

4.13 Inbound Delivery Extractor Configuration

4.13.1 Define Application Object Types for Inbound Delivery Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Appl. Obj. Type	GTT_IDLV_HD
	Description	Extract Inbound Delivery Header information to SAP Business Network Global Track and Trace
	Text	Inb. Delivery Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	Object Type	BUS2015
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_HEADER_NEW
	Del. Obj. Table	DELIVERY_HEADER_OLD
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_MIA_IDLV_HD_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_IDLV_HD_REL
Parameter Setup	TrkID Method	Determine by Function
	Tr.ID Extractor	GTT_MIA_IDLV_HD_TID
	Ctrl Data Function	GTT_MIA_IDLV_HD_OTE
	Planned Event Function	GTT_MIA_IDLV_HD_EE

4.13.2 Define Application Object Types for Inbound Delivery Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Appl. Obj. Type	GTT_IDLV_IT
	Description	Extract Inbound Delivery Item information to SAP Business Network Global Track and Trace
	Text	Inb. Delivery Item
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	Object Type	BUS2015
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Del. Obj. Table	DELIVERY_ITEM_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_MIA_IDLV_IT_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_IDLV_IT_REL
Parameter Setup	TrkID Method	Determine by Function
	Trk. ID Function	GTT_MIA_IDLV_IT_TID
	Ctrl Data Function	GTT_MIA_IDLV_IT_OTE
	Planned Event Function	GTT_MIA_IDLV_IT_EE

4.13.3 Define Event Types for Inbound Delivery Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_MATDOC
	Event Type	GTT_EVT_IDLV_GR
	Description	Delivery Header Goods Receipt Event
	Text	Delivery GR
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_IDLV_HD_GR
	GTT Relevant	X
Control Tables	Main Obj. Table	MATERIAL_HEADER
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_IDLV_HD_GR

4.13.4 Define Event Types for Inbound Delivery Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Event Type	GTT_EVT_IDLV_PA
	Description	Delivery Item Put Away Event
	Text	Put Away Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_IDLV_IT_PA
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Old Main Obj. Table	DELIVERY_ITEM_OLD
	Old Master Table	DELIVERY_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_IDLV_IT_PA

Segment	Field	Value

Header	Bus. Proc. Type	ESC_DELIV
	Event Type	GTT_EVT_IDLV_PACK
	Description	Delivery Item Packing Event
	Text	Delivery Packing
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_IDLV_IT_PKNG
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Old Main Obj. Table	DELIVERY_ITEM_OLD
	Old Master Table	DELIVERY_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_IDLV_IT_PKNG

4.13.5 Cross-processes for Inbound Delivery

The following entries should be maintained in transaction “ZGTT_AOTYPE_RST - AOT Types Restrictions” for the cross-processes tracking scenario.

Restr.ID	**Restr.Pos**	**Option**	**Sign**	**Application Obj.Type**
FU_TO_IDLH	001	Equal To	Include	GTT_IDLV_HD
FU_TO_IDLI	001	Equal To	Include	GTT_IDLV_IT
SH_TO_IDLH	001	Equal To	Include	GTT_IDLV_HD
SH_TO_IDLI	001	Equal To	Include	GTT_IDLV_IT

4.13.6 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace

Maintain the inbound delivery type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_DLVTYPE_RST - GTT Delivery Type Configuration”, then mark it as active.

For example:

Delivery Type	**Active**

EL	X

4.14 Sales Order Extractor Configuration

4.14.1 Define Application Object Types for Sales Order Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SORDER
	Appl. Obj. Type	GTT_SO_HD
	Description	Extract sales order header information to SAP Business Network Global Track and Trace
	Text	Sales Order Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	SALES_ORDER_HEADER_NEW
	Del. Obj. Table	SALES_ORDER_HEADER_OLD
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_SOF_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_SO_HD_REL
Parameter Setup	TrkID Method	Determine by Function
	Tr.ID Extractor	GTT_SOF_SO_HD_TID
	Ctrl Data Function	GTT_SOF_SO_HD_OTE
	Planned Event Function	GTT_SOF_SO_HD_EE

4.14.2 Define Application Object Types for Sales Order Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SORDER
	Appl. Obj. Type	GTT_SO_IT
	Description	Extract sales order item information to SAP Business Network Global Track and Trace
	Text	Sales Order Item
General Data	Seq. No.	20
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	SALES_ORDER_ITEMS_NEW

	Master Table	SALES_ORDER_HEADER_NEW
	Del. Obj. Table	SALES_ORDER_ITEMS_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_SOF_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_SO_IT_REL
Parameter Setup	TrkID Method	Determine by Function
	Trk. ID Function	GTT_SOF_SO_IT_TID
	Ctrl Data Function	GTT_SOF_SO_IT_OTE
	Planned Event Function	GTT_SOF_SO_IT_EE

4.14.3 Cross-processes for Sales Order

The following entries should be maintained in transaction “ZGTT_AOTYPE_RST - AOT Types Restrictions” for the cross-processes tracking scenario.

Restr.ID	Restr.Pos	Option	Sign	Application Obj.Type
DL_TO_SOIT	001	Equal To	Include	GTT_SO_IT
DL_TO_SOHD	001	Equal To	Include	GTT_SO_HD

4.14.4 Maintain Sales Order Types that will be sent to SAP Business Network Global Track and Trace

Maintain the sales order type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_SOTYPE_RST - GTT Sales Doc Type Configuration”, then mark it as active.
For example:

Sales Document Type	Active
ZGTT	X

4.15 Outbound Delivery Extractor Configuration

4.15.1 Define Application Object Types for Outbound Delivery Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV

	Appl. Obj. Type	GTT_ODLV_HD
	Description	Extract delivery header information to SAP Business Network Global Track and Trace
	Text	Delivery Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_HEADER_NEW
	Del. Obj. Table	DELIVERY_HEADER_OLD
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_SOF_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_ODLV_HD_REL
Parameter Setup	TrkID Method	Determine by Function
	Tr.ID Extractor	GTT_SOF_ODLV_HD_TID
	Ctrl Data Function	GTT_SOF_ODLV_HD_OTE
	Planned Event Function	GTT_SOF_ODLV_HD_EE

4.15.2 Define Application Object Types for Outbound Delivery Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Appl. Obj. Type	GTT_ODLV_IT
	Description	Extract delivery item information to SAP Business Network Global Track and Trace
	Text	Delivery Item
General Data	Seq. No.	20
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Del. Obj. Table	DELIVERY_ITEM_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_SOF_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)

	GTT Rel. Function	GTT_SOF_ODLV_IT_REL
Parameter Setup	TrkID Method	Determine by Function
	Trk. ID Function	GTT_SOF_ODLV_IT_TID
	Ctrl Data Function	GTT_SOF_ODLV_IT_OTE
	Planned Event Function	GTT_SOF_ODLV_IT_EE

4.15.3 Define Event Types for Outbound Delivery Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Event Type	GTT_EVT_ODLV_GI
	Description	Delivery Goods Issue event
	Text	Goods Issue Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_SOF_ODLV_GI
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_HEADER_NEW
	Old Main Obj. Table	DELIVERY_HEADER_OLD
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_ODLV_GI_REL

4.15.4 Define Event Types for Outbound Delivery Item

Segment	Field	Value
Header	Bus. Proc. Type	ESC_DELIV
	Event Type	GTT_EVT_ODLV_PA
	Description	Delivery Item Packing event
	Text	Packing Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_SOF_ODLV_IT_PA
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Old Main Obj. Table	DELIVERY_ITEM_OLD

	Old Master Table	DELIVERY_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_ODLV_PA_REL

Segment	**Field**	**Value**
Header	Bus. Proc. Type	ESC_DELIV
	Event Type	GTT_EVT_ODLV_PI
	Description	Delivery Item Picking event
	Text	Picking Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_SOF_ODLV_IT_PI
	GTT Relevant	X
Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Old Main Obj. Table	DELIVERY_ITEM_OLD
	Old Master Table	DELIVERY_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_ODLV_PI_REL

Segment	**Field**	**Value**
Header	Bus. Proc. Type	ESC_DELIV
	Event Type	GTT_EVT_ODLV_POD
	Description	Delivery Item POD event
	Text	POD Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_SOF_ODLV_IT_POD
	GTT Relevant	X

Control Tables	Main Obj. Table	DELIVERY_ITEM_NEW
	Master Table	DELIVERY_HEADER_NEW
	Old Main Obj. Table	DELIVERY_ITEM_OLD
	Old Master Table	DELIVERY_HEADER_OLD
Control Tables – Reference Between Main and Master Table – First Field Reference from Main to Master Table	Uplink Field	VBELN
	Uplink Mode	R
	Uplink Target Fld	VBELN
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_SOF_ODLV_POD_REL

4.15.5 Cross-processes for Outbound Delivery

The following entries should be maintained in transaction “ZGTT_AOTYPE_RST - AOT Types Restrictions” for Cross-Processes tracking scenario.

Restr.ID	Restr.Pos	Option	Sign	Application Obj.Type
SH_TO_ODLH	001	Equal To	Include	GTT_ODLV_HD
FU_TO_ODLH	001	Equal To	Include	GTT_ODLV_HD
FU_TO_ODLI	001	Equal To	Include	GTT_ODLV_IT

4.15.6 Maintain Delivery Types that will be sent to SAP Business Network Global Track and Trace

Maintain the outbound delivery type that you want to send to SAP Business Network Global Track and Trace via transaction “ZGTT_DLVTYPE_RST - GTT Delivery Type Configuration”, then mark it as active.

For example:

Delivery Type	Active
LBNP	X

4.16 Shipment Extractor Configuration

4.16.1 Define Application Object Types for Shipment Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SHIPMT
	Appl. Obj. Type	GTT_SHP_HD
	Description	Extract Shipment Header information to SAP Business Network Global Track and Trace

	Text	Shipment Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	SHIPMENT_HEADER_NEW
	Del. Obj. Table	SHIPMENT_HEADER_OLD
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID by Function	AOID Extractor	GTT_MIA_SHP_HD_AOID
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_SHP_HD_REL
Parameter Setup	TrkID Method	Determine by Function
	Trk. ID Function	GTT_MIA_SHP_HD_TID
	Ctrl Data Function	GTT_MIA_SHP_HD_OTE
	Planned Event Function	GTT_MIA_SHP_HD_EE

4.16.2 Define Event Types for Shipment Header

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SHIPMT
	Event Type	GTT_EVT_SHP_ARRIVE
	Description	Shipment Header Arrival Event
	Text	Arrival Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_SHP_HD_ARR
	GTT Relevant	X
Control Tables	Main Obj. Table	SHIPMENT_HEADER_NEW
	Old Main Obj. Table	SHIPMENT_HEADER_OLD
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_SHP_HD_ARR

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SHIPMT
	Event Type	GTT_EVT_SHP_CHECKIN
	Description	Shipment Header Check In Event
	Text	Check In Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_SHP_HD_CI
	GTT Relevant	X

Control Tables	Main Obj. Table	SHIPMENT_HEADER_NEW
	Old Main Obj. Table	SHIPMENT_HEADER_OLD
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_SHP_HD_CI

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SHIPMT
	Event Type	GTT_EVT_SHP_DEPART
	Description	Shipment Header Departure Event
	Text	Departure Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_SHP_HD_DEP
	GTT Relevant	X
Control Tables	Main Obj. Table	SHIPMENT_HEADER_NEW
	Old Main Obj. Table	SHIPMENT_HEADER_OLD
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_SHP_HD_DEP

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SHIPMT
	Event Type	GTT_EVT_SHP_LOADEND
	Description	Shipment Header Load End Event
	Text	Load End Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_SHP_HD_LE
	GTT Relevant	X
Control Tables	Main Obj. Table	SHIPMENT_HEADER_NEW
	Old Main Obj. Table	SHIPMENT_HEADER_OLD
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_SHP_HD_LE

Segment	Field	Value
Header	Bus. Proc. Type	ESC_SHIPMT
	Event Type	GTT_EVT_SHP_LOADSTAR
	Description	Shipment Header Load Start Event

	Text	Load Start Event
General Data	Seq. No.	10
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_MIA_SHP_HD_LS
	GTT Relevant	X
Control Tables	Main Obj. Table	SHIPMENT_HEADER_NEW
	Old Main Obj. Table	SHIPMENT_HEADER_OLD
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_MIA_SHP_HD_LS

4.17 Freight Unit Extractor Configuration

4.17.1 Define Application Object Types for Freight Unit Header

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Appl. Obj. Type	GTT_FU
	Description	Extract FU Information to SAP Business Network Global Track and Trace
	Text	FU Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
	Del. Obj. Table	TOR_ROOT
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID By Function	AOID Function	GTT_STS_AOID_TOR
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_FU_HD_REL
Parameter Setup	Trk.ID Method	Determine by Function
	Tr. Function	GTT_TS_FU_HD_TID
	Ctrl Data Function	GTT_TS_FU_HD_OTE
	Planned Event Function	GTT_TS_FU_HD_EE

4.17.2 Define Event Types for Freight Unit Header

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR

	Event Type	GTT_EVT_TOR_ARRIVE
	Description	FO/FB/FU Arrival Event
	Text	Arrival Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_ARRIVAL
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_ARRIVE

Segment	**Field**	**Value**
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_COUPLE
	Description	FO/FB/FU Coupling Event
	Text	Coupling Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_COUPLING
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_COUP

Segment	**Field**	**Value**
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_DECOUPLE
	Description	FO/FB/FU Decoupling Event
	Text	Decoupling Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_DECOUPL
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_DECP

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_UNLSTART
	Description	FO/FB/FU Unloading Start Event
	Text	Unloading Start
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_UNLD_STR
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_USTR

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_DELAY
	Description	FO/FB/FU Delay Event
	Text	Delay Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_DELAY
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_DELAY

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_DEPART
	Description	FO/FB/FU Departure Event
	Text	Departure Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_DEPART
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)

	GTT Rel. Function	GTT_TS_TOR_DEPART

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_FU_DELAY
	Description	FU Delay Event
	Text	FU Delay Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_FU_DELAY
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_FU_DELAY

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_LOADEND
	Description	FO/FB/FU Loading End Event
	Text	Loading End Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_LOAD_END
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_LEND

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_LOADSTRT
	Description	FO/FB/FU Loading Start Event
	Text	Loading Start Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_LOAD_STR
	GTT Relevant	X

Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_LSTR

Segment	**Field**	**Value**
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_POD
	Description	FO/FB/FU Proof of Delivery Event
	Text	POD Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_POD
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_POD

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_POPU
	Description	FO/FB/FU Proof of Pickup Event
	Text	POPU Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_POPU
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_POPU

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_UNLEND
	Description	FO/FB/FU Unloading End Event
	Text	Unloading End Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_UNLD_END
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_UEND

4.18 Road Freight Order/Ocean Booking/Air Booking Extractor Configuration

4.18.1 Define Application Object Types for Road Freight Order/Ocean booking/Air Booking Header

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Appl. Obj. Type	GTT_SHP _HD
	Description	Extract FO/FB information to SAP Business Network Global Track and Trace
	Text	FO/FB Header
General Data	Seq. No.	10
	CI for GTT	GTTAPPLOGS
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
	Del. Obj. Table	TOR_ROOT
Object Identification	AOID Method	Determine by Function
Object Identification – Application Object ID Source – Determine AOID By Function	AOID Function	GTT_STS_AOID_TOR
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_FO_HD_REL
Parameter Setup	Trk.ID Method	Determine by Function
	Tr. Function	GTT_TS_FO_HD_TID
	Ctrl Data Function	GTT_TS_FO_HD_OTE
	Planned Event Function	GTT_TS_FO_HD_EE

4.18.2 Define Event Types for Road Freight Order/Ocean Booking/Air Booking Header

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_ARRIVE
	Description	FO/FB/FU Arrival Event
	Text	Arrival Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_ARRIVAL
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT

Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_ARRIVE

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_COUPLE
	Description	FO/FB/FU Coupling Event
	Text	Coupling Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_COUPLING
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_COUP

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_DECOUPLE
	Description	FO/FB/FU Decoupling Event
	Text	Decoupling Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_DECOUPL
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_DECP

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_UNLSTART
	Description	FO/FB/FU Unloading Start Event
	Text	Unloading Start
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_UNLD_STR
	GTT Relevant	X

Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_USTR

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_DELAY
	Description	FO/FB/FU Delay Event
	Text	Delay Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_DELAY
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_DELAY

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_DEPART
	Description	FO/FB/FU Departure Event
	Text	Departure Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_DEPART
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_DEPART

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_LOADEND
	Description	FO/FB/FU Loading End Event
	Text	Loading End Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS

	Event Function	GTT_TS_TOR_LOAD_END
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_LEND

Segment	**Field**	**Value**
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_LOADSTRT
	Description	FO/FB/FU Loading Start Event
	Text	Loading Start Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_LOAD_STR
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_LSTR

Segment	**Field**	**Value**
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_POD
	Description	FO/FB/FU Proof of Delivery Event
	Text	POD Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_POD
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_POD

Segment	**Field**	**Value**
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_POPU
	Description	FO/FB/FU Proof of Pickup Event
	Text	POPU Event

General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_POPU
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_POPU

Segment	Field	Value
Header	Bus. Proc. Type	TMS_TOR
	Event Type	GTT_EVT_TOR_UNLEND
	Description	FO/FB/FU Unloading End Event
	Text	Unloading End Event
General Data	Seq. No.	0
	HCI for GTT	GTTAPPLOGS
	Event Function	GTT_TS_TOR_UNLD_END
	GTT Relevant	X
Control Tables	Main Obj. Table	TOR_ROOT
Global Track & Trace Relevance	GTT Rel. Method	Check Function (Function Module)
	GTT Rel. Function	GTT_TS_TOR_UEND

4.19 TM Configurations

You must do the following configurations in TM in SAP S/4HANA to ensure the following documents can be sent to Global Track and Trace:

- fright unit
- freight order
- freight booking

Procedure

1. Adjust the integration with TM in SAP S/4HANA and SAP EM. The Post Processing Framework (PPF) is used to trigger the communication from SAP Transportation Management (SAP TM) to SAP Event Management (SAP EM). You need to maintain the output management adapter for this communication to work.
    a. Log onto SAP, enter T-code **SPRO** and then click **SAP Reference IMG** to open the **Display IMG** page. Go to **Cross-Application Components** -> **Processes and Tools for Enterprise Applications** -> **Reusable Objects and Functions for BOPF Environment** -> **PPF Adapter for Output Management** -> **Maintain Output Management Adapter Settings**.
    b. In the **Dialog Structure** section, choose **Direct Output Agents (w/o PPF & w/o History)**.
    c. Choose the following entry and enable it.
        i. Business Object: /SCMTMS/TOR
        ii. Node: ROOT

iii. Agent Name: SEND_EM_DATA_FROM_TOR

d. Choose **Synch/Asynch** with value "Has Critical o/p: Process during Save - before Commit". (As described in note 1842397, the Synch/Asynch setting has to be set to "Has Critical o/p: Process during Save - before Commit" in order to use the before image data in the BAdI implementations.)

e. In the **Dialog Structure** section, choose **Nodes for Before Image**.

f. Create the following entries:

Business Object	Node	Sub Node Name
/SCMTMS/TOR	ROOT	EXECUTIONINFORMATION
/SCMTMS/TOR	ROOT	ITEM_TR
/SCMTMS/TOR	ROOT	STOP
/SCMTMS/TOR	ROOT	STOP_SUCCESSOR
/SCMTMS/TOR	ROOT	DOCREFERENCE
/SCMTMS/TOR	ROOT	EXECUTIONINFORMATION_TR
/SCMTMS/TXC	ROOT	TEXT
/SCMTMS/TXC	TEXT	TEXT_CONTENT

2. Adjust document type settings.

Note

Adjust the value of **Appl.Obj.Type** of these document types to ensure it's consistent with the following fields:

- **Appl.Obj.Type** field in **IMG -> Integration with Other SAP Components -> Interface to Global Track and Trace -> Define Application Interface -> Define Used Business Process Types, Appl. Object Types and Event Types -> Business Process Type TMS_TOR -> Define Application Object Types -> Interface to Global Track and Trace**
- **Application Object Type** field in the “gttft1” model (under the tab IDOC Integration) of the **Manage Models** app.

a. Adjust freight unit type settings.

i. On the IMG, go to **Transportation Management -> Planning -> Freight Unit -> Define Freight Unit Types**
ii. In the table, open the applicable freight unit type to be tracked with SAP Event Management.
iii. In the Integration Settings, fill in the **Application Obj.Type** field with value "**GTT_FU**".
iv. In the **Execution Settings**, the **Execution Tracking Relevance** field is set to “Execution Tracking with External Event Management”.

b. Adjust freight order type settings.

i. On the IMG, go to **Transportation Management -> Freight Order Management -> Freight Order -> Define Freight Order Types**

ii. In the table, open the applicable freight order type to be tracked with SAP Event Management.
iii. In the **Integration Settings**, fill in the **Application Obj.Type** field with value **GTT_SHP_HD**.
iv. In the **Execution Settings**, the **Execution Tracking Relevance** field is set to “Execution Tracking with External Event Management”.

c. Adjust the freight booking type settings.

i. On the IMG, go to **Transportation Management** -> **Freight Booking Management** -> **Freight Booking** -> **Define Freight Booking Types**
ii. In the table, open the applicable freight booking type to be tracked with SAP Event Management
iii. In the Integration Settings, fill in the **Application Obj.Type** field with value **GTT_SHP_HD**.
iv. In the **Execution Settings**, the **Execution Tracking Relevance** field is set to “Execution Tracking with External Event Management”

5. CONFIGURATION AND CODING GUIDE – ADVANCED

This chapter has been moved to the guide *How to Send Documents from SAP S/4HANA to SAP Business Network Global Track and Trace* on SAP Help Portal. Please check the Coding Tips section of this guide. You can find this guide at http://help.sap.com/gtt.

6 KNOWN ISSUES

6.1 Planned Event Extension Not Enabled

Currently, on SAP S/4HANA side, the EXTENSION segment of process IDOC is not enabled for the planned event part, which means that you cannot make the user-defined fields for planned events in the *Manage Models* app.

The workaround is to make use of Control Parameter's segment in IDOC and make the field mapping on the tracked process level in the *Manage Models* app.

6.2 One-time locations Relevant

- When the supplier address is changed in the purchase order header, the purchase order item IDOC cannot be triggered. So, the change cannot be updated to its purchase order items in the GTT system.
- After the sales order and the outbound delivery are created, then if you change the address in the sales order, the change cannot be updated to the outbound delivery in the GTT system, because no new outbound delivery IDOC is generated and sent to the GTT system. The same goes for the purchase order and the inbound delivery.
- After the outbound delivery and the LE-TRA shipment are created, then if you change the address in the outbound delivery, the change cannot be updated to the LE-TRA shipment in the GTT system, because no new LE-TRA shipment IDOC is generated and sent to the GTT system. The same goes for the inbound delivery and the LE-TRA shipment.
- If you change the address in the LE-TRA shipment, the change can be updated to the outbound/inbound delivery header through cross-process updates. But it cannot be updated to the item level.

APPENDIX ONE: DEFINE THE UNPLANNED EVENTS FOR AIR BOOKING

You need to define the following unplanned events for air booking before they can be synchronized back from GTT to TM:


- Flight Booked
- Manifest Ready
- Received from Shipper
- Consignee Notified.

To define these unplanned events, do the following:


Note: here the unplanned event “Flight Booked” is used as an example.

1. On the **Display IMG** page, click **Transportation Management**-> **Integration**-> **Tracking and Tracing of Processes and Documents**-> **Define Transportation Activities for Tracking and Tracing.**


2. Select **Event for Business Document** and click **New Entries.**




3. Input the **Event** name, **Description**, **Transp Act** and Click **Save.**




4. Select the event "FLIGHT_BOOKED", then double click **Assignment of Events to Business Object.**



5. Click **New Entries.**



6. Select **"**BO Freight Booking" and Click **Save.**



Results:

The configuration results for these event types should be as follows:

Event	Description	Transportation Activity	Stop Category	Event relevance for category
FLIGHT_BOOKED	Flight Booked	99	blank	BO (Freight Booking)
MANIFEST_READY	Manifest Ready	99	blank	BO (Freight Booking)
RCVD_FROM_SHIPPER	Received from Shipper	99	blank	BO (Freight Booking)
CONSIGNEE_NOTIFIED	Consignee Notified	99	blank	BO (Freight Booking)

Now you can go on to configure for synchronizing these unplanned events back to TM. For configuration details, see Synchronize Actual Events Back to TM System. If the events still cannot be synchronized back to TM, please check the SAP Note 3010748 - Allow unexpected events without location reference in TransportationEventBulkNotification.


APPENDIX TWO: FAQS

This chapter provides you with answers to questions commonly asked about the configuration.


Q1: After the configuration of GTT and SAP TM systems, we found that the freight unit / freight order / freight booking IDOC cannot be sent to SAP Business Network Global Track and Trace, how can we do the troubleshooting?


Step 1: Check the trigger point of the generation of freight unit / freight order / freight booking IDOC

a. Go to T-code `SE19`, fill in the **Enhancement Implementation** with "ZGTT_STS_EI_SEND_TOR_DATA" and click **Display**.



b. Ensure that the **Enhancement Implementation** “ZGTT_STS_EI_SEND_TOR_DATA” is active. In the **Enh. Implementation Elements** tab, ensure that **BAdI Implementation** “ZGTT_STS_BI_SEND_TOR_DATA” is active.







Step 2: Check the freight order / freight booking master data

To send freight orders or freight bookings to SAP Business Network Global Track and Trace, do the following:


a. Assign the carrier.
b. Change the execution status.
   - For freight orders: in the **Execution Status** tab on the top, change the **Execution Status** to “Set to Ready for Transportation Execution” or " Set to In Execution".


Edit GTT Standard Freight Order Type AccAWS 6100063618
Edit
Refresh
Copy
Other Copy Options
Check
Follow Up
Scheduling
Subcontracting
Create Service Order
Schedule
Set Status
Display Settings
General Data
Business Partner
Items
Overview
Stages
Utilization
Blocking Information
Set to Ready for Transportation Execution
Set to Not Ready for Transportation Execution
Set to In Execution
Set to Not Started
Set to Checked Out
Set to Departed
Set to Arrived
Set to Checked In
Set to Loaded
Set to Not Loaded
Set to Unloaded
Set to Not Unloaded
Load Plan Status (Stop)
Execution Status
Fixing
Customs
Charges/Settlement
Cancel Document
Load Plan Status (Packaging)
Load Plan Status (Load Planning)
Truck
Means of Transport:
Vehicle:
Registration Country/Region No.:
Total/Consumed/Remaining Capacity... :
2,000
KG
Total/Consumed/Remaining Capacity... :
20
M3
Maximum Utilization:
0%
Cargo Information
Cargo Weight:
2,000
KG
Cargo Volume:
20
M3
Quantity:
20
EA
Total Weight:
2,000
KG
General Information
Document Type:
STR1
GTT Standard Freight Order Type AccAWS
Description:
GTT Standard Freight Order Type Ac...
Origin of Freight Order:
Manual Creation
Transportation
Carrier:
LBN_CAR100
Executing Carrier:
Communication Party:
Service Level – Carrier:
SCAC:
SCAC:
1
2

- For freight bookings:
  - Air booking: in the **Execution Status** tab on the top, change the **Execution Status** to "Set to MAWB Finalized" or “Set to In Execution”.



  - Ocean booking: in the **Execution Status** tab on the top, change the **Execution Status** to “Set to Ready for Transportation Execution” or " Set to In Execution".




Debugging

If the issue still exists, you can perform the following steps to debug in the extractor code:

a. On the IMG, go to node **Cross-Application Components -> Processes and Tools for Enterprise Applications ->Reusable Objects and Functions for BOPF Environment -> PPF Adapter for Output Management -> Maintain Output Management Adapter Settings.**

b. In the **Dialog Structure** section, choose **Direct Output Agents (w/o PPF & w/o History).** Ensure that the following entry is enabled:



Note: in this entry, the value of **Synch/Asynch** column is “Has Critical o/p: Process during Save - before Commit”.

c. Set a break point in method /SCMTMS/IF_SEND_TOR_DATA~CALL_EVENT_MGR of the BAdI implementing class ZCL_GTT_STS_SEND_TOR_DATA.

d. For the scenario when the freight unit watches the freight order, set additional break point in below places:

- In method ZIF_GTT_STS_BO_READER~CHECK_RELEVANCE of class ZCL_GTT_STS_BO_FU_READER, check the value of “rv_result”. If it is “T”, it means

the freight unit IDOC can be generated. Otherwise, the freight unit IDOC cannot be generated.

- In method ZIF_GTT_STS_BO_READER~CHECK_RELEVANCE of class ZCL_GTT_STS_BO_FO_READER, check the value of “rv_result”. If it is “T”, it means the freight order IDOC can be generated. Otherwise, the freight order IDOC cannot be generated.

Q2: How to add customized planned event and synchronize this event back to SAP TM?


Suppose you want to add the planned event type "quality inspection" for the freight order tracked process, do the following:

Step 1: Create a planned event type in the GTT standard model “gttft1” in the Manage Models app

a. Launch the Manage Models app and go to the GTT standard model “gttft1”.
b. In the **Event Type Pool** tab, click **Create** and fill in the event information in the dialogue. For details, see “Create Event Type” section in Guide for Model Administrators.
Note: the event type must start with "ZZ".For example ZZINSPECTION.

c. Assign the newly created event type to the shipment tracked process.
   - In the **Tracked Process** tab, choose **Admissible Planned Events** from the dropdown list on the right and click **Add**.
   - In the **Details** tab of the dialogue, choose the **Event Type** that you created from the dropdown list and fill in the rest of information.

d. Configure the IDOC mapping
   - Click **Edit** on the top. In the **IDOC Integration** tab, for **Tracked Process** field, choose “Shipment” from the dropdown list.
   - Under **Tracked Process / Events,** fill in **IDOC** and **Event Code** for the newly created event type.



e. In the **User Script Before Standard Script** section, add your script for synchronizing back the customized event to SAP TM.

Example:

```
var inspection_event = modelNamespace + ".Shipment.ZZINSPECTION";
if (inspection_event  == actualEvent.eventType ) {
```

```
    eventForwardToTM = true;

}
```

f. Save you changes and click **Deploy** on the top right to deploy the model. Once the model is successfully deployed, you can see **Active** on the model card with its last operation status “Deployment Success”.

Step 2: Add the ABAP Implementation Code

a. Navigate to the method ZIF_GTT_STS_PE_FILLER~GET_PLANNED_EVENTS of class ZCL_GTT_STS_PE_FO_FILLER in the system.


b. Add the planned event type that you created in the Manage Models app as milestone event. For coding tips, see chapter 5 in this guide.

Note: when you add the planned event type, remember that the event name here must be the same as the event code that you previously maintained in the IDOC mapping.


Step 3: Add the above customized event In SAP TM.

a. On the **Display IMG** page, click **Transportation Management**-> **Integration**-> **Tracking and Tracing of Processes and Documents**-> **Define Transportation Activities for Tracking and Tracing.**


b. Select **Event for Business Document** and click **New Entries.**




c. Input the **Event** name, **Description**, **Transp Act** and Click **Save.**




d. Select the event "ZZ_INSPECTION", then double click **Assignment of Events to Business Object.**



e. Click **New Entries.**



f. Select "TO Freight Order" and Click **Save.**



Now you can go on to configure for synchronizing events back to TM. For configuration details, see Synchronize Actual Events Back to TM System. If the events still cannot be synchronized back to TM, please check the SAP Note 3010748 - Allow unexpected events without location reference in TransportationEventBulkNotification.

Q3: How to update business partner's LBN ID?

To update the LBN ID in SAP Transportation Management (SAP TM) for a logistics service provider (your business partner), proceed as follows in SAP TM:

Step 1: Define Identification Categories for LBN Identification Number
Go to SAP Customizing Implementation Guide under **Cross-Application Components->SAP Business Partner->Business Partner->Basic Settings->Identification Numbers->Define Identification Categories** and maintain the following entry:

ID Cat.	Description	ID Unique	Disp. Only	One ID->BP	Identification Schema
LBN001	LBN Identification			X	

Step 2: Define Identification Types for LBN Identification Number
Go to SAP Customizing Implementation Guide under **Cross-Application Components->SAP Business Partner->Business Partner->Basic Settings->Identification Numbers->Define Identification Types**. Create a new ID Type as follows:

ID Type	Description	ID Categ.	Persons	Organizations
LBN001	LBN Identification	LBN001	X	X

Step 3: Update Business Partner's LBN ID

a. Go to the **Manage Business Partner** transaction (transaction BP).


b. Set the filtering criteria to find the business partner for which you want to update the LBN ID. Double-click the business partner to open its **Display Organization** page.

c. Go to the **Identification** tab. In the **Identification Numbers** section, enter "LBN001" in the **IDType** column.

d. In the **Identification Number** field, enter the LBN ID and save your changes.

Q4: How is the connection established between SAP S/4HANA and SAP Business Network Global Track and Trace? Do I need to configure PI in SAP S/4HANA?

When saving the transaction data, the asynchronized IDOC was sent to establish the connection between SAP S/4HANA and SAP Business Network Global Track and Trace. You don't need to set up PI in SAP S/4HANA.
The data process flow is as below:



Q5: What scenarios are supported in SAP Business Network Global Track and Trace?

1) Purchase Order -> Inbound Delivery -> Shipment.



2) Purchase Order -> Inbound Delivery -> Freight Unit -> Road Freight Order / Ocean Booking / Air Booking.




3) Sales Order -> Outbound Delivery -> Shipment.




4) Sales Order -> Outbound Delivery -> Freight Unit -> Road Freight Order / Ocean Booking / Air Booking.



5) Stock Transport Order
Scenario A:
Purchase Order -> Outbound Delivery -> Shipment.



Scenario B:
Purchase Order -> Outbound Delivery -> Freight Unit -> Road Freight Order / Ocean Booking / Air Booking.



Q6: Do sample codes support one-time locations? Where can I maintain the one-time location address?

Yes. You can maintain one-time locations in the following fields:

Tracked Processes	Fields
Purchase Order	**Address** in Purchase Order header
Purchase Order Item	**Delivery Address** in Purchase Order Item
Inbound Delivery	**Goto**->**Header**->**Partners**->**Partner Function "Supplier"**
Shipment	Fields under **Stages->Departure point / Destination** or you can directly add the one-time location address in the stage
Sales Order	Fields under **Goto**->**Header**->**Partner**->**Partner Function "Sold-To Party" or "Ship-To Party"**
Outbound Delivery	Fields under **Goto**->**Header**->**Partners**->**Partner Function "Ship-To Party"**

Q7: How to stop sending unnecessary IDOCs from SAP S/4HANA to the GTT system?

To do so, you should not mark application object types/event types as “GTT Relevant”.


Take the purchase order as an example, you can perform the following steps:

a. In **Display IMG** page, click **Integration with Other SAP Components** -> **Interface to Global Track and Trace** -> **Define Application Interface.**


b. Choose activity **Define Used Business Process Types, Appl. Object Types and Event Types**.

c. Choose the business process type **“**ESC_PURORD” and double click **Define Application Object Types** on the left.

d. Uncheck the “GTT Relevant” box for application object types “GTT_PO_HD” and “GTT_PO_IT”, and it will stop sending control parameter / planned events / tracking ID of the purchase order and its items.



e. Uncheck the “GTT Relevant” box for event types “GTT_EVT_PO_IT_CF” and “GTT_EVT_PO_IT_DE”, and it will stop sending actual events of the purchase order and its items.



Q8: How to deactivate or activate the application log?


Take the purchase order as an example, to deactivate the application log for application object types and event types, do the following:

a. In **Display IMG** page, click **Integration with Other SAP Components** -> **Interface to Global Track and Trace** -> **Define Application Interface.**


b. Choose activity **Define Used Business Process Types, Appl. Object Types and Event Types**.

c. Choose the business process type **“**ESC_PURORD”

d. To deactivate the application log for application object types, double click **Define Application Object Types** on the left, then check the “Application Log Deactivation” box for application object types “GTT_PO_HD” and “GTT_PO_IT”. It will stop recording the application log for control parameter / planned events / tracking ID of the purchase order and its items.



e. To deactivate the application log for event types, double click **Define Event Types** on the left, then check the “Application Log Deactivation” box for event types “GTT_EVT_PO_IT_CF” and “GTT_EVT_PO_IT_DE”. It will stop recording the application log for actual events of the purchase order and its items.



To activate the application log for application object types and event types, you can uncheck the “Application Log Deactivation” box.

www.sap.com/contactsap

© 2022 SAP SE or an SAP affiliate company. All rights reserved.
No part of this publication may be reproduced or transmitted in any form or for any purpose without the express permission of SAP SE or an SAP affiliate company.

The information contained herein may be changed without prior notice. Some software products marketed by SAP SE and its distributors contain proprietary software components of other software vendors. National product specifications may vary.

These materials are provided by SAP SE or an SAP affiliate company for informational purposes only, without representation or warranty of any kind, and SAP or its affiliated companies shall not be liable for errors or omissions with respect to the materials. The only warranties for SAP or SAP affiliate company products and services are those that are set forth in the express warranty statements accompanying such products and services, if any. Nothing herein should be construed as constituting an additional warranty.

In particular, SAP SE or its affiliated companies have no obligation to pursue any course of business outlined in this document or any related presentation, or to develop or release any functionality mentioned therein. This document, or any related presentation, and SAP SE's or its affiliated companies' strategy and possible future developments, products, and/or platform directions and functionality are all subject to change and may be changed by SAP SE or its affiliated companies at any time for any reason without notice. The information in this document is not a commitment, promise, or legal obligation to deliver any material, code, or functionality. All forward-looking statements are subject to various risks and uncertainties that could cause actual results to differ materially from expectations. Readers are cautioned not to place undue reliance on these forward-looking statements, and they should not be relied upon in making purchasing decisions.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP SE (or an SAP affiliate company) in Germany and other countries. All other product and service names mentioned are the trademarks of their respective companies. See www.sap.com/trademark for additional trademark information and notices.

THE BEST RUN