




## <Rocky9 – VNC>

|                                                                                                                                                                                                                                                         |                                                                                                                                                                                                                                                                                                 |
|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <pre>[root@localhost ~]# sudo dnf install -y tigervnc-server</pre>                                                                                                                                                                                      | <p><b>[1단계: TigerVNC 서버 설치]</b></p> <p>dnf install tigervnc-server -y</p>                                                                                                                                                                                                                       |
| <pre>[root@localhost ~]# sudo vim /etc/tigervnc/vncserver.users # TigerVNC User assignment # # This file assigns users to specific VNC display numbers. # The syntax is &lt;display&gt;=&lt;username&gt;. E.g.: # # :2=andrew # :3=lisa # :1=root</pre> | <p><b>[2단계: 사용자 설정 등록]</b></p> <p>vim /etc/tigervnc/vncserver.users</p> <p>열고</p> <p>:1=root 입력해주세요.</p>                                                                                                                                                                                        |
| <pre>[root@localhost ~]# sudo vim /etc/tigervnc/vncserver.users [root@localhost ~]# vncpasswd Password: Verify: Would you like to enter a view-only password (y/n)? y Password: Verify:</pre>                                                           | <p><b>[3단계: VNC 비밀번호 설정]</b></p> <p>vncpasswd</p> <p>하시고</p> <p>would you like to enter a view-only password 가 뜨면 y 누르고</p> <p>또 password 입력하세요</p>                                                                                                                                             |
| <pre>[root@localhost ~]# dnf groupinstall -y "Server with GUI" systemctl set-default graphical.target</pre>                                                                                                                                             | <p><b>[4단계: 데스크탑 환경 확인, 기존에 GNOME이 있어도 반드시 실행]</b></p> <p>dnf groupinstall -y "Server with GUI"</p> <p>systemctl set-default graphical.target</p>                                                                                                                                               |
| <pre>[root@localhost ~]# mkdir -p /root/.vnc vim /root/.vnc/xstartup [root@localhost ~]# chmod +x /root/.vnc/xstartup  #!/bin/bash unset SESSION_MANAGER unset DBUS_SESSION_BUS_ADDRESS exec /usr/bin/gnome-session &amp;</pre>                         | <p><b>[5단계: xstartup 파일 설정]</b></p> <p>1. mkdir -p ~/.vnc</p> <p>2. vim /root/.vnc/xstartup</p> <p>#!/bin/bash</p> <p>unset SESSION_MANAGER</p> <p>unset DBUS_SESSION_BUS_ADDRESS</p> <p>exec /usr/bin/gnome-session &amp;</p> <p>내용 추가하고 저장</p> <p>3. chmod +x ~/.vnc/xstartup</p> <p>권한부여</p> |
|                                                                                                                                                                                                                                                         | <p><b>[6단계: VNC 서비스 활성화]</b></p> <p>systemctl daemon-reload</p>                                                                                                                                                                                                                                 |

|                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |                                                                                                                                                             |
|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------|
|  <pre> [root@localhost ~]# systemctl daemon-reload systemctl enable vncserver@:1 systemctl start vncserver@:1 Created symlink /etc/systemd/system/multi-user.target.wants/vncserver@:1.service - /usr/lib/systemd/system/vncserver@.service. [root@localhost ~]# systemctl status vncserver@:1 vncserver@:1.service - Remote desktop service (VNC)    Loaded: loaded (/usr/lib/systemd/system/vncserver@.service; enabled; preset: disabled)    Active: active (running) since Wed 2025-10-22 17:00:24 KST; 3s ago      Process: 40330 ExecStartPre=/usr/libexec/vncsession-restore :1 (code=exited, status=0/SUCCESS)      Process: 40340 ExecStart=/usr/libexec/vncsession-start :1 (code=exited, status=0/SUCCESS)     Main PID: 40355 (vncsession)        Tasks: 0 (limit: 22915)       Memory: 1.7M          CPU: 36ms     CGroup: /system.slice/system-vncserver.slice/vncserver@:1.service             └─ 40355 /usr/sbin/vncsession root :1 </pre> | <p>systemctl enable vncserver@:1<br/>systemctl start vncserver@:1</p> <p>하시고<br/>systemctl status vncserver@:1<br/>로 서비스 상태 확인하세요.<br/>(방화벽 모두 꺼주셔야합니다)</p> |
|  <p>VNC Viewer</p> <p>VNC Server: 172.16.16.100:5901</p> <p>Encryption: Let VNC Server choose</p> <p>Connect</p> <p>VNC Viewer - Encryption</p> <p><b>Unencrypted connection</b></p> <p>The connection to this VNC Server will not be encrypted.</p> <p>VNC Server: 172.16.16.100:5901</p> <p>Your authentication credentials will be transmitted securely, but all subsequent data exchanged while the connection is in progress may be susceptible to interception by third parties.</p> <p><input type="checkbox"/> Don't warn me about this again.</p> <p>Continue Cancel</p> <p>VNC Viewer - Authentication</p> <p>VNC Server: 172.16.16.100:5901</p> <p>Username: </p> <p>Password: </p> <p>OK Cancel</p>                                                                                                                                                                                                                                           | <p>&lt;IP&gt;:5901 입력하시고 connect<br/>continue<br/>비밀번호 입력</p>                                                                                               |
|  <p>localhost:localhost:1 (root) - VNC Viewer</p> <p>Activities</p> <p>Oct 22 17:11</p> <p>Rocky</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     | <p>완료</p>                                                                                                                                                   |