



<Ubuntu – TigerVNC>

<pre> root@root:~# apt install tigervnc-standalone-server tigervnc-xorg-extension Reading package lists... Done Building dependency tree... Done Reading state information... Done The following additional packages will be installed: libfile-readbackwards-perl tigervnc-common tigervnc-tools Suggested packages: xfonts-100dpi xfonts-75dpi The following NEW packages will be installed: libfile-readbackwards-perl tigervnc-common tigervnc-standalone-server tigervnc-tools tigervnc-xorg-extension 0 upgraded, 5 newly installed, 0 to remove and 12 not upgraded. Need to get 1,498 kB of archives. After this operation, 3,892 kB of additional disk space will be used. Do you want to continue? [Y/n] y Get:1 http://archive.ubuntu.com/ubuntu noble/universe amd64 libfile-readbackwards-perl all 1.06-2 [10.2 kB] </pre>	[1단계: TigerVNC 서버 설치] apt install tigervnc-standalone-server tigervnc-xorg-extension 입력
<pre> Running kernel seems to be up-to-date. No services need to be restarted. No containers need to be restarted. No user sessions are running outdated binaries. No VM guests are running outdated hypervisor (qemu) binaries on this host. root@root:~# vncpasswd Password: Verify: Would you like to enter a view-only password (y/n)? y Password: Verify: </pre>	[2단계: VNC 비밀번호 설정] vncpasswd VNC 접속에 사용할 비밀번호를 설정합니다. vncpasswd 명령어를 입력하고, 6자 이상의 비밀번호를 입력합니다. '보기 전용' 비밀번호를 설정할지 묻는 메시지가 나타나면 n을 입력하여 건너뛸 수 있습니다.
<pre> root@root:~# mkdir -p ~/.vnc root@root:~# touch ~/.vnc/xstartup root@root:~# chmod u+x ~/.vnc/xstartup root@root:~# ls 'Untitled Folder' team1@root:~\$ sudo -i [sudo] password for team1: root@root:~# vim ~/.vnc/xstartup root@root:~# cd ~/.vnc -bash: cd: ~/.vnc: No such file or directory root@root:~# cd .vnc root@root:~/.vnc# ls passwd xstartup root@root:~/.vnc# vim xstartup root@root:~/.vnc# </pre>	[3단계: xstartup 파일 구성] ~/.vnc/xstartup <pre> #!/bin/bash export XKL_XMODMAP_DISABLE=1 [-x /etc/vnc/xstartup] && exec /etc/vnc/xstartup [-r \$HOME/.Xresources] && xrdp \$HOME/.Xresources vncconfig -iconic & dbus-launch --exit-with-session startplasma-x11 </pre> ~/.vnc/xstartup 파일을 수정하여 VNC 세션에서 사용할 GUI 환경을 지정하고 실행 권한을 부여합니다. ** GNOME 설치 <pre> sudo apt update sudo apt install -y ubuntu-desktop </pre>
	[4단계: VNC 서버 시작] 서버 시작 기본 명령어 : vncserver

 <pre> root@root:~/.vnc# vncserver -localhost no New Xtigervnc server 'root:1 (root)' on port 5901 for display :1. Use xtigervncviewer -SecurityTypes VncAuth,TLSSync -passwd /tmp/tiger/vnc-ynR0td/passwd root:1 to connect to the VNC server. ===== tail /root/.vnc/root:1.log ===== /root/.vnc/xstartup: 9: exec: startx: not found ===== Session startup via '/root/.vnc/xstartup' exited with status 127! Maybe try something simple first, e.g., xtigervncserver -xstartup /usr/bin/stern The X session exited with status 127! Killing Xtigervnc process ID 2407... success! root@root:~/.vnc# </pre>	- 기본적으로 로컬 호스트만 접근 허용함. 그러므로 아래 옵션을 넣어서 켤 것! vncserver -kill :1 vncserver -localhost no :1 # vncserver -localhost no 명령어를 사용하여 VNC 서버를 시작합니다. :1은 디스플레이 번호(포트 5901)를 나타냅니다. 실행 확인 # vncserver -list
 VNC Viewer VNC® Viewer VNC Server: 172.16.254.6:5901 Encryption: Let VNC Server choose About... Options... Connect VNC-Viewer-5.3.3-Windows-64bit.exe	[5단계: VNC 클라이언트로 접속] ip:5901 로 접속(or 5902) VNC 클라이언트를 사용하여 ip:5901 로 접속(or 5902)로 접속하고 2단계에서 설정한 비밀번호를 입력합니다.