一、安装过程

下载相关php安装包,进行解压,进入安装包,进行编译安装,编译

./configure

- --prefix=/soft/php74
- --with-config-file-path=/soft/php74/etc
- --with-libdir=/usr/lib64
- --with-freetype=/usr/include/freetype2/freetype/
- --with-jpeg=/usr/lib64
- --disable-rpath
- --with-curl
- --enable-gd
- --with-gettext
- --with-mysqli
- --with-openssl
- --with-openssl-dir
- --with-iconv
- --with-zip
- --with-pdo-mysql
- --with-pdo-sqlite
- --with-xsl
- --with-zlib
- --with-bz2
- --with-mhash
- --enable-fpm
- --enable-pdo
- --enable-session
- --enable-simplexml
- --enable-bcmath
- --enable-mbregex
- --enable-mbstring
- --enable-opcache
- --enable-pcntl
- --enable-shmop
- --enable-soap
- --enable-sockets
- --enable-sysvmsg
- --enable-sysvsem

- --enable-sysvshm
- --enable-mysqlnd
- --enable-xml
- --enable-phar

如果没有报错就进行编译安装

make && make install

在进行make的时候报错如下: make: *** [ext/phar/phar.php]

解决方法如下: make ZEND_EXTRA_LIBS='-liconv'

二、问题排查

安装的过程中基本没出现什么问题,主要问题出现在php启动的时候,本次的环境是进行php版本升级,由7.2升级到7.4,安装成功后查看phpinfo信息总是显示php版本为7.2,无法切换到新安装的版本。通过分析发现,nginx是通过fastcgi进程管理器与php进行通信,php-fpm为进程管理器的一种,所以初步判断是nginx无法正常与php通信造成的,中间的主要遇到的问题如下:

1、手动启动php-fpm,访问系统提示502,查看日志报错如下:

主要报错原因为nginx和php-fpm的配置sock方式不同,原有的nginx配置方式为为通过文件进行访问,内容如下

而新的php-fpm的访问方式为通过监听端口的方式(可通过查看配置文件,配置文件路径为php7_4/etc/php-fpm.d/www.conf),具体内容如下

```
    I root(55H)@192.168.215.203

 pool name ('www' here)
 [www]
  Per pool prefix
  It only applies on the following directives:
  - 'access.log'
 - 'slowlog'
- 'listen' (unixsocket)
  - 'chroot'
 - 'chdir'
 - 'php_values'
- 'php_admin_values'
  When not set, the global prefix (or /usr/local/php7_4) applies instead.
  Note: This directive can also be relative to the global prefix.
 Default Value: none
 prefix = /path/to/pools/$pool
 Unix user/group of processes
Note: The user is mandatory. If the group is not set, the default user's group
        will be used.
 ser = nobody
group = nobody
  The address on which to accept FastCGI requests.
 Valid syntaxes are:
     'ip.add.re.ss:port'
                            - to listen on a TCP socket to a specific IPv4 address on
                                a specific port;
    '[ip:6:addr:ess]:port' - to listen on a TCP socket to a specific IPv6 address on
                               a specific port;

    to listen on a TCP socket to all addresses
(IPv6 and IPv4-mapped) on a specific port;

   '/path/to/unix/socket' - to listen on a unix socket.
; Note: This value is mandatory.
listen = 127.0.0.1:9000
  Set listen(2) backlog.
  Default Value: 511 (-1 on FreeBSD and OpenBSD)
 ;listen.backlog = 511
 Set permissions for unix socket, if one is used. In Linux, read/write permissions must be set in order to allow connections from a web server. Many BSD-derived systems allow connections regardless of permissions. The owner
  and group can be specified either by name or by their numeric IDs.
  Default Values: user and group are set as the running user
                   mode is set to 0660
 :listen.owner = www-data
;listen.group = www-data
 ;listen.mode = 0660
 When POSIX Access Control Lists are supported you can set them using
  these options, value is a comma separated list of user/group names.
  When set, listen.owner and listen.group are ignored
解决方法:
修改enable-php.conf 文件,修改内容如下:
location \sim [^/].php(/|\$)
try files $uri =404;
fastcgi pass 127.0.0.1:9000;
fastcgi index index.php;
include fastcgi.conf;
}
在nginx中引用该配置文件(nginx配置文件如下: /usr/local/nginx/conf/nginx.conf),内容如下:
```

```
pwxt-admin.qdta.cn.conf pwxt-admin.qdta.cn.conf-- pwxt-operator.qdta.cn.conf [root@qilin-vl0 vhost] # cat pwxt-admin.qdta.cn.conf
   listen 80:
       listen 443 ssl http2;
       server_name pwxt-admin.qdta.cn;
   index index.php index.html index.htm default.php default.html;
   root /home/wwwroot/pwxt-admin.qdta.cn/public;
   ♯SSL-START SSL相关配置,请勿删除或修改下一行带注释的404规则
   #error_page 404/404.html;
   ssl_certificate /www/server/panel/vhost/cert/pwxt-admin.qdta.cn/pwxt-admin.qdta.cn_bundle.pem;
   ssl_certificate_key /www/server/panel/vhost/cert/pwxt-admin.qdta.cn/pwxt-admin.qdta.cn.key;
ssl_protocols ILSvl.1 ILSvl.2 ILSvl.3;
   ss1 ciphers EECDH+CHACHA20:EECDH+CHACHA20-draft:EECDH+AES128:RSA+AES128:EECDH+AES256:RSA+AES256:EECDH+3DES:RSA+3DES:!MD5;
   ssl_prefer_server_ciphers on;
   ssl_session_cache shared:SSL:10m;
   ssl_session_timeout 10m;
   add header Strict-Transport-Security "max-age=31536000";
error_page 497 https://$host$request_uri;
   #SSL-END
   #ERROR-PAGE-START 错误页配置,可以注释、删除或修改
   #error_page 404 /404.html;
    #error_page 502 /502.html;
   #ERROR-PAGE-END
   #PHP-INFO-START PHP引用配置,可以注释或修改
   include /usr/local/nginx/conf/enable-phpl.conf;
   #include /usr/local/nginx/conf/enable-php.conf;
   #PHP-INFO-END
    ♦REWRITE-START URL重写规则引用,修改后将导致面板设置的伪静态规则失效
    #include /www/server/panel/vhost/rewrite/pwxt-admin.yunyouqilu.com.conf;
   #REWRITE-END
   #禁止访问的文件或目录
       location /robot-web/ {
               proxy_pass http://192.168.215.196:8083/;
```

2、修改后报错如下:

提示被拒绝, 错误信息如下:

```
*** Fide No. 15 | Stall 15 | American logs/forct.comin_cits concerned_log and concer
```

通过排查发现少修改了vhost下的enable-php,修改后即可成功

```
    1 root(SSH)@192.168.215.203
    2 root@qilin-v10:/usr/local/n... ×

erver
   listen 80:
      listen 443 ssl http2;
      server_name pwxt-admin.qdta.cn;
   index index.php index.html index.htm default.php default.htm default.html;
   root /home/wwwroot/pwxt-admin.qdta.cn/public;
   #SSL-START SSL相关配置,请勿删除或修改下一行带注释的404规则
   #error page 404/404.html;
   ssl_certificate /www/server/panel/vhost/cert/pwxt-admin.qdta.cn/pwxt-admin.qdta.cn_bundle.pem;
   ssl_certificate_key
                       /www/server/panel/vhost/cert/pwxt-admin.qdta.cn/pwxt-admin.qdta.cn.key;
   ssl protocols TLSv1.1 TLSv1.2 TLSv1.3;
   ssl ciphers EECDH+CHACHA20:EECDH+CHACHA20-draft:EECDH+AES128:RSA+AES128:EECDH+AES256:RSA+AES256:EECDH+3DES:RSA+3DES
   ssl_prefer_server_ciphers on;
   ssl session cache shared:SSL:10m;
   ssl session timeout 10m;
   add_header Strict-Transport-Security "max-age=31536000";
   error_page 497 https://$host$request_uri;
   #SSL-END
   #ERROR-PAGE-START 错误页配置,可以注释、删除或修改
   #error page 404 /404.html;
   #error_page 502 /502.html;
   #ERROR-PAGE-END
   #PHP-INFO-START PHP引用配置,可以注释或修改
   include /usr/local/nginx/conf/enable-phpl.conf;
   #include /usr/local/nginx/conf/enable-php7.4.conf;
   #include /usr/local/nginx/conf/enable-php.conf;
   #PHP-INFO-END
   #REWRITE-START URL重写规则引用,修改后将导致面板设置的伪静态规则失效
   #include /www/server/panel/vhost/rewrite/pwxt-admin.yunyouqilu.com.conf;
   #REWRITE-END
   #禁止访问的文件或目录
      location /robot-web/ {
              proxy_pass http://192.168.215.196:8083/;
   location ~ ^/(\.user.ini|\.htaccess|\.git|\.env|\.svn|\.project|LICENSE|README.md)
```

备注:

手动启动php-fpm: php-fpm -c /usr/local/php7_4/lib/php.ini -y /usr/local/php7_4/etc/php-fpm.conf 当存在多版本php时,通过软连接进行版本切换: ln -sf /usr/local/php7_4/bin/php /usr/bin/php 断开所有php-fpm进程连接: pkill -9 php-fpm 重启php-fpm:

systemctl stop php-fpm systemctl start php-fpm