
limap: A \LaTeX Package and Class for Typesetting Information Maps

Gerd Neugebauer
Net: gene@gerd-neugebauer.de

This file documents limap.dtx version 2.2 as of 2016/05/29.
Documentation date: 2016/05/29

The Information Mapping[®] method provides a methodology for structuring and presenting information. It claims to be useful for readers who are more concerned about finding the right information than reading the document as a whole. Thus short, highly structured, and context free pieces of information are used.

limap provides a \LaTeX package and a \LaTeX class. The package contains definitions to typeset maps and blocks according to the Information Mapping[®] method. The class provides all definitions to typeset a whole document.

Copyright

Copyright © 1999–2016 Gerd Neugebauer

Licenses

The source files of limap and the derived files

- limap.dtx
- limap.ins
- README.md
- Makefile
- limap.sty
- limap.cls
- limap.pdf

may be distributed under the terms of the L^AT_EX Project Public License version 1.3c, as described in the file lpp1.txt.

The documentation can be used under the Creative Commons Attribution-Share Alike 4.0 License (CC BY-SA 4.0).

The files in the samples directory are distributed under Creative Commons CC0 1.0 Universal.

Net

The sources of limap are hosted on Sourceforge as part of the project gene-tex-lib. The sources can be found under the URL <https://sourceforge.net/p/gene-tex-lib/svn/HEAD/tree/limap/>.

A bundled distribution can be obtained via CTAN under the package URL <https://www.ctan.org/pkg/limap> or from the package's home page under <http://www.gerd-neugebauer.de/software/TeX/limap>.

Contact

The author can be contacted under the following coordinates:

Gerd Neugebauer
Im Lerchelsböhl 5
64521 Groß-Gerau
Germany
gene@gerd-neugebauer.de

Contents

| | |
|---|-----------|
| Motivation | 4 |
| Getting Started | 7 |
| Using the Document Class | 8 |
| Document Class Options for Language Selection | 9 |
| Document Class Options for Variant Selection | 10 |
| Document Class Options for Base Class Selection | 11 |
| Using the Package | 12 |
| Package Options for Language Selection | 13 |
| The Block | 15 |
| Configuring Blocks | 16 |
| Configuring the Rules of Blocks | 17 |
| A Wide Block | 18 |
| The Map | 19 |
| Referencing Maps | 21 |
| Configuring Maps | 22 |
| The Table of Contents | 24 |
| Blocks in the Table of Contents | 25 |
| Tables | 26 |
| Configuration | 27 |
| The Configuration File limap.cfg | 28 |
| Changing or Adding Language Specific Settings | 29 |
| The Implementation | 30 |
| The Version Information | 31 |
| The Documentation Driver | 32 |
| The TeX Code | 35 |
| The Package and Class Declarations | 36 |
| Language Specific Macros | 37 |
| Layout Parameters | 42 |
| Adaptable Macros | 45 |
| Internal Macros, Lengths, and Counters | 47 |
| Typesetting a Map | 48 |
| Typesetting a Block | 54 |
| Typesetting a Table of Contents | 55 |
| Typesetting a Table | 57 |
| Typesetting the Title Page | 58 |
| Final Actions | 60 |

Motivation

Methodology


The information mapping® method provides a methodology to structure information in a special way. The aim is to help a reader who uses the document to search for relevant information instead of consuming it from start to end. The information mapping method also claims to raise the productivity of writers.

No tutorial

This document does not include an introduction to the information mapping method itself. The reader is referred to other documents. Maybe an accompanying document will be distributed along with this package.

Unfortunately the methodology – or the name – is protected by a trademark. Thus the teaching of the methodology is restricted to licensed institutions.


Principles



Continuing...

Motivation, Continued

Information Type



Problems of restructuring

You as \LaTeX user may have encountered the problem when restructuring a document: The sections know exactly the level they belong to. If you introduce a new section and put another section into it you have to change all sectioning commands to reflect the new level of the section and their subsections.

The macros of limap abstract away the level of the document structuring. Any structuring unit is a “Block”. It may contain text or other blocks. Such blocks are the replacement or the sectioning commands. When you restructure your document you simply shift the block and anything it contains to the new place and you are done.


The same mechanism can help you to include the same material in several documents – at different sectioning levels!

Continuing...

Motivation, Continued

Structure and constituents

The general approach focuses very much on the structure of the document. The following diagram illustrates the terminology used within this documentation.



Class or package

To support the information mapping[®] method several \LaTeX macros and environments are provided which allow you to enter a logical description of the relevant concepts. Those macros are provided in the package and class file. It is up to you to choose one of them.

Interoperability with other classes and packages

The main part of the user interface is inherited from \LaTeX . The major differences are the sectioning commands which are made obsolete in parts by the information mapping[®] method. Thus most packages can be used to typeset contents of a block.

Getting Started

Introduction

If you are starting to use limap you should be vaguely familiar with the underlying methodology. This documentation does not provide an introduction.

When you start using this class or package you should say “Good bye” to the classical document structuring macros in the L^AT_EX standard classes.

Class or package

First of all you should decide whether to use the limap class or the limap package. The class is meant for a complete document. The package allows to combine limap with arbitrary other document classes.

Contents

In the maps contained herein you will find an introduction on the use of the limap macros and environments. They are accompanied by illustrating sample code.

| <i>Title</i> | <i>Page</i> |
|--------------------------|-------------|
| Using the Document Class | 8 |
| Using the Package | 12 |

Using the Document Class

Using the document class

This package provides both a class file as well as a package. The package contains the definitions of maps, blocks, and others. They can be used together with any base class. This is illustrated in the following preamble:

```
\documentclass{book}
\usepackage{limap}
\begin{document}
```

Suppressing the block lines

This class option `nolines` can be used to suppress the line above and below block. This is illustrated in the following preamble:

```
\documentclass[nolines]{limap}
\begin{document}
```

Other options

Any option not processed by `limap.cls` is passed to the underlying document class used. Thus it is possible to customize the underlying class any further.

Several types of options

In the maps contained herein you will find the supported options for the document class `limap`.

| <i>Title</i> | <i>Page</i> |
|---|-------------|
| Document Class Options for Language Selection | 9 |
| Document Class Options for Variant Selection | 10 |
| Document Class Options for Base Class Selection | 11 |

Document Class Options for Language Selection

Introduction

The document class `limap` inserts some words. Thus it has to know the language it is supposed to use. Thus the language has to be specified as one document class option.

```
\documentclass[german]{limap}
\begin{document}
```

Supported languages

First, we describe the settings influencing the language specific settings. They do not make provisions to use the appropriate hyphenation patterns. They just arrange things such that the internally used texts are displayed in the chosen language.

| Option | Description |
|------------------------|---|
| <code>austrian</code> | Activate the language specific text fragments for the Austrian language (in fact German with one minor modification). |
| <code>english</code> | Activate the language specific text fragments for the English language. |
| <code>french</code> | Activate the language specific text fragments for the French language. |
| <code>german</code> | Activate the language specific text fragments for the German language. |
| <code>USenglish</code> | Activate the language specific text fragments for the American English. |

Default language

The default language is `english`. It is used if no language is set.

Beware of hyphenation

Note that the hyphenation patterns are not loaded automatically. You have to load the hyphenation patterns, for instance with the `babel` package.

This behavior has been chosen to allow you to select the language package of your choice. Also you can pass in additional options to this package more easily.

Document Class Options for Variant Selection

Introduction

The document class `limap` is based on another document class. Thus you can use the well-known macros and environments defined there and take advantage of the extensions provided by `limap`.

```
\documentclass{limap}  
\begin{document}
```

Variants

The class has two additional options to determine the base class to be used. The first option is the variant. It can take the following values:

| Option | Description |
|-------------------|---|
| <code>base</code> | Use the base set of classes. This is the default. |
| <code>koma</code> | Use the set of classes from koma-script . |

Default variant

If no document class option is used then `base` is the default variant.

Document Class Options for Base Class Selection

Introduction

The document class `limap` follows the logic introduced in the L^AT_EX standard document classes. The type of the base document class can be given as argument to the `limap` class.

```
\documentclass[book]{limap}  
\begin{document}
```

Class type

The second option is the class type. It determines which kind of document to typeset. It can take the following values:

| Option | Description |
|---------|-----------------------------------|
| book | Typeset a book type document. |
| report | Typeset a report type document. |
| article | Typeset an article type document. |
| letter | Typeset a letter type document. |

Mapping of variant and type

The following table shows which base classes are loaded according to the given values:

| Type /variant | base | koma |
|---------------|---------|----------|
| book | book | scrbook |
| report | report | scrreprt |
| article | article | scrartcl |
| letter | letter | scrletr |

Default type

The default type is `report`. It is used if no type is set.

Using the Package

Introduction

The package `limap` can be used together with most document classes. An exception are classes for slides like the `beamer` class.

As usual it is declared in the document preamble.

```
\documentclass{report}
\usepackage{limap}
\begin{document}
```

Content

The following additional information is available.

| <i>Title</i> | <i>Page</i> |
|--|-------------|
| Package Options for Language Selection | 13 |

Package Options for Language Selection

Introduction

The package `limap` inserts some words. Thus it has to know the language it is supposed to use. Thus the language has to be specified as package option.

```
\usepackage[german]{limap}
\begin{document}
```

Inheritance of document class options

Alternatively the language selecting option can be specified as document class option. Thus several packages can share the same setting.

```
\documentclass[german]{scrbook}
\documentclass{limap}
\begin{document}
```

Supported languages

Here we describe the settings influencing the language specific settings. They do not make provisions to use the appropriate hyphenation patterns. They just arrange things such that the internally used texts are displayed in the chosen language.

| Option | Description |
|-----------|---|
| austrian | Activate the language specific text fragments for the Austrian language (in fact German with one minor modification). |
| english | Activate the language specific text fragments for the English language. |
| french | Activate the language specific text fragments for the French language. |
| german | Activate the language specific text fragments for the German language. |
| USenglish | Activate the language specific text fragments for the American English. |

Default language

The default language is `english`. It is used if no language is set.

Continuing...

Package Options for Language Selection, Continued

Beware of hyphenation

Note that the hyphenation patterns are not loaded automatically. You have to load the hyphenation patterns, for instance with the `babel` package.

This behavior has been chosen to allow you to select the language package of your choice. Also you can pass in additional options to this package more easily.

The Block

Meaning

A “block” is the essential building units of the limap package. You can think of it as paragraph with a title.

Appearance

The blocks are usually typeset with the block label on the left side and the contents to its right. They are surrounded by white-space and a thin line above and below.

\Block

The macro \Block can be used to typeset an block. It takes one argument which is the block label.

This is a shorthand for denoting a block. The end mark can be omitted if you use the macro instead of the environment. Nevertheless this is deprecated.

Example

The following sample illustrates how to enter a block.

```
\Block{Block Label}
And now comes the block text. It can consist of one or more
classical paragraphs, or tables, or pictures, or something
else.
```

Just in a map

Note that the macro \Block can be used inside a map only. If you try to use it outside the scope of a map you will get an error.

More on blocks

Several more aspects of blocks are covered in the following maps.

| Title | Page |
|---------------------------------|------|
| Configuring Blocks | 16 |
| Configuring the Rules of Blocks | 17 |
| A Wide Block | 18 |

Configuring Blocks

\MapBlockLabelFont

The macro \MapBlockLabelFont determines the font changing command to be used for typesetting the block label. The default is empty.

Colored block labels

The macro \MapBlockLabelFont can for instance be used to achieve colored block labels. For this purpose we can include the package xcolor in the preamble and select for instance a named color for the rule. This is illustrated in the following example.

```
\usepackage[svgnames]{xcolor}
\renewcommand{\MapBlockLabelFont}{\color{Navy}}
```

\MapParskip

The macro \MapParskip determines the vertical distance of the text from the separating rules. The default is 2ex.

```
\renewcommand{\MapParskip}{.25ex}
```

\MapTitleFraction

The macro \MapTitleFraction determines the part of the page width devoted to the block label area. It is a fraction in the range from 0 to 1. The default value of \MapTitleFraction is 0.2.

```
\renewcommand{\MapTitleFraction}{.25}
```

\MapTextFraction

This macro determines the part of the page width devoted to the text area. It is a fraction in the range from 0 to 1. The default value of \MapTextFraction is 0.75.

\MapTitleFraction and \MapTextFraction should add up to something less or equal to 1. Otherwise you will get some “overfull hbox” messages.

```
\renewcommand{\MapTextFraction}{.8}
```

Configuring the Rules of Blocks

Motivation

Blocks are usually surrounded by horizontal rules. The appearance of these rules can be influenced by some macros.

\MapRuleWidth

The macro `\MapRuleWidth` determines the width of the rules drawn between blocks. It is defined as a macro containing a length. The default is `1pt`.

```
\setlength{\MapRuleWidth}{1mm}
```

SUPPRESS visible rules

For some people the rules are distracting since they emphasize the structure too much. In such situations the rule width might be reduced. In the extreme case it can even be set to `0pt` to suppress the lines at all as in the following example:

```
\renewcommand{\MapRuleWidth}{0pt}
```

\MapRuleStart

The macro `\MapRuleStart` is inserted before rules around blocks. It can be used to inject some code before the rule is typeset. Initially it is empty.

Colored rules

The macro `\MapRuleStart` can for instance be used to achieve colored rules. For this purpose we can include the package `xcolor` in the preamble and select a named color for the rule. This is illustrated in the following example.

```
\usepackage[svgnames]{xcolor}
\renewcommand{\MapRuleStart}{\color{Silver}}
```


A Wide Block

| | |
|--------------------|---|
| Motivation | Sometimes it is necessary to extend the content of a block to the whole width of the page. This can be the case for illustrations or large tables. <hr/> |
| \WideBlock | The macro \WideBlock can be used to typeset a piece of information on the whole page width. It is normally used after an initiating block containing the title of the whole construction. |
| | The macro \WideBlock takes one argument which contains the material to span the whole page width. <hr/> |
| Example | The following sample illustrates how to enter a wide block. |
| | <pre>\Block{Block Label} And now comes the block text. \WideBlock{\includegraphics{images/overview.svg}}</pre> <hr/> |
| Block Label | And now comes the wide block produced with the help of TikZ and its decoration with random steps. |

The Map

Structuring documents

The maps are the structuring units of the limap package. Maps may recursively contain maps and other material. The other material is usually named a block. This recursive structure is illustrated in the following figure.



Map

The environment `Map` can be used to typeset a map. It takes a single argument which contains the map title. The map title is typeset above the map and is repeated on each continuation page.

Example

```
\begin{Map}{Map Title}
  \Block{Block Label}
  And now comes the block text. It can consist of
  one or more classical paragraphs, or tables, or
  pictures, or something else.
\end{Map}
```

Continuing...

The Map, Continued

To at most 12 cascaded Maps

There is a technical restriction in the current implementation of Maps. This restriction does not allow more than 12 cascaded Maps, i.e. Maps in Maps ...in Maps.

According to the good old 7 ± 2 rule a full populated document of this level would contain 282 429 536 481 Maps. I think it should take some time until this limit is reached.

More on maps

Some more aspects are covered in the following pages.

| <i>Title</i> | <i>Page</i> |
|------------------|-------------|
| Referencing Maps | 21 |
| Configuring Maps | 22 |

Referencing Maps

Referencing maps

Maps can be referenced in the usual L^AT_EX way. For this purpose you place a macro invocation of \label right behind the beginning of the Map.

Then you can add references somewhere in the document with \ref and \pageref. For backward references two L^AT_EX runs are required.

Example

```
\begin{Map}{Map Title}\label{my.label}
  \Block{Block Label}
  As said on page~\pageref{my.label}...
```

Caveat emptor

limap automatically labels any map with a label of the form Map@*n* where *n* is a sequence number. Thus avoid to use such labels yourself.

Configuring Maps

\MapFont

The macro \MapFont determines the font changing command to be used when starting a new map.

```
\renewcommand\MapFont{\tt}
```

\MapTitleFont

The macro \MapTitleFont determines the font changing command to be used when typesetting the title of a map. The default is \Large.

```
\renewcommand\MapTitleFont{\huge\bfseries}
```

\MapContinued

The macro \MapContinued contains the text appearing at the end of map which are continued on the next page. It is initiated when the class or package is loaded. It can overwritten afterwards – for instance in the preamble.

```
\renewcommand\MapContinued{}
```

\MapContinuing

The macro \MapContinuing contains the text appearing at the beginning of map which are continued from the previous page. It is typeset after the map title. It is initiated when the class or package is loaded. It can overwritten afterwards – for instance in the preamble.

```
\renewcommand\MapContinuing{}
```

\MapTitleContinued-
Font

This macro determines the font changing command to be used for typesetting the additional text after titles on followup pages of multi-page maps.

The default value is \small.

```
\renewcommand\MapTitleContinuedFont{\normalsize}
```

Continuing...

Configuring Maps, Continued

\MapNewpage

The macro \MapNewpage is expanded whenever a new page is required between maps. Thus it can be used to suppress the newpages by \letting it to \relax. Note that this is not in the spirit of the Information Mapping® method.

\MapTOC

The macro \MapTOC is expanded to generate the entry in the table of contents. It can be redefined to allow another behavior.

The Table of Contents

Everything is local

The concept of the underlying methodology is that everything should be addressed relative to the current location. We see this when dealing with maps (see page 19). The same principle is applied to the table of contents.

Direct children are included

The table of contents includes all maps contained in the map in which it appears. This means the immediate children of the map are shown.

Block context required

The table of contents is typeset inside a block (see page 15).

\MapTableOfContents

The macro \MapTableOfContents can be used to typeset the table of contents for a map. This table of contents includes all sub-maps of the map it is contained in – not recursively but only one level deeper.

The macro \MapTableOfContents does not take any argument.

Example

```
\Block{Contents}
And some wise words about the table of contents.
\MapTableOfContents
```

\MapTableOfContentsStyle

The macro \MapTableOfContentsStyle can be used to determine the style of the \MapTableOfContents. The default style is an open layout utilizing the package **booktabs**.

The macro \MapTableOfContentsStyle takes one argument. This argument may have one of the following values:

| Argument | Meaning |
|----------|---------------------------|
| open | an open style for the TOC |
| boxed | a boxed style for the TOC |

Blocks in the Table of Contents

Motivation

Sometimes it can be desirable to add the blocks to the global table of contents. Here we will see how this can be achieved.

\MapBlockStartHook

The macro \MapBlockStartHook is expanded at the beginning of each block if it is defined. It takes a single argument which is the title of the block.

\MapBlockTOC

The macro \MapBlockTOC is a macro which adds one line to the table of contents. It takes one argument which is the text to be added.

Example

Put the following code in the preamble to get the blocks into the table of contents.

```
\let\MapBlockStartHook\MapBlockTOC
```

Tables

Introduction

Tables play an important role as part of maps. Usually they are included into a block and preceded by some useful introduction.

Combination with booktabs

The document class `limap` and the package `limap` automatically include the package `booktabs`. This package contains some support for typesetting proper tables. You should have a look at the documentation of `booktabs` and follow the recommendations given there.

`booktabs` is automatically loaded by `limap` upon start-up.

MapTabular

The environment `MapTabular` provides a convenient way to include a table into a block. It produces a `tabular*` environment and sets the width to the width of the text column of the block.

Example

```
\Block{Table block}
Sheding some insight on the following table.

\begin{MapTabular}{lll}\toprule
a & b & \midrule
x & y & Z\hline
X & Y & Z\bottomrule
\end{MapTabular}
```

\MapTabularFraction

The tabular is always centered in the text column of the block. The macro `\MapTabularFraction` contains a factor for the line width occupied by the tabular. This value is used to determine the width of the tabular. The default value for the macro `\MapTabularFraction` is 0.95.

```
\renewcommand{\MapTabularFraction}{.7}
```

Configuration

Introduction

limap is designed with a set of extension points. Those are mainly definition which can be overwritten to achieve a certain effect.

Configuration in the preamble

Any configuration change performed in the preamble of a document is global. It lasts until overwritten within the document.

Configuration in the document

The configuration parameters can be overwritten in the document just before they are needed. This is not recommended since it makes it harder to achieve consistency.

External configuration

The configuration can be externalised. For this purpose a special file `limap.cfg` is loaded with the class or package in case it exists. This file can contain configuration options for limap. Thus it is possible to share the same appearance among different documents.

Contents

The following maps contain the various aspects of the configuration of limap.

| Title | Page |
|---|------|
| The Configuration File <code>limap.cfg</code> | 28 |
| Changing or Adding Language Specific Settings | 29 |

The Configuration File **limap.cfg**

Default configuration file

When the class or package is loaded as a last action a configuration file is loaded if it can be found. The name of the configuration file is `limap.cfg`. This file can contain re-definitions of the several macros to adjust the behavior of `limap` on a per directory, per user or per installation base.

Note

Some settings are activated before the configuration file is loaded. Thus some settings may not have any effect at all.

Changing or Adding Language Specific Settings

Overview

Several strings are used automatically by the current class or package. Default values for several languages are hardwired in the implementation. Nevertheless it is possible to change those language specific settings.

If you create settings for a new language it is highly recommended to contact the author to integrate them into the default distribution.

The following macros can be redefined in the preamble after the package or class has been loaded to reset the language specific text.

\MapTOCname

The macro \MapTOCname contains the text of the heading in table of contents of maps for the column of map titles. It is initiated when the class or package is loaded. It can be overwritten afterwards – for instance in the preamble.

```
\renewcommand{\MapTOCname}{Issue}
```

\MapTOCpage

The macro \MapTOCpage contains the text of the heading in table of contents of maps for the column of page numbers. It is initiated when the class or package is loaded. It can be overwritten afterwards – for instance in the preamble.

```
\renewcommand{\MapTOCpage}{Reference}
```

Providing a new language

If you want to provide a new language *lang* you can define the macro \LIMAP@SelectLanguage@*lang* which redefines the macros given above. This definition has to be present before the package is loaded.

Note that the macro name contains the @ character. Thus the definition should be made in a package of its own.

The Implementation

Overview

This part of the document describes the implementation. Usually it is not meant for the casual user. Nevertheless it might be fruitful for those searching for inspiration or for tricks when using this class or package.

Contents

| <i>Title</i> | <i>Page</i> |
|---------------------------|-------------|
| The Version Information | 31 |
| The Documentation Driver | 32 |
| The T _E X Code | 35 |

The Version Information

Purpose

The version information is included for printing it on the documentation and at start-up when the class or package is loaded. It has to precede the documentation driver to properly include this information into the printed manual.

\filename \filename is the name of the dtx file containing this class and package.

1 \def\filename{limap.dtx}

\fileversion \fileversion is the version number of the dtx file. It is used as a version number for the class and package.

2 \def\fileversion{2.2}

\filedate \filedate is the change date of the dtx file. It is used as a version date and documentation date.

3 \def\filedate{2016/05/29}

\docversion \docversion is the version number of the documentation. It is identical to the version number of the dtx file.

4 \let\docversion=\fileversion

\docdate \docdate is the change date of the documentation. It is identical to the change date of the dtx file.

5 \let\docdate=\filedate

The Documentation Driver

Purpose

The documentation driver is necessary to provide a self documenting dtx file. With this construction the dtx file can be run through L^AT_EX to produce the documentation.

The driver section contains a complete L^AT_EX document which loads the dtx file. The special class ltxdoc is used and some arrangements are made for this purpose.

Driver code

The driver code is not exported by the installer.

```

6 {*driver}
7 \documentclass[a4paper]{ltxdoc}
8 \RequirePackage{textcomp}
9 \usepackage{limap}
10 \let\LimapFilename\filename
11 \let\LimapFileVersion\fileversion
12 \let\LimapFiledate\filedate
13 \let\LimapDocdate\docdate

```

Page Layout

```

14 \oddsidemargin=10pt
15 \evensidemargin=10pt
16 \textwidth=430pt
17 \textheight=650pt
18 \voffset=-12mm

```

Headings

```

19 \usepackage{fancyhdr}
20 \addtolength{\headheight}{2ex}%
21 \pagestyle{fancy}%
22 \cfoot{}
23 \rhead{\small\sf\thepage}
24 \lhead{\textit{\footnotesize limap} Package and Class}

```

Links and such

```
25 \usepackage{hyperref}
```

Continuing...

The Documentation Driver, Continued

Fonts

```

26 \usepackage{fontspec}
27 \setmainfont{TeX Gyre Heros}
28 \setsansfont{TeX Gyre Heros}[%[Scale=MatchLowercase]
29 \setmonofont{Inconsolata}[%[Scale=MatchLowercase]
```

Coloring

```

30 \usepackage[svgnames]{xcolor}
31 \renewcommand\MapTitleFont{\Large\bfseries\color{Navy}}
32 \renewcommand\MapBlockLabelFont{\bfseries\color{Navy}}
33 \definecolor{linkColor}{rgb}{.66,.2,.2}
34 \hypersetup{colorlinks,
35           citecolor=linkColor,
36           filecolor=linkColor,
37           linkcolor=linkColor,
38           urlcolor=linkColor}
39 \renewcommand\MapRuleStart{\color{Navy}}
40 \renewcommand\MapRuleWidth{1pt}
```

Graphics

```

41 \usepackage{tikz}
42 \usetikzlibrary{decorations.pathmorphing}
43 \usetikzlibrary{shadows}
44 \usetikzlibrary{mindmap}
45 \usetikzlibrary{calc}
```

Saving version

```

46 \let\filename\LimapFilename
47 \let\fileversion\LimapFileversion
48 \let\filedate\LimapFiledate
49 \let\docdate\LimapDocdate
```

Adapting doc.sty

```

50 \def\theCodelineNo{\color{DarkGreen}\rmfamily\scriptsize\arabic{Code-
lineNo}}%
51 \makeatletter
52 \renewcommand\DescribeMacro{\catcode`\\=12\Describe@@Macro}
53 \def\Describe@@Macro#1{\Block{\PrintDescribeMacro{#1}}%
54   \SpecialUsageIndex{#1}\@esphack\ignorespaces}
55 \renewcommand\DescribeEnv{\catcode`\\=12\Describe@@Env}
56 \def\Describe@@Env#1{\Block{\PrintDescribeEnv{#1}}%
57   \SpecialEnvIndex{#1}\@esphack\ignorespaces}
58 \makeatother
59 \let\maketitle\MakeTitle
```

Continuing...

The Documentation Driver, Continued

Some additions

```
60 \newcommand\R{\(\text{\footnotesize\textregistered}\)} }  
61 \let\marginpar\Block  
62 \InputIfFileExists{limap.dcf}{}{}  
63 \RecordChanges  
64 \EnableCrossrefs  
65 \CodeIndex
```

The content

Now everything is prepared. Let the show begin...

```
66 \begin{document}  
67 \DeleteShortVerb{|}  
68 \DocInput{\filename}  
69 %\newpage  
70 %\PrintChanges  
71 \newpage  
72 \setcounter{IndexColumns}{2}  
73 \PrintIndex  
74 \end{document}  
75 </driver>
```

The **T_EX** Code

Overview

The rest of the document describes the implementation. Usually it is not meant for the casual user. Nevertheless it might be fruitful for those searching for inspiration or for tricks when using this class or package.

Contents

| <i>Title</i> | <i>Page</i> |
|--|-------------|
| The Package and Class Declarations | 36 |
| Language Specific Macros | 37 |
| Layout Parameters | 42 |
| Adaptable Macros | 45 |
| Internal Macros, Lengths, and Counters | 47 |
| Typesetting a Map | 48 |
| Typesetting a Block | 54 |
| Typesetting a Table of Contents | 55 |
| Typesetting a Table | 57 |
| Typesetting the Title Page | 58 |
| Final Actions | 60 |

The Package and Class Declarations

Preliminaries

First of all we request a descent version of L^AT_EX to be used. I don't think it does have to be too new.

```
76 \NeedsTeXFormat{LaTeX2e}
```

Package identification

When the package is generated, the package identification is included.

```
77 <*package>
78 \ProvidesPackage{limap}[\filedate\space Gerd Neugebauer]
79 </package>
```

Class identification

When the class is generated, the class identification is included.

```
80 <*class>
81 \ProvidesClass{limap}[\filedate\space Gerd Neugebauer]
82 </class>
```

Language Specific Macros

Introduction

This section contains internal macros used to implement the functionality. New languages can be easily be added. For this purpose only a new macro has to be defined and a package/class option for the convenience of the user.

Consider you want to add a new language “latin” then you have to provide the command `\LIMAP@SelectLanguage@latin`. This macro should simply redefine the macros containing strings of the language specific texts. Examples for other languages are provided in this section.

To enable the language settings for “latin” the macro `\LIMAP@Language` has to be defined to contain the value “latin”. Usually this is accomplished by providing a convenient option to the package or class.

`\defineLimapLanguage` Provide the definitions for a language. The different texts to be used are stored in a macro which defines the target macros when expanded.

```
83 \def\defineLimapLanguage#1#2#3#4#5{%
84   \expandafter\def\csname LIMAP@SelectLanguage@#1\endcsname{%
85     \def\MapContinued{#2}%
86     \def\MapContinuing{#3}%
87     \def\MapTOCname{#4}%
88     \def\MapTOCpage{#5}%
89   }%
90 }
```

Definitions for the language “austrian”

```
91 \defineLimapLanguage{austrian}%
92 { Fortsetzung}{Fortsetzung\ dots}%
93 {Titel}{Seite}
```

Definitions for the language “german”

```
94 \defineLimapLanguage{german}%
95 { Fortsetzung}{Fortsetzung\ dots}%
96 {Titel}{Seite}
```

Definitions for the language “english”

```
97 \defineLimapLanguage{english}%
98 { Continued}{Continuing\ dots}%
99 {Title}{Page}
```

Continuing...

Language Specific Macros, Continued

Definitions for the language “USenglish”

```
100 \defineLimapLanguage{USenglish}%
101   { Continued}{Continuing\dots}%
102   {Title}{Page}
```

Definitions for the language “french”

```
103 \defineLimapLanguage{french}%
104   { continuation}{continuation\dots}%
105   {Intitulé}{Page}
```

\LIMAP@Language The macro \LIMAP@Language determines the language to be used for several small text fragments to be inserted at certain places. It is redefined by package/class options and evaluated at the end to activate the selected settings.

```
106 \providecommand{\LIMAP@Language}{english}
```

```
107 \DeclareOption{austrian}{\renewcommand{\LIMAP@Language}{austrian}}
108 \DeclareOption{german}{\renewcommand{\LIMAP@Language}{german}}
109 \DeclareOption{french}{\renewcommand{\LIMAP@Language}{french}}
110 \DeclareOption{english}{\renewcommand{\LIMAP@Language}{english}}
111 \DeclareOption{USenglish}{\renewcommand{\LIMAP@Language}{USenglish}}
```

\ifLIMAP@strict The boolean \ifLIMAP@strict determines if the lower sectioning macros should be disabled in the class.

```
112 \newif\ifLIMAP@strict \LIMAP@stricttrue
```

```
113 \DeclareOption{nonstrict}{\LIMAP@strictfalse}
```

```
114 \DeclareOption{nolines}{\def\MapRuleWidth{0pt}\ignorespaces}
```

Determining the Appropriate Base Class

115 `(*class)`

`\LIMAP@ClassType` The macro `\LIMAP@ClassType` determines the type of the class to be used. Usually it can take the values book, report, article, and letter (for completeness). This macro is redefined when the options of the class are evaluated. Finally this macro helps to select the appropriate base class.

116 `\providecommand{\LIMAP@ClassType}{report}`

117 `\DeclareOption{book}{\renewcommand{\LIMAP@ClassType}{book}}`
 118 `\DeclareOption{report}{\renewcommand{\LIMAP@ClassType}{report}}`
 119 `\DeclareOption{article}{\renewcommand{\LIMAP@ClassType}{article}}`
 120 `\DeclareOption{letter}{\renewcommand{\LIMAP@ClassType}{letter}}`

`\LIMAP@Variant` The macro `\LIMAP@Variant` determines the variant of the class to be used. Usually it can take the values base and koma. This macro is redefined when the options of the class are evaluated. Finally this macro helps to select the appropriate base class.

121 `\providecommand{\LIMAP@Variant}{base}`

Options for selecting the variant

122 `\DeclareOption{koma}{\renewcommand{\LIMAP@Variant}{koma}}`
 123 `\DeclareOption{base}{\renewcommand{\LIMAP@Variant}{base}}`

Mapping to document class

Define a mapping between the variant and class type to the class name to be used.

124 `\newcommand{\LIMAP@Class@base@article}{article}`
 125 `\newcommand{\LIMAP@Class@base@report}{report}`
 126 `\newcommand{\LIMAP@Class@base@book}{book}`
 127 `\newcommand{\LIMAP@Class@base@letter}{letter}`
 128 `\newcommand{\LIMAP@Class@koma@article}{scrartcl}`
 129 `\newcommand{\LIMAP@Class@koma@report}{scrreprt}`
 130 `\newcommand{\LIMAP@Class@koma@book}{scrbook}`
 131 `\newcommand{\LIMAP@Class@koma@letter}{scrlettr}`
 132 `(*class)`

Continuing...

Determining the Appropriate Base Class, continued

Pass on the unknown options

```
133 <*class>
134 \DeclareOption{\PassOptionsToClass{\CurrentOption}{%
135   \csname LIMAP@Class@\LIMAP@Variant @\LIMAP@ClassType\endcsname}%
136 }
137 </class>
```

Thus the class specific options are completed.

Now we can process all options.

```
138 \ProcessOptions
```

```
139 <*class>
```

The requested class is loaded and the options remaining are processed.

```
140 \LoadClass{\csname
141   LIMAP@Class@\LIMAP@Variant @\LIMAP@ClassType\endcsname}%
142 </class>
```

Loading Required Packages

longtable for breakable tables

The package **longtable** is used internally to implement a part of the required functionality. Thus we need to ensure that it is loaded.

```
143 \RequirePackage{longtable}
```

etoolbox

```
144 \RequirePackage{etoolbox}
```

booktabs for nice tables

The package **booktabs** is used internally to implement a part of the required functionality. Thus we need to ensure that it is loaded.

```
145 \RequirePackage{booktabs}
```

fancyhdr for head and foot lines

```
146 <*class>
147 \RequirePackage{fancyhdr}
148 \addtolength{\headheight}{2ex}%
149 \pagestyle{fancy}%
150 \cfoot{}
151 \rhead{\small\thepage}
152 \lhead{\textit{\footnotesize@title}}
153 \def\@title{}
154 </class>
```

No vertical adjustment of pages

Since the blocks are not supposed to line up at the end of the page we declare **\raggedbottom**.

```
155 \raggedbottom
```

Layout Parameters

Overview

The layout can be influenced by a large number of parameters. Thus the design decisions have been made transparent (to a certain degree at least). These options are not meant to be changed except when a new layout is being designed and implemented.

\MapRuleWidth The macro \MapRuleWidth determines the width of the rules drawn between blocks.

156 \providecommand\MapRuleWidth{.25pt}

\MapRuleStart The macro \MapRuleStart is inserted before the rules drawn between blocks.

157 \newcommand\MapRuleStart{}

\MapContinued This macro determines the text to be used in the title of continued maps. This macro is reset when the language specific initializations are performed.

158 \newcommand\MapContinued{}

\MapContinuing The macro \MapContinuing determines the text to be used at the bottom of the map which is continued. This macro is reset when the language specific initializations are performed.

159 \newcommand\MapContinuing{}

Continuing...

Layout Parameters, Continued

\MapContinuingFormat This macro determines the format of the bottom line on continued maps. I.e. it includes the text as well as font changing commands. The text is passed to this command as argument 1.

```
160 \newcommand{\MapContinuingFormat}[1]{\textit{\footnotesize #1}}
```

\MapContinuedFormat This macro determines the format of the bottom line on continued maps. I.e. it includes the text passed to it as argument 1 as well as font changing commands.

```
161 \newcommand{\MapContinuedFormat}[1]{, {\MapTitleContinuedFont #1}}
```

\MapFont The macro \MapFont determines the font changing command to be used when starting a new map.

```
162 \let{\MapFont}{\textsf{}}
```

\MapTitleFont The macro \MapTitleFont determines the size changing command to be used when typesetting the title of a map.

```
163 \let{\MapTitleFont}{\Large}
```

\MapTitleContinuedFont This macro determines the font changing command to be used for typesetting the additional text after titles on followup pages of multipage maps.

```
164 \let{\MapTitleContinuedFont}{\small}
```

\MapBlockLabelFont This macro determines the font changing command to be used for typesetting the block label.

```
165 \def{\MapBlockLabelFont}{}

---


```

Continuing...

Layout Parameters, Continued

\MapParskip The macro \MapParskip determines the distance of the text from the separating rules.

`166 \newcommand{\MapParskip}{2ex}`

\MapTitleFraction The macro \MapTitleFraction determines the part of the page width devoted to the title area. It is a fraction in the range from 0 to 1.

`167 \newcommand{\MapTitleFraction}{.2}`

\MapTextFraction This macro determines the part of the page width devoted to the text area. It is a fraction in the range from 0 to 1. \MapTitleFraction and \MapTextFraction should add up to something less or equal to 1. Otherwise you will get some “overfull hbox” messages.

`168 \newcommand{\MapTextFraction}{.75}`

Adaptable Macros

Overview

\MapNewpage The macro \MapNewpage is expanded whenever a new page is required between maps. Thus it can be used to suppress the newpages by \letting it to \relax.

```
169 \let\MapNewpage\newpage
```

\MapTOC The macro \MapTOC is expanded to generate the entry in the table of contents. It can be redefined to allow another behavior.

```
170 \newcommand\MapTOC[1]{%
171   \refstepcounter{@nameuse{Map@TOC@name}\the\Map@level}%
172   \addcontentsline{toc}{\@nameuse{Map@TOC@name}\the\Map@level}{#1}%
173 }
```

\MapBlockTOC The macro \MapBlockTOC can be used to add an entry for a block to the table of contents.

```
174 \newcommand\MapBlockTOC[1]{%
175   \begingroup\count0=\Map@Level \advance\count0 1%
176   \addcontentsline{toc}{\@nameuse{Map@TOC@name}\the\count0}{#1}%
177   \endgroup
178 }
```

\MapTOCname The macro \MapTOCname contains the heading for the section title in contents blocks. This macro is reset when the language specific initializations are performed.

```
179 \newcommand\MapTOCname{}
```

Continuing...

Adaptable Macros, Continued

\MapTOCpage The macro \MapTOCpage contains the heading for the page number in contents blocks. This macro is reset when the language specific initializations are performed.

180 \newcommand{\MapTOCpage}{}

\MapTOCheadfont The macro \MapTOCheadfont contains the font switching command for typesetting the head line of map table of contents.

181 \newcommand{\MapTOCheadfont}{\scriptsize\emph{}}

Internal Macros, Lengths, and Counters

This section contains internal macros used to implement the functionality.

\Map@length The length register \Map@length is allocated to store the width of the space between the columns of a block.

182 \newlength{\Map@length}

\Map@level The macro \Map@level determines the level of inclusion of maps. It is used to determine the appearance in the table of contents.

183 \newcount\Map@level
184 \Map@level=0

\Map@blockcount The macro \Map@blockcount is used to count the blocks per map to issue a package warning if required.

185 \newcount\Map@blockcount

\LT@final@warn The macro \LT@final@warn is defined in longtable. It is redefined to show limap are originator.

186 \def\LT@final@warn{%
187 \AtEndDocument{%
188 \PackageWarning{limap}{%
189 {Table \@width s have changed. Rerun LaTeX.\@gobbletwo}}%
190 \global\let\LT@final@warn\relax}}

Typesetting a Map

- Map The environment `Map` determines the appearance of a map. It is implemented as a `longtable` environment which takes care for the page breaks and inserts material at the end of the page and the beginning of the new page upon page break.

```
191 \def\Map#1{%
```

First the messages of `longtable` are modified to show this package name instead.

```
192 \def\LT@err{\PackageError{limap}{}}%
193 \def\LT@warn{\PackageWarning{limap}{}}%
```

The map local macro `\Block` is activated. The counter for blocks is reset.

```
194 \let\Block\Map@Block
195 \let\endBlock\Map@endBlock
196 \Map@blockcount=0
```

The number of the map in the internal counting is set by incrementing the old value.

```
197 \global\advance\Map@no1
```

```
198 \ifx\Map@UP\empty\else
199   \immediate\write\@auxout
200     {\string\expandafter\string\xdef\string\csname\space
201      \Map@parts@\Map@UP\string\endcsname{\string\csname\space
202        \Map@parts@\Map@UP\string\endcsname\the\Map@no:}}%
203 \fi
```

Continuing...

Typesetting a Map, Continued

```

204 \edef\Map@UP{\the\Map@no}%
205 \ifnum\Map@level>0
206   \xdef\Map@up{\Map@UP}% Just to save the value across blocks.
207   \endgroup
208   \Map@end
209   \begingroup
210   \edef\Map@UP{\Map@up}%
211   \def\@currenvir{Map}%
212 \fi
213 \edef\Map@this{\the\Map@no}%

```

The entries for future use of sub-maps are written to the aux file.

```

214 \immediate\write\@auxout
215 {\string\global\string\@namedef{Map@parts@\the\Map@no}{}}%

```

```

216 \global\advance\Map@level1
217 \def\Map@TITLE{#1}%
218 \Map@start
219 }

```

```

220 \def\endMap{%
221   \Map@end
222   \global\advance\Map@level-1
223   \ignorespaces
224 }

```

\ifMap@open@ The conditional `\ifMap@open@` is used to record the opening and closing of the `longtable` environment, since can not be used inside itself. Thus it can be closed before a new instance is opened.

```

225 \newif\ifMap@open@
226 \Map@open@false

```

Continuing...

Typesetting a Map, Continued

\Map@TOC@name The macros \Map@TOC@name... provide a mapping between a number and a sectioning unit. This mapping is used when the entry in the table of contents is generated.

```
227 \@namedef{Map@TOC@name0}{chapter}
228 \@namedef{Map@TOC@name1}{section}
229 \@namedef{Map@TOC@name2}{subsection}
230 \@namedef{Map@TOC@name3}{subsubsection}
231 \@namedef{Map@TOC@name4}{paragraph}
232 \@namedef{Map@TOC@name5}{subparagraph}
233 \@namedef{Map@TOC@name6}{subsubparagraph}
234 \@namedef{Map@TOC@name7}{subsubparagraph}
235 \@namedef{Map@TOC@name8}{subsubparagraph}
236 \@namedef{Map@TOC@name9}{subsubparagraph}
237 \@namedef{Map@TOC@name10}{subsubparagraph}
238 \@namedef{Map@TOC@name11}{subsubparagraph}
239 \@namedef{Map@TOC@name12}{subsubparagraph}
```

Continuing...

Typesetting a Map, Continued

\Map@start The macro \Map@start is used to initiate the use of a map. It takes no arguments. The map title is passed in via the macro \Map@TITLE.

It uses the longtable environment to perform the page breaking and marking of continued pages.

```

240 \newcommand{\Map@start}{%
241   \advance\Map@counter1
242   \setlength{\Map@length}{\textwidth}%
243   \addtolength{\Map@length}{-\MapTitleFraction\textwidth}%
244   \addtolength{\Map@length}{-\MapTextFraction\textwidth}%
245   \ifx\Map@TITLE\empty\else
246     \MapTOC{\Map@TITLE}%
247   \fi
248   \longtable
249     {@{}p{\MapTitleFraction\textwidth}@{\hspace{\Map@length}}}
250       p{\MapTextFraction\textwidth}@{}%
251     \multicolumn{2}{@{}p{\textwidth}@{}}
252       \MapFont{\MapTitleFont\rule{0pt}{3ex}}%
253       \Map@TITLE}%
254   \endfirsthead
255   \multicolumn{2}{@{}p{\textwidth}@{}}
256     \MapFont{\MapTitleFont\rule{0pt}{3ex}}%
257     \Map@TITLE\MapContinuedFormat{\MapContinued}}%
258   \endhead
259   \\
260   &\MapRuleStart
261     \rule{\MapTextFraction\textwidth}{\MapRuleWidth}\newline
262     \mbox{}\hfill
263     \raisebox{3pt}{\MapContinuingFormat{\MapContinuing}}%
264   \endfoot
265   &\MapRuleStart
266     \rule{\MapTextFraction\textwidth}{\MapRuleWidth}%
267     \vspace{\MapParskip}
268   \endlastfoot
269   \xdef\@currentlabel{\Map@TITLE}%
270   \label{Map@\the\Map@no}%
271   \global\Map@open@true
272 }
```

Continuing...

Typesetting a Map, Continued

\Map@end The macro \Map@end is expanded when the end of the end of the longtable environment might be needed. The boolean \ifMap@open@ determines whether such an environment is really open.

```

273 \newcommand{\Map@end}{%
274   \ifMap@open@\vspace*{1.5ex}%
275     \global\Map@open@false
276   \endlongtable
277   \MapNewpage
278 \fi
279 \iftrue
280   \ifnum\Map@blockcount>9
281     \PackageWarning{limap}%
282     {*** The current map contains too much blocks:%
283      \the\Map@blockcount}%
284   \else\ifnum\Map@blockcount>7
285     \PackageWarning{limap}%
286     {--- The current map contains \the\Map@blockcount blocks.}%
287   \fi\fi
288 \fi
289 }
```

\Map@UP The macro \Map@UP contains the number of the parent map or the empty string.

```
290 \newcommand{\Map@UP}{}
```

\Map@no The counter \Map@no contains the sequence number for all maps. This value is used internally to reference single maps.

```
291 \newcount{\Map@no}
```

\Map@counter The counter \Map@counter contains the number of a map in the context of the containing map .

```

292 \newcount{\Map@counter}
293 \Map@counter=0
```

Continuing...

Typesetting a Map, Continued

\Map@parts@ The macro \Map@parts@ is used to store the parts of the top-level maps. This is the initialization of a feature otherwise used in the aux file.

294 \@namedef{Map@parts@}{}

Typesetting a Block

Blocks are the basic building unit of maps. Here the Block is defined in all it's beauty.

- Map@Block This macro is used to typeset a block inside a Map. To avoid abuse outside of a map it is activated within a Map only.

```

295 \newenvironment{Map@Block}[1]{\par
296   \vspace*{-\parskip}\vspace*{-1ex}%
297   \\\\null\par
298   \vspace*{\MapParskip}%
299   \raggedright\hspace{0pt}\MapFont{\MapBlockLabelFont{\#1}}%
300   \gdef\@currentlabel{\#1}%
301   &\parskip=\MapParskip
302   {\MapRuleStart
303     \rule{\MapTextFraction\textwidth}{\MapRuleWidth}}\par
304   \ifx\@undefined\MapBlockStartHook\else
305     \MapBlockStartHook{\#1}%
306   \fi

```

The final action is empty. Thus the block can be used as a simple macro as well.

```

307 }{%
308 }

```

- \Block The macro \Block issues an error when used outside of a Map environment.

```

309 \newcommand\Block[1]{\PackageWarning{limap}{The sectioning command
310       'Block' has been encountered outside the scope of a Map
311       environment.}}

```

- \WideBlock The macro \WideBlock takes one argument which is added to the current block where the whole width of the table is used.

```
312 \newcommand\WideBlock{\\\multicolumn2{@{}l@{}}}
```

Typesetting a Table of Contents

```
313 \newif\if@Map@toc@sep@
```

- \MapTableOfContents@open The macro \MapTableOfContents@open produces the table of contents for the current map. It produces a tabular containing the titles and pages of all maps directly contained in the current map. It utilizes a tabular environment and booktabs.

```
314 \def\MapTableOfContents@open{%
315   \centering
316   \begin{tabular}{p{.6\textwidth}r}\toprule
317     \MapTOCheadfont{\MapTOCname}&
318     \MapTOCheadfont{\MapTOCpage}\midrule
319     \ifcsdef{Map@parts@\the\Map@no}{
320       \edef\Map@tmp@{\csname Map@parts@\the\Map@no\endcsname : }%
321       \expandafter\Map@toc@loop\Map@tmp@%
322       \bottomrule
323     }{}
324   \end{tabular}
325 }
```

- \MapTableOfContents@boxed The macro MapTableOfContents@boxed produces the table of contents for the current map. It produces a tabular containing the titles and pages of all maps directly contained in the current map. It utilizes a tabular environment and booktabs.

```
326 \def\MapTableOfContents@boxed{%
327   \centering
328   \begin{tabular}{|p{.6\textwidth}|r|}\hline
329     \MapTOCheadfont{\MapTOCname}&
330     \MapTOCheadfont{\MapTOCpage}\hline
331     \ifcsdef{Map@parts@\the\Map@no}{
332       \edef\Map@tmp@{\csname Map@parts@\the\Map@no\endcsname : }%
333       \expandafter\Map@toc@loop\Map@tmp@%
334       \hline
335     }{}
336   \end{tabular}
337 }
```

Continuing...

Typesetting a Table of Contents, Continued

\MapTableOfContentsStyle The macro \MapTableOfContentsStyle determines the style of the TOCs. It can take the values open or boxed.

```
338 \newcommand{\MapTableOfContentsStyle}{open}
```

\MapTableOfContents The macro \MapTableOfContents produces the table of contents for the current map. It produces a tabular containing the titles and pages of all maps directly contained in the current map.

```
339 \newcommand{\MapTableOfContents}{\par
340   \global\@Map@toc@sep@false
341   \csname MapTableOfContents@\MapTableOfContentsStyle\endcsname
342   \vspace*{-1.5\parskip}\par\ignorespaces
343 }
```

\Map@toc@loop The macro \Map@toc@loop is a recursive solution to loop through all elements of a list of children. The argument is expected to be a colon separated list of numbers. The end is marked by two colons in row.

Each number is a reference to a map. The respective line in the toc table is produced.

```
344 \def\Map@toc@loop#1:{%
345   \def\Map@tmp@{#1}%
346   \ifx\Map@tmp@\empty
347     \global\let\Map@next@=\relax
348   \else
349     \if@Map@toc@sep@
350       \gdef\Map@next@{\\
351         \ref{Map@#1}&\pageref{Map@#1}%
352         \Map@toc@loop}%
353     \else
354       \gdef\Map@next@{%
355         \ref{Map@#1}&\pageref{Map@#1}%
356         \Map@toc@loop}%
357       \global\@Map@toc@sep@true
358     \fi
359   \fi
360   \Map@next@
361 }
```

Typesetting a Table

\MapTabularFraction The macro \MapTabularFraction contains a factor for the line width. This is used to determine the width of the table. The tabular is centered in the text column.

```
362 \newcommand{\MapTabularFraction}{.95}
```

MapTabular The environment MapTabular produces the tabular environment with the width of the text column.

```
363 \newenvironment{MapTabular}{%
364   \begin{center}%
365   \begin{tabular}{*{(\MapTabularFraction\linewidth)}{c}}%
366 }{%
367   \end{tabular}%
368   \end{center}\ignorespaces%
369 }
```

Typesetting the Title Page

\MakeTitle The macro \MakeTitle can be used as a replacement for the \maketitle macro.

```

370 \newcommand{\MakeTitle}{\thispagestyle{empty}
371   \rule{0pt}{.25\textheight}\par
372   \mbox{}\hfill
373   \begin{minipage}{\MapTextFraction\textwidth}
374     \raggedright
375     \rule{\textwidth}{2pt}\par
376     \vspace*{2.5\MapParskip}%
377     \sf{\huge \@title}\par
378     \vspace*{2.5\MapParskip}%
379     \rule{\textwidth}{2pt}\par
380     \vspace*{2.5\MapParskip}%
381     \MapFont{\large \@author} \par
382     \vspace*{2.5\MapParskip}%
383     \MapFont{\footnotesize \@date}%
384     \vspace*{\MapParskip}%
385   \end{minipage}%
386   \vspace*{-22ex}%
387   \par
388 }
```

Abstract This macro is used to typeset the abstract.

```

389 \newenvironment{Abstract}{\vfill
390   \par
391   \mbox{}\hfill
392   \begin{minipage}{\MapTextFraction\textwidth}\parskip=1ex
393     \rule{\textwidth}{1pt}\medskip\par
394   }{\par\rule{\textwidth}{1pt}
395   \end{minipage}%
396   \par
397 }
```

Continuing...

Typesetting the Title Page, Continued

Use `\maketitle` and `\abstract`

The new `\maketitle` macro is activated for the class.

```
398 <*class>
399 \let\maketitle\MakeTitle
400 \let\abstract\Abstract
401 \let\endabstract\endAbstract
402 />
```

Final Actions

Local configuration

Load the configuration file at the end if it can be found.

```
403 \InputIfFileExists{limap.cfg}{}{}
```

Finally we have to activate the proper settings for the chosen language.

```
404 \csname LIMAP@SelectLanguage@\LIMAP@Language\endcsname
```

```
405 \ifLIMAP@strict
406   \def\chapter{\PackageWarning{limap}{The sectioning command
407     'chapter' is not available.}}
408 % \def\section{\PackageWarning{limap}{The sectioning command
409 %   'section' is not available.}}
410 \def\subsection{\PackageWarning{limap}{The sectioning command
411   'subsection' is not available.}}
412 \def\subsubsection{\PackageWarning{limap}{The sectioning command
413   'subsubsection' is not available.}}
414 \def\paragraph{\PackageWarning{limap}{The sectioning command
415   'paragraph' is not available.}}
416 \def\ subparagraph{\PackageWarning{limap}{The sectioning command
417   ' subparagraph' is not available.}}
418 \def\subsubparagraph{\PackageWarning{limap}{The sectioning command
419   'subsubparagraph' is not available.}}
420 \fi
```

Finale

That's all for this time.

Index

Numbers written in italic refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in roman refer to the code lines where the entry is used.

| Symbols | |
|---------------------------|--|
| \@Map@toc@sep@false | 340 |
| \@Map@toc@sep@true | 357 |
| \@esphack | 54, 57 |
| \@width | 189 |
| A | |
| \Abstract | 400 |
| Abstract (environment) | <u>389</u> |
| \abstract | 400 |
| \AtEndDocument | 187 |
| B | |
| \Block | 53, 56, 61, 194, <u>309</u> |
| C | |
| \count | 175, 176 |
| D | |
| \defineLimapLanguage | <u>83</u> , 91, 94, 97, 100, 103 |
| \Describe@@Env | 55, 56 |
| \Describe@@Macro | 52, 53 |
| \docdate | <u>5</u> , 13, 49 |
| \docversion | 4 |
| E | |
| \endAbstract | 401 |
| \endabSTRACT | 401 |
| \endBlock | 195 |
| \endfirsthead | 254 |
| \endfoot | 264 |
| \endhead | 258 |
| \endlastfoot | 268 |
| \endlongtable | 276 |
| \endMap | 220 |
| environments: | |
| Abstract | <u>389</u> |
| Map | <u>191</u> |
| Map@Block | <u>295</u> |
| MapTabular | <u>363</u> |
| \evensidemargin | 15 |
| F | |
| \filedate | <u>3</u> , 5, 12, 48, 78, 81 |
| \filename | <u>1</u> , 10, 46, 68 |
| \fileversion | <u>2</u> , 4, 11, 47 |
| H | |
| \hline | 328, 330, 334 |
| I | |
| \if@Map@toc@sep@ | 313, 349 |
| \ifcsdef | 319, 331 |
| L | |
| \ifLIMAP@strict | <u>112</u> , 405 |
| \ifMap@open@ | <u>225</u> , 274 |
| \label | 270 |
| \LIMAP@Class@base@article | 124 |
| \LIMAP@Class@base@book | 126 |
| \LIMAP@Class@base@letter | 127 |
| \LIMAP@Class@base@report | 125 |
| \LIMAP@Class@koma@article | 128 |
| \LIMAP@Class@koma@book | 130 |
| \LIMAP@Class@koma@letter | 131 |
| \LIMAP@Class@koma@report | 129 |
| \LIMAP@ClassType | <u>116</u> , 117--120, 135, 141 |
| \LIMAP@Language | <u>106</u> , 107--111, 404 |
| \LIMAP@strictfalse | 113 |
| \LIMAP@stricttrue | 112 |
| \LIMAP@Variant | <u>121</u> , 122, 123, 135, 141 |
| \LimapDocdate | 13, 49 |
| \LimapFiledate | 12, 48 |
| \LimapFilename | 10, 46 |
| \LimapFileVersion | 11, 47 |
| \linewidth | 365 |
| \longtable | 248 |
| \LT@err | 192 |
| \LT@final@warn | <u>186</u> |
| \LT@warn | 193 |
| M | |
| \MakeTitle | <u>59</u> , <u>370</u> , 399 |
| \maketitle | <u>59</u> , 399 |
| \Map | 191 |
| Map (environment) | 191 |
| \Map@up | 206, 210 |
| \Map@Block | 194 |
| Map@Block (environment) | <u>295</u> |
| \Map@blockcount | <u>185</u> , 196, 280, 283, 284, 286 |
| \Map@counter | 241, 292 |
| \Map@end | 208, 221, <u>273</u> |
| \Map@endBlock | 195 |
| \Map@length | <u>182</u> , 242--244, 249 |
| \Map@level | <u>171</u> , 172, 175, <u>183</u> , 205, 216, 222 |
| \Map@next@ | 347, 350, 354, 360 |
| \Map@no | 197, 202, 204, 213, 215, 270, <u>291</u> , 319, 320, 331, 332 |
| \Map@open@false | 226, 275 |
| \Map@open@true | 271 |
| \Map@parts@ | <u>294</u> |
| \Map@start | 218, 240 |
| \Map@this | 213 |
| \Map@TITLE | 217, 245, 246, 253, 257, 269 |
| \Map@tmp@ | 320, 321, 332, 333, 345, 346 |

| | | | |
|---------------------------------|---|------------------------------|---------------------------------|
| \Map@toc@loop | 321, 333, <u>344</u> | \MapTitleContinuedFont | 161, <u>164</u> |
| \Map@TOC@name | <u>227</u> | \MapTitleFont | 31, <u>163</u> , 252, 256 |
| \Map@UP | 198, 201, 202, 204, 206, 210, <u>290</u> | \MapTitleFraction | <u>167</u> , 243, 249 |
| \MapBlockLabelFont | 32, <u>165</u> , 299 | \MapTOC | <u>170</u> , 246 |
| \MapBlockStartHook | 304, 305 | \MapTOCheadfont | <u>181</u> , 317, 318, 329, 330 |
| \MapBlockTOC | <u>174</u> | \MapTOCname | 87, <u>179</u> , 317, 329 |
| \MapContinued | 85, <u>158</u> , 257 | \MapTOCpage | 88, <u>180</u> , 318, 330 |
| \MapContinuedFormat | <u>161</u> , 257 | | |
| \MapContinuing | 86, <u>159</u> , 263 | | |
| \MapContinuingFormat | <u>160</u> , 263 | | |
| \MapFont | <u>162</u> , 252, 256, 299, 381, 383 | \pageref | 351, 355 |
| \MapNewpage | <u>169</u> , 277 | | |
| \MapParskip | <u>166</u> , 267, 298, 301, 376, 378, 380, 382, 384 | \ref | 351, 355 |
| \MapRuleStart | 39, <u>157</u> , 260, 265, 302 | \rmfamily | 50 |
| \MapRuleWidth | 40, 114, <u>156</u> , 261, 266, 303 | | |
| \MapTableOfContents | <u>339</u> | | |
| \MapTableOfContents@boxed | <u>326</u> | | |
| \MapTableOfContents@open | <u>314</u> | | |
| \MapTableOfContentsStyle | <u>338</u> , 341 | | |
| MapTabular (environment) | <u>363</u> | | |
| \MapTabularFraction | <u>362</u> , 365 | | |
| \MapTextFraction | <u>168</u> , 244, 250, 261, 266, 303, 373, 392 | | |
| | | \scriptsize | 50, 181 |
| | | | |
| | | \theCodelineNo | 50 |
| | | | |
| | | \WideBlock | <u>312</u> |
| | | | |

P

\pageref

R

\ref

\rmfamily

S

\scriptsize

T

\theCodelineNo

W

\WideBlock