



ACI Desktop User Interface Manual

© 2003 by ACI Worldwide Inc. All rights reserved.

All information contained in this documentation is confidential and proprietary to ACI Worldwide Inc., and has been delivered for use pursuant to license. No part of this documentation may be photocopied, electronically transferred, modified, or reproduced in any manner that is contrary to license without the prior written consent of ACI Worldwide Inc.

Access Control Server, ACI Automated Case Management System, ACI Card Management System, ACI Claims Manager, ACI Commerce Gateway, ACI Debit Card System, ACI e-Courier, ACI Host Link, ACI Merchant Accounting System, ACI Payments Manager, ACI Proactive Risk Manager, ACI Smart Chip Manager, BASE24, BASE24-atm, BASE24-card, BASE24-check auth, BASE24-configuration manager, BASE24-es, BASE24-frequent shopper, BASE24-infobase, BASE24-pos, BASE24-refunds, BASE24-remote banking, BASE24-teller, NET24, and WINPAY24 are trademarks or registered trademarks of ACI Worldwide Inc., Transaction Systems Architects, Inc., or their subsidiaries.

Other companies' trademarks, service marks, or registered trademarks and service marks are trademarks, service marks, or registered trademarks and service marks of their respective companies.

Contents

Preface.	xi
Section 1	
Introduction.	1-1
Desktop Layout.	1-2
User Interface Framework	1-3
Communication Security	1-4
User Security Server	1-5
Fail Over Support	1-6
Overview of Windows (Screens), Applications, and Tasks	1-7
User Configuration and Management.	1-9
Default Users	1-10
Configuration Files	1-11
Section 2	
Basic Functions	2-1
Start the Desktop.	2-2
Log On	2-4
Log Off (Out)	2-6
Change a Password	2-7
Set General User Preferences	2-8
Set Error Notification Preferences	2-11
Set Sound Preferences	2-13
Send a Snapshot	2-14
Select a Web Server	2-15
Print Functions	2-16
Exit from the Desktop.	2-17
Display User Interface Framework Version Information	2-18

Section 3

General Procedures	3-1
Hyperlinked Field Labels (Names)	3-2
Selectable List Fields	3-3
Table Cell Exception	3-3
Window Toolbars and Pop-up Menus	3-4
Tables	3-5
Select a Row	3-5
Select All Rows in a Table	3-5
Undo Changes to a Table Row	3-5
Table Fields	3-6
Select Table Fields	3-6
Save Records	3-7
Refresh	3-7
Clear/Reset	3-7
Delete Records	3-8

Section 4

User Configuration	4-1
User Security Overview	4-2
User Security Configuration Hierarchy	4-2
User Security Configuration Window Usage	4-3
User Profiles	4-4
Roles	4-4
Permission Groups	4-4
Permissions	4-4
Field Filters	4-5
Task IDs	4-5
Passwords and Password Groups	4-5
Security Groups	4-6
Distributed Security Administration (DSA)	4-7
Steps to Add a User	4-9
Step 1.0: Configure a Password Group	4-10
Step 2.0: Configure a Security Group	4-11
Step 3.0: Configure a User Role	4-15
Step 4.0: Configure the User's Profile	4-23

Section 5

User Management	5-1
User Security Configuration Window Usage	5-2
Set the Status of a User	5-3
Display Active User Sessions	5-4
Active User Session for a Selected User	5-4
Active User Sessions for All Users	5-5
Terminate Active User Sessions (Log off a User)	5-6
Display Password History for a User	5-7
Change a User's Password	5-7
Expire a User's Password	5-7
Expire Passwords by Password Group	5-8

Section 6

User Audit	6-1
User Audit Processing Overview	6-2
Internal XML Audit Message Format	6-3
User Audit Activity Reports	6-4

Section 7

Contingency SAF Processing	7-1
Configure Contingency Processing	7-2
Process Limits	7-2
Process Status	7-3
Contingency Station Name	7-3
Enable and Disable Contingency Processing	7-4

Section 8

Version Checker Server	8-1
Version Checker Overview	8-2
Run the Version Checker Server	8-2
Prompt or Automatic Download	8-2
Version Checker Client Window	8-3
Select All	8-3
Close When Done Option	8-4
Mirror the Repository	8-5
Automatic JAR File Update	8-6

Section 9

Online Help	9-1
Access to JavaHelp from the ACI Desktop.	9-2
JavaHelp Viewer Overview.	9-3
JavaHelp File Types	9-4
JavaHelp Packages for BASE24-es and Payments Manager	9-5
How Context is Implemented in JavaHelp	9-6
Map IDs in Window Properties Files	9-6
Map IDs in JavaHelp Map File (.jhm)	9-7
Map IDs in XML Table of Contents and Index Files.	9-7
Search the Helpset for a Text String	9-8
Custom Online Help	9-9
Customization and Localization Considerations	9-9
Customization of HTML Content Files	9-10
Change the Display of Content.	9-11
Install JavaHelp for Stand-alone Use	9-12

Appendix A

Desktop Window Properties	A-1
Configure Menu Windows	A-2
Acquirer Transactions Allowed Window	A-2
Action Code Profile Configuration Window	A-2
Administrative Card Configuration Window	A-2
Application Parameter Management System Interface Configuration Window ..	A-3
ATM Channel Configuration Window	A-3
ATM Channel Profile Configuration Window	A-3
ATM Device Handler Interface Configuration Window	A-4
ATM Diebold Channel Operator ID Configuration Window.	A-4
ATM Hopper Profile Configuration Window	A-4
ATM Load Profile Window	A-5
ATM Optional Receipt Profile Window.	A-5
ATM Receipt Format Configuration Window	A-5
ATM Receipt Required Type Configuration Window	A-6
Authentication Profile Configuration Window.	A-6
Authorization Script Configuration Window	A-6
BankNet ISO Interface Configuration Window	A-7
BASE24 ISO8583 Host Interface Configuration Window.	A-7

Configure Menu Windows *continued*

BASE24KEYF Configuration Window	A-8
Certificate Management Window	A-8
Channel Security Configuration Window	A-8
Context Profile Configuration Window	A-9
Contingency Interface Configuration Window	A-9
Currency Conversion Rate Configuration Window	A-9
Destination Routing Profile Configuration Window	A-10
Disable KEYGEN Window	A-10
DUKPT Derivation Key Profile Configuration Window	A-10
EPP Serial Number Window	A-11
Euro Opted Currency Configuration Window	A-11
Exported Operators Configuration Window	A-11
File Update Router	A-12
IMT Interface Configuration Window	A-12
Institution Configuration Window	A-12
Instrument Status Mapping Profile Configuration Window	A-13
Instrument Type/Interchange Relationship Window	A-13
Interchange Prefix Configuration Window	A-13
Interface Configuration Windows (Various)	A-14
Interface Security Configuration Window	A-14
Interface Terminal Window	A-14
Internal Message Translation (IMT) Transaction Mapping - ATM Window	A-15
Internal Message Translation (IMT) Transaction Mapping - POS Window	A-15
ISO 93 Host Interface Configuration Window	A-16
ISO Message Profile Configuration Window	A-16
ISO93 Interface Configuration Window	A-16
Issuer Transactions Allowed Profile Configuration Window	A-17
Journal Issuer Profile Relationship Configuration Window	A-17
Journal Profile Configuration Window	A-18
Journal Query Configuration Window	A-18
Journal TDE Suppression Configuration Window	A-18
Linked Currency Configuration	A-19
Master File Key Conversion Window	A-19
MasterCard Debit Switch (MDS) Interface Configuration Window	A-19
Merchant Configuration and Statistics Window	A-20
On-Us Prefix Configuration Window	A-20

Configure Menu Windows *continued*

Perusal Profile Configuration Window	A-21
POS Delivery Channel Configuration and Statistics Window	A-21
POS Delivery Channel Profile Configuration	A-21
Real Time Feed Window	A-22
Routing Configuration - Destination Window	A-22
Routing Configuration - Destination/Source Relationship Window	A-22
Script Editor Window	A-23
Script Repository Window	A-23
Security Device Configuration Window	A-23
Source Routing Profile Configuration Window	A-24
SPDH Device Profile Configuration Window	A-24
Star Network Identifier/Instrument Type Relationship Window	A-24
Star Institution Window	A-25
Star ISO Interface Configuration Window	A-25
Surcharge Profile Configuration Window	A-26
System Algorithm Configuration Window	A-26
System Prefix Configuration Window	A-26
User Profile Relationship Window	A-27
User Security Control Management Window	A-27
User Security Group Configuration Window	A-27
User Security Profile Configuration Window	A-28
User Security Role Configuration Window	A-28
Visa DPS Configuration Window	A-28
VisaNet ISO Interface Configuration Window	A-29
System Operations Menu Windows	A-30
Active Script Statistics and Management Window	A-30
Application Configuration Window	A-30
Application Management Window	A-30
Application Management Comms Handler Window	A-31
Application Management Message Router Summary Window	A-31
Application Management Process Summary Window	A-31
Application Management Queue Summary Window	A-32
Application Management Queue Manager Summary Window	A-32
Application Management Station Summary Window	A-32
ATM Channel Administration Window	A-33
ATM Channel Management - All Channels Window	A-33

System Operations Menu Windows *continued*

ATM Channel Management Window	A-33
ATM Hardware Status Window	A-34
ATM Reload Map Request Window	A-34
ATM Status Query Window	A-34
Audit Store and Forward (SAF) Configuration Window	A-35
Cache Administration Window	A-35
Configuration Properties Window	A-35
Contingency Store and Forward (SAF) Configuration Window	A-36
Database Administration Window	A-36
Environment Configuration Window	A-36
Event Subsystem ID Configuration Window	A-37
External Connection Configuration Window	A-37
File Partition Configuration Window	A-37
Integrated Server Event Configuration and Management Window	A-38
Listener Configuration Window	A-38
Process Configuration Window	A-38
Process Control Window	A-39
Query Execute Window	A-39
Socket Administration Window	A-39
System Monitor Window	A-40
System Properties Window	A-40
Trace Configuration Window	A-40
Trace Filter Profile Configuration Window	A-41
Customer Management Menu Windows	A-42
Card Management Window	A-42
Limit Profile Management Window	A-42
Positive Balance Management Window	A-43
Preauthorization Hold Management Window	A-43
Usages Management Window	A-43
View Menu Windows	A-44
Channel Public Key Perusal Window	A-44
Host Public Key Perusal Window	A-44
Journal Perusal Window	A-45
Tools Menu Windows	A-46
Audit Extract Window	A-46

Appendix B

Task IDs B-1

Appendix C

Permission IDs C-1

Index. Index-1

Preface

The ACI desktop is the user access to the BASE24-es system for configuration, operation, and management functions.

Audience

This manual is written for all users of the ACI desktop, including system administration personnel.

Prerequisites

This manual is written as an introduction to using and understanding the ACI desktop. Readers must know basic graphical user interface (GUI) functionality and procedures, such as using hyperlinks and buttons. The ACI desktop is organized by tasks (i.e., configure, system operations, and customer management) that require basic understanding of managing payment systems and applications.

Software

This manual documents standard processing as of its publication date. Software that is not current and custom software modifications (CSMs) may result in processing that differs from the material presented in this manual.

Manual Summary

The following is a summary of the contents of this manual.

Section 1, “Introduction,” provides an overview of the ACI desktop, windows, communication security, and information about default users. Also included is information about the user interface framework and user security servers.

Section 2, “Basic Functions,” describes how to log on and log off, set user preferences and print, among other basic functions available from the File menu.

Section 3, “General Procedures,” provides an overview of working with windows on the ACI desktop. Topics discussed include working with tables, saving and deleting records, using fields and lists within windows, and using the toolbar.

Section 4, “User Configuration,” provides an overview of user security, distributed security administration (DSA), and how to configure a user of the ACI desktop.

Section 5, “User Management,” describes how to manage and monitor users of the ACI desktop.

Section 6, “User Audit,” describes configuring user auditing using Environment attributes, the User Audit Log data source (USRAULOG), starting and stopping user audit store-and-forward (SAF) processing, user activity reports, and the User Audit Log Report window.

Section 7, “Contingency SAF Processing,” describes how to configure, enable and disable contingency SAF processing.

Section 8, “Version Checker Server,” describes how the Version Checker server manages and updates ACI desktop versions.

Section 9, “Online Help,” describes the desktop online help (JavaHelp) and how to use online help. And, provides information about localizing the ACI desktop and customizing online help.

Appendix A, “Desktop Window Properties,” provides a list of each ACI desktop window, the application (i.e., BASE24-es or Transaction Security Services) for which the window is used, the desktop access to the window, and task IDs and permission IDs for user security purposes.

Appendix B, “Task IDs,” provides a list of each Task ID and associated permission ID and ACI desktop window.

Appendix C, “Permission IDs,” provides a listing of each Permission ID and associated task ID and ACI desktop window.

Publication Identification

Three entries appearing at the bottom of each page uniquely identify this ACI publication. The publication number (for example, ES-CS000-01 for the ***ACI Desktop User Interface Manual***) appears on every page to assist readers in identifying the manual from which a page of information was printed. The publication date (05/2005 for May 2005) indicates the issue of the manual. The software release and version information (R1.0v05.2 for release 1.0, version 05.2) specifies the software that the manual describes. This information matches the document information on the copyright page of the manual.

ACI Worldwide Inc.

Section 1

Introduction

The ACI desktop is the primary user interface for performing the following tasks:

- ❑ Configuring the data sources used by BASE24-es, enhanced authorization for BASE24, Transaction Security Services (TSS), and Payments Manager.
- ❑ System operations, such as process control commands, application management, ATM management, database and environment setup.
- ❑ Customer management of cards, limits, balances, preauthorizations, and usages.
- ❑ Perusal of logged data

This manual is written to assist users of the ACI desktop to perform the tasks listed above and to assist system administrators in setting up users of the ACI desktop.

Topics:

[Desktop Layout](#) (page 1-2)

[User Interface Framework](#) (page 1-3)

[Communication Security](#) (page 1-4)

[User Security Server](#) (page 1-5)

[Fail Over Support](#) (page 1-6)

[Overview of Windows \(Screens\), Applications, and Tasks](#) (page 1-7)


[User Configuration and Management](#) (page 1-9)

[Default Users](#) (page 1-10)

[Configuration Files](#) (page 1-11)

Desktop Layout

The ACI desktop consists of distinctive areas identified in the illustration below.



- **1** – The **Title Bar** displays the name of the desktop.
- **2** – The **Menu Bar** provides access to available functions and application windows.
- **3** – The **Toolbar** contains buttons for common functions, such as logon and logoff.
- **4** – The **Navigation Tree** provides a hierarchical view of the menu bar.
- **5** – The **Application Area** contains opened application windows.
- **6** – The **Status Pane** contains information message about the activity between the desktop and servers. This area by default displays the most recent message. The last fifty messages are accessible using the scroll bar (**7**).

User Interface Framework

The user interface framework is a collection of Java classes, interface applications, rules, guidelines, recommendations, and styles that are used as a template for building and supporting ACI desktop applications. The components of the user interface framework are:

- User interface clients
- User security server
- Web servers
- Version Checker server
- Online help

The components of the user interface framework communicate with each other and applications running on the application host server using a variety technologies. XML messages are passed to application servers on the host using Transmission Control Protocol/Internet Protocol (TCP/IP).

Java-based Remote Method Invocation (RMI) is used for ACI desktops and Web server clients to communicate with servers, and for servers to communicate with the user security server. Web servers communicate with the user security server.

The user interface framework provides the following common desktop functionality and support:

- Common functions, such as logging on and off the desktop, available through the File menu.
- Online help that is context sensitive.
- Comprehensive user security configuration support that allows for controlling user access to windows (screens) and functions.
- Fail over support for user security.
- Automatic version checking upon logon including support for either automatic or user prompted configuration updating.

Each web server is responsible for managing communication among desktop clients and the User Security server. Multiple web servers can be available in groups and are configured for the desktop using the local.cfg file. By defining groups, users can select web servers as applicable.

Communication Security

Connections among ACI desktops, web servers (e.g., WebGate), user security servers, and application servers on the host can be secured with Secure Sockets Layer (SSL).

Certificates are used to authenticate servers to desktop clients, and optionally authenticate clients to servers. Public key cryptography is used to encrypt messages sent among clients and servers.

Note: SSL is configured using SSL specific properties defined using the Application Configuration window (**System Operations > Server Management > Application**). Refer to the *ACI Java Server Framework User Guide* for more information.

The following JAR files provide the support needed for SSL:

- Jcert.jar
- Jnet.jar
- Jsse.jar
- UIFSSLKeys.jar, which contains the default keystores.

Certificates and private keys used for encryption and authentication are maintained in protected files called keystores. BASE24-es provides the following default keystores:

- defaultKS.sto
- dtKS.sto
- ncKS.sto
- entKS.sto

User Security Server

The user security server authenticates and authorizes users, creates and maintains active user sessions, maintains the access level for each user, and assigns tickets. Host applications access the user security server to obtain authorization to complete a function initiated by an authenticated user of the ACI desktop.

For authentication, an individual must provide a user ID and password. This information is passed to the user security server, which checks the information against the user security database to determine whether the individual can access the application. This authentication includes the requirement that the user ID be defined in the user security database and the password must match that recorded for the ID. In addition, the user's security group and password group restrictions are checked. Security groups and password groups are discussed later in section 5.


If a user meets the authentication requirements, the user security server establishes an active session for the user and assigns a *ticket*. The ticket consists of a authorization ID that is used throughout the user's session for authorization checking by the user security server. Tickets cannot be viewed using the ACI desktop. Tickets automatically expire when a user logs off the desktop or is disconnected, such as in the event of a timeout. Users cannot access the functionality of the desktop without a ticket.

User authorization is the validating of each activity initiated by a user. During user authorization the user security server compares the activity initiated by a user to the user's security profile, which defines the functions (i.e., Delete, Save, and View) that a user can perform. This ensures that a user does not perform an activity not authorized by the user's security configuration. See section 4 for more information about functions, task IDs, and permissions.

Fail Over Support


Multiple User Security servers can be configured to access a shared user security database. In the event a user security server is not available, a web server automatically accesses another user security server from the list of configured servers.

In the illustration below, two selectable web servers have access to two User Security servers and both servers are accessing the same shared security database. In the event User Security₁ fails, the web servers still have access to the user security database through User Security₂; thus, providing access to the same database and allowing clients connected the web server group uninterrupted access to the user security database.




Overview of Windows (Screens), Applications, and Tasks

The term *window* is used BASE24-es documentation and online help. This term relates to a collection of graphical user interface (GUI) components (i.e., buttons, fields, field names, tabs, buttons, tables, trees, and messages) that provide access to a particular application, function and data source(s). The Process Control window (shown below) is displayed within the desktop.



Each window is managed by a particular application server on the host. The applications available (therefore, the windows available) depend on the ACI desktop configuration and user security access permissions.

An application (and the corresponding window) is identified by a task ID. Tasks available on a desktop can be viewed in the Task ID selectable field located on the Permissions tab of the User Security Role Configuration window, which is shown below. This window is displayed by accessing **Configure > User Security > Role**.



In the example above, the task ID *ProcessControl* is shown in the Task ID field. A user must be assigned this task ID and the corresponding functions (Send and View) in order to access (display) and use the Process Control window. Task IDs are assigned to user by permissions, permission groups and roles. See section 4 for more information.

User Configuration and Management

The information about the configuration and management of users of the ACI desktop is presented in two sections:

- User Configuration, section 4, which includes:
 - User configuration security overview
 - Distributed security administration (DSA) overview
 - Steps to add a user to the ACI desktop
- User management, section 5, which includes:
 - User status settings
 - User sessions monitoring and control
 - Password and password group control

Default Users

Security Note: Change passwords of default users after installing the desktop.

The **security administrator** (SecAdmin) has access to the user security windows from which additional administrators (profiles) can be configured. The SecAdmin user ID is generic to all BASE24-es applications.

User Name: SecAdmin
Password: SecAdmin01
Role: SecAdminRole

The **system administrator** (SysAdmin) has access to most of the functionality of the desktop, including all TSS, user security, and user interface framework windows and functions. The SysAdmin user ID is generic to all BASE24-es applications.

User Name: SysAdmin
Password: SysAdmin01
Role: SysAdminRole

The **Transaction Security Services system administrator** (TSSSysAdmin) has access to all TSS windows and functions available on the desktop, including the user security and user interface framework windows and functions. The TSSSysAdmin user ID is specific to the Transaction Security Services environment.

User Name: TSSSysAdmin
Password: TSysAdmin01
Role: TSSSysAdminRole

The **Transaction Security Services administrator** (TSSAdmin) has access to all TSS and user interface framework windows and functions, except for the user security windows and functions. The TSSAdmin user IDs is specific to the Transaction Security Services environment.

User Name: TSSAdmin
Password: TSAdmin01
Role: TSSAdminRole

Configuration Files

The user interface framework uses several configuration files. These files are:

- The usec.cfg for configuring user security.
- The local.cfg for configuring the local desktop client.
- The user preferences configuration files (*username.cfg* and *networkname.cfg*). The names of these files vary per the user names and network names.
- The global.cfg and globalprefs.cfg configuration files that define global properties that can be used in the other configuration files.
- The sound.cfg for desktop sounds.

Configuration files contain ASCII formatted key-value pairs (properties) grouped within sections. Section names are enclosed in square brackets “[]”. Keys and values are separated with an equal sign (“=”). Section names and key names are case-insensitive and can be upper case, lower case, or both.

Many local properties can be defined globally across all desktops via the global configuration property file. Also, if a configuration property is not defined in the local configuration file, the desktop checks for an entry in the global configuration file.

ACI Worldwide Inc.

Section 2

Basic Functions

This section provides information about basic functions that can be performed from the ACI desktop.

Topics:

[Start the Desktop](#) (page 2-2)

[Log On](#) (page 2-4)

[Log Off \(Out\)](#) (page 2-6)

[Change a Password](#) (page 2-7)

[Set General User Preferences](#) (page 2-8)

[Set Error Notification Preferences](#) (page 2-11)

[Set Sound Preferences](#) (page 2-13)

[Send a Snapshot](#) (page 2-14)

[Select a Web Server](#) (page 2-15)

[Print Functions](#) (page 2-16)


[Exit from the Desktop](#) (page 2-17)

[Display User Interface Framework Version Information](#) (page 2-18)

Start the Desktop

Each desktop session is started by running the **RunDesktop.bat** batch file. Web servers (e.g., WegGate) and application servers need to be running before the desktop can start.

1. Generally, the RunDesktop.bat file is configured during installation to be accessed through a shortcut located on a client desktop or a menu, such as shown below.



2. When you start the desktop, the desktop contacts the applicable servers and configuration files. Messages about this contact activity display in a desktop console similar to the illustration below.

```

C:\_ACI\ES\Desktop>rem argument 2 is the optional parameter (e.g., -Q for quiet
mode)


C:\_ACI\ES\Desktop>echo copy "C:\_ACI\VersionChecker\VerChk.jar" "C:\_ACI\Version
Checker\vc-temp.jar"
copy "C:\_ACI\VersionChecker\VerChk.jar" "C:\_ACI\VersionChecker\vc-temp.jar"

C:\_ACI\ES\Desktop>copy "C:\_ACI\VersionChecker\VerChk.jar" "C:\_ACI\VersionChec
ker\vc-temp.jar"
1 file(s) copied.


C:\_ACI\ES\Desktop>echo "C:\_ACI\jre1.3.1_01\bin\java" -classpath C:\_ACI\Version
Checker\vc-temp.jar -DLocalConfig="C:\_ACI\ES\Desktop\local.cfg" versionchecker.
client.JarVerChecker
"C:\_ACI\jre1.3.1_01\bin\java" -classpath C:\_ACI\VersionChecker\vc-temp.jar -DLo
calConfig="C:\_ACI\ES\Desktop\local.cfg" versionchecker.client.JarVerChecker

C:\_ACI\ES\Desktop>"C:\_ACI\jre1.3.1_01\bin\java" -classpath "C:\_ACI\VersionChe
cker\vc-temp.jar" -DLocalConfig="C:\_ACI\ES\Desktop\local.cfg" versionchecker.cli
ent.JarVerChecker
Logging to location: C:\_ACI\ES\Logs\VerChkCli
Loading Config...
JAR version checking in progress...
  
```

3. The Version Checker server is automatically accessed to determine whether new and updated JAR files are available from the Server Repository. If JAR files on the local desktop need updating, the Version Checker Client window is displayed for users to download new and updated JAR files.
4. After the desktop establishes contact with the applicable servers and JAR files have been downloaded, the desktop displays the Log In window entry of a user ID (name) and password. The User Name field on the Log In window defaults to the ID of the most recent user to log on to the desktop.




5. The desktop is opened after a valid user ID (name) and password combination has been provided and authenticated by the user security server. The default view of the desktop is shown below.



Log On

To log on, select the Log In function located on the File menu (**File > Log In**), the Log In button () on the toolbar, or navigation tree.




After you successfully logon, you are now an authenticated user and the desktop provides access to those applications (windows) that system administration has assigned to you (i.e., the permissions and permission groups of your user profile).


Authenticated users are issued a ticket that consists of an authorization ID and expiration timestamp. The user security server uses this ticket information during the active session; however, the ticket is not viewable on the desktop for security purposes. Each session is assigned a unique session number used by the user security server for authorization purposes.

In addition to the above, session and window (UI) timeout values are initiated and tracked during a session. A timeout is a defined period of inactivity. Timeout limits are defined in the security groups assigned to users. See section 4 for more information.

If the user name and password are not correct or the user name has been disabled or does not have valid access at the time of login, the user security server does not allow desktop access. In this case a security error message is displayed. The error message is purposely vague to not indicate which information (name or password or both) is incorrect.



A security warning, such as the example below, is displayed upon a successful logon if there were one or more unsuccessful logon attempts before the successful logon.




Log Off (Out)

To log off, select the Log Out function located either on the File menu (**File > Log Out**), the Log Out button () on the toolbar, or navigation tree.

Logging off does not close the desktop. To close the desktop, select **File > Exit**.


When logging off, the desktop displays the Confirm Logout prompt. Click **Yes** to proceed or **No** to cancel.




Change a Password

To change your password, log on to the desktop and select the Change Password function (**File > Change Password**) to display the Change Password window.

Certain password restrictions and requirements apply. These are discussed in section 5.

A dialog box titled "Change Password" with a close button (X) in the top right corner. It contains three text input fields labeled "Old Password", "New Password", and "Verify New Password". At the bottom, there are two buttons: "OK" and "Cancel".


If the new password does not meet one or more password requirements or violates a password restriction, the Password Error message shown at right is displayed.



If the new password is not entered correctly in the Verify New Password field on the Change Password window, the Password Error message shown at right is displayed.




If the password is successfully changed, the Password Information message shown at right is displayed.




Set General User Preferences

Use the General tab on the User Preferences window (**File > Preferences**) to set the following user preferences.




Descriptions of general preferences are shown on the following page.

Preference	Description
Confirm Deletes	Indicates whether the desktop displays a confirmation dialog box before a delete function is processed.
Confirm non-editable row paste	Displays a dialog box indicating that an attempt was made to paste a copied table row onto a non-editable row.
Confirm non-matching row paste	Displays a dialog box indicating that an attempt was made to paste a copied table row onto a table row that has a different number of table cells.
Confirm Updates	Indicates whether the desktop displays a confirmation dialog box that requires a response before an update function is processed.
Currency Format Locale	Sets whether the default currency is obtained from the desktop configuration or user configuration settings.
Debugging Enabled	Enables the writing of debug messages to a debug file (e.g., DeskTop.dbg).
Frame Open Indicator	Indicates whether the Frame Open Indicator (shown below) is displayed in the desktop toolbar while a window is opening. 
Language	Displays menu functions, dialog box text, messages, and field names in the selected language, if the selected language is defined in the properties file for a window
Navigation Tree	Sets whether the navigation tree is displayed upon desktop startup. If checked, the navigation tree is initially displayed. If not checked, it is initially hidden.

Preference	Description
New Window Position	Sets the position of a window when opened as follows: • Bottom • Cascaded • Centered • Frame specified • Left • Right • Top • Top left
Pre-Show Frame	Indicates whether a blank window, such as the example below, is shown while a window is initializing (being opened).  The screenshot shows a window with a purple title bar containing the text 'Authorization Script Configuration' and standard window control icons. The main content area is gray and displays the text 'UI is initializing..' in a blue font.
Screen Print Orientation	Sets the default print orientation to either portrait or landscape.
Status Pane	Indicates whether the status pane is displayed.
Toolbar	Indicates whether the toolbar is displayed.


Set Error Notification Preferences

Use the Error Notification tab on the User Preferences window (**File > Preferences**) to set error notification preferences.




- The Border drop-down list, if checked, sets the border color of fields that are in error.
- Check the Status check box to have error text displayed in the status pane of windows.
- Check the Tooltip check box to display error text in tooltip text. When a window component is in error, the tooltip text associated with the component changes to the error message. Once the error is corrected, the tooltip text reverts back to its normal text. Tooltip text is text that appears in a pop-up window over a field or button.
- Check the Dialog check box to have error text displayed in a dialog box.
- Check the Trap Focus check box to make errors modal, that is, cause errors to be resolved prior to allowing focus on (access to) another window or tab on the window.

The following example shows a field in error with the error preferences set as shown above (border color red around fields in error). The field in error has a red border and the error text is shown in both the tooltip text and status pane.




In the following example, the error text is shown in a dialog box. Error text is displayed in a Dialog box if the Dialog option is selected.



Set Sound Preferences

Use the Sound tab on the User Preferences window (**File > Preferences**) to set the sound played during certain events (as selected in the Events field).



Use the Themes list to select the sound group to apply to the selected event(s). Themes are defined in the sound.cfg configuration file located in the desktop.jar. Default Windows sounds are stored in the Framework\I18N\sounds\windows folder in the **desktop.jar**. The theme selected is stored in the configuration file of the logged on user.

Use the Events box to select an event to be associated with a sound file.

Use the Location field to select the sound file, such as a .AU file (Java) and .WAV file (Windows), to associate with the selected event.


Send a Snapshot

Use the Send Snapshot (**File > Send Snapshot**) function to send an E-mail message (using the Send Snapshot window shown below) about the desktop configuration and a log record (DeskTop.log) of desktop activity to system administrators. The DeskTop.log file is an ASCII text file that contains information about recent desktop activity that is pertinent to system administrators.

The configuration information is sent as a comma separated values (CSV) file that can be opened by many ASCII readers and spreadsheet applications. The configuration information contains the following information:


- User ID and machine (client workstation) ID
- JAR Versions installed
- Local configuration settings
- Version Checker server settings
- Global configuration settings
- User preferences
- Global preferences

The Send Snapshot window:




Select a Web Server

During startup, the desktop attempts to connect to the default web server, which is the last web server to which the desktop last connected. If multiple web servers (web server group) are available, users can access the Connection window to select alternate web servers. The Connection window can be accessed from **File > Connection**



The Connection window displays a selectable list of available web servers. Choose a web server and click **OK**.




If a web server is selected that accesses a different shared user security database, any existing active sessions for the user are terminated and the user is presented with the Log In window prompting the user to provide a valid user ID and password.

Note: The port to which a web server connects must be available (i.e., not used by another system or application); otherwise, a connection error is encountered.

Print Functions

The File menu provides access to the following print-related functions:

- Use the Print Preview (**File > Print Preview**) function to display a selected page, text, or window in a separate print preview window. This shows the selected item as it will appear when the Print function is performed.
- Use the Print function (**File > Print**) to print a selected page, text, or window.
- Use the Print Screen (**File > Print Screen**) function to print the window in focus.
- Use the Page setup (**File > Page Setup**) to set print parameters, such as paper size, source, orientation (portrait or landscape) and margin sizes. The actual Page Setup window displayed is that of the desktop operating system. An example Page Setup window is shown below.



Exit from the Desktop

Use the Exit function (**File > Exit**) to close the ACI desktop. This is different from the Log Out (Logoff) function, which doesn't close the desktop.


Note: You do not need to be logged on to exit. Also, if you exit without logging off, you will be logged off.

Display User Interface Framework Version Information

Access **Help > About** to display version information:



The version (Version 05.2) represents the calendar year and the quarter in which the version was released. For example, 05.2 means 2005, second quarter. Click **Versions** to display detailed version information as shown below:



Section 3

General Procedures

This section provides information useful for all desktop windows.

Topics:

[Hyperlinked Field Labels \(Names\)](#) (page 3-2)

[Selectable List Fields](#) (page 3-3)

[Window Toolbars and Pop-up Menus](#) (page 3-4)

[Tables](#) (page 3-5)


[Save Records](#) (page 3-7)

[Delete Records](#) (page 3-8)

Hyperlinked Field Labels (Names)

Each field is identified by a label (i.e., character string) that is commonly referred to as the field name. Some field labels are also links to other windows for situations where an desired option, such as a profile, is not available and needs to be configured.

In the example below, the field label [Security Group](#) is the field name for the selectable list located to the right of the label and is also a link to the User Security Group Configuration window.



Selectable List Fields

A selectable list field is identified by the down arrow, (▼), that when clicked displays a list of options. Some selectable list fields allow text entry. Such fields have a white background commonly used for text entry fields. In the example below, a new value can be entered or an existing value can be selected.

Interface Name	Select/Enter ▼
----------------	----------------

However, for the following field, text entry is not allowed.

Balance Information	Ledger and Avail... ▼
---------------------	-----------------------

Table Cell Exception

Selectable fields in table cells do not initially display the down arrow. In the table below, the column in which selectable list fields are provided is not initially apparent, all cells appear as text entry fields.

	Input/Receive	Output/Send	Logon Type	Outstanding Request Limit
	station_one	station_one	Combined Acquirer/Issuer	100
	station_two	station_two	Combined Acquirer/Issuer	100

However, the cells in the Logon Type column contain selectable fields as shown below. The down arrow is displayed when a user clicks in the cell.

	Input/Receive	Output/Send	Logon Type	Outstanding Request Limit
	station_one	station_one	Combined Acquirer/Issuer	100
	station_two	station_two	Combined Acquirer/Issuer ▼	100
			Acquirer only Issuer only Combined Acquirer/Issuer Separate Acquirer/Issuer	

Window Toolbars and Pop-up Menus

Each window provides buttons on a toolbar for quick access to the functions that a user can perform from the window. Tooltip help is available to describe the purpose of each button.


An example toolbar is shown below.



Use the grid () on the left of the toolbar to click and drag the toolbar. Moving the toolbar also converts the toolbar to a pop-up window as shown below.



In addition to the toolbars, right clicking in a window displays a pop-up menu of shortcuts to available functions.



Tables

Information displayed in a table is updated using the following functions:

- Insert Row ()
- Delete Row ()
- Select All Rows ()

New entries to a table require a new row (Insert Row function).

Select a Row

A selected row has a modified background, such as a highlighting background color. Non-selected rows have a white background. Rows are selected by clicking anywhere within the row. Multiple rows can be selected while holding down the **Ctrl** (Control) key. In the example below, station_two is selected, station_one is not selected.

	Input/Receive	Output/Send	Logon Type	Outstanding Request Limit
	station_one	station_one	Combined Acquirer/Issuer	100
	station_two	station_two	Combined Acquirer/Issuer	100

Select All Rows in a Table

To select all rows within a table, click on the Select All Rows button as illustrated below.

	Input/Receive	Output/Send	Logon Type	Outstanding Request Limit
	station_one	station_one	Combined Acquirer/Issuer	100
	station_two	station_two	Combined Acquirer/Issuer	100

The Select All Rows button

Undo Changes to a Table Row

To undo any changes made to a row, click the Undo button ().

Table Fields

A field within a table is identified by the column heading. Fields are either text entry, selectable lists, or contain check boxes. Selectable list and text entry fields appear the same though a default value can be shown. Note that a selectable list field within a table cell does not initially display the down arrow button, (), that indicates options are available. To display options in fields that contain selectable lists, click in the field. See the topic [Table Cell Exception](#) (page 3-3) for more information.

Select Table Fields

Table fields, like all fields, can be selected by positioning the cursor on the field and clicking. When a field within a table is selected, a user can navigate among the table fields using the **Tab** key.

For example, in the table below, the field in the selected row located within the Output/Send column has been selected (as indicated by the modified border). This field contains “station_two”.

	Input/Receive	Output/Send	Logon Type	Outstanding Request Limit
	station_one	station_one	Combined Acquirer/Issuer	100
	station_two	station_two	Combined Acquirer/Issuer	100

Pressing the **Tab** key moves focus to the next table field to the right, which is the field in the Logon Type column on the same row, as shown below.


	Input/Receive	Output/Send	Logon Type	Outstanding Request Limit
	station_one	station_one	Combined Acquirer/Issuer	100
	station_two	station_two	Combined Acquirer/Issuer ▼	100

If the last field on the last row is selected (in focus), pressing the **Tab** key moves focus to the first field on the first row of the same table.

Save Records

Click Save () to update the data source with the changes. Changes include saving an existing record as another record by changing the value in the key field. Key fields, which are located at the top of a window below the toolbar, are those used to display a record.

If the Confirm Updates option is selected on the General tab on the User Preferences window (**File > Preferences**), the desktop displays a confirm update prompt (shown below).



If any errors, such as an incorrect or missing value, are detected on a window during a save request, the desktop highlights the errors per the error notification preferences set on the Error Notification tab of the Preferences window.

Refresh

Use Refresh () to undo any unsaved changes that have been made to a record.

Clear/Reset


Use Clear/Reset () to revert to the default view of a window.

Delete Records

Use Delete () to delete a configuration (data source) record.

If only a row or selected rows on a table is to be deleted, use Delete Row ().

It is recommended that the Confirm Deletes option located on the General tab on the User Preferences window be selected. Using the Confirm Deletes option helps prevent accidental deletes because the desktop displays a confirm delete prompt before proceeding with the delete action.



Section 4

User Configuration

The ACI desktop provides access to an integrated user security environment in which each user must be defined in a user security database. This section provides an overview of user security and describes the procedures used for configuring users.

This section consists of two parts: an overview of user security and steps about how to add a user.


Topics:

- [User Security Overview](#) (page 4-2)
 - [User Security Configuration Hierarchy](#) (page 4-2)
 - [User Security Configuration Window Usage](#) (page 4-3)
 - [User Profiles](#) (page 4-4)
 - [Roles](#) (page 4-4)
 - [Permission Groups](#) (page 4-4)
 - [Permissions](#) (page 4-4)
 - [Field Filters](#) (page 4-5)
 - [Task IDs](#) (page 4-5)
 - [Passwords and Password Groups](#) (page 4-5)
 - [Security Groups](#) (page 4-6)
 - [Distributed Security Administration \(DSA\)](#) (page 4-7)
- [Steps to Add a User](#) (page 4-9)
 - [Step 1.0: Configure a Password Group](#) (page 4-10)
 - [Step 2.0: Configure a Security Group](#) (page 4-11)
 - [Step 3.0: Configure a User Role](#) (page 4-15)
 - [Step 4.0: Configure the User's Profile](#) (page 4-23)

User Security Overview


User Security Configuration Hierarchy

The illustration below shows the hierarchy of a user profile.



User Security Configuration Window Usage

The illustration below shows the hierarchy of a user profile and includes the name of the applicable window used to configure and manage user profiles:



User security windows, accessed at **Configure > User Security**, include:

- The **User Security Group Configuration** window for configuring security groups and password groups.
- The **User Security Profile Configuration** window for configuring and viewing information about a user, viewing a user's active sessions, assigning a security group to a user, changing and expiring a user's password, and assigning roles to a user.
- The **User Security Control Management** window for displaying active sessions, logging off selected users, and expiring passwords by password group.
- The **User Security Role Configuration** window for configuring roles, permission groups, permissions, and field filters.

User Profiles

Each user of the desktop is assigned a **user profile** consisting of the following configuration components:

- User ID — A unique character string used to identify a user.
- General user information — Name and contact information about a user.
- User status — Set by the user security server in response to some action, such as too many bad logon attempts, or by security administrative personnel.
- Role(s) — One or more sets of permission groups.
- Security group — A unique ID that defines a set common user security access restrictions.
- Password group — A unique ID that defines a set common user password restrictions.

Roles

A role defines the level of a user's access to the desktop. Each role identifies a job function, such as security administrator, system administrator, manager, and end user, and consists of one or more permission groups. Roles apply to users a set of permissions, tasks, and functions.

A role can contain one or more permission groups. A permission group can contain one or more permissions. Each permission is associated with a task (window application) and defines the functions (e.g., delete, save, send, and view) allowed for that task.

Permission Groups

A permission group is simply a collection of selected permissions that is assigned a unique identifier (the permission group ID) and a description of the purpose or use of the group. Permission groups are used to define a role.

Permissions

Permissions define specific access to a window. Each permission consists of a single task (by task ID), the functions that can be performed within the task, a unique ID (the permission ID), and a description of the purpose or use of the permission.

Field Filters

Field filters restrict a user's access to field values by defining either a single value, multiple values, or a range of values allowed when the filter is applied to the user's profile.

Task IDs

Each task consists of a unique identifier and a group of functions. Each task corresponds to a window on the ACI desktop. For example, the task ID **ProcessControl** can be used in a permission to define the level of access to the Process Control window.

The following line from the `UISecurityIDs.properties` file shows the string (ProcessControl), which is the Task ID, assigned to the corresponding property.

```
security.ui.taskID.PROCESS_CONTROL.text=ProcessControl
```

Passwords and Password Groups

A user's password is stored in the user security database in encrypted form using a Secure Hash Algorithm (SHA1) that is not reversible ensuring that passwords cannot be extracted in clear form from the database.

Password Restrictions

The following restrictions apply to all passwords:

- Characters cannot be repeated sequentially. For example, the string "ABBA" is not valid because of the repeating "B." However, "ABAB" is valid if the minimum length defined in the password group has been met.
- The password cannot be the same as the user ID. For example, a user with the ID "user02" cannot use "user02" as the password.
- A user's password must meet the requirements (discussed below) defined in the password group assigned to the user.

Password Group Requirements

Password groups consist of password requirements that are imposed on all user passwords assigned the group. A password group consists of the following password requirements as configured using the Password Groups tab on the User Security Group Configuration window. A password group is assigned to a user ID using security groups.

- The number of days prior to a password expiration on which the desktop displays a warning dialog prompting a user to change the password.
- The maximum number of days a user can use a password.
- The minimum password length.
- The maximum password length.
- The minimum number of numeric characters required in each password.
- The minimum number of alphabetic characters required in each password.
- The maximum number of old passwords retained for each user (users cannot use retained old passwords).
- The maximum number of password changes allowed during a 24-hour period.

Security Groups

Each user ID (i.e., user profile) must be assigned one and only one security group. However, since a security group can be assigned to multiple users, the security group simplifies the management of user security, assigns passwords by group, and assists in implementing distributed security administration, which is discussed later in this section.

Each user security group is identified by a unique ID and consists of the following common user security access restrictions that apply to all users assigned the security group:

- The time each day a user can log on to the desktop.
- The time each day a user must be logged off the desktop and, after which, can no longer log on to the desktop.
- The days of the week on which a user can log on to the desktop.
- The maximum number of invalid logon attempts allowed for each user. If this value is reached, the user's status is disabled by the user security server.

- The number of minutes, if set, after which the number of invalid logon attempts record is reset to zero.
- The maximum number of active sessions allowed for a user.
- The number of seconds of user inactivity after which the user is automatically logged off the desktop (this is called a **session timeout**).
- The number of seconds of terminal inactivity after which the desktop is disabled and any logged on user is logged off (**UI timeout**).
- The number of days a user's ID can be inactive (not used) after which the user ID status is disabled by the user security server.
- The password group ID defining password requirements applied to all users of the security group.

Distributed Security Administration (DSA)

Each installation is configured with a system administrator and security administrator. The system administrator has access to all applications of the desktop. The security administrator has access to the user security windows. Distributed security administration involves the security administrator configuring other, lower-level, administrators that are assigned a limited set of permissions.


Distributed security administration is enabled by setting the **OwnerIDSupport** property in the usec.cfg file to true.

DSA Setup

Distributed security is implemented by the top-level security administrator by configuring applicable roles, assigning these roles as necessary to security groups, and assigning the security groups to other, lower-level, system administrators.

The top-level security administrator can set up tiers of other system administrators who are limited to a **security domain**, which is a set containing a security group, password group, roles, and permissions as defined by a security role ID. At this level, a role ID is used to restrict users within the domain to a defined set of

permissions (including permission groups), tasks and filters. This methodology can be used to create system administrator groups and departments as shown in the illustration below.



For example, the system administrator assigned Role1 can create user profiles or groups of user profiles having roles that can contain only those permissions, permission groups, tasks, and filters defined for Role1.

With distributed security administration, users, including administrators, cannot access the users and roles of other security domains.

Steps to Add a User

Perform the steps below to add a user. Some steps have additional steps that might be required depending on the extent to which a complete user security system has been configured.


- ❑ [Step 1.0: Configure a Password Group](#) (page 4-10)
- ❑ [Step 2.0: Configure a Security Group](#) (page 4-11)
- ❑ [Step 3.0: Configure a User Role](#) (page 4-15)
 - [Step 3.1: Configure Field Filters](#) (page 4-16)
 - [Step 3.2: Configure Permissions](#) (page 4-19)
 - [Step 3.3: Configure Permission Groups](#) (page 4-21)
- ❑ [Step 4.0: Configure the User's Profile](#) (page 4-23)
 - [Step 4.1: Set the User's Status](#) (page 4-24)
 - [Step 4.2: Assign a Security Group](#) (page 4-24)
 - [Step 4.3: Enter Information about the User](#) (page 4-24)
 - [Step 4.4: Set the User's Password](#) (page 4-24)
 - [Step 4.5: Assign Roles](#) (page 4-26)

Usage Note: To ensure that your changes are implemented in the user security database, click Save () each time you have completed a step.

Tip: If you want to add a new user that is based on an existing user profile, that is, the password group, security group, and roles are already configured as necessary for the new user, go directly to step 4.0 and read the Tip provided in the step.

Step 1.0: Configure a Password Group

On the Password Group tab of the User Security Group Configuration window, enter a new password group name or select an existing password group name, enter the description and set the parameters for the password. See the topic [Passwords and Password Groups](#) (page 4-5) for more information.



The screenshot shows the 'ACI User Security Group Configuration' window with the 'Password Group' tab selected. The 'Password Group' field is set to 'pswd_grp_1'. The 'Description' field contains 'Default password group for end users.' The password requirements are configured as follows:

Parameter	Value
Minimum Length	6
Maximum Length	16
Required Numeric Characters	0
Required Alpha Characters	2
Lifetime Days	30
Old Password Cache	6
Expire Pre-Warn Days	7
Changes Per Day	6

A status bar at the bottom indicates: '0 - 4:18 PM > Password group retrieved.'

A password group must have a unique ID defined in the Password Group field. In the example above, the password **group pswd_grp_1** is shown. This group is described as the default password group for end users. The password requirements are set in the fields provided on the tab.

Password groups are assigned to users (their profiles) through security groups. Therefore, a password group must be assigned to a security group using the Security Group tab of the User Security Group Configuration window. The security group is then used in user profiles.

Step 2.0: Configure a Security Group

Topics in this step to consider:

- ❑ [UI and Session Timeout Considerations](#) (page 4-12)
- ❑ [System Administration Role Filter \(Owner ID\)](#) (page 4-14)

Use the Security Group tab on the User Security Group Configuration window to configure a security group.

The screenshot shows the 'ACI User Security Group Configuration' window with the 'Security Group' tab selected. The 'Security Group' dropdown is set to 'end_user_sec_grp' and the 'SysAdmin Profile' dropdown is empty. The 'Description' field contains 'Security group for end users.' The 'Password Group' dropdown is set to 'pswd_grp_1'. The 'Allowed Time and Days' section shows a 'Begin' time of 08:00 am and an 'End' time of 08:00 pm. The days of the week are listed with checkboxes: Sun (unchecked), Mon (checked), Tue (checked), Wed (checked), Thu (checked), Fri (checked), and Sat (unchecked). Below this, there are six configuration fields: 'Bad Logins Allowed' (11), 'Reset Bad Logins' (3000 seconds), 'Sessions Allowed' (10), 'UI Timeout' (18000 seconds), 'Inactive Days Allowed' (365), and 'Session Timeout' (36000 seconds). The status bar at the bottom indicates '7 - 10:59 AM > Password group retrieved.'

Existing security groups can be selected in the Security Group field or a new security group can be entered in the field. In the above example, the configuration for the **end_user_sec_grp** security group is shown. This group defines standard authentication requirements for users. The password group **pswd_grp_1** is assigned to this security group. As a result, the password requirements defined by **pswd_grp_1** apply to all users of this security group. Users assigned this security group cannot log on to the desktop before 8:00 am and must be logged off by 8:00 pm. Also, users cannot log on to the desktop on Sundays and Saturdays.

UI and Session Timeout Considerations

A security group defines both UI and session timeouts. These timeouts are defined in units of seconds using the Security Group tab of the User Security Group Configuration window. The two timeout types are discussed below and should be considered when configuring a security group.


A UI timeout occurs after a duration of desktop inactivity defined in the UI Timeout field. When a UI timeout event occurs, the user no longer has access to the desktop and any open windows; however, the user's session and the open windows are not closed. Additionally, the desktop displays the Verify Password dialog (shown below) in which the user must provide a valid password to restore access to the desktop and any open windows. The user also has the option to log out at this time.



UI timeouts only occur if the security group to which the user belongs has a configured UI timeout limit greater than zero. Entering a zero ('0') in the UI Timeout field implies no limit of desktop inactivity.

A session timeout occurs after a duration of desktop inactivity defined in the Session Timeout field. When a session timeout event occurs, the user is automatically logged off the desktop and the user must log on (open the Log In window and provide a valid user name and password combination) to obtain access to the desktop. Any windows open upon a session timeout are closed.

When the user's session times out, the desktop displays the following Session Logout message.



If the user's session expires while the Verify Password dialog is displayed and the user has not provided input, the user is still logged out and the user is no longer able to verify the password. All windows are closed, but the desktop remains open.

Session timeouts only occur if the security group to which the user belongs has a configured session timeout limit greater than zero. Entering a zero ('0') in the Session Timeout field implies no limit of desktop inactivity.

Note: If system administrators configuring a security group want to use UI timeouts in an effective manner, then the session timeout value must be greater in terms of minutes than the UI window timeout value. This is because if the session timeout value is less than the UI timeout value, users in the security group will be logged off the desktop (upon a session timeout event) prior to a UI timeout event.

System Administration Role Filter (Owner ID)

When the **OwnerIDSupport** property in the usec.cfg file is set to the true, the Security tab on the User Security Group Configuration window displays the SysAdmin Role Profile selectable field, as shown below.

ACI User Security Group Configuration

Security Group **Password Group**

Security Group: end_user_sec_grp SysAdmin Profile: []

Description: Security group for end users.

Password Group: pswd_grp_1

Allowed Time and Days

Begin: 08:00 am End: 08:00 pm

Sun Mon Tue Wed Thu Fri Sat

☐ ☒ ☒ ☒ ☒ ☒ ☐

Bad Logins Allowed: 11 Reset Bad Logins: 3000 seconds

Sessions Allowed: 10 UI Timeout: 18000 seconds

Inactive Days Allowed: 365 Session Timeout: 36000 seconds


7 - 10:59 AM > Password group retrieved.

An existing role ID can be assigned to a security group using the SysAdmin Role Profile field. Since a role defines a set of permissions (permission groups), tasks IDs and field filters, the role ID at this level limits access to permissions and permission groups that can be configured for users by administrators assigned the security group. To assign a role ID as a filter for a security group, select the role ID in the SysAdmin Profile field.

If a system administration role profile is selected for a security group, only those permission groups, permissions, and tasks defined for the role are accessible to users assigned the security group.

Step 3.0: Configure a User Role

To configure a user role, use the Roles tab on the User Security Role Configuration window.



If the available permission groups meet your needs, enter or select the role ID in the Role field, add or modify the description of the purpose of the role, and select the applicable permissions groups (permission groups can be selected (or deselected) using the check boxes for each group), then go to [Step 4.0: Configure the User's Profile](#) (page 4-23). **Note:** Permissions not defined within your security domain are not available.

If one or more permission groups need to be configured, you might also need to perform one or more of the following steps:

- ❑ [Step 3.1: Configure Field Filters](#) (page 4-16)
- ❑ [Step 3.2: Configure Permissions](#) (page 4-19)
- ❑ [Step 3.3: Configure Permission Groups](#) (page 4-21)

Step 3.1: Configure Field Filters

Field filters are configured using the Filters tab on the User Security Role Configuration window, which is shown below, and are applied to a user's profile through permissions.


The screenshot shows the 'ACI User Security Role Configuration' window with the 'Filters' tab selected. The window has a title bar with standard OS controls and a toolbar with icons for save, delete, and other actions. The 'Filters' tab is active, showing fields for 'Filter ID' (set to 'ExampleFilter') and 'Field ID' (set to 'InstitutionID'). Below these is a 'Description' text area. The 'Filter Type' section has three radio buttons: 'Range', 'Single Value', and 'Multi-Value' (which is selected). To the right of the radio buttons is an 'Add Value' button. The 'Filter Settings' section contains two list boxes: 'All Field Values' (with values 1000, 1005, 1006, 1009, 1010) and 'Selected Field Values' (which is empty). Between the list boxes are four arrow buttons for moving values between them. At the bottom, a status bar shows '0 - 2:09 PM > Filter read.'

Field filters consist of the following elements:

- ❑ Unique identification (the Filter ID field).
- ❑ Field ID, which can be selected, but not entered, in the Field ID field.
- ❑ A description of the purpose and use of the filter (Description field).
- ❑ One or more field values, which can be a single value, multiple values, or a range of values. Field values are defined by filter type and selected in the Filter Settings areas of the tab. This is explained in detail on the next page.


The format of the Filter Settings area is dependent upon the filter type selected, whether Range, Single Value, or Multi-Value.

If **Range** is selected, begin and end values must be entered:



The screenshot shows a 'Filter Type' section with three radio buttons: 'Range' (selected), 'Single Value', and 'Multi-Value'. Below this is a 'Filter Settings' section containing two text input fields labeled 'Begin Value' and 'End Value'.

If **Single Value** is selected, a single filter value must be selected or entered:



The screenshot shows a 'Filter Type' section with three radio buttons: 'Range', 'Single Value' (selected), and 'Multi-Value'. Below this is a 'Filter Settings' section containing a single text input field labeled 'Filter Value' with the value '1000' entered and a dropdown arrow on the right.

The values available in the Filter Value field are those that have been configured using the applicable configuration window. For example, for the InstitutionID field ID, the values shown in the Filter Settings area are those institution IDs that have been configured using the Institution Configuration window.

Tip: Use the asterisk (“*”) to select all current and future field values.

If **Multi-Value** is selected, values must be selected and moved from the All Field Values field to the Selected Field Values field.

To add or remove field values, use the following buttons provided on the tab to perform the desired task:

Button	Task
	Add the selected field value(s) from the All Field Values field to the Selected Field Values field.
	Add all available field values from the All Field Values field to the Selected Field Values field.
	Remove the selected field(s) value from Selected Field Values field back to the All Field Values field.
	Remove all field values from Selected Field Values field back to the All Field Values field.

The values shown in the All Field Values field are those that have been configured using the applicable configuration window. Use the asterisk (“*”) to select all current and future field values. For example, for the InstitutionID field ID, the values shown in the Filter Settings area are those institution IDs that have been configured using the Institution Configuration window.

To add a value not available in the All Field Values field, enter the value in the text entry field to the right of the Filter Type area and click the Add Value button.

Step 3.2: Configure Permissions

Use the Permissions tab on the User Security Role Configuration window, shown below, to create permissions and permission group IDs.

The screenshot shows the 'ACI User Security Role Configuration' window with the 'Permissions' tab selected. The window has a title bar with standard icons and a toolbar with icons for saving, deleting, and other actions. Below the toolbar are four tabs: 'Roles', 'Permission Groups', 'Permissions' (selected), and 'Filters'. The main area contains the following fields and controls:

- Permission ID:** A dropdown menu with 'FullProcessControl' selected.
- Task ID:** A dropdown menu with 'ProcessControl' selected.
- Description:** A text box containing 'Full Process Control permission set.'
- Functions:** A list of functions with checkboxes:
 - ☒ Functions
 - ☒ Send
 - ☒ View
- Filter Description:** A text box containing 'Filter info'.

At the bottom of the window, a status bar displays the text '12 - 11:22 PM > Permission read.'

Permission IDs

A new permission ID can be created (entered) or an existing permission ID can be selected. Permissions are available on the Permissions Group tab for selection when configuring a permission group.

The description should reflect the purpose of the permission and any special information.

Tasks IDs


Each task ID corresponds to an ACI desktop window. You cannot create task IDs using the ACI desktop.

Functions

The functions that a user can perform on a window (task) are defined for each permission on the Permissions tab. A function is selected by entering a check mark in the functions check box. Functions include, but are not limited to, Delete, Save, Send, and View. Functions vary by task ID. For example, the ProcessControl task does not require Delete and Save functions.

Field Filters

If a task ID refers to a window that contains a field or fields that are filterable, the Permissions tab will list the field ID(s) and provide a selectable list of filter IDs that can be selected and applied to the permission. To select field filters (filter IDs), use the Permissions tab on the User Security Role Configuration window, which is shown below.




If the window for a selected task ID contains a field for which one or more predefined field IDs exist, the field ID(s) are shown on the Permissions tab.

Step 3.3: Configure Permission Groups

To configure a new or existing permission group, use the Permission Groups tab on the User Security Role Configuration window. This tab provides a Permission Group field in which a new permission group ID can be entered or an existing permission group can be selected.


Available permissions, as defined per your security domain, are provided on the tab. Permissions are added or removed from a permission group by selecting (entering a check mark) or deselecting (removing a check mark) in the appropriate checkbox.



Permission Information

A description of each permission along with the Task ID assigned to the permission and the allowed functions can be displayed in the Permission Description section of the Permissions Groups tab. To display this information, right click on the desired permission and select Get Info on the pop-up menu. In

the example above, the permission FullProcessControl has been selected and information obtained using the Get Info function is displayed in the Permission Description section.



Step 4.0: Configure the User's Profile

To configure a new user (user profile), display the General tab of the User Security Profile Configuration window, enter the user's unique ID in the User ID field and perform the following steps:

- ❑ Set the user's status
- ❑ Assign a security group
- ❑ Enter information about the user
- ❑ Set the user's password
- ❑ Assign roles to the user

Tip: To add a new user who's profile is based on an existing user profile, display the user profile that you want to use as a template, enter the new user ID and proceed.

Note: When you click Save for a new user, the desktop displays the New User's Password window, which is described in Step 4.4.

Step 4.1: Set the User's Status

User status options:

Active	= Open and active.
Closed/Admin	= Closed without incident.
Closed/Inactive	= Closed, by the User Security server, due to inactivity.
Disabled/Admin	= Disabled, for security reasons, by authorized personnel.
Disabled/System	= Disabled, for security reasons, by the User Security server (e.g., maximum number of log on attempts has been reached).
Temporary	= User can access the desktop for a predefined amount of time.

Step 4.2: Assign a Security Group

Security groups are provided in the selectable field next to the Security Group link. If a desired security group is not available, click on the link to access the User Security Group Configuration window to review existing security groups or configure a new security group. Only those security groups defined for your security domain are available.

Step 4.3: Enter Information about the User

Information about the user includes:

- ❑ Complete name information
- ❑ Contact information, such as phones, Fax and email address
- ❑ Employment information, such as department, manager and location

Step 4.4: Set the User's Password

To set a new user's password, click Save, after which the desktop displays the New User's Password window.


Note: The Password tab of the User Security Profile Configuration window is used for management of existing users, see section 5 for more information.

For users assigned a status other than Temporary, the desktop displays the version of the New User's Password window shown below. Indicate whether the user must change the assigned password during the next logon (or first logon for a new user), and the start date on which the user can logon to the desktop.



The screenshot shows a dialog box titled "ACI New User's Password". It contains two password input fields labeled "New Password" and "Verify Password", both filled with asterisks. Below these is a checkbox labeled "Require password change" which is checked. Underneath is a section titled "New User Start" with a date picker showing "Monday, March 15, 2004". At the bottom are "Ok" and "Cancel" buttons.

When a new temporary user (i.e., user status being set to temporary) is created, the desktop displays the New User's Password window with the option to select the date the temporary user's access to the desktop expires as shown below.



The screenshot shows a dialog box titled "ACI New User's Password". It contains two empty password input fields labeled "New Password" and "Verify Password". Below these is a checkbox labeled "Require password change" which is unchecked. Underneath is a section titled "New User Start" with a date picker showing "Wednesday, March 31, 2004". Below that is a section titled "New User Expire" with a date picker also showing "Wednesday, March 31, 2004". At the bottom are "Ok" and "Cancel" buttons.

Step 4.5: Assign Roles

Use the Roles tab on the User Security Profile window to assign (and remove) the roles defined for a user.



This tab displays all the user roles available within your security domain on the ACI desktop. Roles not defined within your security domain are not displayed. User roles assigned to a user are shown in the User Roles field. Available user roles not assigned to a user are shown in the All Roles field.

To add or remove user roles from a user profile, select the role or roles and use the buttons provided on the tab to perform the desired task. The buttons are:

Button	Task
	Add the selected role(s) to the user profile (move from the All Roles field to the User Roles field).
	Add all available roles to the user profile (move from the All Roles field to the User Roles field).
	Remove the selected role(s) from the user profile (move from the User Roles field to the All Roles field).

Button	Task
	Remove all assigned roles from the user profile (move from the User Roles field to the All Roles field).

To select a role, click on the role. Selected roles have a modified background color. To select multiple roles, press down the **Ctrl** key while selecting roles.

If a particular role is not available or an existing role needs to be changed, click on the Configure Roles link to access the User Security Role Configuration window to configure a new or existing role.

Note: A user cannot change the role configuration for the profile (User ID) that was used to log on. In such situations, when the Roles tab is accessed for that User ID, the All Roles field and User Roles fields are inactive.

ACI Worldwide Inc.

Section 5

User Management

A system administrator can set the status, display and terminate active sessions, and expire passwords by password group of users within the administrator's security domain. This activity is performed from the user security windows as described in this section.

Topics:

[User Security Configuration Window Usage](#) (page 5-2)

[Set the Status of a User](#) (page 5-3)

[Display Active User Sessions](#) (page 5-4)

[Terminate Active User Sessions \(Log off a User\)](#) (page 5-6)

[Display Password History for a User](#) (page 5-7)

[Change a User's Password](#) (page 5-7)


[Expire a User's Password](#) (page 5-7)

[Expire Passwords by Password Group](#) (page 5-8)

See section 4 for information about security domains and distributed security administration (DSA).

User Security Configuration Window Usage

The illustration below shows the hierarchy of a user profile and includes the name of the applicable window used to configure and manage user profiles.



This section discusses using the User Security Profile Configuration and User Security Control Management windows for the management of existing user. See section 4 for information about adding a user.

Set the Status of a User

The user security server maintains a status for each user. A user's status can be changed by the user security server if security and password group requirements have been violated. A user's status can also be changed by authorized users.

Use the General tab on the User Security Profile Configuration window to view and set a user's status.

ACI User Security Profile Configuration

User ID:

General | Active Sessions | Password | Roles

User Status: **Active** (dropdown menu open showing: Active, Closed/Admin, Closed/Inactive, Disabled/Admin, Disabled/System, Temporary)

Security Group:

First Name:

Middle Name:

Last Name:

Department:

Location:

Manager:

Email:

Work Phone:

Mobile Phone:

Fax:

Create Time:

Last Login:

Last Failed Login:

Bad Login Tries:

3 - 11:27 AM > User info loaded.

Authorized users can assign the following status codes to a user:

Active	= Open and active.
Closed/Admin	= Closed without incident.
Closed/Inactive	= Closed, by the User Security server, due to inactivity.
Disabled/Admin	= Disabled, for security reasons, by authorized personnel.
Disabled/System	= Disabled, for security reasons, by the User Security server (e.g., maximum number of log on attempts has been reached).
Temporary	= User can access the desktop for a predefined amount of time.


Display Active User Sessions

When a user has logged on to the desktop by providing a valid user ID and password, the user security server creates an active session for the user. An active session contains the following information:


- ❑ The user's ID.
- ❑ The unique session number assigned by the User Security server.
- ❑ The workstation ID, such as a network ID or URL, from which the user has logged on to the desktop.
- ❑ The date and time the user began the session.
- ❑ The date and time the current session expires.

Information about active user sessions is available on two separate Active Sessions tabs. One tab is provided on the User Security Profile Configuration window and displays the active sessions for a selected user. The other Active Sessions tab is located on the User Security Control Management window and displays active user sessions for all users within a security administrator's security domain (security group to which the administrator has access).

Active User Session for a Selected User





Active User Sessions for All Users



Note: The active sessions of the application can change at any time; therefore, to update the list of active sessions click Refresh ().

Terminate Active User Sessions (Log off a User)


One or more active user sessions can be terminated (i.e., logged off) from either one of the two windows that are used to display active user sessions — the User Security Profile Configuration window and the User Security Control Management window. To log off one or more user sessions, display and select the user session(s) and click Logout Selected.



In the examples above, the user ID end_user has been selected as indicated by the modified background color. Clicking Logout Selected logs this user off the desktop.

Display Password History for a User

Authorized users can view a user's password change history, add or change a the user's password, and expire the user's current password by accessing the Password tab on the User Security Profile window and selecting the user's ID.



Change a User's Password

To change a user's password, display the Password tab on the User Security Profile Configuration window and select the user ID. Enter the new password in both the New Password and Verify Password text boxes and click Save (). If the change is successful, a confirmation message appears in the status pane of the window. Otherwise, an appropriate error message is displayed.


Expire a User's Password

To expire a user's password, display the Password tab on the User Security Profile Configuration window, select the user ID, and click Expire Password. If a user's password has been expired but a new password has not been defined, the user is prompted to create a new password on the next logon attempt.

Expire Passwords by Password Group

Authorized users can access a table that shows the passwords groups that have been assigned to security groups, and can expire all user passwords of users assigned to a password group.

Use the Password Maintenance tab on the User Security Control Management window to view password group usage and expire password groups.



In the example above, the password group named **pswd_grp_1** is used within the **end_user_sec_grp** security group. This row has been selected, as shown by the modified background color. Clicking the Expire Selected button disables the passwords for all users assigned to the **end_user_sec_grp** security group.

Section 6

User Audit

User audit is the logging of user activity to a data source for the purpose of reporting and monitoring the user activity.

Topics:

[User Audit Processing Overview](#) (page 6-2)

[Internal XML Audit Message Format](#) (page 6-3)

[User Audit Activity Reports](#) (page 6-4)

User Audit Processing Overview

Whenever a user of the desktop initiates and completes an activity (e.g., logon, logoff, password changes, delete, or save) from a window, a message that contains information about the user activity is written to the User Audit Log data source.

The audit message sent to the log data source can be one of the following:

- Header information only about the change
- Header information as well as detail information about the before and after images of the affected record

The application server writes this message directly to the USRAULOG data source (UALOGD) or to the Audit Store-and-Forward data source (ASAFD).

For information about enabling user auditing and setting the audit level for a desktop window, refer to the ***ACI Java Server Framework Reference Guide***.

Internal XML Audit Message Format

The information stored in the USRAULOG data source is in XML format. The following example is an XML-formatted message containing user activity information.


```
<?xml version="1.0" encoding="UTF-8" ?>
<AuditReport>
  <AuditDetails row="0">
    <Audit_LoggingRq>
      <Timestamp>TimeStamp Info</Timestamp>
      <ContextDescr>InsertRq</ContextDescr>
      <Ticket>
        <UserID>User Profile ID</UserID>
        <SessionNumber>1</SessionNumber>
        <TerminalID>OMAUUSER/ip_addr</TerminalID>
      </Ticket>
      <ActivityGroup>
        <ActivityType>Table Function</ActivityType>
        <TableGroup>
          <TableName>Table</TableName>
          <KeyGroup>
            <Column>
              <ColumnName>Table Element</ColumnName>
              <BeforeValue />
              <AfterValue>New Value</AfterValue>
            </Column>
            <Key>
              <KeyColumn>
                <ColumnName>Key</ColumnName>
                <AfterValue>New Value</AfterValue>
              </KeyColumn>
            </Key>
          </KeyGroup>
        </TableGroup>
      </ActivityGroup>
    </Audit_LoggingRq>
  </AuditDetails>
</AuditReport>
```

The root element of the XML message is <AuditReport> that includes one or more <AuditDetails></AuditDetails> sections. <AuditDetails> contains important information: a time stamp (<Timestamp>), Context information (<ContextDescr>), ticket information (<Ticket>), and activity information (<ActivityGroup>). Information related to the user and the user's session is included in the ticket. Information about the activity performed and the data source (table) affected is included in the activity group.

Note: Use an XML reporting tool such as XML Spy, MS-Access 2002, or Crystal Reports to evaluate and format the XML information as well as to generate reports.

User Audit Activity Reports

Activity reports for selected users can be initiated from the Audit Extract window (**Tools > Audit Extract**) and sent to a specified file in XML format. User activity is extracted from the User Audit Log data source (USRAULOG) for a specified user ID between a start date and time and an end date and time.



The reports provide the following information:

- Date and time of action.
- User ID performing the action.
- Terminal location from which action was performed.
- Type of action performed.
- File and field name affected by the action, if applicable.
- Before and after image of data modification action, if full auditing is set.

The name of the report to be generated is entered in the Extract File Name field on the window. The location where the file is saved is specified by the **REPORT. USERAUDITLOG.LOC** environment attribute, which contains the directory location. Use the Application Configuration window (**System Operations > Server Management > Application**) to define the value of the **REPORT. USERAUDITLOG.LOC** attribute.

Section 7

Contingency SAF Processing

BASE24-es supports contingency process planning by providing for a means to configure the sending of selected data to remote data sources. This backup data can be accessed in the event of data loss on the primary BASE24-es system.

In BASE24-es, contingency support is a store-and-forward (SAF) process that is configured and controlled using various windows available on the desktop.

Topics:

[Configure Contingency Processing](#) (page 7-2)

[Process Limits](#) (page 7-2)

[Process Status](#) (page 7-3)

[Contingency Station Name](#) (page 7-3)


[Enable and Disable Contingency Processing](#) (page 7-4)

Configure Contingency Processing

The sending of SAF messages using a contingency interface must be configured in order to establish processing parameters. These parameters include:

- Processing limits
- Station through which contingency messages are sent

Use the Contingency Store and Forward Configuration window (**System Operations > Contingency SAF**) to configure limits and timeout values for the contingency interface.



Process Limits

Processing limits control the forwarding of SAF messages to the destination BASE24-es system. These limits prevent processing delays on the application server.

When a SAF message is sent by an application server to the destination BASE24-es system, the application server first checks the number of outstanding messages that are waiting for a response from the destination. If the number is less than the limit defined in the Outstanding Messages Limit field, the application server proceeds with the forwarding of SAF messages.

BASE24-es also requires that the destination responds to a request within a certain amount of time. If a response is not received within this time period (response time limit), the application server either attempts to send the transaction again or logs the transaction, depending on whether the maximum number of retries, which is defined in the Retries Limit field, has been met. The response time limit is set in the Timer Limit (seconds) field.

If a message that failed is to be sent again, the application server waits a number of seconds before attempting to resend - assuming the maximum number of retries defined in the Retry field has not been reached. This amount of time the application server waits to resend is set in the Retry Delay after Message Failure (sec) field.

Process Status

Whether contingency processing is enabled is indicated in the Processing Status field. If enabled, the field displays “Enabled”; otherwise, “Disabled” is displayed.

Contingency processing is enabled and disabled by setting the **UI_CNTNGY_LEVEL** environment attribute using the Process Control window as discussed on the following page.


Contingency Station Name

Each station through which contingency SAF messages are to be sent and received is identified by a symbolic name representative of the platform on which BASE24-es is operating. The station name must be entered in the Contingency Station Name field.

Enable and Disable Contingency Processing

Contingency processing is set using the **UI_CNTNGY_LEVEL** environment attribute.

1. Access the Environment Configuration window and set the environment attribute **UI_CNTNGY_LEVEL** to one of the following values:
 - ▣ 0 = Disable contingency processing
 - ▣ 1 = Enable contingency processing
2. Update the Environment external memory table to the changed value. Do this by sending a command from the Process Control window. Access the window, set the fields to the appropriate values shown below and click Submit ().



Section 8

Version Checker Server

The desktop provides a way for clients to keep their desktop configuration (Java Archive Repository files) current. This configuration support is provided by the Version Checker server.

Topics:

[Version Checker Overview](#) (page 8-2)

[Version Checker Client Window](#) (page 8-3)

[Automatic JAR File Update](#) (page 8-6)

Version Checker Overview

The Version Checker server is a utility that manages the versions of Java Archive Repository (JAR) files of desktop components. This server automatically runs during startup of the desktop at which time it compares the current version of the client JAR files (configuration) to current published versions (new versions), which reside in a predetermined location (i.e., repository). The location of the Version Checker server repository is defined during installation. New JAR files that are to be distributed to clients are placed in this location.

Run the Version Checker Server

The Version Checker server automatically runs when desktops are started due to commands located in the **RunDesktop.bat** file. Desktop shortcuts specified during installation point to this batch file.


Prompt or Automatic Download

The Version Checker server either displays in a window prompt (Version Checker Client window) the JAR files that need to be downloaded or it automatically downloads required JAR files. Whether prompting a user for downloading or automatically downloading is performed by the Version Checker server is dependent upon configuration settings as discussed later in this section.

Version Checker Client Window

The JAR files on the repository for which the version differs from that of the client are displayed in the Version Checker Client window. This window provides a list of the JAR files along with the version number of each JAR file on the repository and the version number of the JAR file on the client. If automatic JAR file updating is enabled (discussed later in this section), then this window is not displayed.

To download JAR files from the repository, select the applicable JAR files and click Update. This update process can be skipped or canceled by clicking the appropriate button on the window.




Select All

The Select All option can be used to select all listed JAR files on the Version Checker Client window. Individual JAR files can be selected by deselecting the Select All option and then clicking in the row or rows for the desired JAR files to download. Only selected JAR files are downloaded.


Close When Done Option

If the Close When Done option is selected, the Version Checker Client window is automatically closed after completion of the download of all selected JAR files. If this option is not selected, then the window is modified, as shown below, for user verification that the download has completed successfully. Click Done to acknowledge the download and to close the window.



Mirror the Repository

Mirroring the repository is similar to updating a client's desktop configuration with new JAR files (updated versions). With simple updating, it is possible for an old jar that no longer exists in the repository to remain on the client; however, by selecting Mirror Repository on the Version Checker Client window, verification is initiated to ensure that no jars reside on the client that are not also on the server repository. That is, any JAR files that exist on the client that do not exist on the current version of the server repository are deleted from the client.



Note: The option to mirror the server repository is only available if the system property **_DMirrorServer** is set to true.

Automatic JAR File Update

The Version Checker server can be configured to download updated and new JAR files automatically. This automatic JAR file updating (called VC quiet mode) is an option presented during installation of the ACI desktop.

Including the parameter “-Q” in the Version Checker server command line located in the **RunDesktop.bat** file enables automatic JAR file updating. Note that the “-Q” is added by BASE24-es during installation when the VC quiet mode option is selected.

For example:

```
call "T:\ESUI\__ES_04.1_NSK\VersionChecker\verChk" -Q
```

Section 9

Online Help

The desktop includes online help that provides information related to windows (screens) and window components (e.g., fields and buttons). Online help is provided in JavaHelp format, which is a Java-based HTML browser that provides structured access to help content.

Topics:

[Access to JavaHelp from the ACI Desktop](#) (page 9-2)

[JavaHelp Viewer Overview](#) (page 9-3)

[JavaHelp File Types](#) (page 9-4)

[JavaHelp Packages for BASE24-es and Payments Manager](#) (page 9-5)

[How Context is Implemented in JavaHelp](#) (page 9-6)

[Search the Helpset for a Text String](#) (page 9-8)

[Custom Online Help](#) (page 9-9)

[Customization of HTML Content Files](#) (page 9-10)

[Change the Display of Content](#) (page 9-11)

[Install JavaHelp for Stand-alone Use](#) (page 9-12)

Access to JavaHelp from the ACI Desktop


JavaHelp can be accessed with or without context.

Accessing JavaHelp with context displays the JavaHelp viewer with content specific to a window or window component, such as the opened window or a field located on the window. To display context help open the Help Pointer by selected **Help > Context Help** on the Menu Bar or clicking  on the toolbar. Use the Help Pointer to click on the window component for which help content is desired. If a window is not open, the Help Pointer is not available. Also, context help can be displayed by placing the cursor in a field and pressing the **F1** key.

To access online help without context (this opens the online help with the home page shown in the content area), select **Help > Help Topics** from the Menu Bar or click () on the toolbar.

JavaHelp Viewer Overview

JavaHelp content is displayed in the JavaHelp viewer, which is an HTML browser specifically designed to function with Java-based applications. This viewer is divided into three distinct panes and a title bar as shown below.



Note: The text shown in the navigation tree is an example and varies from installed JavaHelp versions.

- The **Title Bar** displays the name of the helpset.
- The **Toolbar** provides various menu and button functions.
- The **Navigation Pane** provides Contents and Index tabs useful for navigation to desired help content, and a Search tab for searching content.
- The **Content Pane** displays help content.

JavaHelp File Types

The following files together are referred to as a JavaHelp helpset:

- HTML files in which actual help content resides. The content provided by an HTML file is presented in the Content Pane of the JavaHelp viewer.
- Cascading Style Sheets (CSS) that define the display style of the help content.
- The XML map file, which is identified by the .jhm file extension, that defines the identifiers (map IDs) that correspond windows and window components to the file paths (or URLs) of HTML content files.
- The XML table of contents file that defines and structures the entries in the table of contents tab located in Navigation Pane of the JavaHelp viewer.
- The XML index file that defines and structures the content of the entries in the index tab located in the Navigation Pane of the JavaHelp viewer.
- The helpset file, which is identified by the .hs file extension, that defines the name of the helpset, JavaHelp components used, the name of the XML map file and the names of the XML files for the table of contents and index.
- The images displayed within HTML content files. These are usually in Graphical Interchange Format (GIF) and Joint Photographic Experts Group (JPEG or JPG) formats.

JavaHelp Packages for BASE24-es and Payments Manager

BASE24-es online help is packaged and distributed in the three Java archive files (JAR) each providing unique help as described below.

- The BASE24-es helpset JAR (**ACI_Help_es.jar**) includes the following JavaHelp configuration files for user security help:
 - ❑ ACI_Help.hs
 - ❑ ACI_Help_es.jhm
 - ❑ ACI_Help_esTOC.xml
 - ❑ ACI_Help_esIX.xml
 - ❑ HTML content files (.htm) for BASE24-es
- The TSS helpset JAR (**ACI_Help_tss.jar**) provides the following JavaHelp configuration files to define help for Transaction Security Services windows:
 - ❑ ACI_Help.hs
 - ❑ ACI_Help_tss.jhm
 - ❑ ACI_Help_tssTOC.xml
 - ❑ ACI_Help_tssIX.xml
 - ❑ HTML content files (.htm) for Transaction Security Services help
- Payments Manager JavaHelp is packaged in the **ACI_Help_pm.jar**. This JAR file provides the following JavaHelp configuration files to define help for Payments Manager Java interface applications:
 - ❑ ACI_Help.hs
 - ❑ ACI_Help_pm.jhm
 - ❑ ACI_Help_pmTOC.xml
 - ❑ ACI_Help_pmIX.xml
 - ❑ HTML content files (.htm) for Payments Manager help

How Context is Implemented in JavaHelp

Help context is implemented in JavaHelp by the use of Map IDs. Each map ID appears in the following files:

- The properties file for a window (desktop application)
Note: Most application windows have their own properties file. Also, some properties common among all windows are located in common properties files that are shared among the window properties files.
- The JavaHelp map file (.jhm extension)
- Either or both the XML table of contents file and XML index file (.xml extension)

Map IDs in Window Properties Files

An excerpt from the Authorization Script Configuration window properties file is shown below. This sample shows two properties: **helpID** (lines 04 and 10-18)) and **helpset** (line 05).

Each helpID value is also a map ID in the JavaHelp map file. JavaHelp uses the helpID value (i.e., map ID) to locate and display the appropriate content file for context help. (The helpset property defines the helpset file from the CommonUI properties file that is shared among properties files.)

```
01 ##
02 # Help
03 #
04 AuthScript.helpID=w_authorization_script_configuration
05 AuthScript.helpset={LINK}CommonUI:Common.helpset
06
07 #
08 #Help Topics
09 #
10 AuthScript.AuthName.helpID =f_authorization_name
11 AuthScript.MsgType.helpID =f_message_type
12 AuthScript.AuthScriptName.helpID =f_script_name
13 AuthScript.ScriptEnabledFlag.helpID =f_script_enable_flag
14 AuthScript.MonitorScriptFlag.helpID =f_monitor_enable_flag
15 AuthScript.approvedThresholdLimit.helpID =f_approval_threshold
16 AuthScript.denyThresholdLimit.helpID =f_denial_threshold
17 AuthScript.referThresholdLimit.helpID =f_referral_threshold
18 AuthScript.minScriptTXNCount.helpID=f_minimum_transaction_count
```

Map IDs in JavaHelp Map File (.jhm)

For example, the helpID named **f_authorization_name** on line 10 is mapped to an HTML file within the XML map (.jhm) file as follows:

```
<mapID target="f_authorization_name"
      url="f_authorization_name.htm"/>
<mapID target="w_authorization_script_configuration"
      url="w_authorization_script_configuration.htm"/>
```

Therefore, accessing context help for the Authorization Name field of the Authorization Script Configuration window displays the JavaHelp viewer with the content from the `f_authorization_name.htm` file displayed in the Content Area.

Map IDs in XML Table of Contents and Index Files

For help content accessed from the Contents or Index tabs of the JavaHelp Navigation Pane (i.e., accessing help without context), appropriate entries must appear in the XML table of contents or index files.

For example, window help is accessible from the Contents tab for the desktop online help. The window entries listed in the Contents tab are defined in the XML table of contents file. Continuing with the example properties file on the previous page, the map ID **w_authorization_script_configuration** on line 04 appears in the XML table of contents file as follows:

```
<tocitem target="w_authorization_script_configuration"
      text="Authorization Script Configuration Window" />
```

The target attribute in the line above specifies the map ID (the helpID property value in the window properties file). The text attribute specifies the text string that appears in the Contents tab. If this text string is clicked while displayed in the Contents tab, JavaHelp opens the HTML content file associated with the map ID (as defined in the XML map file).

Below is a line for an index entry for the Authorization Name field.

```
<indexitem text="Authorization Name Field"
      target="f_authorization_name" />
```


Note: By convention, mapIDs and HTML file base names in the desktop JavaHelp are the same (e.g., `w_authorization_script_configuration` mapID is mapped to `w_authorization_script_configuration.htm`). However, this is convention is not necessary, but is used for assisting the management of JavaHelp files and helpIDs.

Search the Helpset for a Text String

The Search tab provides a text entry field (Find) to locate up to 100 occurrences of a text string within a helpset.

Note: Search is not case sensitive.

Enter the text string in the Find text entry field and press the **Enter** key. JavaHelp searches through the helpset and displays a list of topics in which the text string is found. This list is displayed in the Navigation Area by topic title and in descending order of number of matches. Select the desired topic to display the topic's content in the Content area.



Custom Online Help

Online help can be modified in a number of different ways depending on the level of modification desired.

- Content files can be modified for localization purposes.
- Cascading Style Sheets can be modified to change display formats.
- Images referenced in content files can be edited.

Note: Modifying the JavaHelp configuration files can adversely affect the performance of JavaHelp and is not discussed in this manual.

Customization and Localization Considerations

If an installed version of JavaHelp is customized (or localized), care must be taken to avoid overwriting the customized JavaHelp files when accepting an updated help JAR file for placement on the Version Checker server repository. Therefore, the following guidelines can be used to establish procedures for maintaining and protecting customized JavaHelp:

- Always keep a backup of customized files.
- Consider appending an identifier (e.g., “custom”) to the name of customized files. If a help file name is changed, the change must also be made to the XML map file (.jhm file). For example, if the `f_authorization_name.htm` file is customized and renamed to `f_authorization_name_custom.htm`. The `url` attribute in the JavaHelp map file must be changed as follows:

From:

```
<mapID target="f_authorization_name"
      url="f_authorization_name.htm"/>
```

To:

```
<mapID target="f_authorization_name"
      url="f_authorization_name_custom.htm"/>
```

- Another option is to place the customized file in a separate directory as follows:

```
<mapID target="f_authorization_name"
      url="custom/f_authorization_name.htm"/>
```

Customization of HTML Content Files

All content files within the JavaHelp JAR files are in compliance with the W3C HTML revision 3.2 format. This format is required for content files to display properly within the JavaHelp viewer. Certain parts of the HTML revision 4.0 format can be used since it shares most markup tag elements with 3.2; however, care should be taken when implementing revision 4.0 features into content files destined for JavaHelp because certain revision 4.0 features, such as new tags and attributes, may not be supported. To ensure proper behavior of content files in JavaHelp, always test the display characteristics of HTML files in JavaHelp before releasing the help files.

One advantage of the content files being in HTML format is that common editors can be used to modify help content. The specifics of editing HTML files are not discussed here since these depend on the editor used. However, the following general guidelines apply:

1. Before an HTML content file within a JAR file can be edited, the file must be extracted to a working location using a tool, such as WinZip. The extracted HTML file is a copy of the original file. Make a backup of the original file and place in documented directory for later retrieval. All editing should be done on the extracted copy.
2. Select an appropriate HTML editor. Note that some HTML editors add embedded objects, extensive (revision 4.0) styling, and XML tags to HTML code. Such objects can adversely affect the display of content within JavaHelp. As a result, editors that do not automatically add objects are recommended, such as Macromedia's Dreamweaver and any ASCII editor.
3. After the file has been edited and saved to the working location, the modified file must then be added to the applicable JAR file replacing the original file. Keep the file extension the same as the original.
4. If the HTML file name is changed, the JavaHelp map file needs to be updated to reflect the name change.

Change the Display of Content

The characteristics of the content displayed in the JavaHelp viewer can be modified by altering the style properties of the appropriate cascading style sheet file. The name of the style sheet used for any particular JavaHelp installation can vary, but all use the .css file extension. Though the name can vary, the style sheet used is consistent within a helpset. To locate the .css file name, open an HTML content file in an editor and look for the <link> tag in the <head> section of the HTML page. The href attribute in the <link> tag specifies the path to and name of the .css file. For example, the name of the style sheet below is df_screen.css and is located a Templates folder relative to the HTML file:

```
<link rel="StyleSheet" href="Templates/df_screen.css" type="text/css"
      media="screen">
```

All cascading style sheets are located in the Templates folder within the BASE24-es specific JAR file, either ACI_Help_es.jar, ACI_Help_tss.jar and ACI_Help_pm.jar.

Note: To ensure proper functioning of JavaHelp, always test before releasing the modified CSS files.

Install JavaHelp for Stand-alone Use

JavaHelp support is included within the desktop; however, JavaHelp can be installed for direct access to helpset (.hs) files without the need to have the ACI desktop open. Note that Java must be already installed. The remainder of this topic discusses installing JavaHelp on a Java enabled Windows-based PC.

1. Download the latest version of JavaHelp from:


<http://java.sun.com/products/javahelp>

Note: JavaHelp is distributed as a zip file such as **Javahelp 2.0_01.zip** (a more current version might be available).


2. Open the zip file and extract all files to an easily accessible location, such as the root directory (e.g., C:\jh2.0). Among the files extracted is the **hsviewer.jar** file that is needed later in this procedure.
3. Find java.exe and create a shortcut to the file. Java.exe must be already installed. Cut and paste the shortcut to an easily accessible location.

For the illustrations used in the remainder of this procedure, the shortcut name JavaHelp 2.0 is used.

4. Right click on the shortcut and select Properties on the drop-down menu.



The properties for the shortcut are available in the Properties window as shown below.




5. In the Target field located on the Shortcut tab, enter the path to java.exe, followed by a space, the string "-jar", another space, and then the path to the installed location of hsviewer.jar. In the illustration above, the full text of the Target field is partially obscured, but is:

C:\jdk1.3\bin\java.exe -jar c:\jh2.0\demos\bin\hsviewer.jar

6. Click OK.

7. Test the functionality by opening JavaHelp using the shortcut. The following Set HelpSet window should display that can be used to browse to a helpset file (.hs extension).



If the above window does not display, a number of problems could exist. For example, either Java, JavaHelp, or both are not installed properly. Also, the target path in the shortcut could be incorrect. Verify that the paths in the shortcut reflect the actual paths for both java.exe and hsvviewer.jar.

Appendix A

Desktop Window Properties

This section provides overview information for each ACI desktop window.

Information for each window is structured as follows:

Application(s):	A list of applications in which the window is used. Possible applications are BASE24-es and TSS (Transaction Security Services).
Desktop Access:	How to access the window from the ACI desktop menu bar.
Help ID:	The JavaHelp help ID used to apply context help for the window. This is also the basename of the HTML content file for the window. For example, the HTML file for the help ID w_action_code is w_action_code.htm. All window help IDs and HTML content files begin with a w_.
Task ID:	The task ID that corresponds to the window.
Related Task IDs:	Other preconfigured tasks IDs such as those necessary to access hyperlinked windows.
Permission IDs:	Default preconfigured permissions IDs that define user access levels.

Configure Menu Windows

Acquirer Transactions Allowed Window

Application(s):	BASE24-es
Desktop Access:	Configure > Transactions Allowed > Acquirer Transactions Profile
Help ID:	w_acquirer_transactions_allowed_profile_configuration
Task ID:	AcquirerTransactionsAllowed
Related Task IDs:	-
Permission IDs:	FullAcqTransAllowedPermission ViewAcquirerTransactionsAllowed

Action Code Profile Configuration Window

Application(s):	BASE24-es
Desktop Access:	Configure > Action Code Profile
Help ID:	w_action_code
Task ID:	ActionCode
Related Task IDs:	-
Permission IDs:	FullActionCodePermission ViewActionCode

Administrative Card Configuration Window

Application(s):	BASE24-es
Desktop Access:	Configure > Administrative Card
Help ID:	w_administrative_card_configuration
Task ID:	AdministrativeCardManagement
Related Task IDs:	—
Permission IDs:	FullAdminCardMgmtPermission ViewAdministrativeCardMgmnt

Application Parameter Management System Interface Configuration Window

Application(s):	BASE24-es
Desktop Access:	Configure > Interface > Host > Application Parameter Management
Help ID:	w_apms_interface_configuration
Task ID:	APMSInterfaceConfiguration
Related Task IDs:	ContextConfiguration
Permission IDs:	FullAPMSIFCfgPermission ViewAPMSInterfaceConfiguration

ATM Channel Configuration Window

Application(s):	BASE24-es
Desktop Access:	Configure > ATM Framework > ATM Channel
Help ID:	w_atm_channel_configuration
Task ID:	ATMChannel
Related Task IDs:	ATMChannelProfile ATMHardwareStatus InsitutionConfiguration
Permission IDs:	FullATMChannelPermission ViewATMChannel

ATM Channel Profile Configuration Window

Application(s):	BASE24-es
Desktop Access:	Configure > ATM Framework > ATM Channel Profile
Help ID:	w_atm_channel_profile_configuration
Task ID:	ATMChannelProfile
Related Task IDs:	ATMSurcharge
Permission IDs:	FullATMChannelPrflPermission ViewATMChannelProfile

ATM Device Handler Interface Configuration Window

Application(s): BASE24-es

Desktop Access: Configure > Interface > Host > ATM Device Handler

Help ID: w_atm_device_handler_interface_configuration

Task ID: ATMDHInterfaceConfiguration

Related Task IDs: InterfaceConfiguration
AcquirerProfileConfiguration
AcquirerTransactionsAllowed
ActionCode
ISOFrameworkConfiguration
ATMSurcharge

Permission IDs: FullATMDHIFCfgPermission
ViewATMDHInterface

ATM Diebold Channel Operator ID Configuration Window

Application(s): BASE24-es

Desktop Access: Configure > ATM Framework > ATM Diebold Channel Operator

Help ID: w_atm_diebold_channel_id_configuration

Task ID: ATMDieboldChannelOperatorID

Related Task IDs: –

Permission IDs: FullATMDbldChanOprIDPermission
ViewATMDieboldChannelOperator

ATM Hopper Profile Configuration Window

Application(s): BASE24-es

Desktop Access: Configure > ATM Framework > ATM Hopper Profile

Help ID: w_atm_hopper_profile_configuration

Task ID: ATMHopperProfile

Related Task IDs: –

Permission IDs: FullATMHopperPrflPermission
ViewATMHopperProfile

ATM Load Profile Window

Application(s): BASE24-es
Desktop Access: Configure > ATM Framework > ATM Load Profile
Help ID: w_atm_load_profile
Task ID: ATMLoadProfile
Related Task IDs: –
Permission IDs: FullATMLoadProfilePermission
ViewATMLoadProfile

ATM Optional Receipt Profile Window

Application(s): BASE24-es
Desktop Access: Configure > ATM Framework > ATM Optional Receipt Profile
Help ID: w_atm_optional_receipt_profile
Task ID: ATMOptionalReceiptProfile
Related Task IDs: –
Permission IDs: FullATMOptnRcptPrflPermission
ViewATMOptnRcptProfile

ATM Receipt Format Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > ATM Framework > ATM Receipt Format
Help ID: w_atm_receipt_format_profile_configuration
Task ID: ATMReceiptFormat
Related Task IDs: InstitutionConfiguration
Permission IDs: FullATMReceiptFormatPermission
ViewATMReceiptFormat

ATM Receipt Required Type Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > ATM Framework > ATM Receipt Required Type
Help ID: w_atm_receipt_required_type_configuration
Task ID: ATMReceiptRequiredType
Related Task IDs: –
Permission IDs: FullATMRcptReqTypePermission
ViewATMReceiptRequiredType

Authentication Profile Configuration Window

Application(s): TSS
Desktop Access: Configure > Transaction Security > Authentication Profile
Help ID: w_authentication_profile_configuration
Task ID: AuthenticationConfiguration
Related Task IDs: SecurityDeviceConfiguration
Permission IDs: FullAuthentConfigPermission
ViewAuthenticationConfig

Authorization Script Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Script > Authorization Script
Help ID: w_authorization_script_configuration
Task ID: AuthScript
Related Task IDs: –
Permission IDs: FullAuthScriptPermission
ViewAuthScript

BankNet ISO Interface Configuration Window

Application(s): BASE24-es

Desktop Access: Configure > Interface > Network > BankNet ISO

Help ID: w_banknet_iso_interface_configuration

Task ID: BanknetInterface

Related Task IDs: InterfaceConfiguration
BanknetMerchantProgram
AcquirerProfileConfiguration
AcquirerTransactionsAllowed
IssuerTransactionsAllowed
ActionCode
ContextConfiguration
ISOFrameworkConfiguration
ATMSurcharge

Permission IDs: FullBanknetInterfacePermission
ViewBanknetInterface

BASE24 ISO8583 Host Interface Configuration Window

Application(s): BASE24-es

Desktop Access: Configure > Interface > Host > BASE24 ISO8583 Host

Help ID: w_base24_iso8583_host_interface_configuration

Task ID: B24HISOInterfaceConfig

Related Task IDs: InterfaceConfiguration
BanknetMerchantProgram
AcquirerProfileConfiguration
AcquirerTransactionsAllowed
IssuerTransactionsAllowed
ActionCode
ContextConfiguration
ISOFrameworkConfiguration
ATMSurcharge

Permission IDs: FullB24HISOIFConfigPermission
ViewB24HISOInterfaceConfig

BASE24KEYF Configuration Window

Application(s):	TSS
Desktop Access:	Configure > Transaction Security > BASE24 KEYF Configuration
Help ID:	w_base24_keyf_configuration
Task ID:	B24KEYFSecurity
Related Task IDs:	InterfaceSecurityConfiguration
Permission IDs:	FullB24KEYFSecurityPermission ViewB24KEYFSecurity

Certificate Management Window

Application(s):	TSS
Desktop Access:	Configure > Transaction Security > Automated Key Distribution > Certificate Management
Help ID:	w_certificate_management
Task ID:	Certificate
Related Task IDs:	–
Permission IDs:	FullCertificatePermission ViewCertificate

Channel Security Configuration Window

Application(s):	TSS
Desktop Access:	Configure > Transaction Security > Channel
Help ID:	w_channel_security_configuration
Task ID:	ChannelSecurity
Related Task IDs:	ChannelConfiguration SecurityDeviceConfiguration
Permission IDs:	FullChannelSecurityPermission ViewChannelSecurity

Context Profile Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Interface > Context Profile
Help ID: w_context_profile_configuration
Task ID: ContextConfiguration
Related Task IDs: –
Permission IDs: FullContextConfigPermission
ViewContextConfiguration

Contingency Interface Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Interface > Host > Contingency
Help ID: w_contingency_store_and_forward
Task ID: ContingencyInterface
Related Task IDs: InterfaceConfiguration
ContextConfiguration
ATMSurcharge
Permission IDs: FullContingencyIFPermission
ViewContingencyInterface

Currency Conversion Rate Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Currency Conversion > Currency Conversion Rate
Help ID: w_currency_conversion_rate_configuration
Task ID: CurrencyConvRateConfiguration
Related Task IDs: InstitutionConfiguration
Permission IDs: FullCrncyConvRateCfgPermission
ViewCurrencyConvRateConfig

Destination Routing Profile Configuration Window

Application(s):	BASE24-es
Desktop Access:	Configure > Routing > Profile Description > Destination Routing Profile
Help ID:	w_destination_routing_profile_configuration
Task ID:	IssuerProfileConfig
Related Task IDs:	–
Permission IDs:	FullIssProfConfigPermission ViewIssurerProfileConfig

Disable KEYGEN Window

Application(s):	TSS
Desktop Access:	Configure > Transaction Security > Automated Key Distribution > Disable KEYGEN
Help ID:	w_disable_keygen
Task ID:	KEYGENLockdown
Related Task IDs:	–
Permission IDs:	FullKEYGENLockdownPermission

DUKPT Derivation Key Profile Configuration Window

Application(s):	TSS
Desktop Access:	Configure > Transaction Security > DUKPT Derivation Key > Profile
Help ID:	w_dukpt_derivation_key_profile_configuration
Task ID:	B24SPDHDKPTDerivationKey
Related Task IDs:	–
Permission IDs:	FullB24SPDHDKPTDKeyPermission ViewB24SPDHDKPTDerivationKey

EPP Serial Number Window

Application(s):	TSS
Desktop Access:	Configure > Transaction Security > Automated Key Distribution > EPP Serial Number
Help ID:	w_epp_serial_number_configuration
Task ID:	EPPSerialNumberConfig
Related Task IDs:	—
Permission IDs:	FullEPPSerialNumCfgPermission ViewEPPSerialNumberConfig

Euro Opted Currency Configuration Window

Application(s):	BASE24-es
Desktop Access:	Configure > Currency Conversion > Euro Opted Currency
Help ID:	w_euro_opted_currency_configuration
Task ID:	EuroOptedCurrencyConfiguration
Related Task IDs:	—
Permission IDs:	FullEuroOptedCurrCfgPermission ViewEuroOptedCurrencyConfig

Exported Operators Configuration Window

Application(s):	BASE24-es
Desktop Access:	Configure > Script > Exported Operators
Help ID:	w_exported_operators_configuration
Task ID:	ExportedOperator
Related Task IDs:	—
Permission IDs:	FullExportedOperatorPermission ViewExportedOperator

File Update Router

Application(s): BASE24-es
 Desktop Access: Configure > Routing > File Update Router
 Help ID: w_file_update_router_configuration
 Task ID: FileUpdateRouterConfig
 Related Task IDs: –
 Permission IDs: FullFileUpdateRouterConfigPerm

IMT Interface Configuration Window

Application(s): BASE24-es
 Desktop Access: Configure > Interface > Host > Internal Message Translator > Network > IMT Interface
 Help ID: w_imt_interface_configuration
 Task ID: IMTInterface
 Related Task IDs: InterfaceConfiguration
 IMTATMTransactionMapping
 IMTPOSTransactionMapping
 IssuerTransactionsAllowed
 ContextConfiguration
 ISOFrameworkConfiguration
 ATMSurcharge
 Permission IDs: FullIMTInterfacePermission
 ViewIMTInterface

Institution Configuration Window

Application(s): BASE24-es
 Desktop Access: Configure > Institution
 Help ID: w_institution_configuration
 Task ID: InstitutionConfiguration
 Related Task IDs: AcquirerProfileConfiguration
 Permission IDs: FullInstConfigPermission
 ViewInstitutionConfiguration

Instrument Status Mapping Profile Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Interface > Instrument Status Mapping Profile
Help ID: w_instrument_status_mapping_profile_configuration
Task ID: InstrStatusMappingProfile
Related Task IDs: –
Permission IDs: FullInstStatMapPrflPermission
ViewInstStatMapPrflPermission

Instrument Type/Interchange Relationship Window

Application(s): BASE24-es
Desktop Access: Configure > Interface > Instrument Type/Interchange Relationship
Help ID: w_instrument_type_interchange_relationship_configuration
Task ID: InstrumentTypeIchgRelation
Related Task IDs: –
Permission IDs: FullInstTypIchgRelPermission
ViewInstrumentTypeIchgRelation

Interchange Prefix Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Prefix > Not-On-Us > Interchange Prefix
Help ID: w_interchange_prefix_configuration
Task ID: InterchangePrefixConfiguration
Related Task IDs: –
Permission IDs: FullIchgPrefixConfigPermission
ViewInterchangePrefixConfig

Interface Configuration Windows (Various)

Application(s):	BASE24-es
Desktop Access:	See specific window information
Help ID:	w_interface_configuration
Task ID:	InterfaceConfiguration
Related Task IDs:	–
Permission IDs:	FullInterfaceConfigPermission ViewInterfaceConfiguration

Interface Security Configuration Window

Application(s):	TSS
Desktop Access:	Configure > Transaction Security > Interface
Help ID:	w_interface_security_configuration
Task ID:	InterfaceSecurityConfiguration
Related Task IDs:	InterfaceConfiguration SecurityDeviceConfiguration
Permission IDs:	FullFSecurityConfigPermission ViewInterfaceConfiguration

Interface Terminal Window

Application(s):	BASE24-es
Desktop Access:	Configure > Interface > Network > Star > Interface Terminal
Help ID:	w_interface_terminal_configuration
Task ID:	InterfaceTerm
Related Task IDs:	-
Permission IDs:	FullInterfaceTermPermission ViewInterfaceTermPermission

Internal Message Translation (IMT) Transaction Mapping - ATM Window

Application(s):	BASE24-es
Desktop Access:	Configure > Interface > Host > Internal Message Translator > IMT Transaction Mapping - ATM
Help ID:	w_imt_transaction_mapping_atm
Task ID:	IMTATMTransactionMapping
Related Task IDs:	InterfaceConfiguration IMTInterface IssuerTransactionsAllowed ContextConfiguration ISOFrameworkConfiguration ATMSurcharge
Permission IDs:	FullIMTATMTransMapPermission ViewIMTATMTransactionMapping

Internal Message Translation (IMT) Transaction Mapping - POS Window

Application(s):	BASE24-es
Desktop Access:	Configure > Interface > Host > Internal Message Translator > IMT Transaction Mapping - POS
Help ID:	w_imt_transaction_mapping_pos
Task ID:	IMTPOSTransactionMapping
Related Task IDs:	InterfaceConfiguration IMTInterface IssuerTransactionsAllowed ContextConfiguration ISOFrameworkConfiguration ATMSurcharge
Permission IDs:	FullIMTPOSTransMapPermission ViewIMTPOSTransactionMapping

ISO 93 Host Interface Configuration Window

Application(s): BASE24-es

Desktop Access: Configure > Interface > Host > ISO 93 Host

Help ID: w_iso_93_host_interface_configuration

Task ID: B24HISO93InterfaceConfig

Related Task IDs: InterfaceConfiguration
AcquirerProfileConfiguration
AcquirerTransactionsAllowed
IssuerTransactionsAllowed
ActionCode
ContextConfiguration
ISOFrameworkConfiguration
ATMSurcharge

Permission IDs: FullB24HISO93IFConfigPermission
ViewB24HISOInterfaceConfig

ISO Message Profile Configuration Window

Application(s): BASE24-es

Desktop Access: Configure > ISO Message Profile

Help ID: w_iso_framework_configuration

Task ID: ISOFrameworkConfiguration

Related Task IDs: –

Permission IDs: FullISOFrameworkCfgPermission
ViewISOFrameworkConfiguration

ISO93 Interface Configuration Window

Application(s): BASE24-es

Desktop Access: Configure > Interface > Network > ISO93

Help ID: w_interface_configuration

Task ID: ISO93InterfaceCofiguration

Related Task IDs: InterfaceConfiguration
AcquirerProfileConfiguration
AcquirerTransactionsAllowed

IssuerTransactionsAllowed
ActionCode
ContextConfiguration
ISOFrameworkConfiguration
ATMSurcharge
Permission IDs: FullISO93IFConfigPermission
ViewISO93InterfaceConfig

Issuer Transactions Allowed Profile Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Transaction Allowed > Issuer Transactions Profile
Help ID: w_issuer_transactions_allowed_profile_configuration
Task ID: IssuerTransactionsAllowed
Related Task IDs: –
Permission IDs: FullIssTransAllowedPermission
ViewIssurerTransactionsAllowed

Journal Issuer Profile Relationship Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Journal > Issuer Profile Relationship
Help ID: w_journal_issuer_profile_relationship_configuration
Task ID: JournalConfigurationMapping
Related Task IDs: JournalProfileConfiguration
InstitutionConfiguration
Interface Configuration
interface-specific task ID(s)
Permission IDs: FullJrnlCfgMappingPermission
ViewJournalConfigurationMappin

Journal Profile Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Journal > Journal Profile
Help ID: w_journal_profile_configuration
Task ID: JournalProfileConfiguration
Related Task IDs: JournalConfigurationMapping
Permission IDs: FullJrnlProfileCfgPermission
ViewJournalProfileConfig

Journal Query Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Journal > Journal Query
Help ID: w_journal_query_configuration
Task ID: JournalQueryConfiguration
Related Task IDs: JournalQueryExecution
Permission IDs: FullJrnlQueryConfigPermission
ViewJournalQueryConfiguration

Journal TDE Suppression Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Journal > Journal TDE Suppression
Help ID: w_journal_tde_suppression
Task ID: JournalTDESuppression
Related Task IDs: InstitutionConfiguration
InterfaceConfiguration
Permission IDs: FullJrnlTDESuppressPermission
ViewJournalTDESuppression

Linked Currency Configuration

Application(s): BASE24-es
Desktop Access: Configure > Currency Conversion > Linked Currency
Help ID: w_linked_currency_configuration
Task ID: LinkedCurrencyConfiguration
Related Task IDs: –
Permission IDs: FullLinkedCurrCfgPermission
ViewLinkedCurrencyConfig

Master File Key Conversion Window

Application(s): TSS
Desktop Access: Configure > Transaction Security > Master File Key Conversion
Help ID: w_master_file_key_conversion
Task ID: MFKConverter
Related Task IDs: –
Permission IDs: FullMFKConverterPermission
ViewMFKConverter

MasterCard Debit Switch (MDS) Interface Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Interface > Network > MasterCard Debit Switch (MDS)
Help ID: w_mastercard_debit_switch_configuration
Task ID: MaestroDebitSwitch
Related Task IDs: InterfaceConfiguration
AcquirerProfileConfiguration
AcquirerTransactionsAllowed
IssuerTransactionsAllowed
ActionCode

ContextConfiguration
ISOFrameworkConfiguration
ATMSurcharge
Permission IDs: FullMaestroPermission
ViewMaestroDebitSwitch

Merchant Configuration and Statistics Window

Application(s): BASE24-es
Desktop Access: Configure > Merchant Processing > Merchant
Help ID: w_merchant_configuration_and_statistics
Task ID: MerchantConfiguration
Related Task IDs: ChannelConfiguration
InstitutionConfiguration
POSDeliveryChannel
PosDeliveryChannelProfile
Permission IDs: FullMerchantConfigPermission
ViewMerchantConfiguration

On-Us Prefix Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Prefix > On-Us
Help ID: w_prefix_configuration
Task ID: PrefixConfiguration
Related Task IDs: AuthenticationConfiguration
IssuerTransactionsAllowed
InstitutionConfiguration
InterfaceConfiguration
RoutingConfiguration
interface-specific task ID(s)
Permission IDs: FullPrefixConfigPermission
ViewPrefixConfiguration

Perusal Profile Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Journal > Perusal > Perusal Profile
Help ID: w_perusal_profile_configuration
Task ID: PerusalConfiguration
Related Task IDs: –
Permission IDs: FullPerusalConfigPermission
ViewPerusalConfiguration

POS Delivery Channel Configuration and Statistics Window

Application(s): BASE24-es
Desktop Access: Configure > Merchant Processing > POS Delivery Channel
Help ID: w_pos_delivery_channel_configuration_and_statistics
Task ID: POSDeliveryChannel
Related Task IDs: ChannelConfiguration
MerchantConfiguration
POSDeliveryChannelProfile
Permission IDs: FullPOSDlvryChannelPermission
ViewPOSDeliveryChannel

POS Delivery Channel Profile Configuration

Application(s): BASE24-es
Desktop Access: Configure > Merchant Processing > POS Delivery Channel Profile
Help ID: w_pos_delivery_channel_profile_configuration
Task ID: POSDeliveryChannelProfile
Related Task IDs: AcquirerProfileConfiguration
AcquirerTransactionsAllowed
ActionCode
ChannelConfiguration
Permission IDs: FullPOSDlvryChnlPrflPermission
ViewPOSDeliveryChannelProfile

Real Time Feed Window

Application(s):	BASE24-es
Desktop Access:	Configure > Interface > Host > Real Time Feed
Help ID:	w_realtimefeed_interface_configuration
Task ID:	RealTimeFeedInterface
Related Task IDs:	ContextConfiguration ATMSurcharge
Permission IDs:	FullRealTimeFeedIFPermission ViewRealTimeFeedIFPermission

Routing Configuration - Destination Window

Application(s):	BASE24-es
Desktop Access:	Configure > Routing > Destinations
Help ID:	w_routing_configuration_destination
Task ID:	RoutingConfiguration
Related Task IDs:	AcquirerIssuerRelationConfig
Permission IDs:	FullRoutingConfigPermission ViewRoutingConfiguration

Routing Configuration - Destination/Source Relationship Window

Application(s):	BASE24-es
Desktop Access:	Configure > Routing > Destination/Source
Help ID:	w_destination_source_relationship
Task ID:	AcquirerIssuerRelationConfig
Related Task IDs:	AcquirerProfileConfiguration RoutingConfiguration
Permission IDs:	FullAcqIssRelatnCfgPermission ViewRoutingConfiguration

Script Editor Window

Application(s): BASE24-es
Desktop Access: Configure > Script > Editor
Help ID: w_script_editor
Task ID: ScriptEditor
Related Task IDs: ScriptRepository
Permission IDs: FullScriptEditorPermission
ViewScriptEditor

Script Repository Window

Application(s): BASE24-es
Desktop Access: Configure > Script > Repository
Help ID: w_script_repository
Task ID: IWTsocketAdministration
Related Task IDs: ScriptEditor
Permission IDs: FullScriptRepositoryPermission
ViewScriptRepository

Security Device Configuration Window

Application(s): TSS
Desktop Access: Configure > Transaction Security > Security Device
Help ID: w_security_device_configuration
Task ID: SecurityDeviceConfiguration
Related Task IDs: –
Permission IDs: FullSecurityDevCfgPermission
ViewSecurityDeviceConfig

Source Routing Profile Configuration Window

Application(s):	BASE24-es
Desktop Access:	Configure > Routing > Profile Description > Source Routing Profile
Help ID:	w_source_routing_profile_configuration
Task ID:	AcquirerProfileConfiguration
Related Task IDs:	—
Permission IDs:	FullAcqProfileConfigPermission ViewAcquirerProfileConfig

SPDH Device Profile Configuration Window

Application(s):	BASE24-es
Desktop Access:	Configure > Merchant Processing > SPDH Device Profile
Help ID:	w_spdh_device_profile_configuration
Task ID:	SPDHDeviceConfig
Related Task IDs:	—
Permission IDs:	FullSPDHDeviceConfigPermission ViewSPDHDeviceConfig

Star Network Identifier/Instrument Type Relationship Window

Application(s):	BASE24-es
Desktop Access:	Configure > Interface > Network > Star > Star Network Identifier/Instrument Type Relationship
Help ID:	w_star_network_identifier_instrument_type_relationship_configuration
Task ID:	StarNetworkIdRelationship
Related Task IDs:	
Permission IDs:	FullStarNtwkIdRelationPerm ViewStarntwkIdRelationPerm

Star Institution Window

Application(s): BASE24-es
Desktop Access: Configure > Interface > Network > Star > Star Institution
Help ID: w_star_institution_configuration
Task ID: StarInstitution
Related Task IDs: -
Permission IDs: FullStarInstitutionPermission
ViewStarInstitutionPermission

Star ISO Interface Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Interface > Network > Star ISO
Help ID: w_star_iso_interface_configuration
Task ID: StarInterface
Related Task IDs: InterfaceConfiguration
AcquirerProfileConfiguration
AcquirerTransactionsAllowed
IssuerTransactionsAllowed
ActionCode
ContextConfiguration
ISOFrameworkConfiguration
ATMSurcharge
StarInstitution
Permission IDs: FullStarInterfacePermission
ViewStarInterfacePermission

Surcharge Profile Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Surcharge Profile
Help ID: w_surcharge_profile_configuration
Task ID: ATMSurcharge
Related Task IDs: –
Permission IDs: FullATMSurchargePermission
ViewATMSurcharge

System Algorithm Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Prefix > Not-On-Us > System Algorithm
Help ID: w_system_algorithm
Task ID: SystemAlgorithm
Related Task IDs: –
Permission IDs: FullSystemAlgorithmPermission
ViewSystemAlgorithm

System Prefix Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Prefix > Not-On-Us > System Prefix
Help ID: w_system_prefix_configuration
Task ID: SystemPrefix
Related Task IDs: –
Permission IDs: FullSystemPrefixPermission
ViewSystemPrefix

User Profile Relationship Window

Application(s): BASE24-es
Desktop Access: Configure > Journal > Perusal > User Profile Relationship
Help ID: w_user_profile_relationship
Task ID: UserProfileRelation
Related Task IDs: PerusalConfiguration
UserSecurityProfile
Permission IDs: FullUserProfRelationPermission
ViewUserProfileRelation

User Security Control Management Window

Application(s): BASE24-es, TSS
Desktop Access: Configure > User Security > Control
Help ID: w_user_security_control_management
Task ID: UserSecurityControl
Related Task IDs: –
Permission IDs: FullUSCtlPermission

User Security Group Configuration Window

Application(s): BASE24-es, TSS
Desktop Access: Configure > User Security > Group
Help ID: w_user_security_group_configuration
Task ID: UserSecurityGroupConfig
Related Task IDs: UserSecurityProfile (if Distributed Security Administration is enabled)
Permission IDs: FullUSGCfgPermission
ViewUserSecurityGroupConfig

User Security Profile Configuration Window

Application(s): BASE24-es, TSS
Desktop Access: Configure > User Security > Profile
Help ID: w_user_security_profile_configuration
Task ID: UserSecurityProfile
Related Task IDs: UserSecurityGroupConfig
Permission IDs: FullUSPPermission
ViewUserSecurityProfile

User Security Role Configuration Window

Application(s): BASE24-es, TSS
Desktop Access: Configure > User Security > Role
Help ID: w_user_security_role_configuration
Task ID: UserSecurityRoleConfig
Related Task IDs: –
Permission IDs: FullUSRCfgPermission
ViewUserSecurityRoleConfig

Visa DPS Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Interface > Network > Visa DPS
Help ID: w_visa_dps_interface_configuration
Task ID: VisaDPSInterface
Related Task IDs: InterfaceConfiguration
AcquirerProfileConfiguration
AcquirerTransactionsAllowed
IssuerTransactionsAllowed
ActionCode

ContextConfiguration
ISOFrameworkConfiguration
ATMSurcharge
Permission IDs: FullVisaDPSInterfacePermission
ViewVisaDPSInterfacePermission

VisaNet ISO Interface Configuration Window

Application(s): BASE24-es
Desktop Access: Configure > Interface > Network > VisaNet ISO
Help ID: w_visanet_iso_interface_configuration
Task ID: VisanetInterfaceConfig
Related Task IDs: InterfaceConfiguration
AcquirerProfileConfiguration
AcquirerTransactionsAllowed
IssuerTransactionsAllowed
ActionCode
ContextConfiguration
ISOFrameworkConfiguration
ATMSurcharge
Permission IDs: FullVisanetIFConfigPermission
ViewVisanetInterfaceConfig

System Operations Menu Windows

Active Script Statistics and Management Window

Application(s): BASE24-es
Desktop Access: System Operations > Active Script Statistics
Help ID: w_active_script_statistics_and_management
Task ID: ActiveScript
Related Task IDs: AuthScript
Permission IDs: FullActiveScriptPermission

Application Configuration Window

Application(s): BASE24-es, TSS
Desktop Access: System Operations > Server Management > Application
Help ID: w_application_configuration
Task ID: IWTApplicationConfig
Related Task IDs: –
Permission IDs: FullIWTApplCfgPermission
ViewIWTApplicationConfig

Application Management Window

Application(s): BASE24-es
Desktop Access: System Operations > Application Management > Application Management
Help ID:
Task ID: ApplctnManagement
Related Task IDs: –
Permission IDs: FullApplctnManagement
ViewApplctnManagement

Application Management Comms Handler Window

Application(s):	BASE24-es
Desktop Access:	System Operations > Application Management > Comms Handler Summary
Help ID:	w_appmanage_comms_handler_summary
Task ID:	ApplctnManagementSummary
Related Task IDs:	–
Permission IDs:	FullApplctnManagementSummary ViewApplctnManagementSummary

Application Management Message Router Summary Window

Application(s):	BASE24-es
Desktop Access:	System Operations > Application Management > Message Router Summary
Help ID:	w_appmanage_message_router_summary
Task ID:	ApplctnManagementSummary
Related Task IDs:	–
Permission IDs:	FullApplctnManagementSummary ViewApplctnManagementSummary

Application Management Process Summary Window

Application(s):	BASE24-es
Desktop Access:	System Operations > Application Management > Process Summary
Help ID:	w_appmanage_process_summary
Task ID:	ApplctnManagementSummary
Related Task IDs:	–
Permission IDs:	FullApplctnManagementSummary ViewApplctnManagementSummary

Application Management Queue Summary Window

Application(s):	BASE24-es
Desktop Access:	System Operations > Application Management > Queue Summary
Help ID:	w_appmanage_queue_summary
Task ID:	ApplctnManagementSummary
Related Task IDs:	–
Permission IDs:	FullApplctnManagementSummary ViewApplctnManagementSummary

Application Management Queue Manager Summary Window

Application(s):	BASE24-es
Desktop Access:	System Operations > Application Management > Queue Manager Summary
Help ID:	w_appmanage_queue_manager_summary
Task ID:	ApplctnManagementSummary
Related Task IDs:	–
Permission IDs:	FullApplctnManagementSummary ViewApplctnManagementSummary

Application Management Station Summary Window

Application(s):	BASE24-es
Desktop Access:	System Operations > Application Management > Station Summary
Help ID:	w_appmanage_station_summary
Task ID:	ApplctnManagementSummary
Related Task IDs:	–
Permission IDs:	FullApplctnManagementSummary ViewApplctnManagementSummary

ATM Channel Administration Window

Application(s):	BASE24-es
Desktop Access:	System Operations > ATM Framework > ATM Channel Administration
Help ID:	w_atm_channel_administration
Task ID:	ATMChannelAdministration
Related Task IDs:	ATMChannel ATMHopperProfile InstitutionConfiguration
Permission IDs:	FullATMChannelAdminPermission ViewATMChannelAdministration

ATM Channel Management - All Channels Window

Application(s):	BASE24-es
Desktop Access:	System Operations > ATM Framework > ATM Channel Management > All Channels
Help ID:	w_atm_channel_all_channels
Task ID:	ATMChannelManagement
Related Task IDs:	InstitutionConfiguration
Permission IDs:	FullATMChannelMgmtPermission ViewATMChannelManagement

ATM Channel Management Window

Application(s):	BASE24-es
Desktop Access:	System Operations > ATM Framework > ATM Channel Management > Selected Channels
Help ID:	w_atm_channel_management
Task ID:	ATMChanMgmtSelectedChannels
Related Task IDs:	InstitutionConfiguration
Permission IDs:	FullATMChanMgmtSCPermission ViewATMChanMgmtSCPermission

ATM Hardware Status Window

Application(s): BASE24-es
Desktop Access: System Operations > ATM Framework > ATM Hardware Status
Help ID: w_atm_hardware_status
Task ID: ATMHardwareStatus
Related Task IDs: ATM Channel
Permission IDs: FullATMHardwareStatPermission
ViewATMHardwareStatus

ATM Reload Map Request Window

Application(s): BASE24-es
Desktop Access: System Operations > ATM Framework > ATM Reload Map
Help ID: w_atm_reload_map_request
Task ID: ATMReloadMaps
Related Task IDs: –
Permission IDs: FullATMReloadMapsPermission

ATM Status Query Window

Application(s): BASE24-es
Desktop Access: System Operations > ATM Framework > ATM Status Query
Help ID: w_atm_status_query
Task ID: ATMStatusQuery
Related Task IDs: –
Permission IDs: FullATMStatusQueryPermission

Audit Store and Forward (SAF) Configuration Window

Application(s): BASE24-es, TSS
Desktop Access: System Operations > Audit SAF
Help ID: w_audit_store_and_forward_configuration
Task ID: AuditSAFConfig
Related Task IDs: –
Permission IDs: FullAuditSAFConfigPermission
ViewAuditSAFConfig

Cache Administration Window

Application(s): BASE24-es, TSS
Desktop Access: System Operations > Server Management > Server Administration > Cache Administration
Help ID: w_cache_administration
Task ID: IWTCacheAdministration
Related Task IDs: –
Permission IDs: FullIWTCacheAdminPermission
ViewIWTCacheAdminstrationin

Configuration Properties Window

Application(s): BASE24-es, TSS
Desktop Access: System Operations > Server Management > Server Administration > Configuration Properties
Help ID: w_configuration_properties
Task ID: IWTConfigurationAdministration
Related Task IDs: –
Permission IDs: FullIWTConfigAdminPermission
ViewIWTConfigurationAdmin

Contingency Store and Forward (SAF) Configuration Window

Application(s): BASE24-es
Desktop Access: System Operations > Contingency SAF
Help ID: w_contingency_store_and_forward
Task ID: ContingencySAF
Related Task IDs: –
Permission IDs: FullContingencySAFPermission
ViewContingencySAF

Database Administration Window

Application(s): BASE24-es, TSS
Desktop Access: System Operations > Server Management > Server Administration > Database Administration
Help ID: w_database_administration
Task ID: IWTDatabaseAdministration
Related Task IDs: –
Permission IDs: FullIWTDatabaseAdminPermission
ViewIWTDatabaseAdministration

Environment Configuration Window

Application(s): BASE24-es, TSS
Desktop Access: System Operations > Environment
Help ID: w_environment_configuration
Task ID: EnvironmentManagement
Related Task IDs: –
Permission IDs: FullEnvironmentMgmtPermission
ViewEnvironmentManagement

Event Subsystem ID Configuration Window

Application(s): BASE24-es, TSS
Desktop Access: System Operations > Event > Subsystem ID
Help ID: w_event_subsystem_id_configuration
Task ID: EventSubsystemConfiguration
Related Task IDs: –
Permission IDs: FullEventSubConfigPermission
ViewEventSubsystemConfig

External Connection Configuration Window

Application(s): BASE24-es, TSS
Desktop Access: System Operations > Server Management > External Connection
Help ID: w_external_connection_configuration
Task ID: IWTConnectionConfig
Related Task IDs: IWTProcessConfig
Permission IDs: FullIWTConnectionCfgPermission
ViewIWTConnectionConfig

File Partition Configuration Window

Application(s): BASE24-es
Desktop Access: System Operations > Database Management > File Partition
Help ID: w_file_partition_configuration
Task ID: FilePartition
Related Task IDs: –
Permission IDs: FullFilePartitionPermission
ViewFilePartitionPermission

Integrated Server Event Configuration and Management Window

Application(s): BASE24-es, TSS
Desktop Access: System Operations > Event > Event Management
Help ID: w_integrated_server_event_configuration
Task ID: EventConfiguration
Related Task IDs: EventSubsystemConfiguration
Permission IDs: FullEventConfigPermission
ViewEventConfiguration

Listener Configuration Window

Application(s): BASE24-es, TSS
Desktop Access: System Operations > Server Management > Listener
Help ID: w_listener_configuration
Task ID: IWTLListenerConfig
Related Task IDs: IWTPProcessConfig
Permission IDs: FullIWTLListenerCfgPermission
ViewIWTLListenerConfig

Process Configuration Window

Application(s): BASE24-es, TSS
Desktop Access: System Operations > Server Management > Process
Help ID: w_process_configuration
Task ID: IWTPProcessConfig
Related Task IDs: –
Permission IDs: FullIWTPProcessCfgPermission
ViewIWTPProcessConfig

Process Control Window

Application(s): BASE24-es, TSS
Desktop Access: System Operations > Process Control
Help ID: w_process_control
Task ID: ProcessControl
Related Task IDs: –
Permission IDs: FullProcContrlPermission
ViewProcessControl

Query Execute Window

Application(s): BASE24-es
Desktop Access: System Operations > Query Execution
Help ID: w_query_execute
Task ID: JournalQueryExecution
Related Task IDs: JournalQueryConfiguration
Permission IDs: FullJrnlQueryExecutePermission
ViewJournalQueryExecution

Socket Administration Window

Application(s): BASE24-es, TSS
Desktop Access: System Operations > Server Management > Server Administration > Socket Administration
Help ID: w_socket_administration
Task ID: IWTSocketAdministration
Related Task IDs: –
Permission IDs: FullIWTSocketAdminPermission
ViewIWTSocketAdministration

System Monitor Window

Application(s):	BASE24-es, TSS
Desktop Access:	System Operations > Server Management > Server Administration > System Monitor
Help ID:	w_system_monitor
Task ID:	IWTSystemMonitor
Related Task IDs:	IWTDatabaseAdministration IWTSocketAdministration IWTConfigurationAdministration IWTCachAdministration
Permission IDs:	FullIWTSystemMonitorPermission ViewIWTSystemMonitor

System Properties Window

Application(s):	BASE24-es, TSS
Desktop Access:	System Operations > Server Management > Server Administration > System Properties
Help ID:	w_system_properties
Task ID:	IWTSystemProperties
Related Task IDs:	–
Permission IDs:	FullIWTSysPropertiesPermission ViewIWTSystemProperities

Trace Configuration Window

Application(s):	BASE24-es
Desktop Access:	System Operations > Trace > Trace
Help ID:	w_trace_configuration
Task ID:	TraceConfiguration
Related Task IDs:	–
Permission IDs:	FullTraceConfigPermission ViewTraceConfigPermission

Trace Filter Profile Configuration Window

Application(s): BASE24-es
Desktop Access: System Operations > Trace > Trace Filter Profile
Help ID: w_trace_filter_profile_configuration
Task ID: TraceFilterConfiguration
Related Task IDs: –
Permission IDs: FullTraceFilterCfgPermission
ViewTraceFilterCfgPermission

Customer Management Menu Windows

Card Management Window

Application(s):	BASE24-es
Desktop Access:	Customer Management > Card
Help ID:	w_card_management
Task ID:	CardConfiguration
Related Task IDs:	InstitutionConfiguration Usages PreAuthHold PaymentLimitConfig
Permission IDs:	FullCardConfigPermission ViewCardConfiguration

Limit Profile Management Window

Application(s):	BASE24-es
Desktop Access:	Customer Management > Limit Profile
Help ID:	w_limit_profile_configuration
Task ID:	PaymentLimitConfig
Related Task IDs:	InstitutionConfiguration
Permission IDs:	FullPmtLimitConfigPermission ViewPaymentLimitConfig

Positive Balance Management Window

Application(s): BASE24-es
Desktop Access: Customer Management > Positive Balance
Help ID: w_positive_balance_management
Task ID: PositiveBalance
Related Task IDs: InstitutionConfiguration
Usages
PreAuthHold
PaymentLimitConfig
Permission IDs: FullPositiveBalancePermission
ViewPositiveBalance

Preauthorization Hold Management Window

Application(s): BASE24-es
Desktop Access: Customer Management > Preauthorization Hold
Help ID: w_preauthorization_hold_management
Task ID: PreAuthHold
Related Task IDs: InstitutionConfiguration
CardConfiguration
Permission IDs: FullPreAuthHoldPermission
ViewPreAuthHold

Usages Management Window

Application(s): BASE24-es
Desktop Access: Customer Management > Usages
Help ID: w_usages_management
Task ID: Usages
Related Task IDs: InstitutionConfiguration
CardConfiguration
Permission IDs: FullUsagesPermission
ViewUsages

Channel Public Key Perusal Window

Application(s):	BASE24-es, TSS
Desktop Access:	View > Automated Key Distribution > Channel Public Key Perusal
Help ID:	w_channel_public_key_perusal
Task ID:	ChannelPKPerusal
Related Task IDs:	–
Permission IDs:	FullChannelPKPerusalPermission ViewChannelPKPerusal

Host Public Key Perusal Window

Application(s):	BASE24-es TSS
Desktop Access:	View > Automated Key Distribution > Host Public Key Perusal
Help ID:	w_host_public_key_perusal
Task ID:	HostPKPerusal
Related Task IDs:	—
Permission IDs:	FullHostPKperusalPermission ViewHostPKPerusal

Journal Perusal Window

Application(s): BASE24-es
Desktop Access: View > Journal Perusal
Help ID: w_journal_perusal
Task ID: LogFilePerusal
Related Task IDs: –
Permission IDs: FullLogFilePerusalPermission
ViewLogFilePerusal

Tools Menu Windows

Audit Extract Window

Application(s): BASE24-es
Desktop Access: Tools > Audit Extract
Help ID: w_audit_extract
Task ID: UserAuditReport
Related Task IDs: –
Permission IDs: FullUserAuditRptPermission

Appendix B

Task IDs

The following table lists default task IDs and the corresponding permission IDs and ACI desktop window names.

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		AcquirerIssuerRelationConfig AcquirerProfileConfiguration, RoutingConfiguration	Routing Configuration - Destination/Source Relationship) (Configure > Routing > Destination/Source)	FullAcqIssRelatnCf Permission
✓		AcquirerProfileConfiguration	Source Routing Profile Configuration (Configure > Routing > Profile Description > Source Routing Profile)	FullAcqProfileConfig Permission
✓		AcquirerTransactionsAllowed	Acquirer Transactions Allowed Profile Configuration (Configure > Transactions Allowed > Acquirer Transactions Profile)	FullAcqTransAllowed Permission
✓		ActionCode	Action Code Profile Configuration (Configure > Action Code Profile)	FullActionCode Permission
✓		ActiveScript AuthScript	Active Script Statistics and Management (System Operations > Active Script Statistics)	FullActiveScript Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		AdministrativeCardManagement	Administrative Card Configuration (Configure > Administrative Card)	FullAdminCardMgmt Permission
✓		AIBInterface InterfaceConfiguration AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ATMSurcharge	AIB Interface Configuration (Configure > Interface > Host > AIB)	FullAIBInterface Permission
✓		APMSInterfaceConfiguration ContextConfiguration	Application Parameter Management System Interface Configuration (Configure > Interface > Host > Application Parameter Management)	FullAPMSIFCfg Permission
✓		ApplctnManagement	Application Management (System Operations > Application Management > Application Management)	FullApplctnManagement
✓		ApplctnManagement Summary	Application Management Comms Handler Application Management Message Router Summary Application Management Process Summary Application Management Queue Summary Application Management Queue Manager Summary Application Management Station Summary (System Operations > Application Management > ...)	FullApplctnManagement Summary

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		ATMChanMgmtSelectedChannels InstitutionConfiguration	ATM Channel Management (System Operations > ATM Framework > ATM Channel Management > Selected Channels)	FullATMChanMgmtSC Permission
✓		ATMChannel ATMHardwareStatus, InstitutionConfiguration, ATMChannelProfile	ATM Channel Configuration (Configure > ATM Framework > ATM Channel)	FullATMChannel Permission
✓		ATMChannelAdministration ATMChannel, InstitutionConfiguration, ATMHopperProfile	ATM Channel Administration (System Operations > ATM Framework > ATM Channel Administration)	FullATMChannelAdmin Permission
✓		ATMChannelManagement InstitutionConfiguration	ATM Channel Management - All Channels (System Operations > ATM Framework > ATM Channel Management > All Channels)	FullATMChannelMgmt Permission
✓		ATMChannelProfile ATMSurcharge	ATM Channel Profile Configuration (Configure > ATM Framework > ATM Channel Profile)	FullATMChannelPrfl Permission
✓		ATMDHInterfaceConfiguration InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, ActionCode, ISOFrameworkConfiguration, ATMSurcharge	ATM Device Handler Interface Configuration (Configure > Interface > Host > ATM Device Handler)	FullATMDHIFCfg Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		ATMDieboldChannelOperatorID	ATM Diebold Channel Operator ID Configuration (Configure > ATM Framework > ATM Diebold Channel Operator)	FullATMDbldChanOprID Permission
✓		ATMHardwareStatus ATMChannel	ATM Hardware Status (View > ATM Framework > ATM Hardware Status)	FullATMHardwareStat Permission
✓		ATMHopperProfile	ATM Hopper Profile Configuration (Configure > ATM Framework > ATM Hopper Profile)	FullATMHopperPrfl Permission
✓		ATMLoadProfile	ATM Load Profile (Configure > ATM Framework > ATM Load Profile)	FullATMLoadProfile Permission
✓		ATMOptionalReceiptProfile	ATM Optional Receipt Profile (Configure > ATM Framework > ATM Optional Receipt Profile)	FullATMOptnRcptPrfl Permission
✓		ATMReceiptFormat InstitutionConfiguration	ATM Receipt Format Configuration (Configure > ATM Framework > ATM Receipt Format)	FullATMReceiptFormat Permission
✓		ATMReceiptRequiredType	ATM Receipt Required Type Configuration (Configure > ATM Framework > ATM Receipt Required Type)	FullATMRcptReqType Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		ATMReloadMaps	ATM Reload Map Request (System Operations > ATM Framework > ATM Reload Map)	FullATMReloadMaps Permission
✓		ATMStatusQuery	ATM Status Query (System Operations > ATM Framework > ATM Status Query)	FullATMStatusuery Permission
✓		ATMSurcharge	Surcharge Profile Configuration (Configure > Surcharge Profile)	FullATMSurcharge Permission
✓	✓	AuditSAFConfig	Audit Store and Forward (SAF) Configuration (System Operations > Audit SAF)	FullAuditSAFConfig Permission
	✓	AuthenticationConfiguration SecurityDeviceConfiguration	Authentication Profile Configuration (Configure > Transaction Security > Authentication Profile)	FullAuthentConfig Permission
✓		AuthScript	Authorization Script Configuration (Configure > Script > Authorization Script)	FullAuthScript Permission
✓		B24HISO93InterfaceConfig	ISO 93 Host Interface Configuration (Configure > Interface > Host > ISO 93 Host)	FullB24HISO93IFConfig Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		B24HISOInterfaceConfig InterfaceConfiguration, BanknetMerchantProgram, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	BASE24 ISO8583 Host Interface Configuration (Configure > Interface > Host > BASE24 ISO8583 Host)	FullB24HISOIFConfig Permission FullHISO
	✓	B24KEYFSecurity InterfaceSecurityConfiguration	BASE24 KEYF Configuration (Configure > Transaction Security > BASE24 KEYF Configuration)	FullB24KEYFSecurity Permission
	✓	B24SPDHDKPTDerivationKey	DUKPT Derivation Key Profile Configuration (Configure > Transaction Security > DUKPT Derivation Key Profile)	FullB24SPDHDKPTDKey Permission
✓		BanknetInterface InterfaceConfiguration, BanknetMerchantProgram, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	BankNet ISO Interface Configuration (Configure > Interface > Network > BankNet ISO)	FullBanknetInterface Permission
✓		CardConfiguration InstitutionConfiguration, Usages, PreAuthHold, PaymentLimitConfig	Card Management (Customer Management > Card)	FullCardConfig Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
	✓	Certificate	Certificate Management (Configure > Transaction Security > Automated Key Distribution > Certificate Management)	FullCertificate Permission
✓	✓	ChannelPKPerusal	Channel Public Key Perusal (View > Automated Key Distribution > Channel Public Key Perusal)	FullChannelPKPerusal Permission
	✓	ChannelSecurity ChannelConfiguration, SecurityDeviceConfiguration	Channel Security Configuration (Configure > Transaction Security > Channel)	FullChannelSecurity Permission
✓		ContextConfiguration	Context Profile Configuration (Configure > Interface > Context Profile)	FullContextConfig Permission
✓		ContingencyInterface InterfaceConfiguration, ContextConfiguration, ATMSurcharge	Contingency Interface Configuration (Configure > Interface > Host > Contingency)	FullContingencyIF Permission
✓		ContingencySAF	Contingency Store and Forward (SAF) Configuration (System Operations > Contingency SAF)	FullContingencySAF Permission
✓		CurrencyConvRateConfiguration InstitutionConfiguration	Currency Conversion Rate Configuration (Configure > Currency Conversion > Currency Conversion Rate)	FullCrncyConvRateCfg Permission
✓	✓	EnvironmentManagement	Environment Configuration (System Operations > Environment)	FullEnvironmentMgmt Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
	✓	EPPSerialNumberConfig	EPP Serial Number Configuration (Configure > Transaction Security > Automated Key Distribution > EPP Serial Number)	FullEPPSerialNumCfg Permission
✓		EuroOptedCurencyConfiguration	Euro Opted Currency Configuration (Configure > Currency Conversion > Euro Opted Currency)	FullEuroOptedCurrCfg Permission
✓	✓	EventConfiguration EventSubsystemConfiguration	Integrated Server Event Configuration and Management (System Operations > Event > Event Management)	FullEventConfig Permission
✓	✓	EventSubsystemConfiguration	Event Subsystem ID Configuration (System Operations > Event > Subsystem ID)	FullEventSubConfig Permission
✓		ExportedOperator	Exported Operators Configuration (Configure > Script > Exported Operators)	FullExportedOperator Permission
✓		FilePartition	File Partition Configuration (System Operations > Database Management > File Partition)	FullFilePartition Permission
✓		FileUpdateRouterConfig	File Update Router (Configure > Routing > File Update Router)	FullFileUpdateRouterConfig Perm

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓	✓	HostPKPerusal	Host Public Key Perusal (View > Automated Key Distribution > Host Public Key Perusal)	FullHostPKPerusal Permission
✓		IMTATMTransactionMapping	Internal Message Translation (IMT) Transaction Mapping - ATM (Configure > Interface > Host > Internal Message Translator > IMT Transaction Mapping - ATM)	FullIMTATMTransMap Permission
✓		IMTInterface InterfaceConfiguration IMTInterface IMTATMTransactionMapping IMTPOSTransactionMapping, IssuerTransactionsAllowed, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	IMT Interface Configuration (Configure > Interface > Host > Internal Message Translator > Network > IMT Interface)	FullIMTInterface Permission
✓		IMTPOSTransactionMapping	Internal Message Translation (IMT) Transaction Mapping - POS (Configure > Interface > Host > Internal Message Translator > IMT Transaction Mapping - POS)	FullIMTPOSTransMap Permission
✓		InstitutionConfiguration AcquirerProfileConfiguration	Institution Configuration (Configure > Institution)	FullInstConfig Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		InstrStatusMappingProfile	Instrument Status Mapping Profile Configuration (Configure > Interface > Instrument Status Mapping Profile)	FullInstStatMapPrfl Permission
✓		InstrumentTypeIchgRelation	Instrument Type/Interchange Relationship (Configure > Interface > Instrument Type/Interchange Relationship)	FullInstTypIchgRel Permission
✓		InterchangePrefixConfiguration	Interchange Prefix Configuration (Configure > Prefix > Not-On-Us > Interchange Prefix)	FullIchgPrefixConfig Permission
✓		InterfaceConfiguration	All available interface configuration windows.	FullInterfaceConfig Permission
	✓	InterfaceSecurityConfiguration InterfaceConfiguration, SecurityDeviceConfiguration	Interface Security Configuration (Configure > Transaction Security > Interface)	FullIFSecurityConfig Permission
✓		InterfaceTerm	Interface Terminal (Configure > Interface > Network > Star > Interface Terminal)	FullInterfaceTerm Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		ISO93InterfaceConfiguration InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	ISO93 Interface Configuration (Configure > Interface > Network > ISO93)	FullISO93IFConfig Permission
✓		ISOFrameworkConfiguration	ISO Message Profile Configuration (Configure > ISO Message Profile)	FullISOFrameworkCfg Permisson
✓		IssuerProfileConfig	Destination Routing Profile Configuration (Configure > Routing > Profile Description > Destination Routing Profile)	FullIssProfConfig Permission
✓		IssuerTransactionsAllowed	Issuer Transactions Allowed Profile Configuration (Configure > Transactions Allowed > Issuer Transactions Profile)	FullIssTransAllowed Permission
✓	✓	IWTApplicationConfig	Application Configuration (System Operations > Server Management > Application)	FullIWTApplCfg Permission
✓	✓	IWTCacheAdministration	Cache Administration (System Operations > Server Management > Server Administration > Cache Administration)	FullIWTCacheAdmin Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓	✓	IWTConfigurationAdministration	Configuration Properties (System Operations > Server Management > Server Administration > Configuration Properties)	FullIWTConfigAdmin Permission
✓	✓	IWTConnectionConfig IWTProcessConfig	External Connection Configuration (System Operations > Server Management > External Connection)	FullIWTConnectionCfg Permission
✓	✓	IWTDatabaseAdministration	Database Administration (System Operations > Server Management > Server Administration > Database Administration)	FullIWTDatabaseAdmin Permission
✓	✓	IWTListenerConfig IWTProcessConfig	Listener Configuration (System Operations > Server Management > Listener)	FullIWTListenerCfg Permission
✓	✓	IWTProcessConfig	Process Configuration (System Operations > Server Management > Process)	FullIWTProcessCfg Permission
✓	✓	IWTSocketAdministration	Socket Administration (System Operations > Server Management > Server Administration > Socket Administration)	FullIWTSocketAdmin Permission
✓	✓	IWTSystemMonitor\ IWTDatabaseAdministration, IWTSocketAdministration, IWTConfigurationAdministration, IWTCacheAdministration	System Monitor (System Operations > Server Management > Server Administration > System Monitor)	FullIWTSystemMonitor Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓	✓	IWTSystemProperties	System Properties (System Operations > Server Management > Server Administration > System Properties)	FullIWTSysProperties Permission
✓		JournalConfigurationMapping JournalProfileConfiguration, InstitutionConfiguration, InterfaceConfiguration, and the interface-specific task IDs	Journal Issuer Profile Relationship Configuration (Configure > Journal > Issuer Profile Relationship)	FullJrnlCfgMapping Permission
✓		JournalProfileConfiguration JournalConfigurationMapping	Journal Profile Configuration (Configure > Journal > Journal Profile)	FullJrnlProfileCfg Permission
✓		JournalQueryConfiguration JournalQueryExecution	Journal Query Configuration (Configure > Journal > Journal Query)	FullJrnlQueryConfig Permission
✓		JournalQueryExecution JournalQueryConfiguration	Query Execute (System Operations > Query Execution)	FullJrnlQueryExecute Permission
✓		JournalTDESuppression InstitutionConfiguration, InterfaceConfiguration	Journal TDE Suppression Configuration (Configure > Journal > Journal TDE Suppression)	FullJrnlTDESuppress Permission
	✓	KEYGENLockdown	Disable KEYGEN (Configure > Transaction Security > Automated Key Distribution > Disable KEYGEN)	FullKEYGENLockdown Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		LinkedCurrencyConfiguration	Linked Currency Configuration (Configure > Currency Conversion > Linked Currency)	FullLinkedCurrCfg Permission
✓		LogFilePerusal	Journal Perusal (View > Journal Perusal)	FullLogFilePerusal Permission
✓		MaestroDebitSwitch InterfaceConfiguration AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	MasterCard Debit Switch (MDS) Interface Configuration (Configure > Interface Network > MasterCard Debit Switch (MDS))	FullMaestro Permission
✓		MerchantConfiguration ChannelConfiguration, InstitutionConfiguration, POSDeliveryChannel, POSDeliveryChannelProfile	Merchant Configuration and Statistics (Configure > Merchant Processing > Merchant)	FullMerchantConfig Permission
	✓	MFKConverter	Master File Key Conversion (Configure > Transaction Security > Master File Key Conversion)	FullMFKConverter Permission
✓		PaymentLimitConfig InstitutionConfiguration	Limit Profile Management (Customer Management > Limit Profile)	FullPmtLimitConfig Permission
✓		PerusalConfiguration	Perusal Profile Configuration (Configure > Journal > Perusal > Perusal Profile)	FullPerusalConfig Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		POSDeliveryChannel ChannelConfiguration, MerchantConfiguration, POSDeliveryChannelProfile	POS Delivery Channel Configuration and Statistics (Configure > Merchant Processing > POS Delivery Channel)	FullPOSDlvryChannel Permission
✓		POSDeliveryChannelProfile AcquirerProfileConfiguration, AcquirerTransactionsAllowed, ActionCode, ChannelConfiguration	POS Delivery Channel Profile Configuration (Configure > Merchant Processing > POS Delivery Channel Profile)	FullPOSDlvryChnlPrfl Permission
✓		PositiveBalance InstitutionConfiguration, Usages, PreAuthHold, PaymentLimitConfig	Positive Balance Management (Customer Management > Positive Balance)	FullPositiveBalance Permission
✓		PreAuthHold InstitutionConfiguration, CardConfiguration	Preauthorization Hold Management (Customer Management > Preauthorization Hold)	FullPreAuthHold Permission
✓		PrefixConfiguration AuthenticationConfiguration, IssuerTransactionsAllowed, InstitutionConfiguration, InterfaceConfiguration, RoutingConfiguration and, the interface-specific task IDs	On-Us Prefix Configuration (Configure > Prefix > On-Us)	FullPrefixConfig Permission
✓	✓	ProcessControl	Process Control (System Operations > Process Control)	FullProcCtrl FullProcessControl
✓		RealTimeFeedInterface	Real Time Feed Window (Configure > Interface > Host > Real Time Feed)	FullRealTimeFeedIF Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		RoutingConfiguration AcquirerIssuerRelationConfig	Routing Configuration - Destination (Configure > Routing > Destinations)	FullRoutingConfig Permission
✓		ScriptEditor ScriptRepository	Script Editor (Configure > Script > Editor)	FullScriptEditor Permission
✓		ScriptRepository ScriptEditor	Script Repository (Configure > Script > Repository)	FullScriptRepository Permission
	✓	SecurityDeviceConfiguration	Security Device Configuration (Configure > Transaction Security > Security Device)	FullSecurityDevCfg Permission
✓		SPDHDeviceConfig	SPDH Device Profile Configuration (Configure > Merchant Processing > SPDH Device Profile)	FullSPDHDeviceConfig Permission
✓		StarNetworkIdRelationship StarInstitution StarInterface	Star Network Identifier/ Instrument Type Relationship (Configure > Interface > Network > Star > Star Network Identifier/ Instrument Type Relationship)	FullStarNtwkIdRelation Perm

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		StarInstitution StarNetworkIdRelationship StarInterface	Star Institution (Configure > Interface > Network > Star > Star Institution)	FullStarInstitution Permission
✓		StarInterface StarNetworkIdRelationship StarInstitution	Star ISO Interface Configuration (Configure > Interface > Network > Star > Star ISO)	FullStarInterface Permission
✓		SystemAlgorithm	System Algorithm Configuration (Configure > Prefix > Not-On-Us > System Algorithm)	FullSystemAlgoritm Permission
✓		SystemPrefix	System Prefix Configuration (Configure > Prefix > Not-On-Us > System Prefix)	FullSystemPrefix Permission
✓		TraceConfiguration	Trace Configuration (System Operations > Trace > Trace)	FullTraceConfig Permission
✓		TraceFilterConfiguration	Trace Filter Profile Configuration (System Operations > Trace > Trace Filter Profile)	FullTraceFilterCfg Permission
✓		Usages InstitutionConfiguration, CardConfiguration	Usages Management (Customer Management > Usages)	FullUsages Permission
✓		UserAuditReport	Audit Extract Window (Tools > Audit Extract)	FullUserAuditRpt Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		UserProfileRelation PerusalConfiguration, UserSecurityProfile	User Profile Relationship (Configure > Journal > Perusal > User Profile Relation)	FullUserProfRelation Permission
✓	✓	UserSecurityControl UserSecurityControl	User Security Control Management (Configure > User Security > Control)	FullUSCtl Permission
✓	✓	UserSecurityGroupConfig UserSecurityProfile, if Distributed Security Administration is enabled	User Security Group Configuration (Configure > User Security > Group)	FullUSGCfg Permission
✓	✓	UserSecurityProfile UserSecurityGroupConfig	User Security Profile Configuration (Configure > User Security > Profile)	FullUSP Permission
✓	✓	UserSecurityRoleConfig	User Security Role Configuration (Configure > User Security > Role)	FullUSRCfg Permission
✓		VisanetInterfaceConfig InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	VisaNet ISO Interface Configuration (Configure > Interface > Network > VisaNet ISO)	FullVisanetIFConfig Permission

BASE24-es	TSS	Task IDs Related Task IDs	Window (Desktop Access)	Permission ID
✓		VisaDPSInterface InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	Visa DPS Interface Configuration (Configure > Interface > Network > Visa DPS)	FullVisaDPSInterface Permission

ACI Worldwide Inc.

Appendix C

Permission IDs

The following table lists default permission IDs and the corresponding window and task IDs.

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓		FullAcqIssRelatnCfg Permission	Routing Configuration - Destination/Source Relationship) (Configure > Routing > Destination/Source)	AcquirerIssuerRelationConfig AcquirerProfileConfiguration, RoutingConfiguration
✓		FullAcqProfileConfig Permission	Source Routing Profile Configuration (Configure > Routing > Profile Description > Source Routing Profile)	AcquirerProfileConfiguration
✓		FullAcqTransAllowed Permission	Acquirer Transactions Allowed Profile Configuration (Configure > Transactions Allowed > Acquirer Transactions Profile)	AcquirerTransactionsAllowed
✓		FullActionCode Permission	Action Code Profile Configuration (Configure > Action Code Profile)	ActionCode
✓		FullActiveScript Permission	Active Script Statistics and Management (System Operations > Active Script Statistics)	ActiveScript AuthScript

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓		FullAdminCardMgmt Permission	Administrative Card Configuration (Configure > Administrative Card)	AdministrativeCardManagement
✓		FullAIBInterface Permission	AIB Interface Configuration (Configure > Interface > Host > AIB)	AIBInterface InterfaceConfiguration AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ATMSurcharge
✓		FullAPMSIFCf Permission	Application Parameter Management System Interface Configuration (Configure > Interface > Host > Application Parameter Management)	APMSInterfaceConfiguration ContextConfiguration
✓		FullApplctnManagement	Application Management (System Operations > Application Management > Application Management)	ApplctnManagement
✓		FullApplctnManagement Summary	Application Management Comms Handler Application Management Message Router Summary Application Management Process Summary Application Management Queue Summary Application Management Queue Manager Summary Application Management Station Summary (System Operations > Application Management > ...)	ApplctnManagementSummary

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓		FullATMChanMgmtSC Permission	ATM Channel Management (System Operations > ATM Framework > ATM Channel Management > Selected Channels)	ATMChanMgmtSelectedChannels InstitutionConfiguration
✓		FullATMChannelAdmin Permission	ATM Channel Administration (System Operations > ATM Framework > ATM Channel Administration)	ATMChannelAdministration ATMChannel, InstitutionConfiguration, ATMHopperProfile
✓		FullATMChannelMgmt Permission	ATM Channel Management - All Channels (System Operations > ATM Framework > ATM Channel Management > All Channels)	ATMChannelManagement InstitutionConfiguration
✓		FullATMChannel Permission	ATM Channel Configuration (Configure > ATM Framework > ATM Channel)	ATMChannel ATMHardwareStatus, InstitutionConfiguration, ATMChannelProfile
✓		FullATMChannelPrfl Permission	ATM Channel Profile Configuration (Configure > ATM Framework > ATM Channel Profile)	ATMChannelProfile ATMSurcharge
✓		FullATMDbldChanOprID Permission	ATM Diebold Channel Operator ID Configuration (Configure > ATM Framework > ATM Diebold Channel Operator)	ATMDieboldChannelOperatorID

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓		FullATMDHIFCfg Permission	ATM Device Handler Interface Configuration (Configure > Interface > Host > ATM Device Handler)	ATMDHInterfaceConfiguration InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, ActionCode, ISOFrameworkConfiguration, ATMSurcharge
✓		FullATMHardwareStat Permission	ATM Hardware Status (View > ATM Framework > ATM Hardware Status)	ATMHardwareStatus ATMChannel
✓		FullATMHopperPrfl Permission	ATM Hopper Profile Configuration (Configure > ATM Framework > ATM Hopper Profile)	ATMHopperProfile
✓		FullATMLoadProfile Permission	ATM Load Profile (Configure > ATM Framework > ATM Load Profile)	ATMLoadProfile
✓		FullATMOptnRcptPrfl Permission	ATM Optional Receipt Profile (Configure > ATM Framework > ATM Optional Receipt Profile)	ATMOptionalReceiptProfile
✓		FullATMRcptReqType Permission	ATM Receipt Required Type Configuration (Configure > ATM Framework > ATM Receipt Required Type)	ATMReceiptRequiredType
✓		FullATMReceiptFormat Permission	ATM Receipt Format Configuration (Configure > ATM Framework > ATM Receipt Format)	ATMReceiptFormat InstitutionConfiguration

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓		FullATMReloadMaps Permission	ATM Reload Map Request (System Operations > ATM Framework > ATM Reload Map)	ATMReloadMaps
✓		FullATMStatusuery Permission	ATM Status Query (System Operations > ATM Framework > ATM Status Query)	ATMStatusQuery
✓		FullATMSurcharge Permission	Surcharge Profile Configuration (Configure > Surcharge Profile)	ATMSurcharge
✓	✓	FullAuditSAFConfig Permission	Audit Store and Forward (SAF) Configuration (System Operations > Audit SAF)	AuditSAFConfig
	✓	FullAuthentConfig Permission	Authentication Profile Configuration (Configure > Transaction Security > Authentication Profile)	AuthenticationConfiguration SecurityDeviceConfiguration
✓		FullAuthScript Permission	Authorization Script Configuration (Configure > Script > Authorization Script)	AuthScript
✓		FullB24HISO93IFConfig Permission	ISO 93 Host Interface Configuration (Configure > Interface > Host > ISO 93 Host)	B24HISO93InterfaceConfig

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓		FullB24HISOIFConfig Permission	BASE24 ISO8583 Host Interface Configuration (Configure > Interface > Host > BASE24 ISO8583 Host)	B24HISOInterfaceConfig InterfaceConfiguration, BanknetMerchantProgram, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge
	✓	FullB24KEYFSecurity Permission	BASE24 KEYF Configuration (Configure > Transaction Security > BASE24 KEYF Configuration)	B24KEYFSecurity InterfaceSecurityConfiguration
	✓	FullB24SPDHDKPTDKey Permission	DUKPT Derivation Key Profile Configuration (Configure > Transaction Security > DUKPT Derivation Key Profile)	B24SPDHDKPTDerivationKey
✓		FullBanknetInterface Permission	BankNet ISO Interface Configuration (Configure > Interface > Network > BankNet ISO)	BanknetInterface InterfaceConfiguration, BanknetMerchantProgram, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge
✓		FullCardConfig Permission	Card Management (Customer Management > Card)	CardConfiguration InstitutionConfiguration, Usages, PreAuthHold, PaymentLimitConfig

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
	✓	FullCertificate Permission	Certificate Management (Configure > Transaction Security > Automated Key Distribution > Certificate Management)	Certificate
✓	✓	FullChannelPKPerusal Permission	Channel Public Key Perusal (View > Automated Key Distribution > Channel Public Key Perusal)	ChannelPKPerusal
	✓	FullChannelSecurity Permission	Channel Security Configuration (Configure > Transaction Security > Channel)	ChannelSecurity ChannelConfiguration, SecurityDeviceConfiguration
✓		FullContextConfig Permission	Context Profile Configuration (Configure > Interface > Context Profile)	ContextConfiguration
✓		FullContingencyIF Permission	Contingency Interface Configuration (Configure > Interface > Host > Contingency)	ContingencyInterface InterfaceConfiguration, ContextConfiguration, ATMSurcharge
✓		FullContingencySAF Permission	Contingency Store and Forward (SAF) Configuration (System Operations > Contingency SAF)	ContingencySAF
✓		FullCrncyConvRateCfg Permission	Currency Conversion Rate Configuration (Configure > Currency Conversion > Currency Conversion Rate)	CurrencyConvRateConfiguration InstitutionConfiguration
✓	✓	FullEnvironmentMgmt Permission	Environment Configuration (System Operations > Environment)	EnvironmentManagement

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
	✓	FullEPPSerialNumCfg Permission	EPP Serial Number Configuration (Configure > Transaction Security > Automated Key Distribution > EPP Serial Number)	EPPSerialNumberConfig
✓		FullEuroOptedCurrCfg Permission	Euro Opted Currency Configuration (Configure > Currency Conversion > Euro Opted Currency)	EuroOptedCurencyConfiguration
✓	✓	FullEventConfig Permission	Integrated Server Event Configuration and Management (System Operations > Event > Event Management)	EventConfiguration EventSubsystemConfiguration
✓	✓	FullEventSubConfig Permission	Event Subsystem ID Configuration (System Operations > Event > Subsystem ID)	EventSubsystemConfiguration
✓		FullExportedOperator Permission	Exported Operators Configuration (Configure > Script > Exported Operators)	ExportedOperator
✓		FullFilePartition Permission	File Partition Configuration (System Operations > Database Management > File Partition)	FilePartition
✓		FullFileUpdateRouterConfig Perm	File Update Router (Configure > Routing > File Update Router)	FileUpdateRouterConfig

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓	✓	FullHostPKPerusal Permission	Host Public Key Perusal (View > Automated Key Distribution > Host Public Key Perusal)	HostPKPerusal
✓		FullIchgPrefixConfig Permission	Interchange Prefix Configuration (Configure > Prefix > Not-On-Us > Interchange Prefix)	InterchangePrefixConfiguration
	✓	FullIFSecurityConfig Permission	Interface Security Configuration (Configure > Transaction Security > Interface)	InterfaceSecurityConfiguration InterfaceConfiguration, SecurityDeviceConfiguration
✓		FullIMTATMTransMap Permission	Internal Message Translation (IMT) Transaction Mapping - ATM (Configure > Interface > Host > Internal Message Translator > IMT Transaction Mapping - ATM)	IMTATMTransactionMapping
✓		FullIMTInterface Permission	IMT Interface Configuration (Configure > Interface > Host > Internal Message Translator > Network > IMT Interface)	IMTInterface InterfaceConfiguration IMTInterface IMTATMTransactionMapping IMTPOSTransactionMapping, IssuerTransactionsAllowed, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓		FullIMTPOSTransMap Permission	Internal Message Translation (IMT) Transaction Mapping - POS (Configure > Interface > Host > Internal Message Translator > IMT Transaction Mapping - POS)	IMTPOSTransactionMapping
✓		FullInstConfig Permission	Institution Configuration (Configure > Institution)	InstitutionConfiguration AcquirerProfileConfiguration
✓		FullInstStatMapPrfl Permission	Instrument Status Mapping Profile Configuration (Configure > Interface > Instrument Status Mapping Profile)	InstrStatusMappingProfile
✓		FullInstTypIchgRel Permission	Instrument Type/Interchange Relationship (Configure > Interface > Instrument Type/Interchange Relationship)	InstrumentTypeIchgRelation
✓		FullInterfaceConfig Permission	All available interface configuration windows.	InterfaceConfiguration
✓		FullInterfaceTerm Permission	Interface Terminal (Configure > Interface > Network > Star > Interface Terminal)	InterfaceTerm

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓		FullISO93IFConfig Permission	ISO93 Interface Configuration (Configure > Interface > Network > ISO93)	ISO93InterfaceConfiguration InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge
✓		FullISOFrameworkCfg Permisson	ISO Message Profile Configuration (Configure > ISO Message Profile)	ISOFrameworkConfiguration
✓		FullIssProfConfig Permission	Destination Routing Profile Configuration (Configure > Routing > Profile Description > Destination Routing Profile)	IssuerProfileConfig
✓		FullIssTransAllowed Permission	Issuer Transactions Allowed Profile Configuration (Configure > Transactions Allowed > Issuer Transactions Profile)	IssuerTransactionsAllowed
✓	✓	FullIWTAplCfg Permission	Application Configuration (System Operations > Server Management > Application)	IWTApplicationConfig
✓	✓	FullIWTCacheAdmin Permission	Cache Administration (System Operations > Server Management > Server Administration > Cache Administration)	IWTCacheAdministration

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓	✓	FullIWTConfigAdmin Permission	Configuration Properties (System Operations > Server Management > Server Administration > Configuration Properties)	IWTConfigurationAdministration
✓	✓	FullIWTConnectionCfg Permission	External Connection Configuration (System Operations > Server Management > External Connection)	IWTConnectionConfig IWTProcessConfig
✓	✓	FullIWTDatabaseAdmin Permission	Database Administration (System Operations > Server Management > Server Administration > Database Administration)	IWTDatabaseAdministration
✓	✓	FullIWTLListenerCfg Permission	Listener Configuration (System Operations > Server Management > Listener)	IWTListenerConfig IWTProcessConfig
✓	✓	FullIWTProcessCfg Permission	Process Configuration (System Operations > Server Management > Process)	IWTProcessConfig
✓	✓	FullIWTSocketAdmin Permission	Socket Administration (System Operations > Server Management > Server Administration > Socket Administration)	IWTSocketAdministration
✓	✓	FullIWTSysProperties Permission	System Properties (System Operations > Server Management > Server Administration > System Properties)	IWTSystemProperties

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓	✓	FullIWTSysMonitor Permission	System Monitor (System Operations > Server Management > Server Administration > System Monitor)	IWTSysMonitor\ IWTDATABASEAdministration, IWTSocketAdministration, IWTCConfigurationAdministration, IWTCachAdministration
✓		FullJrnlCfgMapping Permission	Journal Issuer Profile Relationship Configuration (Configure > Journal > Issuer Profile Relationship)	JournalConfigurationMapping JournalProfileConfiguration, InstitutionConfiguration, InterfaceConfiguration, and the interface-specific task IDs
✓		FullJrnlProfileCfg Permission	Journal Profile Configuration (Configure > Journal > Journal Profile)	JournalProfileConfiguration JournalConfigurationMapping
✓		FullJrnlQueryConfig Permission	Journal Query Configuration (Configure > Journal > Journal Query)	JournalQueryConfiguration JournalQueryExecution
✓		FullJrnlQueryExecute Permission	Query Execute (System Operations > Query Execution)	JournalQueryExecution JournalQueryConfiguration
✓		FullJrnlTDESuppress Permission	Journal TDE Suppression Configuration (Configure > Journal > Journal TDE Suppression)	JournalTDESuppression InstitutionConfiguration, InterfaceConfiguration
	✓	FullKEYGENLockdown Permission	Disable KEYGEN (Configure > Transaction Security > Automated Key Distribution > Disable KEYGEN)	KEYGENLockdown

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓		FullLinkedCurrCfg Permission	Linked Currency Configuration (Configure > Currency Conversion > Linked Currency)	LinkedCurrencyConfiguration
✓		FullLogFilePerusal Permission	Journal Perusal (View > Journal Perusal)	LogFilePerusal
✓		FullMaestro Permission	MasterCard Debit Switch (MDS) Interface Configuration (Configure > Interface Network > MasterCard Debit Switch (MDS))	MaestroDebitSwitch InterfaceConfiguration AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge
✓		FullMerchantConfig Permission	Merchant Configuration and Statistics (Configure > Merchant Processing > Merchant)	MerchantConfiguration ChannelConfiguration, InstitutionConfiguration, POSDeliveryChannel, POSDeliveryChannelProfile
	✓	FullMFKConverter Permission	Master File Key Conversion (Configure > Transaction Security > Master File Key Conversion)	MFKConverter
✓		FullPerusalConfig Permission	Perusal Profile Configuration (Configure > Journal > Perusal > Perusal Profile)	PerusalConfiguration
✓		FullPmtLimitConfig Permission	Limit Profile Management (Customer Management > Limit Profile)	PaymentLimitConfig InstitutionConfiguration

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓		FullPOSDlvryChannel Permission	POS Delivery Channel Configuration and Statistics (Configure > Merchant Processing > POS Delivery Channel)	POSDeliveryChannel ChannelConfiguration, MerchantConfiguration, POSDeliveryChannelProfile
✓		FullPOSDlvryChnlPrfl Permission	POS Delivery Channel Profile Configuration (Configure > Merchant Processing > POS Delivery Channel Profile)	POSDeliveryChannelProfile AcquirerProfileConfiguration, AcquirerTransactionsAllowed, ActionCode, ChannelConfiguration
✓		FullPositiveBalance Permission	Positive Balance Management (Customer Management > Positive Balance)	PositiveBalance InstitutionConfiguration, Usages, PreAuthHold, PaymentLimitConfig
✓		FullPreAuthHold Permission	Preauthorization Hold Management (Customer Management > Preauthorization Hold)	PreAuthHold InstitutionConfiguration, CardConfiguration
✓		FullPrefixConfig Permission	On-Us Prefix Configuration (Configure > Prefix > On-Us)	PrefixConfiguration AuthenticationConfiguration, IssuerTransactionsAllowed, InstitutionConfiguration, InterfaceConfiguration, RoutingConfiguration and, the interface-specific task IDs
✓	✓	FullProcContrl FullProcessControl	Process Control (System Operations > Process Control)	ProcessControl
✓		FullRealTimeFeedIF Permission	Real Time Feed Window (Configure > Interface > Host > Real Time Feed)	RealTimeFeedInterface

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓		FullRoutingConfig Permission	Routing Configuration - Destination (Configure > Routing > Destinations)	RoutingConfiguration AcquirerIssuerRelationConfig
✓		FullScriptEditor Permission	Script Editor (Configure > Script > Editor)	ScriptEditor ScriptRepository
✓		FullScriptRepository Permission	Script Repository (Configure > Script > Repository)	ScriptRepository ScriptEditor
	✓	FullSecurityDevCfg Permission	Security Device Configuration (Configure > Transaction Security > Security Device)	SecurityDeviceConfiguration
✓		FullSPDHDeviceConfig Permission	SPDH Device Profile Configuration (Configure > Merchant Processing > SPDH Device Profile)	SPDHDeviceConfig
✓		FullStarNtwkIdRelationPerm	Star Network Identifier/ Instrument Type Relationship (Configure > Interface > Network > Star > Star Network Identifier/ Instrument Type Relationship)	StarNetworkIdRelationship

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓		FullStarInstitution Permission	Star Institution (Configure > Interface > Network > Star > Star Institution)	StarInstitution
✓		FullStarInterface Permission	Star ISO Interface Configuration (Configure > Interface > Network > Star > Star ISO)	StarInterface
✓		FullSystemAlgoritm Permission	System Algorithm Configuration (Configure > Prefix > Not-On-Us > System Algorithm)	SystemAlgorithm
✓		FullSystemPrefix Permission	System Prefix Configuration (Configure > Prefix > Not-On-Us > System Prefix)	SystemPrefix
✓		FullTraceConfig Permission	Trace Configuration (System Operations > Trace > Trace)	TraceConfiguration
✓		FullTraceFilterCfg Permission	Trace Filter Profile Configuration (System Operations > Trace > Trace Filter Profile)	TraceFilterConfiguration
✓		FullUsages Permission	Usages Management (Customer Management > Usages)	Usages InstitutionConfiguration, CardConfiguration

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓	✓	FullUSCtl Permission	User Security Control Management (Configure > User Security > Control)	UserSecurityControl UserSecurityControl
✓		FullUserAuditRpt Permission	Audit Extract Window (Tools > Audit Extract)	UserAuditReport
✓		FullUserProfRelation Permission	User Profile Relationship (Configure > Journal > Perusal > User Profile Relation)	UserProfileRelation PerusalConfiguration, UserSecurityProfile
✓	✓	FullUSGCfg Permission	User Security Group Configuration (Configure > User Security > Group)	UserSecurityGroupConfig UserSecurityProfile, if Distributed Security Administration is enabled
✓	✓	FullUSP Permission	User Security Profile Configuration (Configure > User Security > Profile)	UserSecurityProfile UserSecurityGroupConfig
✓	✓	FullUSRCfg Permission	User Security Role Configuration (Configure > User Security > Role)	UserSecurityRoleConfig
✓		FullVisanetIFConfig Permission	VisaNet ISO Interface Configuration (Configure > Interface > Network > VisaNet ISO)	VisanetInterfaceConfig InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge

BASE24-es	TSS	Permission ID	Window (Desktop Access)	Task IDs Related Task IDs
✓		FullVisaDPSInterface Permission	Visa DPS Interface Configuration (Configure > Interface > Network > Visa DPS)	VisaDPSInterface InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge

ACI Worldwide Inc.

Index

A

Access user security windows, [4-3](#)
Active user sessions, [5-4](#)
Application Area, [1-2](#)
ASAFD, [6-2](#)
Authenticated users, [2-4](#)
Automatic JAR file updating, [8-6](#)

C

Cascading Style Sheets (CSS), JavaHelp, [9-4](#)
Clear/Reset, [3-7](#)
Confirm deletes check box, [2-9](#)
Confirm deletes prompt, [3-8](#)
Confirm updates check box, [2-9](#)
Content files, JavaHelp, [9-4](#)
Context sensitive help, [9-6](#)
Currency format locale, [2-9](#)
Custom online help, [9-9](#)

D

Default users, [1-10](#)
Delete records, [3-8](#)
Desktop console, [2-2](#)
Desktop layout (areas), [1-2](#)
DeskTop.log file, [2-14](#)
Distributed Security Administration (DSA), [4-7](#)
DSA (Distributed Security Administration), [4-7](#)

F

Fail over support, [1-6](#)
Field labels, [3-2](#)
Filter settings, [4-17](#)
Frame open indicator, [2-9](#)

G

Get Info function, [4-21](#)

H

Helpset file, JavaHelp, [9-4](#)
hsvviewer.jar, [9-12](#)

I

Images, JavaHelp, [9-4](#)

J

JAR files for JavaHelp, [9-5](#)
JAR versions, [2-18](#)
JavaHelp, [9-1](#)
JavaHelp configuration files, [9-4](#)
JavaHelp viewer, [9-3](#)

L

local.cfg, [1-3](#)

M

Map IDs, [9-6](#)
Menu Bar, [1-2](#)
Mirroring, [8-5](#)

N

Navigation tree, [1-2](#)
Navigation tree check box, [2-9](#)

O

Online help viewer (JavaHelp), [9-3](#)
OwnerIDSupport property, [4-7](#)

P

Packaging of online help, [9-5](#)
Password error alert message, [2-7](#)
Password group, [4-5](#)
Passwords, [4-5](#)
 change by a user, [2-7](#)
 change by an administrator, [5-7](#)
 restrictions, [4-5](#)

P continued

Permission groups, [4-4](#)
Permissions, [4-4](#)
Pre-show frame indicator, [2-10](#)
Print (setup, preview), [2-16](#)
Print Screen Orientation, [2-10](#)
Procedures
 Access online help from the desktop, [9-2](#)
 Access user security windows, [4-3](#)
 Assign a security group, [4-24](#)
 Assign a system administration role filter, [4-14](#)
 Assign roles to a user, [4-26](#)
 Change a password (by a user), [2-7](#)
 Change a user password (by admin), [5-7](#)
 Change the display of JavaHelp content, [9-11](#)
 Configure a password group, [4-10](#)
 Configure a security group, [4-11](#)
 Configure a user role, [4-15](#)
 Configure contingency processing, [7-2](#)
 Configure field filters, [4-16](#)
 Configure permission groups, [4-21](#)
 Configure permissions, [4-19](#)
 Create custom JavaHelp content HTML files, [9-10](#)
 Create custom online help, [9-9](#)
 Delete records, [3-8](#)
 Disable contingency processing, [7-4](#)
 Display active user sessions, [5-4](#)
 Display the user interface framework version, [2-18](#)
 Display user password history, [5-7](#)
 Enable contingency processing, [7-4](#)
 Exit from the desktop, [2-17](#)
 Expire a user password, [5-7](#)
 Expire passwords by password group, [5-8](#)
 Hide or show the navigation tree, [2-9](#)
 Install JavaHelp, [9-12](#)
 Log off (out), [2-6](#)
 Log off a user, [5-6](#)
 Log on, [2-4](#)
 Mirror the repository, [8-5](#)
 Save records, [3-7](#)
 Search the helpset, [9-8](#)
 Select a web server, [2-15](#)
 Send a snapshot, [2-14](#)
 Set a user status, [5-3](#)
 Set Error Notification settings, [2-11](#)
 Set sound preferences, [2-13](#)
 Set user preferences, [2-8](#)
 Start the ACI desktop, [2-2](#)
 Terminate an active user session, [5-6](#)
 View active user sessions (refreshing, updating), [5-5](#)
 View password change history, [5-7](#)
 Window toolbars and pop-up menus use, [3-4](#)
 Work with tables, [3-5](#)
Process limits, [7-2](#)

R

Refresh, [3-7](#)

REPORT.USERAUDITLOG.LOC environment attribute, [6-4](#)
Roles, [4-4](#)
Rows (in tables)
 inserting, [3-5](#)
 selecting, [3-5](#)
RunDesktop.bat, [2-2](#), [8-2](#)

S

Save, [3-7](#)
Search the helpset, [9-8](#)
Secure Sockets Layer (SSL) protocol, [1-4](#)
Security domains, [4-7](#)
Security error alert message, [2-4](#)
Security groups (users), [4-6](#)
Security warning alert message, [2-5](#)
Selectable list fields, [3-3](#)
Selecting rows, [3-5](#)
Session timeout, [4-7](#), [4-12](#)
Sessions (active), [5-4](#)
Snapshots, [2-14](#)
sound.cfg, [2-13](#)
Status Pane, [1-2](#)
Status pane, [2-10](#)
SysAdmin Profile, [4-14](#)
System Administration Profile, [4-14](#)

T

Table cell exception, [3-3](#)
Ticket, [1-5](#)
Timeouts
 session, [4-12](#)
 UI, [4-12](#)
Title Bar, [1-2](#)
Toolbar, [1-2](#), [2-10](#)
Tooltip text, [2-11](#)

U

UI timeout, [4-12](#)
UI_CNTNGY_LEVEL environment attribute, [7-3](#)
User authentication, [1-5](#)
User authorization, [1-5](#)
User interface framework, [1-3](#)
User interface framework version, [2-18](#)
User Preferences window
 Error Notification tab, [2-11](#)
 General tab, [2-8](#)
 Sound tab, [2-13](#)
User roles, [4-4](#)

U continued

- User Security Control Management window
 - Active Sessions tab, [5-4](#), [5-6](#)
 - Password Maintenance tab, [5-8](#)
- User Security Group Configuration window
 - Password Group tab, [4-10](#)
 - Security Group tab, [4-11](#)
- User Security Profile Configuration window
 - Active Sessions tab, [5-4](#), [5-6](#)
 - General tab, [4-23](#), [5-3](#)
- User Security Profile window
 - Password tab, [5-7](#)
 - Roles tab, [4-26](#)
- User Security Role Configuration window
 - Permission Groups tab, [4-21](#)
 - Permissions tab, [4-19](#)
 - Roles tab, [4-15](#)
- User security server
 - Fail over support, [1-6](#)
 - overview, [1-5](#)
- User sessions, [5-4](#)
- User status, [5-3](#)

V

- VC quiet mode, [8-6](#)
- Version Checker Client window, [8-3](#)
- Version Checker Server, [8-2](#)
- Versions, [2-18](#)

W

- Web server, [2-15](#)
- Web servers, [1-3](#)

X

- XML audit message format, [6-3](#)
- XML index file, JavaHelp, [9-4](#)
- XML map file, JavaHelp, [9-4](#)
- XML table of contents, JavaHelp, [9-4](#)

ACI Worldwide Inc.