

ACI Desktop User Interface Manual

BASE24-esTM



© 2005 by ACI Worldwide Inc. All rights reserved.

All information contained in this documentation is confidential and proprietary to ACI Worldwide Inc., and has been delivered for use pursuant to license. No part of this documentation may be photocopied, electronically transferred, modified, or reproduced in any manner that is contrary to license without the prior written consent of ACI Worldwide Inc.

Access Control Server, ACI Automated Case Management System, ACI Card Management System, ACI Claims Manager, ACI Commerce Gateway, ACI Debit Card System, ACI e-Courier, ACI Host Link, ACI Merchant Accounting System, ACI Payments Manager, ACI Proactive Risk Manager, ACI Smart Chip Manager, BASE24, BASE24-atm, BASE24-card, BASE24-check auth, BASE24-configuration manager, BASE24-es, BASE24-frequent shopper, BASE24-infobase, BASE24-pos, BASE24-refunds, BASE24-remote banking, BASE24-teller, NET24, and WINPAY24 are trademarks or registered trademarks of ACI Worldwide Inc., Transaction Systems Architects, Inc., or their subsidiaries.

Other companies' trademarks, service marks, or registered trademarks and service marks are trademarks, service marks, or registered trademarks and service marks of their respective companies.

Contents

Preface	vii
1: Introduction	1-1
Desktop Layout	1-2
User Interface Framework	1-3
Communication Security	1-4
User Security Server	1-5
Fail Over Support	1-6
Overview of Windows (Screens), Applications, and Tasks	1-7
User Configuration and Management	1-8
Default Users	1-9
BASE24-es	1-9
TSS	1-9
Configuration Files	1-10
2: Basic Functions	2-1
Start the Desktop	2-2
Log On (In)	2-5
Security Error	2-6
Security Warning	2-6
Concurrent Sessions	2-6
Log Off (Out)	2-8
Change a Password	2-9
Set General User Preferences	2-10
Set Error Notification Preferences	2-13
Set Sound Preferences	2-14
Send a Snapshot	2-15
Connect to a Web Server	2-16
Print Functions	2-17
Exit from the Desktop	2-18
Display Framework Version Information	2-19

3: User Configuration	3-1
User Security Configuration Hierarchy	3-2
User Security Configuration Window Usage	3-3
User Profiles	3-4
Roles	3-4
Passwords and Password Groups	3-5
Security Groups	3-6
Distributed Security Administration (DSA)	3-8
DSA Setup	3-8
Steps to Add a User	3-10
Step 1.0: Configure a Password Group	3-11
Step 2.0: Configure a Security Group	3-12
Step 3.0: Configure a User Role	3-16
Step 4.0: Configure the User's Profile	3-23
4: User Management	4-1
User Management Window Usage	4-2
Set the Status of a User	4-3
Display Active User Sessions	4-4
Active User Session for a Selected User	4-4
Active User Sessions for All Users	4-5
Terminate Active User Sessions (Log off a User)	4-6
Display Password History for a User	4-7
Change a User's Password	4-7
Expire a User's Password	4-7
Expire Passwords by Password Group	4-8
5: User Auditing	5-1
Internal XML Audit Message Format	5-2
User Audit Activity Reports	5-3
Automated User Auditing	5-4
6: Version Checker Server	6-1
Version Checker Client Window	6-2
Select All	6-2
Close When Done Option	6-3
Mirror the Repository	6-4
Automatic JAR File Update	6-5

7: Online Help	7-1
Helpset Viewer Overview	7-2
Access to JavaHelp from the ACI Desktop.	7-3
With Context.	7-3
Without Context	7-3
JavaHelp Files	7-4
JavaHelp Packages	7-4
Helpset File	7-5
How Context is Implemented in JavaHelp	7-6
Search the Helpset for a Text String	7-7
Custom Help Content	7-8
Customization of HTML Content Files	7-9
Change the Display of Content	7-10
Install JavaHelp for Stand-alone Use	7-11
 A: Desktop Windows	 A-1
 B: Task IDs	 B-1
 C: Permission IDs	 C-1
 Index	 Index-1

ACI Worldwide Inc.

Preface

The ACI desktop is the user access to certain ACI applications for configuration, operation, and management functions.

Audience

This manual is written for all users of the ACI desktop, including system administration personnel.

Prerequisites

Readers must know basic graphical user interface (GUI) functionality and procedures, such as using hyperlinks and buttons. The ACI desktop is organized by tasks (i.e., configure, system operations, and customer management) that require basic understanding of managing payment systems and applications.

Software

This manual documents standard processing as of its publication date. Software that is not current and custom software modifications (CSMs) may result in processing that differs from the material presented in this manual.

Manual Summary

Section 1, Introduction, provides an overview of the ACI desktop, windows, communication security, and information about default users. Also included is information about the user interface framework and user security servers.

Section 2, Basic Functions, describes how to log on and log off, set user preferences, and print, among other basic functions available from the File menu.

Section 3, User Configuration, provides an overview of user security, distributed security administration (DSA), and how to configure a user of the ACI desktop.

Section 4, User Management, describes how to manage and monitor users of the ACI desktop.

Section 5, User Auditing, provides an overview of user auditing of the ACI desktop, including generating audit reports.

Section 6, Version Checker Server, describes how the Version Checker server manages and updates ACI desktop versions.

Section 7, Online Help, describes the desktop online help (JavaHelp) and how to use online help. And, provides information about localizing the ACI desktop and customizing online help.

Appendix A, Desktop Windows, provides a list of each ACI desktop window and related permission and task IDs.

Appendix B, Task IDs, provides a list of each Task ID and related permission ID and ACI desktop window.

Appendix C, Permission IDs, provides a listing of each Permission ID and related task ID and ACI desktop window.

Publication Identification

Three entries appearing at the bottom of each page uniquely identify this ACI publication. The date indicates the issue of the manual. The software release and version information (R1.0v05.4 for release 1.0, version 05.4) specifies the software that the manual describes. The publication number (for example, CF-CS000-01ES for the *ACI Desktop User Interface Manual*) appears on every page to assist readers in identifying the manual from which a page of information was printed. This information matches the document information on the copyright page of the manual.

1: Introduction


The ACI desktop is the primary user interface for performing the following tasks:

- Configuring the data sources used in the following applications:
 - BASE24-es
 - Enhanced authorization for BASE24
 - Transaction Security Services (TSS)
 - Payments Manager
- System operations, such as process control commands, application management, ATM management, database and environment setup
- Customer management of cards, limits, balances, preauthorizations, and usages
- Perusal of logged data

This manual is written to assist users of the ACI desktop to perform the tasks listed above and to assist system administrator in managing users.

Desktop Layout

The ACI desktop consists of distinctive areas identified in the illustration below.



- **1** – The **Title Bar** displays the name of the desktop.
- **2** – The **Menu Bar** provides access to available functions and application windows.
- **3** – The **Toolbar** contains buttons for common functions, such as login, logoff, and online help.
- **4** – The **Navigation Tree** provides a hierarchical view of the menu bar.
- **5** – The **Application Area** contains opened application windows.
- **6** – The **Status Pane** contains informational messages about the activity between the desktop and servers. This area by default displays the most recent message. The last fifty messages are accessible using the scroll bar (**7**).

User Interface Framework

The user interface framework is a collection of Java classes, interface applications, rules, guidelines, recommendations, and styles that are used as a template for building and supporting ACI desktop applications. The components of the user interface framework include:

- User interface clients
- User security server
- Web servers
- Version Checker server
- Online help

These components communicate with each other and with applications running on the application host server using a variety technologies. XML messages are passed to application servers on the host using Transmission Control Protocol/Internet Protocol (TCP/IP).

Java-based Remote Method Invocation (RMI) is used for ACI desktops and Web server clients to communicate with servers, and for servers to communicate with the user security server. Web servers communicate with the user security server.

The user interface framework provides the following common desktop functionality and support:

- Common functions, such as logging on and off the desktop, available through the File menu.
- Online help that is context sensitive.
- Comprehensive user security configuration support that allows for controlling user access to windows (screens) and functions.
- Fail over support for user security.
- Automatic version checking upon logon including support for either automatic or user prompted configuration updating.

Each web server is responsible for managing communication among desktop clients and the User Security server. Multiple web servers can be available in groups and are configured for the desktop using the local.cfg file. By defining groups, users can select web servers as applicable.

Communication Security

Connections among ACI desktops, web servers (e.g., WebGate), user security servers, and application servers on the host can be secured with Secure Sockets Layer (SSL).

Certificates are used to authenticate servers to desktop clients, and optionally authenticate clients to servers. Public key cryptography is used to encrypt messages sent among clients and servers.

Note: SSL is configured using SSL specific properties defined using the Application Configuration window (**System Operations > Server Management > Application**). Refer to the *ACI Java Server Framework User Guide* for more information.

The following Java™ Archive files provide the support needed for SSL:

- Jcert.jar
- Jnet.jar
- Jsse.jar
- UIFSSLKeys.jar, which contains the default keystores.

Certificates and private keys used for encryption and authentication are maintained in protected files called keystores. These files vary by application and are identified by .sto.

User Security Server

The user security server authenticates and authorizes users, creates and maintains active user sessions, maintains the access level for each user, and assigns tickets. Host applications access the user security server to obtain authorization to complete a function initiated by an authenticated user of the ACI desktop.

For authentication, an individual must provide a user ID and password. This information is passed to the user security server, which checks the information against the user security database to determine whether the individual can access the application. This authentication includes the requirement that the user ID be defined in the user security database and the password must match that recorded for the ID. In addition, the user's security group and password group restrictions are checked. Security groups and password groups are discussed later in section 5.


If a user meets the authentication requirements, the user security server establishes an active session for the user and assigns a *ticket*. The ticket consists of a authorization ID that is used throughout the user's session for authorization checking by the user security server. Tickets cannot be viewed using the ACI desktop. Tickets automatically expire when a user logs off the desktop or is disconnected, such as in the event of a timeout. Users cannot access the functionality of the desktop without a ticket.

User authorization is the validating of each activity initiated by a user. During user authorization the user security server compares the activity initiated by a user to the user's security profile, which defines the functions (i.e., Delete, Save, and View) that a user can perform. This ensures that a user does not perform an activity not authorized by the user's security configuration.

Fail Over Support

Multiple User Security servers can be configured to access a shared user security database. In the event a user security server is not available, a web server automatically accesses another user security server from the list of configured servers.

In the illustration below, two selectable web servers have access to two User Security servers and both servers are accessing the same shared security database. In the event User Security₁ fails, the web servers still have access to the user security database through User Security₂; thus, providing access to the same database and allowing clients connected the web server group uninterrupted access to the user security database.



Overview of Windows (Screens), Applications, and Tasks

The term *window* is used in documentation and online help. This term relates to a collection of graphical user interface (GUI) components (i.e., buttons, fields, field names, tabs, buttons, tables, trees, and messages) that provide access to a particular application, function and data source(s).

Each window is managed by a particular application server on the host. The applications available (therefore, the windows available) depend on the ACI desktop configuration and user security access permissions.

An application (and the corresponding window) is identified by a task ID. Tasks available on a desktop can be viewed in the Task ID selectable field located on the Permissions tab of the User Security Role Configuration window (**Configure > User Security > Role**).

Note: ACI desktop windows are listed in Appendix A. Task IDs are listed in Appendix B.

User Configuration and Management

Information about the configuration and management of users of the ACI desktop is presented in two sections:

- User Configuration, section 3, which includes:
 - User configuration security overview
 - Distributed security administration (DSA) overview
 - Steps to add a user to the ACI desktop
- User management, section 4, which includes:
 - User status settings
 - User sessions monitoring and control
 - Password and password group control

Default Users

Security Note: Change passwords of default users immediately after installing the desktop. Changing the default user passwords is required to meet Payment Card Industry (PCI) data security standards.

BASE24-es

The **security administrator** (SecAdmin) has access to the user security windows from which additional administrators (profiles) can be configured.

User Name: SecAdmin
Password: SecAdmin01
Role: SecAdminRole

The **system administrator** (SysAdmin) has access to most of the functionality of the desktop, including all TSS, user security, and user interface framework windows and functions.

User Name: SysAdmin
Password: SysAdmin01
Role: SysAdminRole

TSS

The **Transaction Security Services system administrator** (TSSSysAdmin) has access to all TSS windows and functions available on the desktop, including the user security and user interface framework windows and functions.

User Name: TSSSysAdmin
Password: TSSSysAdmin01
Role: TSSSysAdminRole

The **Transaction Security Services administrator** (TSSAdmin) has access to all TSS and user interface framework windows and functions, except for the user security windows and functions.

User Name: TSSAdmin
Password: TSSAdmin01
Role: TSSAdminRole

Configuration Files

The following configuration files in the user interface framework are used by the desktop:

- The usec.cfg for configuring user security.
- The local.cfg for configuring the local desktop client.
- The user preferences configuration files (*username.cfg* and *networkname.cfg*). The names of these files vary per the user names and network names.
- The global.cfg and globalprefs.cfg configuration files that define global properties that can be used in the other configuration files.
- The sound.cfg for desktop sounds.

Configuration files contain ASCII formatted key-value pairs (properties) grouped within sections. Section names are enclosed in square brackets “[]”. Keys and values are separated with an equal sign (“=”). Section names and key names are case-insensitive and can be upper case, lower case, or both.

Many local properties can be defined globally across all desktops via the global configuration property file. Also, if a configuration property is not defined in the local configuration file, the desktop checks for an entry in the global configuration file.


2: Basic Functions

This section provides information about functions that can be performed from the ACI desktop. These functions are available on the File menu.

Start the Desktop

Each desktop session is started by running the **RunDesktop.bat** batch file; however, the node controller and application servers need to be running before the desktop can start.

1. Generally, the RunDesktop.bat file is configured during installation to be accessed through a shortcut located on a client desktop or a menu, such as shown below.



2. When the desktop is started, it contacts the applicable servers and configuration files. Messages about this contact activity are displayed in a desktop console similar to the illustration below.

```

C:\_ACI\ES\Desktop>rem argument 2 is the optional parameter (e.g., -Q for quiet
node)


C:\_ACI\ES\Desktop>echo copy "C:\_ACI\VersionChecker\VerChk.jar" "C:\_ACI\Versio
nChecker\vc-temp.jar"
copy "C:\_ACI\VersionChecker\VerChk.jar" "C:\_ACI\VersionChecker\vc-temp.jar"

C:\_ACI\ES\Desktop>copy "C:\_ACI\VersionChecker\VerChk.jar" "C:\_ACI\VersionChe
cker\vc-temp.jar"
1 file(s) copied.


C:\_ACI\ES\Desktop>echo "C:\_ACI\jre1.3.1_01\bin\java" -classpath C:\_ACI\Versio
nChecker\vc-temp.jar -DLocalConfig="C:\_ACI\ES\Desktop\local.cfg" versionchecker.
client.JarVerChecker
"C:\_ACI\jre1.3.1_01\bin\java" -classpath C:\_ACI\VersionChecker\vc-temp.jar -DLo
calConfig="C:\_ACI\ES\Desktop\local.cfg" versionchecker.client.JarVerChecker

C:\_ACI\ES\Desktop>"C:\_ACI\jre1.3.1_01\bin\java" -classpath "C:\_ACI\VersionChe
cker\vc-temp.jar" -DLocalConfig="C:\_ACI\ES\Desktop\local.cfg" versionchecker.cli
ent.JarVerChecker
Logging to location: C:\_ACI\ES\Logs\VerChkCli
Loading Config...
JAR version checking in progress...
  
```


3. The Version Checker server is automatically accessed to determine whether new and updated JAR files are available from the Server Repository. If JAR files on the local desktop need updating, the Version Checker Client window (an example is shown below) is displayed for users to download new and updated JAR files. The Version Checker and the client window are discussed in section 6.



4. After the desktop establishes contact with the applicable servers and JAR files have been downloaded, the desktop displays the Log In window entry of a user ID (name) and password. The User Name field on the Log In window defaults to the ID of the most recent user to log on to the desktop.




5. The desktop opens after a valid user ID (name) and password combination has been provided and authenticated by the user security server. The default view of the desktop is shown below.



Log On (In)

To log on, select the Log In function located on the File menu (**File > Log In**), the Log In button () on the toolbar, or navigation tree.




After a successful logon (authenticated user) the desktop provides access to those applications (windows) that system administration has assigned to the user (i.e., the permissions and permission groups of the user's profile).

Authenticated users are issued a ticket that consists of an authorization ID and expiration timestamp. The user security server uses this ticket information during the active session; however, the ticket is not viewable on the desktop for security purposes. Each session is assigned a unique session number used by the user security server for authorization purposes.

In addition to the above, session and window (UI) timeout values are initiated and tracked during a session. A timeout is a defined period of inactivity. Timeout limits are defined in the security groups assigned to users.


Security Error

If the user name and password are not correct or the user name has been disabled or does not have valid access at the time of login, the user security server does not allow the user access to the desktop. In this case a security error message (shown below) is displayed. The error message is purposely vague so not to indicate which information (name or password or both) is incorrect.



Security Warning

A security warning, such as the example below, is displayed upon a successful logon if there were one or more unsuccessful logon attempts before the successful logon.




Concurrent Sessions

The number of concurrent active sessions allowed for a user is limited to a maximum as defined in the Security Group of the user's profile. A possible scenario in which a user might have concurrent active sessions is by logging on from another terminal without logging off from an active session that was started at another terminal.


User has Less than Maximum Number of Allowed Active Sessions

This version of the Session Information dialog is displayed if a user has one or more existing active sessions when logging on, and this number of sessions is fewer than the maximum number as defined in the user's Security Group.



User has the Maximum Number of Allowed Active Sessions

This version of the Session Information dialog is displayed if a user upon login has already reached the maximum number of allowed active sessions defined in the user's Security Group.




Log Off (Out)

To log off, select the Log Out function located either on the File menu (**File > Log Out**), the Log Out button () on the toolbar, or navigation tree.

Logging off does not close the desktop. To close the desktop, select **File > Exit**.


When logging off, the desktop displays the Confirm Logout prompt. Click **Yes** to proceed or **No** to cancel.




Change a Password

To change a password, log on to the desktop and select the Change Password function (**File > Change Password**) to display the Change Password window.

Certain password restrictions and requirements apply in the User Configuration section of this manual.




If the new password does not meet one or more password requirements or violates a password restriction, the Password Error message shown at right is displayed.



If the new password is not entered correctly in the Verify New Password field on the Change Password window, the Password Error message shown at right is displayed.



If the password is successfully changed, the Password Information message shown at right is displayed.




Set General User Preferences

Use the General tab on the User Preferences window (**File > Preferences**) to set the following user preferences.




Descriptions of general preferences are shown on the following page.

Preference	Description
Confirm Deletes	Indicates whether the desktop displays a confirmation dialog box before a delete function is processed.
Confirm non-editable row paste	Displays a dialog box indicating that an attempt was made to paste a copied table row onto a non-editable row.
Confirm non-matching row paste	Displays a dialog box indicating that an attempt was made to paste a copied table row onto a table row that has a different number of table cells.
Confirm Updates	Indicates whether the desktop displays a confirmation dialog box that requires a response before an update function is processed.
Currency Format Locale	Sets whether the default currency is obtained from the desktop configuration or user configuration settings.
Debugging Enabled	Enables the writing of debug messages to a debug file (e.g., DeskTop.dbg).
Frame Open Indicator	Indicates whether the Frame Open Indicator (shown below) is displayed in the desktop toolbar while a window is opening. 
Language	Displays menu functions, dialog box text, messages, and field names in the selected language, if the selected language is defined in the properties file for a window. This also allows access to available localized online help (online help provided in a different language or dialect).
Navigation Tree	Sets whether the navigation tree is displayed upon desktop startup. If checked, the navigation tree is initially displayed. If not checked, it is initially hidden.

Preference	Description
New Window Position	Sets the position of a window when opened as follows: • Bottom • Cascaded • Centered • Frame specified • Left • Right • Top • Top left
Pre-Show Frame	Indicates whether a blank window, such as the example below, is shown while a window is initializing (being opened). 
Screen Print Orientation	Sets the default print orientation to either portrait or landscape.
Status Pane	Indicates whether the status pane is displayed.
Toolbar	Indicates whether the toolbar is displayed.

Set Error Notification Preferences


Use the Error Notification tab on the User Preferences window (**File > Preferences**) to set error notification preferences.



- The Border drop-down list, if checked, sets the border color of fields that are in error.
- Check the Status check box to have error text displayed in the status pane of windows.
- Check the Tooltip check box to display error text in tooltip text. When a window component is in error, the tooltip text associated with the component changes to the error message. Once the error is corrected, the tooltip text reverts back to its normal text. Tooltip text is text that appears in a pop-up window over a field or button.
- Check the Dialog check box to have error text displayed in a dialog box.
- Check the Trap Focus check box to make errors modal, that is, require errors to be resolved prior to allowing focus on (access to) another window or tab on the window.

Set Sound Preferences

Use the Sound tab on the User Preferences window (**File > Preferences**) to set the sound played during certain events (as selected in the Events field).



Use the Themes list to select the sound group to apply to the selected event(s). Themes are defined in the sound.cfg configuration file located in the desktop.jar. Default Windows sounds are stored in the Framework\I18N\sounds\windows folder in the **desktop.jar**. The theme selected is stored in the configuration file of the logged on user.

Use the Events box to select an event to be associated with a sound file.

Use the Location field to select the sound file, such as a .AU file (Java) and .WAV file (Windows), to associate with the selected event.


Send a Snapshot

Use the Send Snapshot (**File > Send Snapshot**) function to send an E-mail message (using the Send Snapshot window shown below) about the desktop configuration and a log record (DeskTop.log) of desktop activity to system administrators. The DeskTop.log file is an ASCII text file that contains information about recent desktop activity that is pertinent to system administrators.

The configuration information is sent as a comma separated values (CSV) file that can be opened by many ASCII readers and spreadsheet applications. The configuration information contains the following information:


- User ID and machine (client workstation) ID
- JAR versions installed
- Local configuration settings
- Version Checker server settings
- Global configuration settings
- User preferences
- Global preferences

The Send Snapshot window:




Connect to a Web Server

During startup, the ACI desktop attempts to connect to the default web server, which is the last web server to which the ACI desktop last connected. If multiple web servers are available, a user can access the Connection window (**File > Connection**) to select an alternate.



The Connection window displays a selectable list of available web servers. Choose a web server and click the OK button.




If a web server is selected that accesses a different shared user security database, any existing active sessions for the user are terminated. Also, the port to which a web server connects must be available (i.e., not used by another system or application); otherwise, a connection error is encountered.

Print Functions

The File menu provides access to the following print-related functions:

- Use the Print Preview (**File > Print Preview**) function to display a selected page, text, or window in a separate print preview window. This shows the selected item as it will appear when the Print function is performed.
- Use the Print function (**File > Print**) to print a selected page, text, or window.
- Use the Print Screen (**File > Print Screen**) function to print the window in focus.
- Use the Page setup (**File > Page Setup**) to set print parameters, such as paper size, source, orientation (portrait or landscape) and margin sizes. The actual Page Setup window displayed is that of the desktop operating system. An example Page Setup window is shown below.



Exit from the Desktop

Use the Exit function (**File > Exit**) to close the ACI desktop. This is different from the Log Out (Logoff) function, which doesn't close the desktop.


Note: A user does not need to be logged on to exit. Also, if a user exits without logging off, the user is automatically logged off from the desktop.

Display Framework Version Information

Access **Help > About** to display desktop version information as shown below:



Click **Versions** to display detailed version information as shown below:



ACI Worldwide Inc.


3: User Configuration

The ACI desktop provides access to an integrated user security environment in which each user must be defined in a user security database. This section provides an overview of user security and describes the procedures used for configuring users.

This section consists of two parts: an overview of user security and steps about how to add a user.


User Security Configuration Hierarchy

The user profile is central to establishing a user's access level to the ACI desktop. Each user is assigned a unique profile that consists of the integral components of user security, some of which, such as security and password groups, can be shared among multiple users. The hierarchy of a user profile is shown below.



User Security Configuration Window Usage

User profiles are maintained from the ACI desktop using various user security windows. The hierarchy of a user profile and the names of the windows used to maintain user profiles is shown below.



All user security windows are accessed at **Configure > User Security**.

User Profiles

Each user of the desktop is assigned a **user profile** consisting of the following configuration components:

- User ID — A unique character string used to identify a user.
- General user information — Name and contact information about a user.
- User status — Set by the user security server in response to some action, such as too many bad logon attempts, or by security administrative personnel.
- Role(s) — One or more sets of permission groups.
- Security group — A unique ID that defines a set common user security access restrictions.
- Password group — A unique ID that defines a set common user password restrictions.

Roles

A role defines the level of a user's access to the desktop. Each role identifies a job function, such as security administrator, system administrator, manager, and end user, and consists of one or more permission groups. Roles apply a set of permissions, tasks, and functions to users.

A role can contain one or more permission groups. A permission group can contain one or more permissions. Each permission is associated with a task (window application) and defines the functions (e.g., delete, save, send, and view) allowed for that task.

Permission Groups

A permission group is a collection of selected permissions that is assigned a unique identifier (the permission group ID) and a description of the purpose or use of the group.

Permissions

Permissions define specific access to a window. Each permission consists of a single task (by task ID), the functions that can be performed within the task, a unique ID (the permission ID), and a description of the purpose or use of the permission.

Field Filters

Field filters restrict a user's access to field values by defining either a single value, multiple values, or a range of values allowed.

Task IDs

Each task consists of a unique identifier and a group of functions (e.g., delete, save, send, and view) and corresponds to a window on the ACI desktop. Available task IDs and functions for each task ID are provided on the Permissions tab of the User Security Role Configuration window and are used to create permission IDs. Task IDs can be used in multiple permissions.

Passwords and Password Groups

A user's password is stored in the user security database in encrypted form using a Secure Hash Algorithm (SHA1) that is not reversible ensuring that passwords cannot be extracted in clear form from the database.

Password Restrictions

The following restrictions apply to all passwords:

- Characters cannot be repeated sequentially. For example, the string "ABBA" is not valid because of the repeating "B." However, "ABAB" is valid if the minimum length defined in the password group has been met.
- The password cannot be the same as the user ID. For example, a user with the ID "user02" cannot use "user02" as the password.
- A user's password must meet the requirements (discussed below) defined in the password group assigned to the user.

Password Group Requirements

Password groups consist of password requirements that are imposed on all user passwords assigned the group. A password group consists of the following password requirements as configured using the Password Groups tab on the User Security Group Configuration window.

- The number of days prior to a password expiration on which the desktop displays a warning dialog prompting a user to change the password.
- The maximum number of days a user can use a password.
- The minimum password length.
- The maximum password length.
- The minimum number of numeric characters required in each password.
- The minimum number of alphabetic characters required in each password.
- The maximum number of old passwords retained for each user (users cannot use retained old passwords).
- The maximum number of password changes allowed during a 24-hour period.

Security Groups

Each user must be assigned one and only one security group. However, since a security group can be assigned to multiple users, the security group simplifies the management of user security, assigns passwords by group, and assists in implementing distributed security administration, which is discussed later in this section.

Each user security group consists of the following common user security access restrictions that apply to all users assigned the security group:

- The time each day a user can log on to the desktop.
- The time each day a user must be logged off the desktop and, after which, can no longer log on to the desktop.
- The days of the week on which a user can log on to the desktop.
- The maximum number of invalid logon attempts allowed for each user. If this value is reached, the user's status is disabled by the user security server.
- The number of minutes, if set, after which the number of invalid logon attempts is reset to zero.
- The maximum number of active sessions allowed for a user.

When a user fails to log off correctly from the desktop or if a system outage occurs during a user's active session, the user security database still maintains a record of the active session, thus resulting in a user being prompted that the maximum number of active sessions has been reached. Therefore, if the

maximum number of active sessions has been reached by a user attempting to log on to the desktop, the user is presented with an option to stop one or more of the active sessions.

- The number of seconds of user inactivity after which the user is automatically logged off the desktop (this is called a **session timeout**).
- The number of seconds of terminal inactivity after which the desktop is disabled and any logged on user is logged off (**UI timeout**).
- The number of days a user's ID can be inactive (not used) after which the user ID status is disabled by the user security server.
- The password group ID defining password requirements applied to all users of the security group.

Distributed Security Administration (DSA)


Each installation is configured with a system administrator and security administrator. The system administrator has access to all applications of the desktop. The security administrator has access to the user security windows. Distributed security administration involves the security administrator configuring other, lower-level, administrators that are assigned a limited set of permissions.

Distributed security administration is enabled by setting the **OwnerIDSupport** property in the usec.cfg file to true.

DSA Setup

Distributed security is implemented by the top-level security administrator by configuring applicable roles, assigning these roles as necessary to security groups, and assigning the security groups to other, lower-level, system administrators.

The top-level security administrator can set up tiers of other system administrators who are limited to a **security domain**, which is a set containing a security group, password group, roles, and permissions as defined by a security role ID. At this level, a role ID is used to restrict users within the domain to a defined set of permissions (including permission groups), tasks and filters. This methodology can be used to create system administrator groups and departments as shown in the illustration below.



For example, the system administrator assigned Role1 can create user profiles or groups of user profiles having roles that can contain only those permissions, permission groups, tasks, and filters defined for Role1.

With distributed security administration, users, including administrators, cannot access the users and roles of other security domains.

Steps to Add a User

Note: Some steps have additional steps (i.e., steps 3.1 – 3.3 and 4.1 – 4.4) that might not be required depending on the extent to which a complete user security system has been configured.

- ❑ Step 1.0: Configure a Password Group
- ❑ Step 2.0: Configure a Security Group
- ❑ Step 3.0: Configure a User Role
 - Step 3.1: Configure Field Filters
 - Step 3.2: Configure Permissions
 - Step 3.3: Configure Permission Groups
- ❑ Step 4.0: Configure the User's Profile
 - Step 4.1: Set the User's Status
 - Step 4.2: Assign a Security Group
 - Step 4.3: Enter Information about the User
 - Step 4.4: Set the User's Password
 - Step 4.5: Assign Roles

Usage Note: To ensure that changes are implemented in the user security database, click Save () each time a step has been completed.

Tip: If a new user is to be based on an existing user profile, that is, the password group, security group, and roles are already configured as necessary for the new user, go directly to step 4.0 and read the Tip provided in the step.

Step 1.0: Configure a Password Group

Use the Password Group tab on the User Security Group Configuration window to configure a password group.

The screenshot shows the 'ACI User Security Group Configuration' window with the 'Password Group' tab selected. The 'Password Group' dropdown is set to 'pswd_grp_1'. The 'Description' field contains 'Default password group for end users.' The password requirements are configured as follows:

Minimum Length	6	Lifetime Days	30
Maximum Length	16	Old Password Cache	6
Required Numeric Characters	0	Expire Pre-Warn Days	7
Required Alpha Characters	2	Changes Per Day	6

A status bar at the bottom indicates: '0 - 4:18 PM > Password group retrieved.'

In the example above, the password group **pswd_grp_1** is shown. This group is described as the default password group for end users. The password requirements are set in the fields provided on the tab.

Password groups are assigned to users (their profiles) through security groups. Therefore, a password group must be assigned to a security group using the Security Group tab of the User Security Group Configuration window. The security group is then used in user profiles.

Step 2.0: Configure a Security Group

Topics in this step to consider are listed below. These topics are discussed on the following pages.

- ❑ UI and Session Timeout Considerations
- ❑ System Administration Role Filter (Owner ID)

Use the Security Group tab on the User Security Group Configuration window to configure a security group.

The screenshot shows the 'ACI User Security Group Configuration' window with the 'Security Group' tab selected. The configuration includes the following fields and settings:

- Security Group:** end_user_sec_grp
- SysAdmin Profile:** (empty dropdown)
- Description:** Security group for end users.
- Password Group:** pswd_grp_1
- Allowed Time and Days:**
 - Begin:** 08:00 am
 - End:** 08:00 pm
 - Days:** Sun (unchecked), Mon (checked), Tue (checked), Wed (checked), Thu (checked), Fri (checked), Sat (unchecked)
- Bad Logins Allowed:** 11
- Reset Bad Logins:** 3000 seconds
- Sessions Allowed:** 10
- UI Timeout:** 18000 seconds
- Inactive Days Allowed:** 365
- Session Timeout:** 36000 seconds

The status bar at the bottom indicates: 7 - 10:59 AM > Password group retrieved.

In the example above, the configuration for the **end_user_sec_grp** security group is shown. This group defines standard authentication requirements for users. The password group **pswd_grp_1** is assigned to this security group. As a result, the password requirements defined by **pswd_grp_1** apply to all users of this security group. Users assigned this security group cannot log on to the desktop before 8:00 am and must be logged off by 8:00 pm. Also, users cannot log on to the desktop on Sundays and Saturdays.

UI and Session Timeout Considerations

A security group defines both UI and session timeouts. These timeouts are defined in units of seconds using the Security Group tab of the User Security Group Configuration window. The two timeout types are discussed below and should be considered when configuring a security group.


A UI timeout occurs after a duration of desktop inactivity defined in the UI Timeout field. When a UI timeout event occurs, the user no longer has access to the desktop and any open windows; however, the user's session and the open windows are not closed. When a UI timeout event occurs, the desktop displays the Verify Password dialog (shown below) in which the user must provide a valid password to restore access to the desktop and any open windows. The user also has the option to log out at this time.



UI timeouts only occur if the security group to which the user belongs has a configured UI timeout limit greater than zero. Entering a zero ('0') in the UI Timeout field implies no limit of desktop inactivity.

A session timeout occurs after a duration of desktop inactivity defined in the Session Timeout field. When a session timeout event occurs, the user is automatically logged off the desktop and the user must log on (open the Log In window and provide a valid user name and password combination) to obtain access to the desktop. Any windows open upon a session timeout are closed.

When the user's session times out, the desktop displays the following Session Logout message.



If the user's session expires while the Verify Password dialog is displayed and the user has not provided input, the user is still logged out and the user is no longer able to verify the password. All windows are closed, but the desktop remains open.

Session timeouts only occur if the security group to which the user belongs has a configured session timeout limit greater than zero. Entering a zero ('0') in the Session Timeout field implies no limit of desktop inactivity.

Note: If system administrators configuring a security group want to use UI timeouts in an effective manner, then the session timeout value must be greater in terms of minutes than the UI window timeout value. This is because if the session timeout value is less than the UI timeout value, users in the security group will be logged off the desktop (upon a session timeout event) prior to a UI timeout event.

System Administration Role Filter (Owner ID)

When the **OwnerIDSupport** property in the usec.cfg file is set to the true, the Security tab on the User Security Group Configuration window displays the SysAdmin Profile selectable field, as shown below.

ACI User Security Group Configuration

Security Group **Password Group**

Security Group: end_user_sec_grp SysAdmin Profile: []

Description: Security group for end users.

Password Group: pswd_grp_1

Allowed Time and Days

Begin: 08:00 am End: 08:00 pm

Sun Mon Tue Wed Thu Fri Sat

☐ ☒ ☒ ☒ ☒ ☒ ☐

Bad Logins Allowed: 11 Reset Bad Logins: 3000 seconds

Sessions Allowed: 10 UI Timeout: 18000 seconds

Inactive Days Allowed: 365 Session Timeout: 36000 seconds


7 - 10:59 AM > Password group retrieved.

An existing role ID can be assigned to a security group using the SysAdmin Profile field. Since a role defines a set of permissions (permission groups), tasks IDs and field filters, the role ID at this level limits access to permissions and permission groups that can be configured for users by administrators assigned the security group. To assign a role ID as a filter for a security group, select the role ID in the SysAdmin Profile field.

If a system administration role profile is selected for a security group, only those permission groups, permissions, and tasks defined for the role are accessible to users assigned the security group.

Step 3.0: Configure a User Role

To configure a user role, use the Roles tab on the User Security Role Configuration window.



If the available permission groups meet existing needs, enter or select the role ID in the Role field, add or modify the description of the purpose of the role, and select the applicable permissions groups (permission groups can be selected and deselected using the check boxes for each group), then go to Step 4.0: Configure the User's Profile. **Note:** Permissions not defined within your security domain are not available.

If one or more permission groups need to be configured, the following steps might also need to be performed.

- ❑ Step 3.1: Configure Field Filters
- ❑ Step 3.2: Configure Permissions
- ❑ Step 3.3: Configure Permission Groups

Step 3.1: Configure Field Filters

Field filters are configured using the Filters tab on the User Security Role Configuration window, which is shown below, and are applied to a user's profile through permissions.

The screenshot shows the 'ACI User Security Role Configuration' window with the 'Filters' tab selected. The window has a title bar with standard OS controls and a toolbar with icons for save, print, delete, and other functions. Below the toolbar are four tabs: 'Roles', 'Permission Groups', 'Permissions', and 'Filters'. The 'Filters' tab is active, displaying the following fields and controls:

- Filter ID:** A dropdown menu showing 'ExampleFilter'.
- Field ID:** A dropdown menu showing 'InstitutionID'.
- Description:** A text input field.
- Filter Type:** Three radio buttons: 'Range' (unselected), 'Single Value' (unselected), and 'Multi-Value' (selected). To the right is an 'Add Value' button.
- Filter Settings:** A section containing two list boxes and four arrow buttons.
 - All Field Values:** A list box containing the values 1000, 1005, 1006, 1009, and 1010.
 - Selected Field Values:** An empty list box.
 - Arrows:** Four buttons between the list boxes: a right arrow (→), a double right arrow (⇒), a left arrow (←), and a double left arrow (⇐).

At the bottom of the window, a status bar displays the text '0 - 2:09 PM > Filter read.'.

Field filters consist of the following elements:

- ❑ Unique identification (the Filter ID field)
- ❑ Field ID
- ❑ A description of the purpose and use of the filter
- ❑ One or more field values, which can be a single value, multiple values, or a range of values.

The format of the Filter Settings area is dependent upon the filter type selected, whether Range, Single Value, or Multi-Value.

If **Range** is selected, begin and end values must be entered:

The screenshot shows a dialog box titled "Filter Type" with three radio buttons: "Range" (selected), "Single Value", and "Multi-Value". Below this is a section titled "Filter Settings" containing two text input fields labeled "Begin Value" and "End Value".

If **Single Value** is selected, a single filter value must be selected or entered:

The screenshot shows the same "Filter Type" dialog box, but now the "Single Value" radio button is selected. In the "Filter Settings" section, there is a single text input field labeled "Filter Value" containing the value "1000".

The values available in the Filter Value field are those that have been configured using the applicable configuration window. For example, for the InstitutionID field ID, the values shown in the Filter Settings area are those institution IDs that have been configured using the Institution Configuration window.

Tip: Use the asterisk (“*”) to select all current and future field values.

If **Multi-Value** is selected, values must be selected and moved from the All Field Values field to the Selected Field Values field.

The screenshot shows the "Filter Type" dialog box with the "Multi-Value" radio button selected. To the right of the radio buttons is a text input field and an "Add Value" button. Below the "Filter Settings" section, there are two list boxes: "All Field Values" on the left and "Selected Field Values" on the right. The "All Field Values" list contains the values "*", "0001", "0002", "0003", "1000", and "1002". Between the two list boxes are four buttons: a right arrow, a double right arrow, a left arrow, and a double left arrow. The "Selected Field Values" list is currently empty.

To add or remove field values, use the following buttons provided on the tab to perform the desired task:

Button	Task
	Add the selected field value(s) from the All Field Values field to the Selected Field Values field.
	Add all available field values from the All Field Values field to the Selected Field Values field.
	Remove the selected field(s) value from Selected Field Values field back to the All Field Values field.
	Remove all field values from Selected Field Values field back to the All Field Values field.


To select a value, click on the value. Selected values have a modified background color. To select multiple values, press down the **Ctrl** key while selecting values.

The values shown in the All Field Values field are those that have been configured using the applicable configuration window. Use the asterisk (“*”) to select all current and future field values. For example, for the InstitutionID field ID, the values shown in the Filter Settings area are those institution IDs that have been configured using the Institution Configuration window.

To add a value not available in the All Field Values field, enter the value in the text entry field to the right of the Filter Type area and click the Add Value button.

Step 3.2: Configure Permissions

Use the Permissions tab on the User Security Role Configuration window to create permissions and permission group IDs.



Permission IDs

A new permission ID can be created (entered) or an existing permission ID can be selected. Permissions are available on the Permissions Group tab for selection when configuring a permission group.

The description is to state the purpose of the permission and any special information.

Tasks IDs

Each task ID corresponds to an ACI desktop window. **Note:** Task IDs cannot be created using the ACI desktop.

Functions

The functions that a user can perform on a window (task) are defined for each permission on the Permissions tab. A function is selected by entering a check mark in the functions check box. Functions include, but are not limited to, Delete, Save, Send, and View. The available functions vary by task ID.

Field Filters

If a task ID refers to a window that contains a field or fields that are filterable, the Permissions tab will list the field ID(s) and provide a selectable list of filter IDs that can be selected and applied to the permission.

The field IDs **InstitutionID** and **Issuer** are shown in the example below for the Institution Configuration window.

The screenshot shows the 'ACI User Security Role Configuration' window with the 'Permissions' tab selected. The 'Permission ID' is 'somePermissionID' and the 'Task ID' is 'someTaskID'. The 'Description' field contains 'Description and use information about somePermissionID.'.

Under the 'Functions' section, there are two filterable fields:

- InstitutionID**: A dropdown menu showing 'ExampleFilter'. A yellow callout box points to it with the text 'These are field IDs.'.
- Issuer**: A dropdown menu showing '--none--'. A yellow callout box points to it with the text 'No filter ID has been selected for the Issuer Field ID as indicated by --none--.'.

Below these fields is a 'Filter Description' section with the text 'Filter info'.

A yellow callout box points to the 'ExampleFilter' dropdown with the text 'This is a filter ID.'.

The status bar at the bottom shows '16 - 1:25 PM > Permission read.'


Step 3.3: Configure Permission Groups

To configure a new or existing permission group, use the Permission Groups tab on the User Security Role Configuration window. This tab provides a Permission Group field in which a new permission group ID can be entered or an existing permission group can be selected.

Available permissions, as defined per your security domain, are provided on the tab. Permissions are added or removed from a permission group by selecting (entering a check mark) or deselecting (removing a check mark) in the appropriate checkbox.

Permission Information

A description of each permission along with the Task ID assigned to the permission and the allowed functions can be displayed in the Permission Description section of the Permissions Groups tab. To display this information, right click on the desired permission and select Get Info on the pop-up menu. In the example above, the permission FullProcessControl has been selected and information obtained using the Get Info function is displayed in the Permission Description section.



Step 4.0: Configure the User's Profile

To configure a new user (user profile), display the General tab of the User Security Profile Configuration window, enter the user's unique ID in the User ID field and perform the following steps:

- ❑ Set the user's status
- ❑ Assign a security group
- ❑ Enter information about the user
- ❑ Set the user's password
- ❑ Assign roles to the user

Tip: To add a new user whose profile is based on an existing user profile, display the user profile that is to be used as a template and enter the new user ID.

Note: When the Save button is clicked for a new user, the desktop displays the New User's Password window, which is described in Step 4.4.

Step 4.1: Set the User's Status

User status options:

Active	= Open and active.
Closed/Admin	= Closed without incident.
Closed/Inactive	= Closed, by the User Security server, due to inactivity.
Disabled/Admin	= Disabled, for security reasons, by authorized personnel.
Disabled/System	= Disabled, for security reasons, by the User Security server (e.g., maximum number of log on attempts has been reached).
Temporary	= User can access the desktop for a predefined amount of time.

Step 4.2: Assign a Security Group

Security groups are provided in the selectable field next to the Security Group link. If a desired security group is not available, click on the link to access the User Security Group Configuration window to review existing security groups or configure a new security group. Only those security groups defined for your security domain are available.

Step 4.3: Enter Information about the User

Information about the user includes:

- ❑ Complete name information
- ❑ Contact information, such as phones, Fax and email address
- ❑ Employment information, such as department, manager and location

Step 4.4: Set the User's Password

To set a new user's password, click Save, after which the desktop displays the New User's Password window.

Note: The Password tab of the User Security Profile Configuration window is used for management of existing users, see section 5 for more information.

For users assigned a status other than Temporary, the desktop displays the version of the New User's Password window shown below. Indicate whether the user must change the assigned password during the next logon (or first logon for a new user), and the start date on which the user can logon to the desktop.



The dialog box is titled "ACI New User's Password". It contains the following fields and controls:

- New Password:** A text box with a masked password "*****".
- Verify Password:** A text box with a masked password "*****".
- Require password change:** A checked checkbox.
- New User Start:** A date selection box showing "Monday, March 15, 2004".
- Buttons:** "Ok" and "Cancel" buttons at the bottom.

When a new temporary user (i.e., user status being set to temporary) is created, the desktop displays the New User's Password window with the option to select the date the temporary user's access to the desktop expires as shown below.




The dialog box is titled "ACI New User's Password". It contains the following fields and controls:

- New Password:** An empty text box.
- Verify Password:** An empty text box.
- Require password change:** An unchecked checkbox.
- New User Start:** A date selection box showing "Wednesday, March 31, 2004".
- New User Expire:** A date selection box showing "Wednesday, March 31, 2004".
- Buttons:** "Ok" and "Cancel" buttons at the bottom.

Step 4.5: Assign Roles

Use the Roles tab on the User Security Profile window to assign (and remove) the roles defined for a user.



This tab displays all the user roles available within your security domain on the ACI desktop. Roles not defined within your security domain are not displayed. User roles assigned to a user are shown in the User Roles field. Available user roles not assigned to a user are shown in the All Roles field. To add or remove user roles from a user profile, select the role or roles and use the buttons provided on the tab to perform the desired task. The buttons are:

Button	Task
	Add the selected role(s) to the user profile (move from the All Roles field to the User Roles field).
	Add all available roles to the user profile (move from the All Roles field to the User Roles field).
	Remove the selected role(s) from the user profile (move from the User Roles field to the All Roles field).
	Remove all assigned roles from the user profile (move from the User Roles field to the All Roles field).

To select a role, click on the role. Selected roles have a modified background color. To select multiple roles, press down the **Ctrl** key while selecting roles.

If a particular role is not available or an existing role needs to be changed, click on the Configure Roles link to access the User Security Role Configuration window to configure a new or existing role.

Note: A user cannot change the role configuration for the profile (User ID) that was used to log on. In such situations, when the Roles tab is accessed for that User ID, the All Roles field and User Roles fields are inactive.


ACI Worldwide Inc.

4: User Management

System administrators can set the status, display and terminate active sessions, and expire passwords by password group of users within the administrator's security domain. This activity is performed from the user security windows as described in this section.

User Management Window Usage

The illustration below shows the hierarchy of a user profile and includes the name of the applicable window used to manage user profiles.



The User Security Profile Configuration window is mostly used for configuring a user profile; however, it can be used to view a user's active sessions, to change an existing user's status and to manage a user's password.

The User Security Control Management window is used to view and manage the active sessions for all users. The window can also be used to expire passwords by password group.

Set the Status of a User

The user security server maintains a status for each user. A user's status can be changed by the user security server if security and password group requirements have been violated. A user's status can also be changed by authorized users.

Use the General tab on the User Security Profile Configuration window to view and set a user's status.

ACI User Security Profile Configuration

User ID: end_user

General | Active Sessions | Password | Roles

User Status: Active (dropdown menu open showing: Active, Closed/Admin, Closed/Inactive, Disabled/Admin, Disabled/System, Temporary)

Security Group: end_user_sec_grp

First Name: [text box]
 Middle Name: [text box]
 Last Name: [text box]
 Department: [text box]
 Location: [text box]
 Manager: [text box]
 Email: [text box]

Work Phone: [text box]
 Mobile Phone: [text box]
 Fax: [text box]
 Create Time: 12/30/02 2:01 PM
 Last Login: 1/29/03 9:06 AM
 Last Failed Login: 1/28/03 9:42 AM
 Bad Login Tries: 0

3 - 11:27 AM > User info loaded.

Authorized users can assign the following status codes to a user:

- | | |
|-----------------|---|
| Active | = Open and active. |
| Closed/Admin | = Closed without incident. |
| Closed/Inactive | = Closed, by the User Security server, due to inactivity. |
| Disabled/Admin | = Disabled, for security reasons, by authorized personnel. |
| Disabled/System | = Disabled, for security reasons, by the User Security server (e.g., maximum number of log on attempts has been reached). |
| Temporary | = User can access the desktop for a predefined amount of time. |


Display Active User Sessions

When a user has logged on to the desktop by providing a valid user ID and password, the user security server creates an active session for the user. An active session contains the following information:


- ❑ The user's ID.
- ❑ The unique session number assigned by the User Security server.
- ❑ The workstation ID, such as a network ID or URL, from which the user has logged on to the desktop.
- ❑ The date and time the user began the session.
- ❑ The date and time the current session expires.

Information about active user sessions is available on two separate Active Sessions tabs. One tab is provided on the User Security Profile Configuration window and displays the active sessions for a selected user. The other Active Sessions tab is located on the User Security Control Management window and displays active user sessions for all users within a security administrator's security domain (security group to which the administrator has access).

Active User Session for a Selected User





Active User Sessions for All Users



Note: The active sessions of the application can change at any time; therefore, to update the list of active sessions click Refresh ().

Terminate Active User Sessions (Log off a User)


One or more active user sessions can be terminated (i.e., logged off) from either one of the two windows that are used to display active user sessions — the User Security Profile Configuration window and the User Security Control Management window. To log off one or more user sessions, display and select the user session(s) and click Logout Selected.



In the examples above, the user ID end_user has been selected as indicated by the modified background color. Clicking Logout Selected logs this user off the desktop.

Display Password History for a User

Authorized users can view a user's password change history, add or change a the user's password, and expire the user's current password by accessing the Password tab on the User Security Profile window and selecting the user's ID.



Change a User's Password

To change a user's password, display the Password tab on the User Security Profile Configuration window and select the user ID. Enter the new password in both the New Password and Verify Password text boxes and click Save (). If the change is successful, a confirmation message appears in the status pane of the window. Otherwise, an appropriate error message is displayed.


Expire a User's Password

To expire a user's password, display the Password tab on the User Security Profile Configuration window, select the user ID, and click Expire Password. If a user's password has been expired but a new password has not been defined, the user is prompted to create a new password on the next logon attempt.

Expire Passwords by Password Group

Authorized users can access a table that shows the password groups that have been assigned to security groups, and can expire all user passwords of users assigned to a password group.

Use the Password Maintenance tab on the User Security Control Management window to view password group usage and expire password groups.



In the example above, the password group named **pswd_grp_1** is used within the **end_user_sec_grp** security group. This row has been selected, as shown by the modified background color. Clicking the Expire Selected button disables the passwords for all users assigned to the **end_user_sec_grp** security group.

5: User Auditing

User audit is the logging of user activity to a data source for the purpose of reporting and monitoring the user activity.

Whenever a user of the desktop initiates and completes an activity (e.g., logon, logoff, password changes, delete, or save) from a window, a message that contains information about the user activity is written to the User Audit Log data source.

The audit message sent to the log data source can be one of the following:

- Header information only about the change
- Header information as well as detail information about the before and after images of the affected record

The application server writes this message directly to the USRAULOG data source or to the Audit_Store_and_Forward data source.

For information about enabling user auditing and setting the audit level for a desktop window, refer to the *ACI Java Server Framework Reference Guide* for information about audit properties, such as:

- `db.audit.db-service-name`
- `db.audited`
- `db.audited.db-service-name`

Internal XML Audit Message Format

The information stored in the USRAULOG data source is in XML format. The following example is an XML-formatted message containing user activity information.


```
<?xml version="1.0" encoding="UTF-8" ?>
<AuditReport>
  <AuditDetails row="0">
    <Audit_LoggingRq>
      <TimeStamp>TimeStamp Info</TimeStamp>
      <ContextDescr>InsertRq</ContextDescr>
      <Ticket>
        <UserID>User Profile ID</UserID>
        <SessionNumber>1</SessionNumber>
        <TerminalID>OMAUUSER/ip_addr</TerminalID>
      </Ticket>
      <ActivityGroup>
        <ActivityType>Table Function</ActivityType>
        <TableGroup>
          <TableName>Table</TableName>
          <KeyGroup>
            <Column>
              <ColumnName>Table Element</ColumnName>
              <BeforeValue />
              <AfterValue>New Value</AfterValue>
            </Column>
            <Key>
              <KeyColumn>
                <ColumnName>Key</ColumnName>
                <AfterValue>New Value</AfterValue>
              </KeyColumn>
            </Key>
          </KeyGroup>
        </TableGroup>
      </ActivityGroup>
    </Audit_LoggingRq>
  </AuditDetails>
</AuditReport>
```

The root element of the XML message is <AuditReport> that includes one or more <AuditDetails></AuditDetails> sections. <AuditDetails> contains important information: a time stamp (<TimeStamp>), Context information (<ContextDescr>), ticket information (<Ticket>), and activity information (<ActivityGroup>). Information related to the user and the user's session is included in the ticket. Information about the activity performed and the data source (table) affected is included in the activity group.

Note: Use an XML reporting tool such as XML Spy, MS-Access 2002, or Crystal Reports to evaluate and format the XML information as well as to generate reports.

User Audit Activity Reports

Activity reports for selected users can be initiated from the Audit Extract window (**Tools > Audit Extract**) and sent to a specified file in XML format. User activity is extracted from the USRAULOG data source for a specified user ID between a start date and time and an end date and time.



The reports provide the following information:

- Date and time of action.
- User ID performing the action.
- Terminal location from which action was performed.
- Type of action performed.
- File and field name affected by the action, if applicable.
- Before and after image of data modification action, if full auditing is set.

The name of the report to be generated is entered in the Extract File Name field on the window. The location where the file is saved is specified by the **REPORT.USERAUDITLOG.LOC** property, which contains the directory location. Use the Application Configuration window (**System Operations > Server Management > Application**) to define the value of the **REPORT.USERAUDITLOG.LOC** property.

Automated User Auditing

User auditing can be performed automatically by specifying the `com.aciworldwide.common.timertask.UserAuditReport` classname for the configuration properties file `timertask.function.n.classname` configuration parameter. The Java Server Framework application specified as the `timertask.manager.processid` invokes the classname at application initialization.

The following properties are used to configure automated user audit reporting:

Property	Description
<code>report.userauditlog.loc</code>	The file path for the user audit report.
<code>report.userauditlog.name</code>	The name of the user audit report.
<code>report.userauditlog.offset.days</code>	The number of days prior to the current day to use for obtaining user activity for the report.
<code>report.userauditlog.report.starttime</code>	The time at which the report is generated.

Refer to the *ACI Java Server Framework Reference Guide* for more information about the above properties.

6: Version Checker Server


The desktop provides a way for clients to keep desktop configuration current. This configuration support is provided by the Version Checker server, which is a utility that manages the versions of Java™ Archive (JAR) files of desktop components. This server automatically runs during startup of the desktop at which time it compares the current version of the client JAR files (configuration) to current published versions (new versions), which reside in a predetermined location (i.e., repository). The location of the Version Checker server repository is defined during installation. New JAR files that are to be distributed to clients are placed in this location.

The Version Checker server automatically runs when a desktop is started per commands located in the **RunDesktop.bat** file. Desktop shortcuts specified during installation point to this batch file. Whether a user is prompted to accept any new JAR files or the JAR files are automatically downloaded is dependent upon configuration settings as discussed in this section.

Version Checker Client Window

The JAR files on the repository for which the version differs from that of the client are displayed in the Version Checker Client window. This window provides a list of the JAR files along with the version number of each JAR file on the repository and the version number of the JAR file on the client. If automatic JAR file updating is enabled (discussed later in this section), then this window is not displayed.

To download JAR files from the repository, select the applicable JAR files and click Update. This update process can be skipped or canceled by clicking the appropriate button on the window.




Select All

The Select All option can be used to select all listed JAR files on the Version Checker Client window. Individual JAR files can be selected by deselecting the Select All option and then clicking in the row or rows for the desired JAR files to download. Only selected JAR files are downloaded.


Close When Done Option

If the Close When Done option is selected, the Version Checker Client window is automatically closed after completion of the download of all selected JAR files. If this option is not selected, then the window is modified, as shown below, for user verification that the download has completed successfully. Click Done to acknowledge the download and to close the window.



Mirror the Repository

By selecting Mirror Repository on the Version Checker Client window, verification is initiated to ensure that no jars reside on the client that are not also on the server repository. That is, any JAR files that exist on the client that do not exist on the current version of the server repository are deleted from the client.



Automatic JAR File Update

The Version Checker server can be configured to download updated and new JAR files automatically. This automatic JAR file updating (called VC quiet mode) is an option presented during installation of the ACI desktop.

Including the parameter “-Q” in the Version Checker server command line located in the **RunDesktop.bat** file enables automatic JAR file updating. Note that the “-Q” is added during installation when the VC quiet mode option is selected.

For example:

```
call "T:\ESUI\__ES_04.1_NSK\VersionChecker\verChk" -Q
```


ACI Worldwide Inc.

7: Online Help

The ACI desktop provides online help for windows (screens), window components (e.g., buttons, and fields), and general topical information. The online help is displayed in a Java-based HTML browser, called the **Helpset Viewer** that provides structured access and context-sensitive access to the help content.

Helpset Viewer Overview

JavaHelp content is displayed in the Helpset Viewer (shown below), which is an HTML browser specifically designed to function with Java-based applications.



The components of the Helpset Viewer are:

- 1** — The **Title Bar** in which the name of the helpset is displayed.
- 2** — The **Toolbar** that contains various menu and button functions.
- 3** — The **Navigation Pane** in which are located Contents and Index tabs useful for navigating to desired help content, and a Search tab for searching content.
- 4** — The **Content Pane** in which help content is displayed.
- 5** — The **Contents** tab that provides structured access to window-level help files.
- 6** — The **Index** tab that provides alphabetical access to all help topics.
- 7** — The **Search** tab for searching help content.

Access to JavaHelp from the ACI Desktop

JavaHelp content can be accessed with or without context. These two methods are explained below.

With Context

Accessing online help with context displays the Helpset Viewer with content displayed in the Content Pane that is specific to a window or window component. To display help with context from the ACI desktop, select **Help > Context Help** on the Menu Bar or click  on the toolbar. Either of these actions display the Help Pointer  to use for clicking in a general area of a window for window-level help or on a window field for field-level help.

If a window is not open, help with context is not available because an active window in the Application Area of the ACI desktop is necessary to provide context. When context help is not available, the Context Help function and the  button are inactive.

Note that the traditional way to access field-level help by placing the cursor in the field and pressing the **F1** key can also be used when a window is active in the Application Area of the ACI desktop.

Without Context

To display online help without context from the ACI desktop, select **Help > Help Topics** from the Menu Bar or click  on the Toolbar. A window does not need to be open to access online help without context. When online help is accessed using this method, the Helpset Viewer is displayed with the default home page provided in the content pane and the default TOC view in the navigation pane. The image on the previous page is the default view of online help when accessed without context.

If the Help Topics function and the  button are not enabled, then the ACI desktop does not have access to online help. Check with a System Administrator to obtain ACI online help.

JavaHelp Files

The following files together are referred to as a **JavaHelp helpset**:

- The **helpset file** (ACI_Help.hs), which is identified by the .hs file extension, defines the name of the helpset displayed in the Title Bar, the JavaHelp components used, the name of the map file, the names of the table of contents and index files, and the ID of the default content file to display in the Content Pane when help is accessed without context. The helpset file is the top-level file in the JavaHelp helpset.

Be careful not to confuse JavaHelp helpset with the helpset (.hs) file.

JavaHelp helpset refers to a collection of JavaHelp files as discussed on this page.

- The **map file** (map.jhm) is an XML file identified by the .jhm file extension that corresponds identifiers to HTML content files. This file is necessary to provide context-sensitive help for windows and window components of the ACI desktop as discussed later in this section.
- The **table of contents file** (toc.xml) that defines the structure and links of the text entries of the Contents tab located in the Navigation Pane of the Helpset Viewer.
- The **index file** (ix.xml) that defines the structure and links of the text entries of the Index tab located in the Navigation Pane of the Helpset Viewer.
- **HTML files** in which help content resides. Content is displayed in the Content Pane of the Helpset Viewer.
- **Cascading Style Sheets (CSS)** define the style rules applied to the content files.
- The **images** displayed within HTML content files. Images used in content are in Graphical Interchange Format (GIF) and Joint Photographic Experts Group (JPEG or JPG) formats.

JavaHelp Packages

ACI online help is packaged and distributed in the following Java™ Archive (JARs) files:

- **ACI_Help_es.jar** that provides the JavaHelp for BASE24-es.
- **ACI_Help_tss.jar** that provides the JavaHelp configuration for Transaction Security Services (TSS).

Helpset File

The helpset file is a JavaHelp-specific XML file that defines the Java components used, home page, map file, TOC, index, and views. Below is an example helpset file.

```
<?xml version='1.0' encoding='ISO-8859-1' ?>
<!DOCTYPE helpset
  PUBLIC "-//Sun Microsystems Inc.//DTD JavaHelp HelpSet Version 2.0//EN"
  "http://java.sun.com/products/javahelp/helpset_2_0.dtd">
<helpset version="2.0">
  <title>ACI Online Help</title>
  <maps>
    <homeID>splash</homeID>
    <mapref location="map.jhm" />
  </maps>
  <view>
    <name>TOC</name>
    <label>Contents</label>
    <type>javax.help.TOCView</type>
    <data>toc.xml</data>
  </view>
  <view>
    <name>Index</name>
    <label>Index</label>
    <type>javax.help.IndexView</type>
    <data>ix.xml</data>
  </view>
  <view>
    <name>Search</name>
    <label>Search</label>
    <type>javax.help.SearchView</type>
    <data engine="com.sun.java.help.search.DefaultSearchEngine">
      JavaHelpSearch
    </data>
  </view>
</helpset>
```

How Context is Implemented in JavaHelp


Help context is implemented in JavaHelp by the use of unique identifiers. Each identifier (referred to as a map ID or help ID) appears as necessary in the following files:

- The property (.properties) file for a window (desktop application)

Note: Most application windows have their own properties file. Also, some properties common among all windows are located in common properties files that are shared among the window properties files.

- The JavaHelp map file, map.jhm
- The table of contents file, toc.xml
- The index file, ix.xml

The use and relationship of the identifiers in the above files is shown in the following illustration.




Search the Helpset for a Text String

The Search tab provides a text entry field (Find) to locate up to 100 occurrences of a text string within a helpset.

Note: Search is not case sensitive.

Enter the text string in the Find text entry field and press the **Enter** key. JavaHelp searches through the helpset and displays a list of topics in which the text string is found. This list is displayed in the Navigation Area by topic title and in descending order of number of matches. Select the desired topic to display the topic's content in the Content area.



Custom Help Content

Online help can be modified in a number of different ways depending on the level of modification desired.

- Content files can be modified.
- Cascading style sheets can be modified to change display formats.
- Images referenced in content files can be edited.

Note: Modifying the JavaHelp configuration files can adversely affect the performance of JavaHelp and is not discussed in this manual.

If an installed version of JavaHelp is customized, care must be taken to avoid overwriting the customized JavaHelp files when accepting an updated help JAR file for placement on the Version Checker server repository. Therefore, the following guidelines can be used to establish procedures for maintaining and protecting customized JavaHelp:

- Always keep a backup of both original and customized files.
- Consider appending an identifier (e.g., “custom”) to the name of customized files. If a help file name is changed, the change must also be made to the map.jhm file. For example, a file named f_connection.htm file is customized and renamed to f_connection_custom.htm. The url attribute in the map.jhm file must be changed as follows:

From:

```
<mapID target="f_connection"
      url="f_connection.htm"/>
```

To:

```
<mapID target="f_connection"
      url="f_connection_custom.htm"/>
```

- Another option is to keep the same name of the file but place the customized file into a separate directory as follows:

```
<mapID target="f_connection"
      url="custom/f_connection.htm"/>
```

Customization of HTML Content Files

All content files within the JavaHelp JAR files are in compliance with the W3C HTML revision 3.2 format. This format is required for content files to display properly within the Helpset Viewer. Certain parts of the HTML revision 4.0 format can be used since it shares most markup tag elements with 3.2; however, care should be taken when implementing revision 4.0 features into content files destined for JavaHelp because certain revision 4.0 features might not be supported. To ensure proper behavior of content files in JavaHelp, always test the display characteristics of HTML files in JavaHelp before releasing the help files.

One advantage of the content files being in HTML format is that common editors can be used to modify help content. The specifics of editing HTML files are not discussed here since these depend on the editor used; however, the following general guidelines apply regardless of the editor used:

1. Before an HTML content file within a JAR file can be edited, the file must be extracted to a working location using a tool, such as WinZip. The extracted HTML file is a copy of the original file. Make a backup of the original file and place it in a specified archive directory for later retrieval. All editing should be done on the extracted copy.
2. Select an appropriate HTML editor. Note that some HTML editors automatically add embedded XML, HTML and other types of objects to HTML code. Such objects can adversely affect the display of the content within JavaHelp. As a result, editing tools that do not automatically add objects are recommended. Such tools include Macromedia's Dreamweaver and any ASCII editor
3. The modified HTML file must be saved to a working location. The modified file must then be added to the applicable JAR file replacing the original file in the JAR (the original being maintained in the archive directory location). Do not change the file extension.
4. If the name of the HTML file is changed to reflect customization, such as from `f_connection.htm` to `f_connection_custom.htm`, the URL attribute of the `map.jhm` file needs to be updated to reflect the name change.

Change the Display of Content

The format and style of the content displayed in the Helpset Viewer can be modified by altering the values of the style properties in the applicable cascading style sheet (CSS) file. CSS files are defined in the <head>...</head> section of each HTML file used in the ACI online help using <link> tags as follows:

```
<link rel="StyleSheet" href="Templates/forScreen.css" type="text/css"
media="screen">
```

```
<link rel="StyleSheet" href="Templates/forPrint.css" type="text/css"
media="print">
```

CSS files are located in the Templates folder within the applicable helpset JAR (ACI_Help_es.jar or ACI_Help_tss.jar).

Note: To ensure that content displays properly in the Helpset Viewer, always test before releasing the modified CSS files.

Install JavaHelp for Stand-alone Use

JavaHelp support is included within the ACI desktop; however, JavaHelp can be installed for direct access to helpset (.hs) files without the need to have the ACI desktop open. Note that Java must be already installed. The remainder of this topic discusses installing JavaHelp on a Java enabled Windows-based PC.

1. Download the latest version of JavaHelp from:


<http://java.sun.com/products/javahelp>

Note: JavaHelp is distributed as a zip file such as **Javahelp 2.0_02.zip** (a more current version might be available).


2. Open the zip file and extract all files to an easily accessible location, such as (e.g., C:\jh2.0). Among the files extracted is the **hsvviewer.jar** file that is needed later in this procedure.
3. Find java.exe and create a shortcut to the file. Java.exe must be already installed. Cut and paste the shortcut to an easily accessible location.

For the illustrations used in the remainder of this procedure, the shortcut name JavaHelp 2.0 is used.

4. Right click on the shortcut and select Properties on the drop-down menu.



The properties for the shortcut are available in the Properties window as shown below.




5. In the Target field located on the Shortcut tab, enter the path to java.exe, followed by a space, the string "-jar", another space, and then the path to the installed location of hviewer.jar. In the illustration above, the full text of the Target field is partially obscured, but is:

C:\jdk1.3\bin\java.exe -jar c:\jh2.0\demos\bin\hviewer.jar

6. Click OK.

7. Test the functionality by opening JavaHelp by clicking on the shortcut, after which the following Set HelpSet window should display that can be used to browse to a helpset file (.hs extension).



If the above window does not display, a number of problems could exist. For example, either Java, JavaHelp, or both are not installed properly. Also, the target path in the shortcut could be incorrect. Verify that the paths in the shortcut reflect the actual paths for both `java.exe` and `hsvviewer.jar`.

ACI Worldwide Inc.

A: Desktop Windows

The following table lists ACI desktop windows and the corresponding permission IDs and task IDs.

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Acquirer Transactions Allowed Profile Configuration Desktop Access: Configure > Transactions Allowed > Acquirer Transactions Profile Help ID: w_acquirer_transactions_ allowed_profile_configuration	AcquirerTransactionsAllowed	FullAcqTransAllowed Permission
✓		Action Code Profile Configuration Desktop Access: Configure > Action Code Profile Help ID: w_action_code	ActionCode	FullActionCode Permission
✓		Active Script Statistics and Management Desktop Access: System Operations > Active Script Statistics Help ID: w_active_script_statistics_and_ management	ActiveScript AuthScript	FullActiveScript Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Administrative Card Configuration Desktop Access: Configure > Administrative Card Help ID: w_administrative_card_configuration	AdministrativeCardManagement	FullAdminCardMgmt Permission
✓		All available interface configuration windows. Desktop Access: Configure > Interface > ... Help ID: w_interface_configuration	InterfaceConfiguration	FullInterfaceConfig Permission
✓	✓	Application Configuration Desktop Access: System Operations > Server Management > Application Help ID: w_application_configuration	IWTApplicationConfig	FullIWTAppICfg Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Application Management Comms Handler¹ Application Management Message Router Summary² Application Management Process Summary³ Application Management Queue Summary⁴ Application Management Queue Manager Summary⁵ Application Management Station Summary⁶ Desktop Access: System Operations > Application Management > ... Help IDs: ¹ w_appmanage_comms_handler_summary ² w_appmanage_message_router_summary ³ w_appmanage_process_summary ⁴ w_appmanage_queue_summary ⁵ w_appmanage_queue_manager_summary ⁶ w_appmanage_station_summary	ApplctnManagement Summary	FullApplctnManagement Summary
✓		Application Management Desktop Access: System Operations > Application Management > Application Management Help ID: w_application_configuration	ApplctnManagement	FullApplctnManagement

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Application Parameter Management System Interface Configuration Desktop Access: Configure > Interface > Host > Application Parameter Management Help ID: w_apms_interface_configuration	APMSInterfaceConfiguration ContextConfiguration	FullAPMSIFCfg Permission
✓		ATM Channel Administration Desktop Access: System Operations > ATM Framework > ATM Channel Administration Help ID: w_atm_channel_administration	ATMChannelAdministration ATMChannel, InstitutionConfiguration, ATMHopperProfile	FullATMChannelAdmin Permission
✓		ATM Channel Configuration Desktop Access: Configure > ATM Framework > ATM Channel Help ID: w_atm_channel_configuration	ATMChannel ATMHardwareStatus, InstitutionConfiguration, ATMChannelProfile	FullATMChannel Permission
✓		ATM Channel Management - All Channels Desktop Access: System Operations > ATM Framework > ATM Channel Management > All Channels Help ID: w_atm_channel_all_channels	ATMChannelManagement InstitutionConfiguration	FullATMChannelMgmt Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		ATM Channel Management Desktop Access: System Operations > ATM Framework > ATM Channel Management > Selected Channels Help ID: w_atm_channel_management	ATMChanMgmtSelectedChannels InstitutionConfiguration	FullATMChanMgmtSC Permission
✓		ATM Channel Profile Configuration Desktop Access: Configure > ATM Framework > ATM Channel Profile Help ID: w_atm_channel_profile_ configuration	ATMChannelProfile ATMSurcharge	FullATMChannelPrfl Permission
✓		ATM Device Handler Interface Configuration Desktop Access: Configure > Interface > Host > ATM Device Handler Help ID: w_atm_device_handler_ interface_configuration	ATMDHInterfaceConfiguration InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, ActionCode, ISOFrameworkConfiguration, ATMSurcharge	FullATMDHIFCfg Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		ATM Diebold Channel Operator ID Configuration Desktop Access: Configure > ATM Framework > ATM Diebold Channel Operator Help ID: w_atm_diebold_channel_id_ configuration	ATMDieboldChannelOperatorID	FullATMDbldChanOprID Permission
✓		ATM Hardware Status Desktop Access: View > ATM Framework > ATM Hardware Status Help ID: w_atm_hardware_status	ATMHardwareStatus ATMChannel	FullATMHardwareStat Permission
✓		ATM Hopper Profile Configuration Desktop Access: Configure > ATM Framework > ATM Hopper Profile Help ID: w_atm_hopper_profile_ configuration	ATMHopperProfile	FullATMHopperPrfl Permission
✓		ATM Load Profile Desktop Access: Configure > ATM Framework > ATM Load Profile Help ID: w_atm_load_profile	ATMLoadProfile	FullATMLoadProfile Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		ATM Optional Receipt Profile Desktop Access: Configure > ATM Framework > ATM Optional Receipt Profile Help ID: w_atm_optional_receipt_profile	ATMOptionalReceiptProfile	FullATMOptnRcptPrfl Permission
✓		ATM Receipt Format Configuration Desktop Access: Configure > ATM Framework > ATM Receipt Format Help ID: w_atm_receipt_format_profile_ configuration	ATMReceiptFormat InstitutionConfiguration	FullATMReceiptFormat Permission
✓		ATM Receipt Required Type Configuration Desktop Access: Configure > ATM Framework > ATM Receipt Required Type Help ID: w_atm_receipt_required_type_ configuration	ATMReceiptRequiredType	FullATMRcptReqType Permission
✓		ATM Reload Map Request Desktop Access: System Operations > ATM Framework > ATM Reload Map Help ID: w_atm_reload_map_request	ATMReloadMaps	FullATMReloadMaps Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		ATM Status Query Desktop Access: System Operations > ATM Framework > ATM Status Query Help ID: w_atm_status_query	ATMStatusQuery	FullATMStatusuery Permission
✓		Audit Extract Window Desktop Access: Tools > Audit Extract Help ID: w_audit_extract	UserAuditReport	FullUserAuditRpt Permission
✓	✓	Audit Store and Forward (SAF) Configuration Desktop Access: System Operations > Audit SAF Help ID: w_audit_store_and_forward_ configuration	AuditSAFConfig	FullAuditSAFConfig Permission
	✓	Authentication Profile Configuration (Configure > Transaction Security > Authentication Profile) Help ID: w_authentication_profile_ configuration	AuthenticationConfiguration SecurityDeviceConfiguration	FullAuthentConfig Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Authorization Script Configuration Desktop Access: Configure > Script > Authorization Script Help ID: w_authorization_script_configuration	AuthScript	FullAuthScript Permission
✓		BankNet ISO Interface Configuration Desktop Access: Configure > Interface > Network > BankNet ISO Help ID: w_banknet_iso_interface_configuration	BanknetInterface InterfaceConfiguration, BanknetMerchantProgram, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	FullBanknetInterface Permission
✓		BASE24 ISO8583 Host Interface Configuration Desktop Access: Configure > Interface > Host > BASE24 ISO8583 Host Help ID: w_base24_iso8583_host_interface_configuration	B24HISOInterfaceConfig InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge TermLnFiidMap TokenProfile	FullB24HISOIFConfig Permission FullHISO
	✓	BASE24 KEYF Configuration Desktop Access: Configure > Transaction Security > BASE24 KEYF Configuration Help ID: w_base24_keyf_configuration	B24KEYFSecurity InterfaceSecurityConfiguration	FullB24KEYFSecurity Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
	✓	BNTng Key Header Configuration Desktop Access: Configure > Transaction Security > BNTng Header Help ID: w_bntng_key_header_configuration	BNTngHeaderConfig	FullBNTngHeader Configuration
✓	✓	Cache Administration Desktop Access: System Operations > Server Management > Server Administration > Cache Administration Help ID: w_cache_administration	IWTCacheAdministration	FullIWTCacheAdmin Permission
✓		Card Management Desktop Access: Customer Management > Card Help ID: w_card_management	CardConfiguration InstitutionConfiguration, Usages, PreAuthHold, PaymentLimitConfig	FullCardConfig Permission
	✓	Certificate Management Desktop Access: Configure > Transaction Security > Automated Key Distribution > Certificate Management Help ID: w_certificate_management	Certificate	FullCertificate Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓	✓	Channel Public Key Perusal Desktop Access: View > Automated Key Distribution > Channel Public Key Perusal Help ID: w_channel_public_key_perusal	ChannelPKPerusal	FullChannelPKPerusal Permission
	✓	Channel Security Configuration Desktop Access: Configure > Transaction Security > Channel Help ID: w_channel_security_ configuration	ChannelSecurity ChannelConfiguration, SecurityDeviceConfiguration	FullChannelSecurity Permission
✓	✓	Configuration Properties Desktop Access: System Operations > Server Management > Server Administration > Configuration Properties Help ID: w_configuration_properties	IWTConfigurationAdministration	FullIWTConfigAdmin Permission
✓		Context Profile Configuration Desktop Access: Configure > Interface > Context Profile Help ID: w_context_profile_configuration	ContextConfiguration	FullContextConfig Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Contingency Interface Configuration Desktop Access: Configure > Interface > Host > Contingency Help ID: w_contingency_interface_configuration	ContingencyInterface InterfaceConfiguration, ContextConfiguration, ATMSurcharge	FullContingencyIF Permission
✓		Contingency Store and Forward (SAF) Configuration Desktop Access: System Operations > Contingency SAF Help ID: w_contingency_store_and_forward	ContingencySAF	FullContingencySAF Permission
✓		Currency Conversion Rate Configuration Desktop Access: Configure > Currency Conversion > Currency Conversion Rate Help ID: w_currency_conversion_rate_configuration	CurrencyConvRateConfiguration InstitutionConfiguration	FullCrncyConvRateCfg Permission
✓	✓	Database Administration Desktop Access: System Operations > Server Management > Server Administration > Database Administration Help ID: w_database_administration	IWTDATABASEAdministration	FullIWTDATABASEAdmin Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Destination Routing Profile Configuration Desktop Access: Configure > Routing > Profile Description > Destination Routing Profile Help ID: w_destination_routing_profile_configuration	IssuerProfileConfig	FullIssProfConfig Permission
	✓	Disable KEYGEN Desktop Access: Configure > Transaction Security > Automated Key Distribution > Disable KEYGEN Help ID: w_disable_keygen	KEYGENLockdown	FullKEYGENLockdown Permission
	✓	DUKPT Derivation Key Profile Configuration Desktop Access: Configure > Transaction Security > DUKPT Derivation Key Profile Help ID: w_dukpt_derivation_key_profile_configuration	B24SPDHDKPTDerivationKey	FullB24SPDHDKPTDKey Permission
✓	✓	Environment Configuration Desktop Access: System Operations > Environment Help ID: w_environment_configuration	EnvironmentManagement	FullEnvironmentMgmt Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
	✓	EPP Serial Number Configuration Desktop Access: Configure > Transaction Security > Automated Key Distribution > EPP Serial Number Help ID: w_epp_serial_number_configuration	EPPSerialNumberConfig	FullEPPSerialNumCfg Permission
✓		Euro Opted Currency Configuration Desktop Access: Configure > Currency Conversion > Euro Opted Currency Help ID: w_euro_opted_currency_configuration	EuroOptedCurrencyConfiguration	FullEuroOptedCurrCfg Permission
✓	✓	Event Configuration and Management Desktop Access: System Operations > Event > Event Management Help ID: w_integrated_server_event_configuration	EventConfiguration EventSubsystemConfiguration	FullEventConfig Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓	✓	Event Subsystem ID Configuration Desktop Access: System Operations > Event > Subsystem ID Help ID: w_event_subsystem_id_configuration	EventSubsystemConfiguration	FullEventSubConfig Permission
✓		Exported Operators Configuration Desktop Access: Configure > Script > Exported Operators Help ID: w_exported_operators_configuration	ExportedOperator	FullExportedOperator Permission
✓	✓	External Connection Configuration Desktop Access: System Operations > Server Management > External Connection Help ID: w_external_connection_configuration	IWTConnectionConfig IWTProcessConfig	FullIWTConnectionCfg Permission
✓		File Partition Configuration Desktop Access: System Operations > Database Management > File Partition Help ID: w_file_partition_configuration	FilePartition	FullFilePartition Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		File Update Router Desktop Access: Configure > Routing > File Update Router Help ID: w_file_update_router_ configuration	FileUpdateRouterConfig	FullFileUpdateRouterConfig Perm
✓	✓	Host Public Key Perusal Desktop Access: View > Automated Key Distribution > Host Public Key Perusal Help ID: w_host_public_key_perusal	HostPKPerusal	FullHostPKPerusal Permission
✓		IFX Host Action Code Profile Configuration Desktop Access: Configure > Interface > Host > IFX Host > IFX Host Action Code Profile Help ID: w_ifx_host_action_code_profile_ configuration	IFXHostActionCode	FullIFXHostActionCode Perm

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		IFX Host Configuration Desktop Access: Configure > Interface > Host > IFX Host > IFX Host Interface Help ID: w_ifx_host_interface_ configuration	IFXHostInterface InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, FullIFXHostActionCodePerm IssuerTransactionsAllowed, ContextConfiguration, ATMSurcharge IFXHostActionCode	FullIFXHostInterfacePerm
✓		IMT Interface Configuration Desktop Access: Configure > Interface > Host > Internal Message Translator > Network > IMT Interface Help ID: w_imt_interface_configuration	IMTInterface InterfaceConfiguration IMTInterface IMTATMTransactionMapping IMTPOSTransactionMapping, IssuerTransactionsAllowed, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge TokenProfile	FullIMTInterface Permission
✓		Institution Configuration Desktop Access: Configure > Institution Help ID: w_institution_configuration	InstitutionConfiguration AcquirerProfileConfiguration	FullInstConfig Permission
✓		Instrument Status Mapping Profile Configuration Desktop Access: Configure > Interface > Instrument Status Mapping Profile Help ID: w_instrument_status_mapping_ profile_configuration	InstrStatusMappingProfile	FullInstStatMapPrfl Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Instrument Type/Interchange Relationship Desktop Access: Configure > Interface > Instrument Type/Interchange Relationship Help ID: w_instrument_type_interchange_relationship_configuration	InstrumentTypeIchgRelation	FullInstTypIchgRel Permission
✓		Interchange Prefix Configuration Desktop Access: Configure > Prefix > Not-On-Us > Interchange Prefix Help ID: w_interchange_prefix_configuration	InterchangePrefixConfiguration	FullIchgPrefixConfig Permission
	✓	Interface Security Configuration Desktop Access: Configure > Transaction Security > Interface Help ID: w_interface_security_configuration	InterfaceSecurityConfiguration InterfaceConfiguration, SecurityDeviceConfiguration	FullIFSecurityConfig Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Interface Terminal Desktop Access: Configure > Interface > Network > Star > Interface Terminal Help ID: w_interface_terminal_configuration	InterfaceTerm	FullInterfaceTerm Permission
✓		Internal Message Translation (IMT) Transaction Mapping - ATM Desktop Access: Configure > Interface > Host > Internal Message Translator > IMT Transaction Mapping - ATM Help ID: w_imt_transaction_mapping_atm	IMTATMTransactionMapping	FullIMTATMTransMap Permission
✓		Internal Message Translation (IMT) Transaction Mapping - POS Desktop Access: Configure > Interface > Host > Internal Message Translator > IMT Transaction Mapping - POS Help ID: w_imt_transaction_mapping_pos	IMTPOSTransactionMapping	FullIMTPOSTransMap Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Interpay (BIM) Interface Configuration Desktop Access: TBD Help ID: TBD	InterpayInterface	FullInterpayIFPermission
✓		ISO 93 Host Interface Configuration Desktop Access: Configure > Interface > Host > ISO 93 Host Help ID: w_iso_93_host_interface_configuration	ISO93InterfaceConfiguration InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	FullISO93IFConfig Permission
✓		ISO Message Profile Configuration Desktop Access: Configure > ISO Message Profile Help ID: w_iso_framework_configuration	ISOFrameworkConfiguration	FullISOFrameworkCfg Permisson
✓		ISO93 Interface Configuration Desktop Access: Configure > Interface > Network > ISO93 Help ID: w_interface_configuration	ISO93InterfaceConfiguration InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	FullISO93IFConfig Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Issuer Transactions Allowed Profile Configuration Desktop Access: Configure > Transactions Allowed > Issuer Transactions Profile Help ID: w_issuer_transactions_allowed_profile_configuration	IssuerTransactionsAllowed	FullIssTransAllowed Permission
✓		Journal Issuer Profile Relationship Configuration Desktop Access: Configure > Journal > Issuer Profile Relationship Help ID: w_journal_issuer_profile_relationship_configuration	JournalConfigurationMapping JournalProfileConfiguration, InstitutionConfiguration, InterfaceConfiguration, and the interface-specific task IDs	FullJrnlCfgMapping Permission
✓		Journal Perusal Desktop Access: View > Journal Perusal Help ID: w_journal_perusal	LogFilePerusal	FullLogFilePerusal Permission
✓		Journal Profile Configuration Desktop Access: Configure > Journal > Journal Profile Help ID: w_journal_profile_configuration	JournalProfileConfiguration JournalConfigurationMapping	FullJrnlProfileCfg Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Journal Query Configuration Desktop Access: Configure > Journal > Journal Query Help ID: w_journal_query_configuration	JournalQueryConfiguration JournalQueryExecution	FullJrnlQueryConfig Permission
✓		Journal TDE Suppression Configuration Desktop Access: Configure > Journal > Journal TDE Suppression Help ID: w_journal_tde_suppression	JournalTDESuppression InstitutionConfiguration, InterfaceConfiguration	FullJrnlTDESuppress Permission
✓		LINK ISO Interface (LIS5) Configuration Desktop Access: Configure > Interface > Network > LINK ISO Help ID: w_link_lis5_interface_ configuration	LIS5Interface InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	FullLIS5Permission
✓		Limit Profile Management Desktop Access: Customer Management > Limit Profile Help ID: w_limit_profile_configuration	PaymentLimitConfig InstitutionConfiguration	FullPmtLimitConfig Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Linked Currency Configuration Desktop Access: Configure > Currency Conversion > Linked Currency Help ID: w_linked_currency_ configuration	LinkedCurrencyConfiguration	FullLinkedCurrCfg Permission
✓	✓	Listener Configuration Desktop Access: System Operations > Server Management > Listener Help ID: w_listener_configuration	IWTListenerConfig IWTProcessConfig	FullIWTListenerCfg Permission
	✓	Master File Key Conversion Desktop Access: Configure > Transaction Security > Master File Key Conversion Help ID: w_master_file_key_conversion	MFKConverter	FullMFKConverter Permission
✓		MasterCard Debit Switch (MDS) Interface Configuration Desktop Access: Configure > Interface Network > MasterCard Debit Switch (MDS) Help ID: w_mastercard_debit_switch_ configuration	MaestroDebitSwitch InterfaceConfiguration AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	FullMaestro Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Merchant Configuration and Statistics Desktop Access: Configure > Merchant Processing > Merchant Help ID: w_merchant_configuration_and_statistics	MerchantConfiguration ChannelConfiguration, InstitutionConfiguration, POSDeliveryChannel, POSDeliveryChannelProfile	FullMerchantConfig Permission
✓		On-Us Prefix Configuration Desktop Access: Configure > Prefix > On-Us Help ID: w_prefix_configuration	PrefixConfiguration AuthenticationConfiguration, IssuerTransactionsAllowed, InstitutionConfiguration, InterfaceConfiguration, RoutingConfiguration and, the interface-specific task IDs	FullPrefixConfig Permission
✓		Perusal Profile Configuration Desktop Access: Configure > Journal > Perusal > Perusal Profile Help ID: w_perusal_profile_configuration	PerusalConfiguration	FullPerusalConfig Permission
✓		POS Delivery Channel Configuration and Statistics Desktop Access: Configure > Merchant Processing > POS Delivery Channel Help ID: w_pos_delivery_channel_configuration_and_statistics	POSDeliveryChannel ChannelConfiguration, MerchantConfiguration, POSDeliveryChannelProfile	FullPOSDeliveryChannel Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		POS Delivery Channel Profile Configuration Desktop Access: Configure > Merchant Processing > POS Delivery Channel Profile Help ID: w_pos_delivery_channel_profile_configuration	POSDeliveryChannelProfile AcquirerProfileConfiguration, AcquirerTransactionsAllowed, ActionCode, ChannelConfiguration	FullPOSDivryChnlPrfl Permission
✓		Positive Balance Management Desktop Access: Customer Management > Positive Balance Help ID: w_positive_balance_management	PositiveBalance InstitutionConfiguration, Usages, PreAuthHold, PaymentLimitConfig	FullPositiveBalance Permission
✓		Preauthorization Hold Management Desktop Access: Customer Management > Preauthorization Hold Help ID: w_preauthorization_hold_management	PreAuthHold InstitutionConfiguration, CardConfiguration	FullPreAuthHold Permission
✓	✓	Process Configuration Desktop Access: System Operations > Server Management > Process Help ID: w_process_configuration	IWTPProcessConfig	FullIWTPProcessCfg Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓	✓	Process Control Desktop Access: System Operations > Process Control Help ID: w_process_control	ProcessControl	FullProcContrl FullProcessControl
✓		Query Execute Desktop Access: System Operations > Query Execution Help ID: w_query_execute	JournalQueryExecution JournalQueryConfiguration	FullJrnlQueryExecute Permission
✓		Real Time Feed Window Desktop Access: Configure > Interface > Host > Real Time Feed Help ID: w_realtimefeed_interface_ configuration	RealTimeFeedInterface	FullRealTimeFeedIF Permission
✓		Routing Configuration - Destination Desktop Access: Configure > Routing > Destinations Help ID: w_routing_configuration_ destination	RoutingConfiguration AcquirerIssuerRelationConfig	FullRoutingConfig Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Routing Configuration - Destination/Source Relationship) Desktop Access: Configure > Routing > Destination/Source Help ID: w_destination_source_relationship	AcquirerIssuerRelationConfig AcquirerProfileConfiguration, RoutingConfiguration	FullAcqIssRelatnCf Permission
✓		Script Editor Desktop Access: Configure > Script > Editor Help ID: w_script_editor	ScriptEditor ScriptRepository	FullScriptEditor Permission
✓		Script Repository Desktop Access: Configure > Script > Repository Help ID: w_script_repository	ScriptRepository ScriptEditor	FullScriptRepository Permission
	✓	Security Device Configuration Desktop Access: Configure > Transaction Security > Security Device Help ID: w_security_device_configuration	SecurityDeviceConfiguration	FullSecurityDevCfg Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓	✓	Socket Administration Desktop Access: System Operations > Server Management > Server Administration > Socket Administration Help ID: w_socket_administration	IWTSocketAdministration	FullIWTSocketAdmin Permission
✓		Source Routing Profile Configuration Desktop Access: Configure > Routing > Profile Description > Source Routing Profile Help ID: w_source_routing_profile_ configuration	AcquirerProfileConfiguration	FullAcqProfileConfig Permission
✓		SPDH Device Profile Configuration Desktop Access: Configure > Merchant Processing > SPDH Device Profile Help ID: w_spdh_device_profile_ configuration	SPDHDeviceConfig	FullSPDHDeviceConfig Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		STAR Institution Desktop Access: Configure > Interface > Network > Star > Star Institution Help ID: w_star_institution_configuration	StarInstitution StarNetworkIdRelationship StarInterface	FullStarInstitution Permission
✓		STAR ISO Interface Configuration Desktop Access: Configure > Interface > Network > Star > Star ISO Help ID: w_star_iso_interface_configuration	StarInterface StarNetworkIdRelationship StarInstitution	FullStarInterface Permission
✓		STAR Network Identifier/ Instrument Type Relationship Desktop Access: Configure > Interface > Network > Star > Star Network Identifier/ Instrument Type Relationship Help ID: w_star_network_identifier_instrument_type_relationship_configuration	StarNetworkIdRelationship StarInstitution StarInterface	FullStarNtwkIdRelation Perm

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Surcharge Profile Configuration Desktop Access: Configure > Surcharge Profile Help ID: w_surcharge_profile_configuration	ATMSurcharge	FullATMSurcharge Permission
✓		System Algorithm Configuration Desktop Access: Configure > Prefix > Not-On-Us > System Algorithm Help ID: w_system_algorithm	SystemAlgorithm	FullSystemAlgoritm Permission
✓	✓	System Monitor Desktop Access: System Operations > Server Management > Server Administration > System Monitor Help ID: w_system_monitor	IWTSysSystemMonitor\ IWTSDatabaseAdministration, IWTSocketAdministration, IWTCOnfigurationAdministration, IWTCachAdministration	FullIWTSysSystemMonitor Permission
✓		System Prefix Configuration Desktop Access: Configure > Prefix > Not-On-Us > System Prefix Help ID: w_system_prefix_configuration	SystemPrefix	FullSystemPrefix Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓	✓	System Properties Desktop Access: System Operations > Server Management > Server Administration > System Properties Help ID: w_system_properties	IWTSystemProperties	FullIWTSystemProperties Permission
✓		Terminal Logical Network/FIID Mapping Desktop Access: Configure > Interface > Host > BASE24ISO8583 Host > Terminal Logical Network/ FIID Mapping Help ID: w_terminal_logical_network_ fiid_mapping	TermLnFiidMap	FulltermLnFiidMapPerm
✓		Token Profile Configuration Desktop Access: Configure > Token Profile Help ID: w_token_profile_configuration	TokenProfile	FullTokenProfilePermission
✓		Trace Configuration Desktop Access: System Operations > Trace > Trace Help ID: w_trace_configuration	TraceConfiguration	FullTraceConfig Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Trace Filter Profile Configuration Desktop Access: System Operations > Trace > Trace Filter Profile Help ID: w_trace_filter_profile_configuration	TraceFilterConfiguration	FullTraceFilterCfg Permission
✓		Usages Management Desktop Access: Customer Management > Usages Help ID: w_usages_management	Usages InstitutionConfiguration, CardConfiguration	FullUsages Permission
✓		User Profile Relationship Desktop Access: Configure > Journal > Perusal > User Profile Relation Help ID: w_user_profile_relationship	UserProfileRelation PerusalConfiguration, UserSecurityProfile	FullUserProfRelation Permission
✓	✓	User Security Control Management Desktop Access: Configure > User Security > Control Help ID: w_user_security_control_management	UserSecurityControl UserSecurityControl	FullUSCtl Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓	✓	User Security Group Configuration Desktop Access: Configure > User Security > Group Help ID: w_user_security_group_configuration	UserSecurityGroupConfig UserSecurityProfile, if Distributed Security Administration is enabled	FullUSGCfg Permission
✓	✓	User Security Profile Configuration Desktop Access: Configure > User Security > Profile Help ID: w_user_security_profile_configuration	UserSecurityProfile UserSecurityGroupConfig	FullUSP Permission
✓	✓	User Security Role Configuration Desktop Access: Configure > User Security > Role Help ID: w_user_security_role_configuration	UserSecurityRoleConfig	FullUSRCfg Permission
✓		Visa Acquirers Configuration Desktop Access: Configure > Interface > Network > VisaNet > Visa Acquirer Help ID: w_visa_acquirers_configuration	VisaAcquirers	FullVisaAcquirers Permission

BASE24-es	TSS	Window (Desktop Access)	Task IDs Related Task IDs	Permission ID
✓		Visa DPS Interface Configuration Desktop Access: Configure > Interface > Network > Visa DPS Help ID: w_visa_dps_interface_ configuration	VisaDPSInterface InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	FullVisaDPSInterface Permission
✓		VisaNet ISO Interface Configuration Desktop Access: Configure > Interface > Network > VisaNet > VisaNet ISO Help ID: w_visanet_iso_interface_ configuration	VisanetInterfaceConfig InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge VisaAcquirers	FullVisanetIFConfig Permission

B: Task IDs

The following table lists default Task IDs and the corresponding ACI desktop window names and task IDs.

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		AcquirerTransactionsAllowed	FullAcqTransAllowed Permission	Acquirer Transactions Allowed Profile Configuration Desktop Access: Configure > Transactions Allowed > Acquirer Transactions Profile Help ID: w_acquirer_transactions_ allowed_profile_configuration
✓		ActionCode	FullActionCode Permission	Action Code Profile Configuration Desktop Access: Configure > Action Code Profile Help ID: w_action_code
✓		ActiveScript AuthScript	FullActiveScript Permission	Active Script Statistics and Management Desktop Access: System Operations > Active Script Statistics Help ID: w_active_script_statistics_and_ management

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		AdministrativeCardManagement	FullAdminCardMgmt Permission	Administrative Card Configuration Desktop Access: Configure > Administrative Card Help ID: w_administrative_card_ configuration
✓		InterfaceConfiguration	FullInterfaceConfig Permission	All available interface configuration windows. Desktop Access: Configure > Interface > ... Help ID: w_interface_configuration
✓	✓	IWTApplicationConfig	FullIWTApplCfg Permission	Application Configuration Desktop Access: System Operations > Server Management > Application Help ID: w_application_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		ApplctnManagement Summary	FullApplctnManagement Summary	Application Management Comms Handler¹ Application Management Message Router Summary² Application Management Process Summary³ Application Management Queue Summary⁴ Application Management Queue Manager Summary⁵ Application Management Station Summary⁶ Desktop Access: System Operations > Application Management > ... Help IDs: ¹ w_appmanage_comms_ handler_summary ² w_appmanage_message_ router_summary ³ w_appmanage_process_ summary ⁴ w_appmanage_queue_ summary ⁵ w_appmanage_queue_ manager_summary ⁶ w_appmanage_station_ summary
✓		ApplctnManagement	FullApplctnManagement	Application Management Desktop Access: System Operations > Application Management > Application Management Help ID: w_application_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		APMSInterfaceConfiguration ContextConfiguration	FullAPMSIFCfg Permission	Application Parameter Management System Interface Configuration Desktop Access: Configure > Interface > Host > Application Parameter Management Help ID: w_apms_interface_configuration
✓		ATMChannelAdministration ATMChannel, InstitutionConfiguration, ATMHopperProfile	FullATMChannelAdmin Permission	ATM Channel Administration Desktop Access: System Operations > ATM Framework > ATM Channel Administration Help ID: w_atm_channel_administration
✓		ATMChannel ATMHardwareStatus, InstitutionConfiguration, ATMChannelProfile	FullATMChannel Permission	ATM Channel Configuration Desktop Access: Configure > ATM Framework > ATM Channel Help ID: w_atm_channel_configuration
✓		ATMChannelManagement InstitutionConfiguration	FullATMChannelMgmt Permission	ATM Channel Management - All Channels Desktop Access: System Operations > ATM Framework > ATM Channel Management > All Channels Help ID: w_atm_channel_all_channels

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		ATMChanMgmtSelectedChannels InstitutionConfiguration	FullATMChanMgmtSC Permission	ATM Channel Management Desktop Access: System Operations > ATM Framework > ATM Channel Management > Selected Channels Help ID: w_atm_channel_management
✓		ATMChannelProfile ATMSurcharge	FullATMChannelPrfl Permission	ATM Channel Profile Configuration Desktop Access: Configure > ATM Framework > ATM Channel Profile Help ID: w_atm_channel_profile_ configuration
✓		ATMDHInterfaceConfiguration InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, ActionCode, ISOFrameworkConfiguration, ATMSurcharge	FullATMDHIFCf Permission	ATM Device Handler Interface Configuration Desktop Access: Configure > Interface > Host > ATM Device Handler Help ID: w_atm_device_handler_ interface_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		ATMDieboldChannelOperatorID	FullATMDbldChanOprID Permission	ATM Diebold Channel Operator ID Configuration Desktop Access: Configure > ATM Framework > ATM Diebold Channel Operator Help ID: w_atm_diebold_channel_id_ configuration
✓		ATMHardwareStatus ATMChannel	FullATMHardwareStat Permission	ATM Hardware Status Desktop Access: View > ATM Framework > ATM Hardware Status Help ID: w_atm_hardware_status
✓		ATMHopperProfile	FullATMHopperPrfl Permission	ATM Hopper Profile Configuration Desktop Access: Configure > ATM Framework > ATM Hopper Profile Help ID: w_atm_hopper_profile_ configuration
✓		ATMLoadProfile	FullATMLoadProfile Permission	ATM Load Profile Desktop Access: Configure > ATM Framework > ATM Load Profile Help ID: w_atm_load_profile

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		ATMOptionalReceiptProfile	FullATMOptnRcptPrfl Permission	ATM Optional Receipt Profile Desktop Access: Configure > ATM Framework > ATM Optional Receipt Profile Help ID: w_atm_optional_receipt_profile
✓		ATMReceiptFormat InstitutionConfiguration	FullATMReceiptFormat Permission	ATM Receipt Format Configuration Desktop Access: Configure > ATM Framework > ATM Receipt Format Help ID: w_atm_receipt_format_profile_ configuration
✓		ATMReceiptRequiredType	FullATMRcptReqType Permission	ATM Receipt Required Type Configuration Desktop Access: Configure > ATM Framework > ATM Receipt Required Type Help ID: w_atm_receipt_required_type_ configuration
✓		ATMReloadMaps	FullATMReloadMaps Permission	ATM Reload Map Request Desktop Access: System Operations > ATM Framework > ATM Reload Map Help ID: w_atm_reload_map_request

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		ATMStatusQuery	FullATMStatusuery Permission	ATM Status Query Desktop Access: System Operations > ATM Framework > ATM Status Query Help ID: w_atm_status_query
✓		UserAuditReport	FullUserAuditRpt Permission	Audit Extract Window Desktop Access: Tools > Audit Extract Help ID: w_audit_extract
✓	✓	AuditSAFConfig	FullAuditSAFConfig Permission	Audit Store and Forward (SAF) Configuration Desktop Access: System Operations > Audit SAF Help ID: w_audit_store_and_forward_ configuration
	✓	AuthenticationConfiguration SecurityDeviceConfiguration	FullAuthentConfig Permission	Authentication Profile Configuration (Configure > Transaction Security > Authentication Profile Help ID: w_authentication_profile_ configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		AuthScript	FullAuthScript Permission	Authorization Script Configuration Desktop Access: Configure > Script > Authorization Script Help ID: w_authorization_script_ configuration
✓		BanknetInterface InterfaceConfiguration, BanknetMerchantProgram, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	FullBanknetInterface Permission	BankNet ISO Interface Configuration Desktop Access: Configure > Interface > Network > BankNet ISO Help ID: w_banknet_iso_interface_ configuration
✓		B24HISOInterfaceConfig InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge TermLnFiidMap TokenProfile	FullB24HISOIFConfig Permission FullHISO	BASE24 ISO8583 Host Interface Configuration Desktop Access: Configure > Interface > Host > BASE24 ISO8583 Host Help ID: w_base24_iso8583_host_ interface_configuration
	✓	B24KEYFSecurity InterfaceSecurityConfiguration	FullB24KEYFSecurity Permission	BASE24 KEYF Configuration Desktop Access: Configure > Transaction Security > BASE24 KEYF Configuration Help ID: w_base24_keyf_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
	✓	BNTngHeaderConfig	FullBNTngHeader Configuration	BNTng Key Header Configuration Desktop Access: Configure > Transaction Security > BNTng Header Help ID: w_bntng_key_header_ configuration
✓	✓	IWTCacheAdministration	FullIWTCacheAdmin Permission	Cache Administration Desktop Access: System Operations > Server Management > Server Administration > Cache Administration Help ID: w_cache_administration
✓		CardConfiguration InstitutionConfiguration, Usages, PreAuthHold, PaymentLimitConfig	FullCardConfig Permission	Card Management Desktop Access: Customer Management > Card Help ID: w_card_management
	✓	Certificate	FullCertificate Permission	Certificate Management Desktop Access: Configure > Transaction Security > Automated Key Distribution > Certificate Management Help ID: w_certificate_management

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓	✓	ChannelPKPerusal	FullChannelPKPerusal Permission	Channel Public Key Perusal Desktop Access: View > Automated Key Distribution > Channel Public Key Perusal Help ID: w_channel_public_key_perusal
	✓	ChannelSecurity ChannelConfiguration, SecurityDeviceConfiguration	FullChannelSecurity Permission	Channel Security Configuration Desktop Access: Configure > Transaction Security > Channel Help ID: w_channel_security_ configuration
✓	✓	IWTConfigurationAdministration	FullIWTConfigAdmin Permission	Configuration Properties Desktop Access: System Operations > Server Management > Server Administration > Configuration Properties Help ID: w_configuration_properties
✓		ContextConfiguration	FullContextConfig Permission	Context Profile Configuration Desktop Access: Configure > Interface > Context Profile Help ID: w_context_profile_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		ContingencyInterface InterfaceConfiguration, ContextConfiguration, ATMSurcharge	FullContingencyIF Permission	Contingency Interface Configuration Desktop Access: Configure > Interface > Host > Contingency Help ID: w_contingency_interface_ configuration
✓		ContingencySAF	FullContingencySAF Permission	Contingency Store and Forward (SAF) Configuration Desktop Access: System Operations > Contingency SAF Help ID: w_contingency_store_and_ forward
✓		CurrencyConvRateConfiguration InstitutionConfiguration	FullCrncyConvRateCfg Permission	Currency Conversion Rate Configuration Desktop Access: Configure > Currency Conversion > Currency Conversion Rate Help ID: w_currency_conversion_rate_ configuration
✓	✓	IWTDatabaseAdministration	FullIWTDatabaseAdmin Permission	Database Administration Desktop Access: System Operations > Server Management > Server Administration > Database Administration Help ID: w_database_administration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		IssuerProfileConfig	FullIssProfConfig Permission	Destination Routing Profile Configuration Desktop Access: Configure > Routing > Profile Description > Destination Routing Profile Help ID: w_destination_routing_profile_ configuration
	✓	KEYGENLockdown	FullKEYGENLockdown Permission	Disable KEYGEN Desktop Access: Configure > Transaction Security > Automated Key Distribution > Disable KEYGEN Help ID: w_disable_keygen
	✓	B24SPDHDKPTDerivationKey	FullB24SPDHDKPTDKey Permission	DUKPT Derivation Key Profile Configuration Desktop Access: Configure > Transaction Security > DUKPT Derivation Key Profile Help ID: w_dukpt_derivation_key_ profile_configuration
✓	✓	EnvironmentManagement	FullEnvironmentMgmt Permission	Environment Configuration Desktop Access: System Operations > Environment Help ID: w_environment_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
	✓	EPPSerialNumberConfig	FullEPPSerialNumCfg Permission	EPP Serial Number Configuration Desktop Access: Configure > Transaction Security > Automated Key Distribution > EPP Serial Number Help ID: w_epp_serial_number_ configuration
✓		EuroOptedCurrencyConfiguration	FullEuroOptedCurrCfg Permission	Euro Opted Currency Configuration Desktop Access: Configure > Currency Conversion > Euro Opted Currency Help ID: w_euro_opted_currency_ configuration
✓	✓	EventConfiguration EventSubsystemConfiguration	FullEventConfig Permission	Event Configuration and Management Desktop Access: System Operations > Event > Event Management Help ID: w_integrated_server_event_ configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓	✓	EventSubsystemConfiguration	FullEventSubConfig Permission	Event Subsystem ID Configuration Desktop Access: System Operations > Event > Subsystem ID Help ID: w_event_subsystem_id_ configuration
✓		ExportedOperator	FullExportedOperator Permission	Exported Operators Configuration Desktop Access: Configure > Script > Exported Operators Help ID: w_exported_operators_ configuration
✓	✓	IWTConnectionConfig IWTPProcessConfig	FullIWTConnectionCfg Permission	External Connection Configuration Desktop Access: System Operations > Server Management > External Connection Help ID: w_external_connection_ configuration
✓		FilePartition	FullFilePartition Permission	File Partition Configuration Desktop Access: System Operations > Database Management > File Partition Help ID: w_file_partition_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		FileUpdateRouterConfig	FullFileUpdateRouterConfig Perm	File Update Router Desktop Access: Configure > Routing > File Update Router Help ID: w_file_update_router_ configuration
✓	✓	HostPKPerusal	FullHostPKPerusal Permission	Host Public Key Perusal Desktop Access: View > Automated Key Distribution > Host Public Key Perusal Help ID: w_host_public_key_perusal
✓		IFXHostActionCode	FullIFXHostActionCode Perm	IFX Host Action Code Profile Configuration Desktop Access: Configure > Interface > Host > IFX Host > IFX Host Action Code Profile Help ID: w_ifx_host_action_code_profile_ configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		IFXHostInterface InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, FullIFXHostActionCodePerm IssuerTransactionsAllowed, ContextConfiguration, ATMSurcharge IFXHostActionCode	FullIFXHostInterfacePerm	IFX Host Configuration Desktop Access: Configure > Interface > Host > IFX Host > IFX Host Interface Help ID: w_ifx_host_interface_ configuration
✓		IMTInterface InterfaceConfiguration IMTInterface IMTATMTransactionMapping IMTPOSTransactionMapping, IssuerTransactionsAllowed, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge TokenProfile	FullIMTInterface Permission	IMT Interface Configuration Desktop Access: Configure > Interface > Host > Internal Message Translator > Network > IMT Interface Help ID: w_imt_interface_configuration
✓		InstitutionConfiguration AcquirerProfileConfiguration	FullInstConfig Permission	Institution Configuration Desktop Access: Configure > Institution Help ID: w_institution_configuration
✓		InstrStatusMappingProfile	FullInstStatMapPrfl Permission	Instrument Status Mapping Profile Configuration Desktop Access: Configure > Interface > Instrument Status Mapping Profile Help ID: w_instrument_status_mapping_ profile_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		InstrumentTypeIchgRelation	FullInstTypIchgRel Permission	Instrument Type/Interchange Relationship Desktop Access: Configure > Interface > Instrument Type/Interchange Relationship Help ID: w_instrument_type_interchange_ relationship_configuration
✓		InterchangePrefixConfiguration	FullIchgPrefixConfig Permission	Interchange Prefix Configuration Desktop Access: Configure > Prefix > Not-On-Us > Interchange Prefix Help ID: w_interchange_prefix_ configuration
	✓	InterfaceSecurityConfiguration InterfaceConfiguration, SecurityDeviceConfiguration	FullIFSecurityConfig Permission	Interface Security Configuration Desktop Access: Configure > Transaction Security > Interface Help ID: w_interface_security_ configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		InterfaceTerm	FullInterfaceTerm Permission	Interface Terminal Desktop Access: Configure > Interface > Network > Star > Interface Terminal Help ID: w_interface_terminal_ configuration
✓		IMTATMTransactionMapping	FullIMTATMTransMap Permission	Internal Message Translation (IMT) Transaction Mapping - ATM Desktop Access: Configure > Interface > Host > Internal Message Translator > IMT Transaction Mapping - ATM Help ID: w_imt_transaction_mapping_atm
✓		IMTPOSTransactionMapping	FullIMTPOSTransMap Permission	Internal Message Translation (IMT) Transaction Mapping - POS Desktop Access: Configure > Interface > Host > Internal Message Translator > IMT Transaction Mapping - POS Help ID: w_imt_transaction_mapping_pos

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		InterpayInterface	FullInterpayIFPermission	Interpay (BIM) Interface Configuration Desktop Access: TBD Help ID: TBD
✓		ISO93InterfaceConfiguration InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	FullISO93IFConfig Permission	ISO 93 Host Interface Configuration Desktop Access: Configure > Interface > Host > ISO 93 Host Help ID: w_iso_93_host_interface_ configuration
✓		ISOFrameworkConfiguration	FullISOFrameworkCfg Permisson	ISO Message Profile Configuration Desktop Access: Configure > ISO Message Profile Help ID: w_iso_framework_configuration
✓		ISO93InterfaceConfiguration InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	FullISO93IFConfig Permission	ISO93 Interface Configuration Desktop Access: Configure > Interface > Network > ISO93 Help ID: w_interface_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		IssuerTransactionsAllowed	FullIssTransAllowed Permission	Issuer Transactions Allowed Profile Configuration Desktop Access: Configure > Transactions Allowed > Issuer Transactions Profile Help ID: w_issuer_transactions_allowed_ profile_configuration
✓		JournalConfigurationMapping JournalProfileConfiguration, InstitutionConfiguration, InterfaceConfiguration, and the interface-specific task IDs	FullJrnlCfgMapping Permission	Journal Issuer Profile Relationship Configuration Desktop Access: Configure > Journal > Issuer Profile Relationship Help ID: w_journal_issuer_profile_ relationship_configuration
✓		LogFilePerusal	FullLogFilePerusal Permission	Journal Perusal Desktop Access: View > Journal Perusal Help ID: w_journal_perusal
✓		JournalProfileConfiguration JournalConfigurationMapping	FullJrnlProfileCfg Permission	Journal Profile Configuration Desktop Access: Configure > Journal > Journal Profile Help ID: w_journal_profile_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		JournalQueryConfiguration JournalQueryExecution	FullJrnlQueryConfig Permission	Journal Query Configuration Desktop Access: Configure > Journal > Journal Query Help ID: w_journal_query_configuration
✓		JournalTDESuppression InstitutionConfiguration, InterfaceConfiguration	FullJrnlTDESuppress Permission	Journal TDE Suppression Configuration Desktop Access: Configure > Journal > Journal TDE Suppression Help ID: w_journal_tde_suppression
✓		LIS5Interface InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	FullLIS5Permission	LINK ISO Interface (LIS5) Configuration Desktop Access: Configure > Interface > Network > LINK ISO Help ID: w_link_lis5_interface_ configuration
✓		PaymentLimitConfig InstitutionConfiguration	FullPmtLimitConfig Permission	Limit Profile Management Desktop Access: Customer Management > Limit Profile Help ID: w_limit_profile_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		LinkedCurrencyConfiguration	FullLinkedCurrCfg Permission	Linked Currency Configuration Desktop Access: Configure > Currency Conversion > Linked Currency Help ID: w_linked_currency_ configuration
✓	✓	IWTListenerConfig IWTProcessConfig	FullIWTListenerCfg Permission	Listener Configuration Desktop Access: System Operations > Server Management > Listener Help ID: w_listener_configuration
	✓	MFKConverter	FullMFKConverter Permission	Master File Key Conversion Desktop Access: Configure > Transaction Security > Master File Key Conversion Help ID: w_master_file_key_conversion
✓		MaestroDebitSwitch InterfaceConfiguration AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	FullMaestro Permission	MasterCard Debit Switch (MDS) Interface Configuration Desktop Access: Configure > Interface Network > MasterCard Debit Switch (MDS) Help ID: w_mastercard_debit_switch_ configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		MerchantConfiguration ChannelConfiguration, InstitutionConfiguration, POSDeliveryChannel, POSDeliveryChannelProfile	FullMerchantConfig Permission	Merchant Configuration and Statistics Desktop Access: Configure > Merchant Processing > Merchant Help ID: w_merchant_configuration_and_ statistics
✓		PrefixConfiguration AuthenticationConfiguration, IssuerTransactionsAllowed, InstitutionConfiguration, InterfaceConfiguration, RoutingConfiguration and, the interface-specific task IDs	FullPrefixConfig Permission	On-Us Prefix Configuration Desktop Access: Configure > Prefix > On-Us Help ID: w_prefix_configuration
✓		PerusalConfiguration	FullPerusalConfig Permission	Perusal Profile Configuration Desktop Access: Configure > Journal > Perusal > Perusal Profile Help ID: w_perusal_profile_configuration
✓		POSDeliveryChannel ChannelConfiguration, MerchantConfiguration, POSDeliveryChannelProfile	FullPOSDlvryChannel Permission	POS Delivery Channel Configuration and Statistics Desktop Access: Configure > Merchant Processing > POS Delivery Channel Help ID: w_pos_delivery_channel_ configuration_and_statistics

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		POSDeliveryChannelProfile AcquirerProfileConfiguration, AcquirerTransactionsAllowed, ActionCode, ChannelConfiguration	FullPOSDlvryChnlPrfl Permission	POS Delivery Channel Profile Configuration Desktop Access: Configure > Merchant Processing > POS Delivery Channel Profile Help ID: w_pos_delivery_channel_ profile_configuration
✓		PositiveBalance InstitutionConfiguration, Usages, PreAuthHold, PaymentLimitConfig	FullPositiveBalance Permission	Positive Balance Management Desktop Access: Customer Management > Positive Balance Help ID: w_positive_balance_ management
✓		PreAuthHold InstitutionConfiguration, CardConfiguration	FullPreAuthHold Permission	Preauthorization Hold Management Desktop Access: Customer Management > Preauthorization Hold Help ID: w_preauthorization_hold_ management
✓	✓	IWTProcessConfig	FullIWTProcessCfg Permission	Process Configuration Desktop Access: System Operations > Server Management > Process Help ID: w_process_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓	✓	ProcessControl	FullProcContrl FullProcessControl	Process Control Desktop Access: System Operations > Process Control Help ID: w_process_control
✓		JournalQueryExecution JournalQueryConfiguration	FullJrnlQueryExecute Permission	Query Execute Desktop Access: System Operations > Query Execution Help ID: w_query_execute
✓		RealTimeFeedInterface	FullRealTimeFeedIF Permission	Real Time Feed Window Desktop Access: Configure > Interface > Host > Real Time Feed Help ID: w_realtimefeed_interface_ configuration
✓		RoutingConfiguration AcquirerIssuerRelationConfig	FullRoutingConfig Permission	Routing Configuration - Destination Desktop Access: Configure > Routing > Destinations Help ID: w_routing_configuration_ destination

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		AcquirerIssuerRelationConfig AcquirerProfileConfiguration, RoutingConfiguration	FullAcqIssRelatnCfg Permission	Routing Configuration - Destination/Source Relationship) Desktop Access: Configure > Routing > Destination/Source Help ID: w_destination_source_relationship
✓		ScriptEditor ScriptRepository	FullScriptEditor Permission	Script Editor Desktop Access: Configure > Script > Editor Help ID: w_script_editor
✓		ScriptRepository ScriptEditor	FullScriptRepository Permission	Script Repository Desktop Access: Configure > Script > Repository Help ID: w_script_repository
	✓	SecurityDeviceConfiguration	FullSecurityDevCfg Permission	Security Device Configuration Desktop Access: Configure > Transaction Security > Security Device Help ID: w_security_device_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓	✓	IWTSocketAdministration	FullIWTSocketAdmin Permission	Socket Administration Desktop Access: System Operations > Server Management > Server Administration > Socket Administration Help ID: w_socket_administration
✓		AcquirerProfileConfiguration	FullAcqProfileConfig Permission	Source Routing Profile Configuration Desktop Access: Configure > Routing > Profile Description > Source Routing Profile Help ID: w_source_routing_profile_ configuration
✓		SPDHDeviceConfig	FullSPDHDeviceConfig Permission	SPDH Device Profile Configuration Desktop Access: Configure > Merchant Processing > SPDH Device Profile Help ID: w_spdh_device_profile_ configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		StarInstitution StarNetworkIdRelationship StarInterface	FullStarInstitution Permission	STAR Institution Desktop Access: Configure > Interface > Network > Star > Star Institution Help ID: w_star_institution_configuration
✓		StarInterface StarNetworkIdRelationship StarInstitution	FullStarInterface Permission	STAR ISO Interface Configuration Desktop Access: Configure > Interface > Network > Star > Star ISO Help ID: w_star_iso_interface_ configuration
✓		StarNetworkIdRelationship StarInstitution StarInterface	FullStarNtwkIdRelation Perm	STAR Network Identifier/ Instrument Type Relationship Desktop Access: Configure > Interface > Network > Star > Star Network Identifier/ Instrument Type Relationship Help ID: w_star_network_identifier_ instrument_type_relationship_ configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		ATMSurcharge	FullATMSurcharge Permission	Surcharge Profile Configuration Desktop Access: Configure > Surcharge Profile Help ID: w_surcharge_profile_ configuration
✓		SystemAlgorithm	FullSystemAlgorith Permission	System Algorithm Configuration Desktop Access: Configure > Prefix > Not-On-Us > System Algorithm Help ID: w_system_algorithm
✓	✓	IWTSystemMonitor\ IWTDatabaseAdministration, IWTSocketAdministration, IWTConfigurationAdministration, IWTCachAdministration	FullIWTSystemMonitor Permission	System Monitor Desktop Access: System Operations > Server Management > Server Administration > System Monitor Help ID: w_system_monitor
✓		SystemPrefix	FullSystemPrefix Permission	System Prefix Configuration Desktop Access: Configure > Prefix > Not-On-Us > System Prefix Help ID: w_system_prefix_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓	✓	IWTSystemProperties	FullIWTSystemProperties Permission	System Properties Desktop Access: System Operations > Server Management > Server Administration > System Properties Help ID: w_system_properties
✓		TermLnFiidMap	FulltermLnFiidMapPerm	Terminal Logical Network/FIID Mapping Desktop Access: Configure > Interface > Host > BASE24ISO8583 Host > Terminal Logical Network/ FIID Mapping Help ID: w_terminal_logical_network_ fiid_mapping
✓		TokenProfile	FullTokenProfilePermission	Token Profile Configuration Desktop Access: Configure > Token Profile Help ID: w_token_profile_configuration
✓		TraceConfiguration	FullTraceConfig Permission	Trace Configuration Desktop Access: System Operations > Trace > Trace Help ID: w_trace_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		TraceFilterConfiguration	FullTraceFilterCfg Permission	Trace Filter Profile Configuration Desktop Access: System Operations > Trace > Trace Filter Profile Help ID: w_trace_filter_profile_ configuration
✓		Usages InstitutionConfiguration, CardConfiguration	FullUsages Permission	Usages Management Desktop Access: Customer Management > Usages Help ID: w_usages_management
✓		UserProfileRelation PerusalConfiguration, UserSecurityProfile	FullUserProfRelation Permission	User Profile Relationship Desktop Access: Configure > Journal > Perusal > User Profile Relation Help ID: w_user_profile_relationship
✓	✓	UserSecurityControl UserSecurityControl	FullUSCtl Permission	User Security Control Management Desktop Access: Configure > User Security > Control Help ID: w_user_security_control_ management

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓	✓	UserSecurityGroupConfig UserSecurityProfile, if Distributed Security Administration is enabled	FullUSGCfg Permission	User Security Group Configuration Desktop Access: Configure > User Security > Group Help ID: w_user_security_group_ configuration
✓	✓	UserSecurityProfile UserSecurityGroupConfig	FullUSP Permission	User Security Profile Configuration Desktop Access: Configure > User Security > Profile Help ID: w_user_security_profile_ configuration
✓	✓	UserSecurityRoleConfig	FullUSRCfg Permission	User Security Role Configuration Desktop Access: Configure > User Security > Role Help ID: w_user_security_role_ configuration
✓		VisaAcquirers	FullVisaAcquirers Permission	Visa Acquirers Configuration Desktop Access: Configure > Interface > Network > VisaNet > Visa Acquirer Help ID: w_visa_acquirers_configuration

BASE24-es	TSS	Task IDs Related Task IDs	Permission ID	Window (Desktop Access)
✓		VisaDPSInterface InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	FullVisaDPSInterface Permission	Visa DPS Interface Configuration Desktop Access: Configure > Interface > Network > Visa DPS Help ID: w_visa_dps_interface_ configuration
✓		VisanetInterfaceConfig InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge VisaAcquirers	FullVisanetIFConfig Permission	VisaNet ISO Interface Configuration Desktop Access: Configure > Interface > Network > VisaNet > VisaNet ISO Help ID: w_visanet_iso_interface_ configuration

C: Permission IDs

The following table lists default permission IDs and the corresponding window and task IDs.

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullAcqTransAllowed Permission	AcquirerTransactionsAllowed	Acquirer Transactions Allowed Profile Configuration Desktop Access: Configure > Transactions Allowed > Acquirer Transactions Profile Help ID: w_acquirer_transactions_ allowed_profile_configuration
✓		FullActionCode Permission	ActionCode	Action Code Profile Configuration Desktop Access: Configure > Action Code Profile Help ID: w_action_code
✓		FullActiveScript Permission	ActiveScript AuthScript	Active Script Statistics and Management Desktop Access: System Operations > Active Script Statistics Help ID: w_active_script_statistics_and_ management

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullAdminCardMgmt Permission	AdministrativeCardManagement	Administrative Card Configuration Desktop Access: Configure > Administrative Card Help ID: w_administrative_card_ configuration
✓		FullInterfaceConfig Permission	InterfaceConfiguration	All available interface configuration windows. Desktop Access: Configure > Interface > ... Help ID: w_interface_configuration
✓	✓	FullIWTAplCfg Permission	IWTApplicationConfig	Application Configuration Desktop Access: System Operations > Server Management > Application Help ID: w_application_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullApplctnManagement Summary	ApplctnManagement Summary	Application Management Comms Handler¹ Application Management Message Router Summary² Application Management Process Summary³ Application Management Queue Summary⁴ Application Management Queue Manager Summary⁵ Application Management Station Summary⁶ Desktop Access: System Operations > Application Management > ... Help IDs: ¹ w_appmanage_comms_ handler_summary ² w_appmanage_message_ router_summary ³ w_appmanage_process_ summary ⁴ w_appmanage_queue_ summary ⁵ w_appmanage_queue_ manager_summary ⁶ w_appmanage_station_ summary
✓		FullApplctnManagement	ApplctnManagement	Application Management Desktop Access: System Operations > Application Management > Application Management Help ID: w_application_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullAPMSIFCfg Permission	APMSInterfaceConfiguration ContextConfiguration	Application Parameter Management System Interface Configuration Desktop Access: Configure > Interface > Host > Application Parameter Management Help ID: w_apms_interface_configuration
✓		FullATMChannelAdmin Permission	ATMChannelAdministration ATMChannel, InstitutionConfiguration, ATMHopperProfile	ATM Channel Administration Desktop Access: System Operations > ATM Framework > ATM Channel Administration Help ID: w_atm_channel_administration
✓		FullATMChannel Permission	ATMChannel ATMHardwareStatus, InstitutionConfiguration, ATMChannelProfile	ATM Channel Configuration Desktop Access: Configure > ATM Framework > ATM Channel Help ID: w_atm_channel_configuration
✓		FullATMChannelMgmt Permission	ATMChannelManagement InstitutionConfiguration	ATM Channel Management - All Channels Desktop Access: System Operations > ATM Framework > ATM Channel Management > All Channels Help ID: w_atm_channel_all_channels

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullATMChanMgmtSC Permission	ATMChanMgmtSelectedChannels InstitutionConfiguration	ATM Channel Management Desktop Access: System Operations > ATM Framework > ATM Channel Management > Selected Channels Help ID: w_atm_channel_management
✓		FullATMChannelPrfl Permission	ATMChannelProfile ATMSurcharge	ATM Channel Profile Configuration Desktop Access: Configure > ATM Framework > ATM Channel Profile Help ID: w_atm_channel_profile_ configuration
✓		FullATMDHIFCf Permission	ATMDHInterfaceConfiguration InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, ActionCode, ISOFrameworkConfiguration, ATMSurcharge	ATM Device Handler Interface Configuration Desktop Access: Configure > Interface > Host > ATM Device Handler Help ID: w_atm_device_handler_ interface_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullATMDbldChanOprID Permission	ATMDieboldChannelOperatorID	ATM Diebold Channel Operator ID Configuration Desktop Access: Configure > ATM Framework > ATM Diebold Channel Operator Help ID: w_atm_diebold_channel_id_ configuration
✓		FullATMHardwareStat Permission	ATMHardwareStatus ATMChannel	ATM Hardware Status Desktop Access: View > ATM Framework > ATM Hardware Status Help ID: w_atm_hardware_status
✓		FullATMHopperPrfl Permission	ATMHopperProfile	ATM Hopper Profile Configuration Desktop Access: Configure > ATM Framework > ATM Hopper Profile Help ID: w_atm_hopper_profile_ configuration
✓		FullATMLoadProfile Permission	ATMLoadProfile	ATM Load Profile Desktop Access: Configure > ATM Framework > ATM Load Profile Help ID: w_atm_load_profile

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullATMOptnRcptPrfl Permission	ATMOptionalReceiptProfile	ATM Optional Receipt Profile Desktop Access: Configure > ATM Framework > ATM Optional Receipt Profile Help ID: w_atm_optional_receipt_profile
✓		FullATMReceiptFormat Permission	ATMReceiptFormat InstitutionConfiguration	ATM Receipt Format Configuration Desktop Access: Configure > ATM Framework > ATM Receipt Format Help ID: w_atm_receipt_format_profile_ configuration
✓		FullATMRcptReqType Permission	ATMReceiptRequiredType	ATM Receipt Required Type Configuration Desktop Access: Configure > ATM Framework > ATM Receipt Required Type Help ID: w_atm_receipt_required_type_ configuration
✓		FullATMReloadMaps Permission	ATMReloadMaps	ATM Reload Map Request Desktop Access: System Operations > ATM Framework > ATM Reload Map Help ID: w_atm_reload_map_request

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullATMStatusuery Permission	ATMStatusQuery	ATM Status Query Desktop Access: System Operations > ATM Framework > ATM Status Query Help ID: w_atm_status_query
✓		FullUserAuditRpt Permission	UserAuditReport	Audit Extract Window Desktop Access: Tools > Audit Extract Help ID: w_audit_extract
✓	✓	FullAuditSAFConfig Permission	AuditSAFConfig	Audit Store and Forward (SAF) Configuration Desktop Access: System Operations > Audit SAF Help ID: w_audit_store_and_forward_ configuration
	✓	FullAuthentConfig Permission	AuthenticationConfiguration SecurityDeviceConfiguration	Authentication Profile Configuration (Configure > Transaction Security > Authentication Profile) Help ID: w_authentication_profile_ configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullAuthScript Permission	AuthScript	Authorization Script Configuration Desktop Access: Configure > Script > Authorization Script Help ID: w_authorization_script_ configuration
✓		FullBanknetInterface Permission	BanknetInterface InterfaceConfiguration, BanknetMerchantProgram, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	BankNet ISO Interface Configuration Desktop Access: Configure > Interface > Network > BankNet ISO Help ID: w_banknet_iso_interface_ configuration
✓		FullB24HISOIFConfig Permission FullHISO	B24HISOInterfaceConfig InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge TermLnFiidMap TokenProfile	BASE24 ISO8583 Host Interface Configuration Desktop Access: Configure > Interface > Host > BASE24 ISO8583 Host Help ID: w_base24_iso8583_host_ interface_configuration
	✓	FullB24KEYFSecurity Permission	B24KEYFSecurity InterfaceSecurityConfiguration	BASE24 KEYF Configuration Desktop Access: Configure > Transaction Security > BASE24 KEYF Configuration Help ID: w_base24_keyf_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
	✓	FullBNTngHeader Configuration	BNTngHeaderConfig	BNTng Key Header Configuration Desktop Access: Configure > Transaction Security > BNTng Header Help ID: w_bntng_key_header_ configuration
✓	✓	FullIWTCacheAdmin Permission	IWTCacheAdministration	Cache Administration Desktop Access: System Operations > Server Management > Server Administration > Cache Administration Help ID: w_cache_administration
✓		FullCardConfig Permission	CardConfiguration InstitutionConfiguration, Usages, PreAuthHold, PaymentLimitConfig	Card Management Desktop Access: Customer Management > Card Help ID: w_card_management
	✓	FullCertificate Permission	Certificate	Certificate Management Desktop Access: Configure > Transaction Security > Automated Key Distribution > Certificate Management Help ID: w_certificate_management

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓	✓	FullChannelPKPerusal Permission	ChannelPKPerusal	Channel Public Key Perusal Desktop Access: View > Automated Key Distribution > Channel Public Key Perusal Help ID: w_channel_public_key_perusal
	✓	FullChannelSecurity Permission	ChannelSecurity ChannelConfiguration, SecurityDeviceConfiguration	Channel Security Configuration Desktop Access: Configure > Transaction Security > Channel Help ID: w_channel_security_ configuration
✓	✓	FullIWTConfigAdmin Permission	IWTConfigurationAdministration	Configuration Properties Desktop Access: System Operations > Server Management > Server Administration > Configuration Properties Help ID: w_configuration_properties
✓		FullContextConfig Permission	ContextConfiguration	Context Profile Configuration Desktop Access: Configure > Interface > Context Profile Help ID: w_context_profile_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullContingencyIF Permission	ContingencyInterface InterfaceConfiguration, ContextConfiguration, ATMSurcharge	Contingency Interface Configuration Desktop Access: Configure > Interface > Host > Contingency Help ID: w_contingency_interface_ configuration
✓		FullContingencySAF Permission	ContingencySAF	Contingency Store and Forward (SAF) Configuration Desktop Access: System Operations > Contingency SAF Help ID: w_contingency_store_and_ forward
✓		FullCrncyConvRateCfg Permission	CurrencyConvRateConfiguration InstitutionConfiguration	Currency Conversion Rate Configuration Desktop Access: Configure > Currency Conversion > Currency Conversion Rate Help ID: w_currency_conversion_rate_ configuration
✓	✓	FullIWTDDatabaseAdmin Permission	IWTDDatabaseAdministration	Database Administration Desktop Access: System Operations > Server Management > Server Administration > Database Administration Help ID: w_database_administration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullIssProfConfig Permission	IssuerProfileConfig	Destination Routing Profile Configuration Desktop Access: Configure > Routing > Profile Description > Destination Routing Profile Help ID: w_destination_routing_profile_ configuration
	✓	FullKEYGENLockdown Permission	KEYGENLockdown	Disable KEYGEN Desktop Access: Configure > Transaction Security > Automated Key Distribution > Disable KEYGEN Help ID: w_disable_keygen
	✓	FullB24SPDHUKPTDKey Permission	B24SPDHUKPTDerivationKey	DUKPT Derivation Key Profile Configuration Desktop Access: Configure > Transaction Security > DUKPT Derivation Key Profile Help ID: w_dukpt_derivation_key_ profile_configuration
✓	✓	FullEnvironmentMgmt Permission	EnvironmentManagement	Environment Configuration Desktop Access: System Operations > Environment Help ID: w_environment_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
	✓	FullEPPSerialNumCfg Permission	EPPSerialNumberConfig	EPP Serial Number Configuration Desktop Access: Configure > Transaction Security > Automated Key Distribution > EPP Serial Number Help ID: w_epp_serial_number_ configuration
✓		FullEuroOptedCurrCfg Permission	EuroOptedCurrencyConfiguration	Euro Opted Currency Configuration Desktop Access: Configure > Currency Conversion > Euro Opted Currency Help ID: w_euro_opted_currency_ configuration
✓	✓	FullEventConfig Permission	EventConfiguration EventSubsystemConfiguration	Event Configuration and Management Desktop Access: System Operations > Event > Event Management Help ID: w_integrated_server_event_ configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓	✓	FullEventSubConfig Permission	EventSubsystemConfiguration	Event Subsystem ID Configuration Desktop Access: System Operations > Event > Subsystem ID Help ID: w_event_subsystem_id_ configuration
✓		FullExportedOperator Permission	ExportedOperator	Exported Operators Configuration Desktop Access: Configure > Script > Exported Operators Help ID: w_exported_operators_ configuration
✓	✓	FullIWTConnectionCfg Permission	IWTConnectionConfig IWTProcessConfig	External Connection Configuration Desktop Access: System Operations > Server Management > External Connection Help ID: w_external_connection_ configuration
✓		FullFilePartition Permission	FilePartition	File Partition Configuration Desktop Access: System Operations > Database Management > File Partition Help ID: w_file_partition_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullFileUpdateRouterConfig Perm	FileUpdateRouterConfig	File Update Router Desktop Access: Configure > Routing > File Update Router Help ID: w_file_update_router_ configuration
✓	✓	FullHostPKPerusal Permission	HostPKPerusal	Host Public Key Perusal Desktop Access: View > Automated Key Distribution > Host Public Key Perusal Help ID: w_host_public_key_perusal
✓		FullIFXHostActionCode Perm	IFXHostActionCode	IFX Host Action Code Profile Configuration Desktop Access: Configure > Interface > Host > IFX Host > IFX Host Action Code Profile Help ID: w_ifx_host_action_code_profile_ configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullIFXHostInterfacePerm	IFXHostInterface InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, FullIFXHostActionCodePerm IssuerTransactionsAllowed, ContextConfiguration, ATMSurcharge IFXHostActionCode	IFX Host Configuration Desktop Access: Configure > Interface > Host > IFX Host > IFX Host Interface Help ID: w_ifx_host_interface_ configuration
✓		FullIMTInterface Permission	IMTInterface InterfaceConfiguration IMTInterface IMTATMTransactionMapping IMTPOSTransactionMapping, IssuerTransactionsAllowed, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge TokenProfile	IMT Interface Configuration Desktop Access: Configure > Interface > Host > Internal Message Translator > Network > IMT Interface Help ID: w_imt_interface_configuration
✓		FullInstConfig Permission	InstitutionConfiguration AcquirerProfileConfiguration	Institution Configuration Desktop Access: Configure > Institution Help ID: w_institution_configuration
✓		FullInstStatMapPrfl Permission	InstrStatusMappingProfile	Instrument Status Mapping Profile Configuration Desktop Access: Configure > Interface > Instrument Status Mapping Profile Help ID: w_instrument_status_mapping_ profile_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullInstTypIchgRel Permission	InstrumentTypeIchgRelation	Instrument Type/Interchange Relationship Desktop Access: Configure > Interface > Instrument Type/Interchange Relationship Help ID: w_instrument_type_interchange_ relationship_configuration
✓		FullIchgPrefixConfig Permission	InterchangePrefixConfiguration	Interchange Prefix Configuration Desktop Access: Configure > Prefix > Not-On-Us > Interchange Prefix Help ID: w_interchange_prefix_ configuration
	✓	FullIFSecurityConfig Permission	InterfaceSecurityConfiguration InterfaceConfiguration, SecurityDeviceConfiguration	Interface Security Configuration Desktop Access: Configure > Transaction Security > Interface Help ID: w_interface_security_ configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullInterfaceTerm Permission	InterfaceTerm	Interface Terminal Desktop Access: Configure > Interface > Network > Star > Interface Terminal Help ID: w_interface_terminal_ configuration
✓		FullIMTATMTransMap Permission	IMTATMTransactionMapping	Internal Message Translation (IMT) Transaction Mapping - ATM Desktop Access: Configure > Interface > Host > Internal Message Translator > IMT Transaction Mapping - ATM Help ID: w_imt_transaction_mapping_atm
✓		FullIMTPOSTransMap Permission	IMTPOSTransactionMapping	Internal Message Translation (IMT) Transaction Mapping - POS Desktop Access: Configure > Interface > Host > Internal Message Translator > IMT Transaction Mapping - POS Help ID: w_imt_transaction_mapping_pos

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullInterpayIFPermission	InterpayInterface	Interpay (BIM) Interface Configuration Desktop Access: TBD Help ID: TBD
✓		FullISO93IFConfig Permission	ISO93InterfaceConfiguration InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	ISO 93 Host Interface Configuration Desktop Access: Configure > Interface > Host > ISO 93 Host Help ID: w_iso_93_host_interface_ configuration
✓		FullISOFrameworkCfg Permisson	ISOFrameworkConfiguration	ISO Message Profile Configuration Desktop Access: Configure > ISO Message Profile Help ID: w_iso_framework_configuration
✓		FullISO93IFConfig Permission	ISO93InterfaceConfiguration InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	ISO93 Interface Configuration Desktop Access: Configure > Interface > Network > ISO93 Help ID: w_interface_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullIssTransAllowed Permission	IssuerTransactionsAllowed	Issuer Transactions Allowed Profile Configuration Desktop Access: Configure > Transactions Allowed > Issuer Transactions Profile Help ID: w_issuer_transactions_allowed_ profile_configuration
✓		FullJrnlCfgMapping Permission	JournalConfigurationMapping JournalProfileConfiguration, InstitutionConfiguration, InterfaceConfiguration, and the interface-specific task IDs	Journal Issuer Profile Relationship Configuration Desktop Access: Configure > Journal > Issuer Profile Relationship Help ID: w_journal_issuer_profile_ relationship_configuration
✓		FullLogFilePerusal Permission	LogFilePerusal	Journal Perusal Desktop Access: View > Journal Perusal Help ID: w_journal_perusal
✓		FullJrnlProfileCfg Permission	JournalProfileConfiguration JournalConfigurationMapping	Journal Profile Configuration Desktop Access: Configure > Journal > Journal Profile Help ID: w_journal_profile_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullJrnlQueryConfig Permission	JournalQueryConfiguration JournalQueryExecution	Journal Query Configuration Desktop Access: Configure > Journal > Journal Query Help ID: w_journal_query_configuration
✓		FullJrnlTDESuppress Permission	JournalTDESuppression InstitutionConfiguration, InterfaceConfiguration	Journal TDE Suppression Configuration Desktop Access: Configure > Journal > Journal TDE Suppression Help ID: w_journal_tde_suppression
✓		FullLIS5Permission	LIS5Interface InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	LINK ISO Interface (LIS5) Configuration Desktop Access: Configure > Interface > Network > LINK ISO Help ID: w_link_lis5_interface_ configuration
✓		FullPmtLimitConfig Permission	PaymentLimitConfig InstitutionConfiguration	Limit Profile Management Desktop Access: Customer Management > Limit Profile Help ID: w_limit_profile_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullLinkedCurrCfg Permission	LinkedCurrencyConfiguration	Linked Currency Configuration Desktop Access: Configure > Currency Conversion > Linked Currency Help ID: w_linked_currency_ configuration
✓	✓	FullIWTListenerCfg Permission	IWTListenerConfig IWTProcessConfig	Listener Configuration Desktop Access: System Operations > Server Management > Listener Help ID: w_listener_configuration
	✓	FullMFKConverter Permission	MFKConverter	Master File Key Conversion Desktop Access: Configure > Transaction Security > Master File Key Conversion Help ID: w_master_file_key_conversion
✓		FullMaestro Permission	MaestroDebitSwitch InterfaceConfiguration AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	MasterCard Debit Switch (MDS) Interface Configuration Desktop Access: Configure > Interface Network > MasterCard Debit Switch (MDS) Help ID: w_mastercard_debit_switch_ configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullMerchantConfig Permission	MerchantConfiguration ChannelConfiguration, InstitutionConfiguration, POSDeliveryChannel, POSDeliveryChannelProfile	Merchant Configuration and Statistics Desktop Access: Configure > Merchant Processing > Merchant Help ID: w_merchant_configuration_and_ statistics
✓		FullPrefixConfig Permission	PrefixConfiguration AuthenticationConfiguration, IssuerTransactionsAllowed, InstitutionConfiguration, InterfaceConfiguration, RoutingConfiguration and, the interface-specific task IDs	On-Us Prefix Configuration Desktop Access: Configure > Prefix > On-Us Help ID: w_prefix_configuration
✓		FullPerusalConfig Permission	PerusalConfiguration	Perusal Profile Configuration Desktop Access: Configure > Journal > Perusal > Perusal Profile Help ID: w_perusal_profile_configuration
✓		FullPOSDlrvyChannel Permission	POSDeliveryChannel ChannelConfiguration, MerchantConfiguration, POSDeliveryChannelProfile	POS Delivery Channel Configuration and Statistics Desktop Access: Configure > Merchant Processing > POS Delivery Channel Help ID: w_pos_delivery_channel_ configuration_and_statistics

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullPOSDlvryChnlPrfl Permission	POSDeliveryChannelProfile AcquirerProfileConfiguration, AcquirerTransactionsAllowed, ActionCode, ChannelConfiguration	POS Delivery Channel Profile Configuration Desktop Access: Configure > Merchant Processing > POS Delivery Channel Profile Help ID: w_pos_delivery_channel_ profile_configuration
✓		FullPositiveBalance Permission	PositiveBalance InstitutionConfiguration, Usages, PreAuthHold, PaymentLimitConfig	Positive Balance Management Desktop Access: Customer Management > Positive Balance Help ID: w_positive_balance_ management
✓		FullPreAuthHold Permission	PreAuthHold InstitutionConfiguration, CardConfiguration	Preauthorization Hold Management Desktop Access: Customer Management > Preauthorization Hold Help ID: w_preauthorization_hold_ management
✓	✓	FullIWTPProcessCfg Permission	IWTPProcessConfig	Process Configuration Desktop Access: System Operations > Server Management > Process Help ID: w_process_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓	✓	FullProcContrl FullProcessControl	ProcessControl	Process Control Desktop Access: System Operations > Process Control Help ID: w_process_control
✓		FullJrnlQueryExecute Permission	JournalQueryExecution JournalQueryConfiguration	Query Execute Desktop Access: System Operations > Query Execution Help ID: w_query_execute
✓		FullRealTimeFeedIF Permission	RealTimeFeedInterface	Real Time Feed Window Desktop Access: Configure > Interface > Host > Real Time Feed Help ID: w_realtimefeed_interface_ configuration
✓		FullRoutingConfig Permission	RoutingConfiguration AcquirerIssuerRelationConfig	Routing Configuration - Destination Desktop Access: Configure > Routing > Destinations Help ID: w_routing_configuration_ destination

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullAcqIssRelatnCfg Permission	AcquirerIssuerRelationConfig AcquirerProfileConfiguration, RoutingConfiguration	Routing Configuration - Destination/Source Relationship) Desktop Access: Configure > Routing > Destination/Source Help ID: w_destination_source_relationship
✓		FullScriptEditor Permission	ScriptEditor ScriptRepository	Script Editor Desktop Access: Configure > Script > Editor Help ID: w_script_editor
✓		FullScriptRepository Permission	ScriptRepository ScriptEditor	Script Repository Desktop Access: Configure > Script > Repository Help ID: w_script_repository
	✓	FullSecurityDevCfg Permission	SecurityDeviceConfiguration	Security Device Configuration Desktop Access: Configure > Transaction Security > Security Device Help ID: w_security_device_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓	✓	FullIWTSocketAdmin Permission	IWTSocketAdministration	Socket Administration Desktop Access: System Operations > Server Management > Server Administration > Socket Administration Help ID: w_socket_administration
✓		FullAcqProfileConfig Permission	AcquirerProfileConfiguration	Source Routing Profile Configuration Desktop Access: Configure > Routing > Profile Description > Source Routing Profile Help ID: w_source_routing_profile_ configuration
✓		FullSPDHDeviceConfig Permission	SPDHDeviceConfig	SPDH Device Profile Configuration Desktop Access: Configure > Merchant Processing > SPDH Device Profile Help ID: w_spdh_device_profile_ configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullStarInstitution Permission	StarInstitution StarNetworkIdRelationship StarInterface	STAR Institution Desktop Access: Configure > Interface > Network > Star > Star Institution Help ID: w_star_institution_configuration
✓		FullStarInterface Permission	StarInterface StarNetworkIdRelationship StarInstitution	STAR ISO Interface Configuration Desktop Access: Configure > Interface > Network > Star > Star ISO Help ID: w_star_iso_interface_ configuration
✓		FullStarNtwkIdRelation Perm	StarNetworkIdRelationship StarInstitution StarInterface	STAR Network Identifier/ Instrument Type Relationship Desktop Access: Configure > Interface > Network > Star > Star Network Identifier/ Instrument Type Relationship Help ID: w_star_network_identifier_ instrument_type_relationship_ configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullATMSurcharge Permission	ATMSurcharge	Surcharge Profile Configuration Desktop Access: Configure > Surcharge Profile Help ID: w_surcharge_profile_ configuration
✓		FullSystemAlgoritm Permission	SystemAlgorithm	System Algorithm Configuration Desktop Access: Configure > Prefix > Not-On-Us > System Algorithm Help ID: w_system_algorithm
✓	✓	FullIWTSytemMonitor Permission	IWTSystemMonitor\ IWTDatabaseAdministration, IWTSocketAdministration, IWTConfigurationAdministration, IWTCachAdministration	System Monitor Desktop Access: System Operations > Server Management > Server Administration > System Monitor Help ID: w_system_monitor
✓		FullSystemPrefix Permission	SystemPrefix	System Prefix Configuration Desktop Access: Configure > Prefix > Not-On-Us > System Prefix Help ID: w_system_prefix_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓	✓	FullIWTSysProperties Permission	IWTSystemProperties	System Properties Desktop Access: System Operations > Server Management > Server Administration > System Properties Help ID: w_system_properties
✓		FulltermLnFiidMapPerm	TermLnFiidMap	Terminal Logical Network/FIID Mapping Desktop Access: Configure > Interface > Host > BASE24ISO8583 Host > Terminal Logical Network/ FIID Mapping Help ID: w_terminal_logical_network_ fiid_mapping
✓		FullTokenProfilePermission	TokenProfile	Token Profile Configuration Desktop Access: Configure > Token Profile Help ID: w_token_profile_configuration
✓		FullTraceConfig Permission	TraceConfiguration	Trace Configuration Desktop Access: System Operations > Trace > Trace Help ID: w_trace_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullTraceFilterCfg Permission	TraceFilterConfiguration	Trace Filter Profile Configuration Desktop Access: System Operations > Trace > Trace Filter Profile Help ID: w_trace_filter_profile_ configuration
✓		FullUsages Permission	Usages InstitutionConfiguration, CardConfiguration	Usages Management Desktop Access: Customer Management > Usages Help ID: w_usages_management
✓		FullUserProfRelation Permission	UserProfileRelation PerusalConfiguration, UserSecurityProfile	User Profile Relationship Desktop Access: Configure > Journal > Perusal > User Profile Relation Help ID: w_user_profile_relationship
✓	✓	FullUSCtl Permission	UserSecurityControl UserSecurityControl	User Security Control Management Desktop Access: Configure > User Security > Control Help ID: w_user_security_control_ management

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓	✓	FullUSGCfg Permission	UserSecurityGroupConfig UserSecurityProfile, if Distributed Security Administration is enabled	User Security Group Configuration Desktop Access: Configure > User Security > Group Help ID: w_user_security_group_ configuration
✓	✓	FullUSP Permission	UserSecurityProfile UserSecurityGroupConfig	User Security Profile Configuration Desktop Access: Configure > User Security > Profile Help ID: w_user_security_profile_ configuration
✓	✓	FullUSRCfg Permission	UserSecurityRoleConfig	User Security Role Configuration Desktop Access: Configure > User Security > Role Help ID: w_user_security_role_ configuration
✓		FullVisaAcquirers Permission	VisaAcquirers	Visa Acquirers Configuration Desktop Access: Configure > Interface > Network > VisaNet > Visa Acquirer Help ID: w_visa_acquirers_configuration

BASE24-es	TSS	Permission ID	Task IDs Related Task IDs	Window (Desktop Access)
✓		FullVisaDPSInterface Permission	VisaDPSInterface InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge	Visa DPS Interface Configuration Desktop Access: Configure > Interface > Network > Visa DPS Help ID: w_visa_dps_interface_ configuration
✓		FullVisanetIFConfig Permission	VisanetInterfaceConfig InterfaceConfiguration, AcquirerProfileConfiguration, AcquirerTransactionsAllowed, IssuerTransactionsAllowed, ActionCode, ContextConfiguration, ISOFrameworkConfiguration, ATMSurcharge VisaAcquirers	VisaNet ISO Interface Configuration Desktop Access: Configure > Interface > Network > VisaNet > VisaNet ISO Help ID: w_visanet_iso_interface_ configuration

Index

A

Access user security windows, [3-3](#)
Active sessions
 Maximum allowed, [3-6](#)
Active user sessions, [4-4](#)
Application Area, [1-2](#)
Audit_Store_and_Forward data source, [5-1](#)
Authenticated users, [2-5](#)
Automatic JAR file updating, [6-5](#)

C

Cascading Style Sheets (CSS), JavaHelp, [7-4](#)
Confirm deletes check box, [2-11](#)
Confirm updates check box, [2-11](#)
Content files, JavaHelp, [7-4](#)
Context sensitive help, [7-6](#)
Currency format locale, [2-11](#)
Custom online help, [7-8](#)

D

Default users, [1-9](#)
Desktop console, [2-2](#)
Desktop layout (areas), [1-2](#)
DeskTop.log file, [2-15](#)
Distributed Security Administration (DSA), [3-8](#)
DSA (Distributed Security Administration), [3-8](#)

F

Fail over support, [1-6](#)
Filter settings, [3-17](#)
Frame open indicator, [2-11](#)

G

Get Info function, [3-22](#)

H

Helpset file, JavaHelp, [7-4](#)
Helpset Viewer, [7-1](#)
hsviewer.jar, [7-11](#)

I

Images, JavaHelp, [7-4](#)

J

JAR files for JavaHelp, [7-4](#)
JAR versions, [2-19](#)
JavaHelp, [7-1](#)
JavaHelp configuration files, [7-4](#)
JavaHelp viewer, [7-2](#)

L

local.cfg, [1-3](#)

M

Map file, JavaHelp, [7-4](#)
Map IDs
 Help IDs, [7-6](#)
Maximum number of allowed active sessions, [3-6](#)
Menu Bar, [1-2](#)
Mirroring, [6-4](#)

N

Navigation tree, [1-2](#)
Navigation tree check box, [2-11](#)

O

Online help viewer (JavaHelp), [7-2](#)
OwnerIDSupport property, [3-8](#)

P

- Packaging of online help, [7-4](#)
- Password error alert message, [2-9](#)
- Password group, [3-5](#)
- Passwords, [3-5](#)
 - change by a user, [2-9](#)
 - change by an administrator, [4-7](#)
 - restrictions, [3-5](#)
- Permission groups, [3-4](#)
- Permissions, [3-4](#)
- Pre-show frame indicator, [2-12](#)
- Print (setup, preview), [2-17](#)
- Print Screen Orientation, [2-12](#)
- Procedures
 - Access online help from the desktop, [7-3](#)
 - Access user security windows, [3-3](#)
 - Assign a security group, [3-24](#)
 - Assign a system administration role filter, [3-15](#)
 - Assign roles to a user, [3-26](#)
 - Change a password (by a user), [2-9](#)
 - Change a user password (by admin), [4-7](#)
 - Change the display of JavaHelp content, [7-10](#)
 - Configure a password group, [3-11](#)
 - Configure a security group, [3-12](#)
 - Configure a user role, [3-16](#)
 - Configure field filters, [3-17](#)
 - Configure permission groups, [3-22](#)
 - Configure permissions, [3-20](#)
 - Connect to a web server, [2-16](#)
 - Create custom JavaHelp content HTML files, [7-9](#)
 - Create custom online help, [7-8](#)
 - Display active user sessions, [4-4](#)
 - Display the user interface framework version, [2-19](#)
 - Display user password history, [4-7](#)
 - Exit from the desktop, [2-18](#)
 - Expire a user password, [4-7](#)
 - Expire passwords by password group, [4-8](#)
 - Hide or show the navigation tree, [2-11](#)
 - Install JavaHelp, [7-11](#)
 - Log off (out), [2-8](#)
 - Log off a user, [4-6](#)
 - Log on, [2-5](#)
 - Mirror the repository, [6-4](#)
 - Search the helpset, [7-7](#)
 - Send a snapshot, [2-15](#)
 - Set a user status, [4-3](#)
 - Set Error Notification settings, [2-13](#)
 - Set sound preferences, [2-14](#)
 - Set user preferences, [2-10](#)
 - Start the ACI desktop, [2-2](#)
 - Terminate an active user session, [4-6](#)
 - View active user sessions (refreshing, updating), [4-5](#)
 - View password change history, [4-7](#)

R

- REPORT.USERAUDITLOG.LOC environment attribute, [5-3](#)
- Roles, [3-4](#)
- RunDesktop.bat, [2-2](#), [6-1](#)

S

- Search the helpset, [7-7](#)
- Secure Sockets Layer (SSL) protocol, [1-4](#)
- Security domains, [3-8](#)
- Security error alert message, [2-6](#)
- Security groups (users), [3-6](#)
- Security warning alert message, [2-6](#)
- Session timeout, [3-7](#), [3-13](#)
- Sessions (active), [4-4](#)
- Snapshots, [2-15](#)
- sound.cfg, [2-14](#)
- Status Pane, [1-2](#)
- Status pane, [2-12](#)
- SysAdmin Profile, [3-15](#)
- System Administration Profile, [3-15](#)

T

- Table of contents, JavaHelp, [7-4](#)
- Ticket, [1-5](#)
- Timeouts
 - session, [3-13](#)
 - UI, [3-13](#)
- Title Bar, [1-2](#)
- Toolbar, [1-2](#), [2-12](#)
- Tooltip text
 - display errors in, [2-13](#)

U

- UI timeout, [3-13](#)
- User authentication, [1-5](#)
- User authorization, [1-5](#)
- User interface framework, [1-3](#)
- User interface framework version, [2-19](#)
- User Preferences window
 - Error Notification tab, [2-13](#)
 - General tab, [2-10](#)
 - Sound tab, [2-14](#)
- User roles, [3-4](#)
- User Security Group Configuration window
 - Password Group tab, [3-11](#)
- User Security Control Management window
 - Active Sessions tab, [4-4](#), [4-6](#)
 - Password Maintenance tab, [4-8](#)

U *continued*

- User Security Group Configuration window
 - Security Group tab, [3-12](#)
- User Security Profile Configuration window
 - Active Sessions tab, [4-4](#), [4-6](#)
 - General tab, [3-23](#), [4-3](#)
- User Security Profile window
 - Password tab, [4-7](#)
 - Roles tab, [3-26](#)
- User Security Role Configuration window
 - Permission Groups tab, [3-22](#)
 - Permissions tab, [3-20](#)
 - Roles tab, [3-16](#)
- User security server
 - Fail over support, [1-6](#)
 - overview, [1-5](#)
- User sessions, [4-4](#)
- User status, [4-3](#)
- USRAULOG data source, [5-1](#)

V

- VC quiet mode, [6-5](#)
- Version Checker Client window, [6-2](#)
- Version Checker Server, [6-1](#)
- Versions, [2-19](#)

W

- Web server
 - selecting, [2-16](#)
- Web servers, [1-3](#)

X

- XML audit message format, [5-2](#)
- XML index file, JavaHelp, [7-4](#)

ACI Worldwide Inc.