

ACI Desktop User Interface Manual

BASE24-esTM



© 2006 by ACI Worldwide Inc. All rights reserved.

All information contained in this documentation is confidential and proprietary to ACI Worldwide Inc., and has been delivered for use pursuant to license. No part of this documentation may be photocopied, electronically transferred, modified, or reproduced in any manner that is contrary to license without the prior written consent of ACI Worldwide Inc.

Access Control Server, ACI Automated Case Management System, ACI Card Management System, ACI Claims Manager, ACI Commerce Gateway, ACI Debit Card System, ACI e-Courier, ACI Host Link, ACI Merchant Accounting System, ACI Payments Manager, ACI Proactive Risk Manager, ACI Smart Chip Manager, BASE24, BASE24-atm, BASE24-card, BASE24-check auth, BASE24-configuration manager, BASE24-es, BASE24-frequent shopper, BASE24-infobase, BASE24-pos, BASE24-refunds, BASE24-remote banking, BASE24-teller, NET24, and WINPAY24 are trademarks or registered trademarks of ACI Worldwide Inc., Transaction Systems Architects, Inc., or their subsidiaries.

Other companies' trademarks, service marks, or registered trademarks and service marks are trademarks, service marks, or registered trademarks and service marks of their respective companies.

Contents

Preface	v
Conventions Used in This Manual	vii
1: Introduction	1-1
Communication Security	1-3
User Security Server	1-4
Configuration Files	1-5
2: Getting Started and Basic Functions	2-1
Connection Information	2-2
Log On	2-2
Connect to a Web Server (or Node Controller)	2-4
Change a Password	2-5
Log Off and Exit	2-5
User Preferences	2-6
General Preferences	2-6
Error Notification Preferences	2-9
Sound Preferences	2-10
Snapshots	2-11
Display Framework Version Information	2-12
3: User Configuration	3-1
User Security Configuration Window Usage	3-2
User Profiles	3-3
Roles	3-3
Passwords and Password Groups	3-4
Security Groups	3-5
Distributed Security Administration (DSA)	3-7
Steps to Add a User	3-8

4: User Management	4-1
Set the Status of a User	4-2
Active User Session Management	4-3
Terminate Active User Sessions (Log off a User)	4-4
Password Management	4-5
5: User Auditing	5-1
User Audit Activity Reports	5-2
Automated User Auditing	5-5
6: Version Checker	6-1
7: Online Help	7-1
Access to JavaHelp from the ACI Desktop	7-2
With Context	7-2
Without Context	7-2
JavaHelp Files	7-3
JavaHelp Packages	7-3
Helpset File	7-4
How Context is Implemented in JavaHelp	7-5
Search the Helpset for a Text String	7-6
Custom Help Content	7-7
Customization of HTML Content Files	7-8
Change the Display of Content	7-9
Install JavaHelp for Stand-alone Use	7-10
A: Task IDs, Windows, and Permissions	A-1
Index	Index-1

Preface

The ACI desktop is the user access to the following ACI applications for configuration, operation, and management functions:

- BASE24-es
- Enhanced authorization for BASE24 applications
- Transaction Security Services (TSS)
- ACI Payments Manager

Audience

This manual is written for all users of the ACI desktop, including system administration personnel.

Prerequisites

Readers must know basic graphical user interface (GUI) functionality and procedures, such as using hyperlinks and buttons. The ACI desktop is organized by tasks (i.e., configure, system operations, and customer management) that require basic understanding of managing payment systems and applications.

Software

This manual documents standard processing as of its publication date. Software that is not current and custom software modifications (CSMs) may result in processing that differs from the material presented in this manual.

Manual Summary

Section 1, “Introduction,” provides an overview of the ACI desktop, windows, communication security, and information about default users. Also included is information about the user interface framework and user security servers.

Section 2, “Getting Started and Basic Functions,” describes how to log on and log off, set user preferences, and print, among other basic functions available from the File menu.

Section 3, “User Configuration,” provides an overview of user security, distributed security administration (DSA), and how to configure a user of the ACI desktop.

Section 4, “User Management,” describes how to manage and monitor users of the ACI desktop.

Section 5, “User Auditing,” provides an overview of user auditing of the ACI desktop, including generating audit reports.

Section 6, “Version Checker,” describes how the Version Checker manages and updates ACI desktop versions.

Section 7, “Online Help,” describes the desktop online help (JavaHelp) and how to use online help. Provides information about localizing the ACI desktop and customizing online help.

Appendix A, “Task IDs, Windows, and Permissions,” provides a list of each ACI desktop window and related permission and task IDs.

Publication Identification

Information appears at the bottom of each page to identify this manual. This information includes:

- ❑ Publication date (Jun-2006)
- ❑ BASE24-es release and version number (R1.0v06.2)
- ❑ Publication number (CF-CS000-01ES)

Conventions Used in This Manual




This manual uses the symbol shown at the left to alert you to cross-industry best practices for protecting sensitive data that is stored, processed, or transmitted in a BASE24-es system. Whenever you see this symbol, you should carefully review the information provided next to the symbol to ensure you are implementing cross-industry best practices for securing data. Refer to the ***BASE24-es Security Best Practices*** for more information about configuring the BASE24-es product to comply with cross-industry best practices.

ACI Worldwide Inc.

1: Introduction

The user interface of the ACI desktop consists of distinctive areas identified in the illustration below.



- **1** – The **Title Bar** displays the name of the desktop.
- **2** – The **Menu Bar** provides access to available functions and application windows.
- **3** – The **Toolbar** contains buttons for common functions, such as logon, logoff, and online help.
- **4** – The **Navigation Tree** provides a hierarchical view of the menu bar.
- **5** – The **Application Area** contains opened application windows.
- **6** – The **Status Pane** contains informational messages about the activity between the desktop and servers. Right click on this pane to see additional messages previously received messages.

The key component of the ACI desktop is the **user interface framework**, which is a collection of Java classes, interface applications, rules, guidelines, recommendations, and styles that are used as a template for building and supporting ACI desktop applications. The components of the user interface framework include:

- User interface clients for which common functions, such as logging on and off the desktop, are available through the File menu
- User security server
- Web servers, such as WebGate (for BASE24-es, enhanced authorization for BASE24, and TSS)

Each web server is responsible for managing communication among desktop clients and the user security server. Multiple web servers can be available in groups and are configured for the desktop using the local.cfg file. By defining groups, users can select web servers as applicable.

- Version Checker for automatic client version checking and updating
- Online help that is context sensitive

These components communicate with each other and with applications running on the application host server using a variety technologies. XML messages are passed to application servers on the host using Transmission Control Protocol/Internet Protocol (TCP/IP).

Hypertext Transfer Protocol (HTTP) is used for ACI desktops to communicate with web servers clients. Java-based Remote Method Invocation (RMI) is used to communicate with the user security server.

Communication Security

Connections among ACI desktops, web servers, user security servers, and application servers on the host can be configured to be secured using Secure Sockets Layer (SSL).

Certificates are used to authenticate servers to desktop clients, and optionally authenticate clients to servers. Public key cryptography is used to encrypt messages sent among clients and servers.

Note: SSL is configured using SSL specific properties defined using the Application Configuration window (**System Operations > Server Management > Application**). Refer to the *ACI Java Server Framework User Guide* for more information.

The following Java™ Archive files provide the support needed for SSL:

- Jcert.jar
- Jnet.jar
- Jsse.jar
- UIFSSLKeys.jar, which contains the default keystores.

Certificates and private keys used for encryption and authentication are maintained in protected files called keystores. These files vary by application and are identified by .sto.



Note: Custom communication developed and implemented for TCP/IP lines outside of the ACI desktop must be secured using SSL.

User Security Server

The user security server authenticates and authorizes users, creates and maintains active user sessions, and maintains the access level for each user. Host applications access the user security server to obtain authorization to complete a function initiated by an authenticated user of the ACI desktop.

For authentication, an individual must provide a user ID and password. This information is passed to the user security server, which checks the information against the user security database to determine whether the individual can access the application. This authentication includes the requirement that the user ID be defined in the user security database and the password must match that recorded for the ID. In addition, the user's security group and password group restrictions are checked.

User authorization is the validating of each activity initiated by a user. During user authorization the user security server compares the activity initiated by a user to the user's security profile, which defines the functions (i.e., Delete, Save, and View) that a user can perform. This ensures that a user does not perform an activity not authorized by the user's security configuration.

See section 3 (User Configuration) and section 4 (User Management) for more information.

Configuration Files

The following configuration files in the user interface framework are used by the desktop:

- The usec.cfg for configuring user security.
- The local.cfg for configuring the local desktop client.
- The user preferences configuration files (*username.cfg* and *networkname.cfg*). The names of these files vary per the user names and network names.
- The global.cfg and globalprefs.cfg configuration files that define global properties that can be used in the other configuration files.
- The sound.cfg for desktop sounds.


Configuration files contain ASCII formatted key-value pairs (properties) grouped within sections. Section names are enclosed in square brackets “[]”. Keys and values are separated with an equal sign (“=”). Section names and key names are case-insensitive and can be upper case, lower case, or both.

Many local properties can be defined globally across all desktops via the global configuration property file. Also, if a configuration property is not defined in the local configuration file, the desktop checks for an entry in the global configuration file.

ACI Worldwide Inc.

2: Getting Started and Basic Functions

Each desktop session is started by running the **RunDesktop.bat** batch file, which is usually configured during installation to be accessed through a shortcut located on a client desktop or a menu. For example:



When the desktop is started, it contacts the applicable servers and configuration files and which point the Version Checker is accessed to determine whether new and updated JAR files are available from the Server Repository. If JAR files on the local desktop need updating, the Version Checker Client window is displayed for users to download new and updated JAR files (see section 6 for more information).

After the desktop establishes contact with the applicable servers and JAR files have been downloaded, the desktop displays the Log In window for entry of a user ID (name) and password. The desktop opens after a valid user ID (name) and password combination has been provided and authenticated by the user security server. The file menu functions (e.g., Configure) and windows that are presented are dependent upon the user's configuration settings.


This section discusses logging on to the desktop, connecting to web servers (or node controllers), setting user preferences, sending desktop snapshots, and viewing version information.

Connection Information

This topic provides information for logging on, concurrent sessions, connecting to a web server (or node controller), changing passwords, and logging off.

Log On


To log on, select the Log In function located on the File menu (**File > Log In**), the Log In button () on the toolbar, or navigation tree.




After a successful logon (authenticated user) the desktop provides access to those applications (windows) that system administration has assigned to the user (i.e., the permissions and permission groups of the user's profile). Each session is assigned a unique session number used by the user security server for authorization purposes.

In addition to the above, session and window (UI) timeout values are initiated and tracked during a session. A timeout is a defined period of inactivity. Timeout limits are defined in the security groups assigned to users.

If the user name and password are not correct or the user name has been disabled or does not have valid access at the time of login, the user security server does not allow the user access to the desktop. In this case a security error message (shown below) is displayed. The error message is purposely vague so not to indicate which information (name or password or both) is incorrect.




A **security warning**, such as the example below, is displayed upon a successful logon if there were one or more unsuccessful logon attempts before the successful logon.




Concurrent Sessions

The number of **concurrent active sessions** allowed for a user is limited to a maximum as defined in the Security Group of the user's profile. A possible scenario in which a user might have concurrent active sessions is by logging on from another terminal without logging off from an active session that was started at another terminal.

This version of the Session Information dialog is displayed if a user has one or more existing active sessions when logging on, and this number of sessions is fewer than the maximum number as defined in the user's Security Group.



This version of the Session Information dialog is displayed if a user upon logon has already reached the maximum number of allowed active sessions defined in the user's Security Group.



Connect to a Web Server (or Node Controller)


During startup, the ACI desktop attempts to connect to the default (or most recently used) web server (or node controller for ACI Payments Manager). If multiple web servers (or node controllers) are available, a user can access the Connection window (**File > Connection**) to select an alternate.

The Connection window displays a selectable list of available web servers (or node controllers) from which one can be selected.

If the one selected accesses a different shared user security database, any existing active sessions for the user are terminated. Also, the port used must be available (i.e., not used by another system or application); otherwise, a connection error is encountered.

Change a Password

To change a password, log on to the desktop and select the Change Password function (**File > Change Password**) to display the Change Password window:



Certain password restrictions and requirements apply. See section 3 for more information.

Log Off and Exit

To log off, select the Log Out function located either on the File menu (**File > Log Out**), the Log Out button () on the toolbar, or navigation tree.

Logging off does not close the desktop. To close the desktop, select **File > Exit**.


Note: A user does not need to be logged on to exit. Also, if a user exits without logging off, the user is automatically logged off from the desktop.

User Preferences

Each user can set desktop characteristics to desired preferences by accessing **File > Preferences**. These preferences are discussed below.

General Preferences

Use the General tab of the User Preferences window to set the following user preferences.




Descriptions of general preferences are discussed below.

Preference	Description
Confirm Deletes	Indicates whether the desktop displays a confirmation dialog box before a delete function is processed.
Confirm non-editable row paste	Displays a dialog box indicating that an attempt was made to paste a copied table row onto a non-editable row.
Confirm non-matching row paste	Displays a dialog box indicating that an attempt was made to paste a copied table row onto a table row that has a different number of table cells.
Confirm Updates	Indicates whether the desktop displays a confirmation dialog box that requires a response before an update function is processed.
Currency Format Locale	Sets whether the default currency is obtained from the desktop configuration or user configuration settings.
Debugging Enabled	Enables the writing of debug messages to a debug file (e.g., DeskTop.dbg).
Frame Open Indicator	Indicates whether a Frame Open Indicator is displayed in the desktop toolbar while a window is opening.
Language	Displays menu functions, dialog box text, messages, and field names in the selected language, if the selected language is defined in the properties file for a window. This also allows access to available localized online help (online help provided in a different language or dialect).
Navigation Tree	Sets whether the navigation tree is displayed upon desktop startup. If checked, the navigation tree is initially displayed. If not checked, it is initially hidden.

Preference	Description
New Window Position	Sets the position of a window when opened as follows: • Bottom • Cascaded • Centered • Frame specified • Left • Right • Top • Top left
Pre-Show Frame	Indicates whether a blank window is shown while a window is initializing (being opened).
Screen Print Orientation	Sets the default print orientation to either portrait or landscape.
Status Pane	Indicates whether the status pane is displayed.
Toolbar	Indicates whether the toolbar is displayed.

Error Notification Preferences


Use the Error Notification tab to set error notification preferences.



Preference	Description
Border Color	Sets the border color of fields that are in error.
Status	Indicates whether error text is displayed in the status pane of windows.
Tooltip	Indicates whether error messages are displayed in tooltip text. Tooltip text is text that appears in a pop-up window over a field or button.
Dialog	Indicates whether error messages are displayed in a dialog box.
Trap Focus	Makes error messages modal, that is, a user is required to resolve an error before focus can be change to another window or tab.

Sound Preferences

Use the Sound tab to set the sound played during certain events (as selected in the Events field).



Preference	Description
Themes	Sets the sound group to apply to the selected event(s). Themes are defined in the sound.cfg configuration file located in the desktop.jar. The theme selected is stored in the configuration file of the logged on user.
Events	An event to be associated with a sound file.
Location	The location of the sound file, such as a .AU file (Java) and .WAV file (Windows), to associate with the selected event.

Snapshots

Use the Send Snapshot (**File > Send Snapshot**) function to send an E-mail message (using the Send Snapshot window shown below) about the desktop configuration and a log record (DeskTop.log) of desktop activity to system administrators. The DeskTop.log file is an ASCII text file that contains information about recent desktop activity that is pertinent to system administrators.

The configuration information is sent as a comma separated values (CSV) file that can be opened by many ASCII readers and spreadsheet applications. The configuration information contains the following information:


- User ID and machine (client workstation) ID
- JAR versions installed
- Local configuration settings
- Version Checker settings
- Global configuration settings
- User preferences
- Global preferences

Display Framework Version Information

Access **Help > About** to display desktop version information as shown below:




Click **Versions** to display detailed version information as shown below:




3: User Configuration

The ACI desktop provides access to an integrated user security environment in which each user must be defined in a user security database. This section consists of two parts: an overview of user security and steps about how to add a user. It also discusses the user profile which is central to establishing a user's access level to the ACI desktop. Each profile defines the integral components of user security, some of which, such as security and password groups, can be shared among multiple users. The hierarchy of a user profile is shown below.



User Security Configuration Window Usage

User profiles are maintained from the ACI desktop using various user security windows. The hierarchy of a user profile from the previous page is shown below with the names and usage of the user security windows added.



All user security windows are accessed at **Configure > User Security**.

User Profiles

Each user is assigned a **user profile** consisting of the following configuration components:

- User ID — A unique character string used to identify a user.
- General user information — Name and contact information about a user.
- User status — Set by the user security server in response to some action, such as too many bad logon attempts, or by security administrative personnel.
- Role(s) — One or more sets of permission groups.
- Security group — A unique ID that defines a set of common user security access restrictions.
- Password group — A unique ID that defines a set of common user password restrictions.

Roles

A role defines the level of a user's access to the desktop. Each role identifies a job function, such as security administrator, system administrator, manager, and end user. Roles apply a set of permissions, tasks, and functions to users.

A role can contain one or more permission groups. A permission group can contain one or more permissions. Each permission is associated with a task (window application) and defines the functions (e.g., delete, save, send, and view) allowed for that task.

Permission Groups

A permission group is a collection of selected permissions that is assigned a unique identifier (the permission group ID) and a description of the purpose or use of the group.

Permissions

Permissions define specific access to a window. Each permission consists of a single task (task ID), the functions that can be performed within the task, a unique ID (the permission ID), and a description of the purpose or use of the permission.

Field Filters

Field filters restrict a user's access to field values by defining either a single value, multiple values, or a range of values allowed.

Task IDs

Each task consists of a unique identifier and a group of functions (e.g., delete, save, send, and view) and corresponds to a window on the ACI desktop. Available task IDs and functions for each task ID are provided on the Permissions tab of the User Security Role Configuration window and are used to create permission IDs. Task IDs can be used in multiple permissions.

Passwords and Password Groups



A user's password is stored in the user security database in encrypted form using a Secure Hash Algorithm (SHA1) that is not reversible ensuring that passwords cannot be extracted in clear form from the database.

Note: When a new user is added, the option to force the new user to change his or her password on first use can be selected.

Password Restrictions (Complex Passwords)

Passwords comply with Payment Card Industry complex password requirements that are summarized below.

- Passwords are case sensitive.
- The minimum length is seven characters.
- Alphabetic, numeric, and special characters are permitted.
- Password history is maintained.
- Passwords cannot be shared.
- Characters cannot be repeated sequentially. For example, a password with the string "BB" appearing anywhere in the password is not valid.
- The password cannot be the same as the user ID. For example, a user with the ID "enduser02" cannot use "enduser02" as the password.
- A user's password must meet the requirements (discussed below) defined in the password group assigned to the user.

Password Group Requirements

Password groups consist of password requirements that are imposed on all user passwords assigned the group. A password group consists of the following password requirements as configured using the Password Groups tab on the User Security Group Configuration window.

- The number of days prior to a password expiration on which the desktop displays a warning dialog prompting a user to change the password.
- The maximum number of days a user can use a password.
- The minimum password length (7 characters or more).
- The maximum password length.
- The minimum number of numeric characters required in each password.
- The minimum number of alphabetic characters required in each password.
- The maximum number of old passwords retained for each user (users cannot use retained old passwords).
- The maximum number of password changes allowed during a 24-hour period.

Security Groups

Each user must be assigned one and only one security group. However, since a security group can be assigned to multiple users, the security group simplifies the management of user security, assigns passwords by group, and assists in implementing distributed security administration, which is discussed later in this section.

Each user security group consists of the following common user security access restrictions that apply to all users assigned the security group:

- The time each day a user can log on to the desktop.
- The time each day a user must be logged off the desktop and, after which, can no longer log on to the desktop.
- The days of the week on which a user can log on to the desktop.
- The maximum number of invalid logon attempts allowed for each user. If this value is reached, the user's status is disabled by the user security server.
- The number of minutes, if set, after which the number of invalid logon attempts is reset to zero.


- The maximum number of active sessions allowed for a user.
When a user fails to log off correctly from the desktop or if a system outage occurs during a user's active session, the user security database still maintains a record of the active session. Therefore, if the maximum number of active sessions has been reached by a user attempting to log on to the desktop, the user is presented with an option to stop one or more of the active sessions.
- The number of seconds of user inactivity after which the user is automatically logged off the desktop (this is called a **session timeout**).
- The number of seconds of terminal inactivity after which the desktop is disabled and any logged on user is logged off (this is called a **UI timeout**).
- The number of days a user's ID can be inactive (not used) after which the user ID status is disabled by the user security server.
- The password group ID defining password requirements applied to all users of the security group.

Distributed Security Administration (DSA)

Each installation is configured with a system administrator and security administrator. The system administrator has access to all applications of the desktop. The security administrator has access to the user security windows. Distributed security administration involves the security administrator configuring other, lower-level, administrators that are assigned a limited set of permissions. Distributed security administration is enabled by setting the **OwnerIDSupport** property in the usec.cfg file to true.

Distributed security is implemented by the top-level security administrator by configuring applicable roles, assigning these roles as necessary to security groups, and assigning the security groups to other, lower-level, system administrators.

The top-level security administrator can set up tiers of other system administrators who are limited to a **security domain**, which is a set containing a security group, password group, roles, and permissions as defined by a security role ID. At this level, a role ID is used to restrict users within the domain to a defined set of permissions (including permission groups), tasks and filters. This methodology can be used to create system administrator groups and departments as shown in the illustration below.



For example, the system administrator assigned Role1 can create user profiles or groups of user profiles having roles that can contain only those permissions, permission groups, tasks, and filters defined for Role1. With distributed security administration, users, including administrators, cannot access the users and roles of other security domains.

Steps to Add a User

Note: Some steps have additional steps (i.e., steps 3.1 – 3.3 and 4.1 – 4.5). Whether these additional steps are required depends on the extent to which a complete user security system has been configured.

- ❑ Step 1.0: Configure a Password Group
- ❑ Step 2.0: Configure a Security Group
- ❑ Step 3.0: Configure a User Role
 - Step 3.1: Configure Field Filters
 - Step 3.2: Configure Permissions
 - Step 3.3: Configure Permission Groups
- ❑ Step 4.0: Configure the User's Profile
 - Step 4.1: Set the User's Status
 - Step 4.2: Assign a Security Group
 - Step 4.3: Enter Information about the User
 - Step 4.4: Set the User's Password
 - Step 4.5: Assign Roles

Usage Note: To ensure that changes are implemented in the user security database, click Save () each time a step has been completed.

Tip: If a new user is to be based on an existing user profile, that is, the password group, security group, and roles are already configured, go directly to step 4.0 and read the Tip provided in the step.

Step 1.0: Configure a Password Group

Use the Password Group tab on the User Security Group Configuration window to configure a password group.

The screenshot shows the 'User Security Group Configuration' window with the 'Password Group' tab selected. The 'Password Gr...' dropdown is set to 'pswd_grp_1'. The 'Description' field contains 'Default password group for end users.' Below this, there are two columns of settings, each with a label and a numeric input field with up/down arrows:

Minimum Length	7	Lifetime Days	30
Maximum Length	10	Old Password Cache	5
Required Numeric Characters	2	Expire Pre-Warn Days	7
Required Alpha Characters	2	Changes Per Day	3

In the example above, the password group **pswd_grp_1** is shown. This group is described as the default password group for end users. The password requirements are set in the fields provided on the tab.

Password groups are assigned to users (their profiles) through security groups. Therefore, a password group must be assigned to a security group using the Security Group tab of the User Security Group Configuration window. The security group is then used in user profiles.

Step 2.0: Configure a Security Group

Topics in this step to consider are listed below and are discussed on the following pages.

- ❑ UI and Session Timeout Considerations
- ❑ System Administration Role Filter (Owner ID)

Use the Security Group tab on the User Security Group Configuration window to configure a security group.

The screenshot shows the 'User Security Group Configuration' window with the 'Security Group' tab selected. The configuration includes the following fields and settings:

- Security Group:** end_user_sec_grp
- Description:** Security group for end users.
- Password Group:** pswd_grp_1
- SysAdmin Profile:** (empty)
- Allowed Time and Days:**
 - Begin:** 08:00 am
 - End:** 05:00 pm
 - Days:** Sun (unchecked), Mon (checked), Tue (checked), Wed (checked), Thu (checked), Fri (checked), Sat (unchecked)
- Bad Logins Allowed:** 3
- Reset Bad Logins:** 3000 seconds
- Sessions Allowed:** 1
- UI Timeout:** 1800 seconds
- Inactive Days Allowed:** 60
- Session Timeout:** 3600 seconds

In the example above, the configuration for the **end_user_sec_grp** security group is shown. This group defines standard authentication requirements for users. The password group **pswd_grp_1** is assigned to this security group. As a result, the password requirements defined by **pswd_grp_1** apply to all users of this security group. Users assigned this security group cannot log on to the desktop before 8:00 am and must be logged off by 8:00 pm. Also, users cannot log on to the desktop on Sundays and Saturdays.

UI and Session Timeout Considerations

A security group defines both UI and session timeouts. These timeouts are defined in units of seconds using the Security Group tab of the User Security Group Configuration window.

A UI timeout occurs after a duration of desktop inactivity defined in the UI Timeout field. When a UI timeout event occurs, the user no longer has access to the desktop and any open windows; however, the user's session and the open windows are not closed but the desktop displays the Verify Password dialog in which the user must provide a valid password to restore access to the desktop and any open windows. The user also has the option to log out at this time.

UI timeouts only occur if the security group to which the user belongs has a configured UI timeout limit greater than zero. Entering a zero ('0') in the UI Timeout field implies no limit of desktop inactivity.

A session timeout occurs after a duration of desktop inactivity defined in the Session Timeout field. When a session timeout event occurs, the user is automatically logged off the desktop and the user must log on (open the Log In window and provide a valid user name and password combination) to obtain access to the desktop. Any windows open upon a session timeout are closed.

If the user's session expires while the Verify Password dialog is displayed and the user has not provided input, the user is still logged out and the user is no longer able to verify the password. All windows are closed, but the desktop remains open.

Session timeouts only occur if the security group to which the user belongs has a configured session timeout limit greater than zero. Entering a zero ('0') in the Session Timeout field implies no limit of desktop inactivity.

To use UI timeouts in an effective manner, the session timeout must be greater than the UI timeout. This is because if the session timeout is less than the UI timeout, users in the security group will be logged off the desktop (upon a session timeout event) prior to a UI timeout event.

A UI timeout event should occur first so that a user can be alerted and take necessary action to save work. Having a session timeout less than the UI timeout negates the purpose of the UI timeout.

System Administration Role Filter (Owner ID)


When the **OwnerIDSupport** property in the usec.cfg file is set to the true, the Security tab on the User Security Group Configuration window displays the SysAdmin Profile selectable field.

An existing role ID can be assigned to a security group using the SysAdmin Profile field. Since a role defines a set of permissions (permission groups), tasks IDs and field filters, the role ID at this level limits access to permissions and permission groups that can be configured for users by administrators assigned the security group. To assign a role ID as a filter for a security group, select the role ID in the SysAdmin Profile field.

If a system administration role profile is selected for a security group, only those permission groups, permissions, and tasks defined for the role are accessible to users assigned the security group.

Step 3.0: Configure a User Role

To configure a user role, use the Roles tab on the User Security Role Configuration window.



If the available permission groups meet existing needs, enter or select the role ID in the Role field, add or modify the description of the purpose of the role, and select the applicable permissions groups (permission groups can be selected and deselected using the check boxes for each group), then go to Step 4.0: Configure the User's Profile. **Note:** Permissions not defined within your security domain are not available.

If one or more permission groups need to be configured, the following steps might also need to be performed.

- ❑ Step 3.1: Configure Field Filters
- ❑ Step 3.2: Configure Permissions
- ❑ Step 3.3: Configure Permission Groups

Step 3.1: Configure Field Filters

Note: The functionality of field filtering is the same among applications, but the implementation can vary. The example below is for BASE24-es. Your application and configuration might differ. In ACI Payments Manager, Business Units are filterable, and the Institution ID, such as in the example, is not applicable.

Field filters are configured using the Filters tab on the User Security Role Configuration window, which is shown below, and are applied to a user's profile through permissions.

The screenshot shows the 'User Security Role Configuration' window with the 'Filters' tab selected. The window has a title bar with a red triangle icon and standard window controls. Below the title bar is a toolbar with icons for save, print, refresh, delete, and help. The main area contains the following fields and controls:


- Filter ID:** A text input field with a dropdown arrow.
- Field ID:** A text input field with a dropdown arrow.
- Description:** A large text input field.
- Filter Type:** A group box containing three radio buttons: ☒ Range, ☐ Single Value, and ☐ Multi-Value.
- Filter Settings:** A group box containing two text input fields: **Begin Value** and **End Value**.

Field filters consist of the following elements:

- ❑ Unique identification (the Filter ID field)
- ❑ Field ID
- ❑ A description of the purpose and use of the filter
- ❑ One or more field values, which can be a single value, multiple values, or a range of values.


The format of the Filter Settings area is dependent upon the filter type selected, whether Range, Single Value, or Multi-Value.

If **Range** is selected, begin and end values must be entered:



The screenshot shows a 'Filter Type' section with three radio buttons: 'Range' (selected), 'Single Value', and 'Multi-Value'. Below this is a 'Filter Settings' section containing two text input fields labeled 'Begin Value' and 'End Value'.

If **Single Value** is selected, a single filter value must be selected or entered:



The screenshot shows a 'Filter Type' section with three radio buttons: 'Range', 'Single Value' (selected), and 'Multi-Value'. Below this is a 'Filter Settings' section containing a single dropdown menu labeled 'Filter Value'.

The values available in the Filter Value field are those that have been configured using the applicable configuration window. For example, for the InstitutionID field ID, the values shown in the Filter Settings area are those institution IDs that have been configured using the Institution Configuration window.

Tip: Use the asterisk (“*”) to select all current and future field values.

If **Multi-Value** is selected, values must be selected and moved from the All Field Values field to the Selected Field Values field.

To add or remove field values, use the following buttons provided on the tab to perform the desired task:

Button	Task
	Add the selected field value(s) from the All Field Values field to the Selected Field Values field.
	Add all available field values from the All Field Values field to the Selected Field Values field.
	Remove the selected field(s) value from Selected Field Values field back to the All Field Values field.
	Remove all field values from Selected Field Values field back to the All Field Values field.

To select a value, click on the value. Selected values have a modified background color. To select multiple values, press down the **Ctrl** key while selecting values.

The values shown in the All Field Values field are those that have been configured using the applicable configuration window. Use the asterisk (“*”) to select all current and future field values. For example, for the InstitutionID field ID, the values shown in the Filter Settings area are those institution IDs that have been configured using the Institution Configuration window.

To add a value not available in the All Field Values field, enter the value in the text entry field to the right of the Filter Type area and click the Add Value button.

Step 3.2: Configure Permissions

Use the Permissions tab on the User Security Role Configuration window to create permissions and permission group IDs.

The screenshot shows the 'User Security Role Configuration' window with the 'Permissions' tab selected. The window has a title bar with standard Windows controls. Below the title bar is a toolbar with icons for file operations. The main area contains four tabs: 'Roles', 'Permission Groups', 'Permissions' (selected), and 'Filters'. The 'Permissions' tab displays the following fields:

- Permission ID:** A dropdown menu showing 'FullAcctStatusMappingProfile'.
- Task ID:** A dropdown menu showing 'AcctStatusMappingProfile'.
- Description:** A text field containing 'FullAcctStatusMappingProfile'.

Below these fields is a tree view on the left showing a folder 'Functions' with three sub-items: 'Delete', 'Save', and 'View'. Each sub-item has a checkbox and a small icon. To the right of the tree view is a large empty rectangular area. At the bottom right, there is a section labeled 'Filter Description' with a text area containing 'Filter info'. A status bar at the bottom of the window displays 'Permission read.'.

Permission IDs

A new permission ID can be created (entered) or an existing permission ID can be selected. Permissions are available on the Permissions Group tab for selection when configuring a permission group.

The description is to state the purpose of the permission and any special information.

Tasks IDs

Each task ID corresponds to an ACI desktop window. **Note:** Task IDs cannot be created using the ACI desktop.

Functions

The functions that a user can perform on a window (task) are defined for each permission on the Permissions tab. A function is selected by entering a check mark in the functions check box. Functions include, but are not limited to, Delete, Save, Send, and View. The available functions vary by task ID.

Field Filters

If a task ID refers to a window that contains a field or fields that are filterable, the Permissions tab will list the field ID(s) and provide a selectable list of filter IDs that can be selected and applied to the permission.

The field IDs **InstitutionID** and **Issuer** are shown in the example below for the Institution Configuration window.

Note: The actual filterable fields varies by application. See the boxed note in step 3.1 for more information.

The screenshot shows the 'User Security Role Configuration' window with the 'Permissions' tab selected. The window has a title bar with standard OS controls. Below the title bar is a toolbar with icons for save, delete, and other actions. The main area contains several fields and a list of functions.

Fields:

- Permission ID: FullInstConfigPermission
- Task ID: InstitutionConfiguration
- Description: Full Institution Configuration permission set.

Functions:

- Functions: A list of functions with checkboxes. The 'InstitutionID' function is checked.

Filter Description:

- Filter info: A text area for filter information.

Bottom status bar: Permission read.

Step 3.3: Configure Permission Groups

To configure a new or existing permission group, use the Permission Groups tab on the User Security Role Configuration window. This tab provides a Permission Group field in which a new permission group ID can be entered or an existing permission group can be selected.

Available permissions, as defined per your security domain, are provided on the tab. Permissions are added or removed from a permission group by selecting (entering a check mark) or deselecting (removing a check mark) in the appropriate checkbox.

Permission Information

A description of each permission along with the Task ID assigned to the permission and the allowed functions can be displayed in the Permission Description section of the Permissions Groups tab. To display this information, right click on the desired permission and select Get Info on the pop-up menu.

Step 4.0: Configure the User's Profile

To configure a new user (user profile), display the General tab of the User Security Profile Configuration window, enter the user's unique ID in the User ID field and perform the following steps:

- ❑ Set the user's status
- ❑ Assign a security group
- ❑ Enter information about the user
- ❑ Set the user's password
- ❑ Assign roles to the user

The screenshot shows the 'User Security Profile Configuration' window with the 'General' tab selected. The 'User ID' field is set to 'end_user_1'. Below the tabs, there are two columns of fields. The left column includes 'User Status' (set to 'Active'), 'First Name' (placeholder '<given_name>'), 'Middle Name' (empty), 'Last Name' (placeholder '<family_name>'), 'Department' (placeholder '<department_id>'), 'Location' (empty), 'Manager' (empty), and 'Email' (empty). The right column includes 'Security Group' (set to 'end_user_sec_grp'), 'Work Phone' (empty), 'Mobile Phone' (empty), 'Fax' (empty), 'Create Time' (05/08/06 2:01 PM), 'Last Login' (05/18/06 9:01 AM), 'Last Failed Login' (05/09/06 9:05 AM), and 'Bad Login Tries' (1). The window has a standard Windows-style title bar and a toolbar with icons for save, refresh, and delete.

Tip: To add a new user whose profile is based on an existing user profile, display the user profile that is to be used as a template and replace the text in the User ID field with the new user ID.

Note: When the Save button is clicked for a new user, the desktop displays the New User's Password window, which is described in Step 4.4.

Step 4.1: Set the User's Status

User status options:

Active	= Open and active.
Closed/Admin	= Closed without incident.
Closed/Inactive	= Closed, by the user security server, due to inactivity.
Disabled/Admin	= Disabled, for security reasons, by authorized personnel.
Disabled/System	= Disabled, for security reasons, by the user security server (e.g., maximum number of log on attempts has been reached).
Temporary	= User can access the desktop for a predefined amount of time.

Step 4.2: Assign a Security Group

Security groups are provided in the selectable field next to the Security Group link. If a desired security group is not available, click on the link to access the User Security Group Configuration window to review existing security groups or configure a new security group. Only those security groups defined for your security domain are available.

Step 4.3: Enter Information about the User

Information about the user includes:

- ❑ Complete name information
- ❑ Contact information, such as phones, Fax and email address
- ❑ Employment information, such as department, manager and location

Step 4.4: Set the User's Password

To set a new user's password, click Save, after which the desktop displays the New User's Password window.

Note: The Password tab of the User Security Profile Configuration window is used for management of existing users, see the User Management section for more information.

For users assigned a status other than Temporary, the desktop displays the version of the New User's Password window shown below. Indicate whether the user must change the assigned password during the next logon (or first logon for a new user), and the start date on which the user can log on to the desktop.



The dialog box titled "New User's Password" has a blue title bar with a red triangle icon and a close button. It contains two password input fields labeled "New Password" and "Verify Password", both filled with asterisks. Below these is a checkbox labeled "Require password change" which is checked. Underneath is a date selection field labeled "New User Start" showing "Monday, March 15, 2006". At the bottom are "Ok" and "Cancel" buttons.


When a new temporary user (i.e., user status being set to temporary) is created, the desktop displays the New User's Password window, shown below, for indicating whether the user must change the password on logging on, and for setting the start and expiration dates for which the user is active.



The dialog box titled "New User's Password" has a blue title bar with a red triangle icon and a close button. It contains two empty password input fields labeled "New Password" and "Verify Password". Below these is an unchecked checkbox labeled "Require password change". Underneath is a date selection field labeled "New User Start" showing "Wednesday, March 31, 2006". Below that is another date selection field labeled "New User Expire" also showing "Wednesday, March 31, 2006". At the bottom are "Ok" and "Cancel" buttons.

Step 4.5: Assign Roles

Use the Roles tab on the User Security Profile window to assign (and remove) the roles defined for a user.



This tab displays all the user roles available within your security domain on the ACI desktop. Roles not defined within your security domain are not displayed. User roles assigned to a user are shown in the User Roles field. Available user roles not assigned to a user are shown in the All Roles field. To add or remove user roles from a user profile, select the role or roles and use the buttons provided on the tab to perform the desired task. The buttons are:

Button	Task
	Add the selected role(s) to the user profile (move from the All Roles field to the User Roles field).
	Add all available roles to the user profile (move from the All Roles field to the User Roles field).

Button	Task
	Remove the selected role(s) from the user profile (move from the User Roles field to the All Roles field).
	Remove all assigned roles from the user profile (move from the User Roles field to the All Roles field).

To select a role, click on the role. Selected roles have a modified background color. To select multiple roles, press down the **Ctrl** key while selecting roles.


If a particular role is not available or an existing role needs to be changed, click on the Configure Roles link to access the User Security Role Configuration window to configure a new or existing role.

Note: A user cannot change the role configuration for the profile (User ID) that was used to log on. In such situations, when the Roles tab is accessed for that User ID, the All Roles field and User Roles fields are inactive.

4: User Management

System administrators can set the status, display and terminate active sessions, and expire passwords by password group of users within the administrator's security domain. This activity is performed from the user security windows as described in this section.

The illustration below shows the user profile and includes the name of the applicable windows used to manage user profiles.



The User Security Profile Configuration window is mostly used for configuring a user profile; however, it can be used to view a user's active sessions, to change an existing user's status and to manage a user's password.

The User Security Control Management window is used to view and manage the active sessions for all users. The window can also be used to expire passwords by password group.

Set the Status of a User

The user security server maintains a status for each user. A user's status can be changed by the user security server if security and password group requirements have been violated. A user's status can also be changed by authorized users.

Use the General tab on the User Security Profile Configuration window to view and set a user's status.

User Security Profile Configuration

User ID: end_user

General | Roles | Password | Active Sessions

User Status: Active (dropdown menu open showing: Active, Closed/Admin, Closed/Inactive, Disabled/Admin, Disabled/System, Temporary)

Security Group: end_user_sec_grp

First Name: [empty]

Middle Name: [empty]

Last Name: [empty]

Department: [empty]

Location: [empty]

Manager: [empty]

Email: [empty]

Work Phone: [empty]

Mobile Phone: [empty]

Fax: [empty]

Create Time: 1/11/06 1:00 PM

Last Login: 3/15/06 4:55 PM

Last Failed Login: 2/2/06 2:07 PM

Bad Login Tries: 1

Authorized users can assign the following status codes to a user:

- | | |
|-----------------|---|
| Active | = Open and active. |
| Closed/Admin | = Closed without incident. |
| Closed/Inactive | = Closed, by the user security server, due to inactivity. |
| Disabled/Admin | = Disabled, for security reasons, by authorized personnel. |
| Disabled/System | = Disabled, for security reasons, by the user security server (e.g., maximum number of log on attempts has been reached). |
| Temporary | = User can access the desktop for a predefined amount of time. |

Active User Session Management

When a user has logged on to the desktop by providing a valid user ID and password, the user security server creates an active session for the user. An active session contains the following information:

- ❑ The user's ID.
- ❑ The unique session number assigned by the user security server.
- ❑ The workstation ID, such as a network ID or URL, from which the user has logged on to the desktop.
- ❑ The date and time the user began the session.
- ❑ The date and time the current session expires.


Information about active user sessions is available on two separate Active Sessions tabs. One tab is provided on the User Security Profile Configuration window and displays the active sessions for a selected user. The other Active Sessions tab is located on the User Security Control Management window and displays active user sessions for all users within a security administrator's security domain (security group to which the administrator has access).

Active User Session for a Selected User:

The screenshot shows a window titled "User Security Profile Configuration". It has a menu bar with icons for file operations and a toolbar. Below the toolbar is a "User ID" dropdown menu set to "end_user". There are four tabs: "Password", "Roles", "General", and "Active Sessions", with "Active Sessions" being the active tab. The "Active Sessions" tab contains a table with two columns, both labeled "Workstation ID". The first row of the table has the values "Network/URL" and "2006-3-24 08:43:11.39". Below the table is a "Password" label. At the bottom of the window, there is a blue link labeled "All Active Sessions" and a button labeled "Logout Selected".

Workstation ID	Workstation ID
Network/URL	2006-3-24 08:43:11.39

Active User Sessions for All Users:



Note: The active sessions of the application can change at any time; therefore, to update the list of active sessions click Refresh ().

Terminate Active User Sessions (Log off a User)

One or more active user sessions can be terminated (i.e., logged off) from either one of the two windows that are used to display active user sessions — the User Security Profile Configuration window and the User Security Control Management window. To log off one or more user sessions, display and select the user session(s) and click Logout Selected.

Password Management

Authorized users can view a user's password change history, add or change a user's password, and expire the user's current password by accessing the Password tab on the User Security Profile window and selecting the user's ID.

To change a user's password, display the Password tab on the User Security Profile Configuration window and select the user ID. Enter the new password in both the New Password and Verify Password text boxes and click Save (). If the change is successful, a confirmation message appears in the status pane of the window. Otherwise, an appropriate error message is displayed.

To expire a user's password, display the Password tab on the User Security Profile Configuration window, select the user ID, and click Expire Password. If a user's password has been expired but a new password has not been defined, the user is prompted to create a new password on the next logon attempt.

Authorized users can access a table that shows the password groups that have been assigned to security groups, and can expire all user passwords of users assigned to a password group.

Use the Password Maintenance tab on the User Security Control Management window to view password group usage and expire password groups.

ACI Worldwide Inc.

5: User Auditing

User audit is the logging of user activity to a data source for the purpose of reporting and monitoring the user activity.

Whenever a user of the desktop initiates and completes an activity (e.g., logon, logoff, password changes, delete, or save) from a window, a message that contains information about the user activity is written to the User Audit Log data source.

The audit message sent to the log data source can be one of the following:

- Header information only about the changes to affected records
- Header information and detail information about the before and after data images of affected records

ACI Worldwide Inc.


The application server writes audit messages directly to the USRAULOG data source or to the Audit_Store_and_Forward data source depending on the middle ware capabilities of the hardware platform.

For information about enabling user auditing and setting the audit level for a desktop window, refer to the *ACI Java Server Framework Reference Guide* for information about audit properties, such as:

- `db.audit.db-service-name`
- `db.audited`
- `db.audited.db-service-name`

User Audit Activity Reports


Activity reports for selected users can be initiated using the Audit Report Wizard located on the Tools menu. User activity is extracted from the USRAULOG data source for a specified user ID between a start date and time and an end date and time. This information can be viewed on the ACI desktop or sent to a designated file. The location where the file is saved is specified by the **REPORT. USERAUDITLOG.LOC** property, which contains the directory location.



The reports provide the following information:

- Date and time of action.
- User ID performing the action.
- Terminal location from which action was performed.
- Type of action performed.
- File and field name affected by the action, if applicable.
- Before and after image of data modification action, if full auditing is set.

When a report is completed, the results are shown in the Audit Report Viewer for which an example is shown below.



Select an entry Audit Summary table and click the Details button to display detail information. For example:

The screenshot shows the 'Audit Report Viewer' application window. It is divided into two main sections: 'Audit Summary' and 'Audit Detail'.

Audit Summary: This section contains a table with 8 columns: #, Local D..., User ID, Workst..., Activit..., Activit..., Result, and Service. The table lists five entries. Entry 2 is selected, showing a 'Logon' activity for user 'guestu...' on 'B24ES/...' with a result of 'OK'.

#	Local D...	User ID	Workst...	Activit...	Activit...	Result	Service
1	Wed M...	guestu...	B24ES/...	Logon	USEC	Alread...	
2	Wed M...	guestu...	B24ES/...	Logon	USEC	OK	
3	Wed M...	guestus...	B24ES/...	Logoff	USEC		
4	Wed M...	guestus...	B24ES/...	Logon	USEC	Already...	
5	Wed M...	guestus...	B24ES/...	Logoff	USEC		

Below the table are two buttons: 'Detail' and 'More'.

Audit Detail: This section shows a hierarchical tree view of the selected entry (row 2). The tree structure is as follows:

- AuditReport :
 - AuditDetails :
 - row : 2
 - Audit_loggingRq :
 - Timestamp : 2006-05-24T06:17:20.38Z
 - ContextDescr : USEC
 - Ticket :
 - UserID : guestuser14
 - SessionNumber : 7
 - TerminalID : B24Es/123.45.6.7
 - ErrorData : OK
 - ActivityGroup :
 - ActivityType : Logon

Automated User Auditing

User audit extracts to file can be performed automatically by specifying the `com.aciworldwide.common.timertask.UserAuditReport` classname for the configuration properties file `timertask.function.n.classname` configuration parameter. The Java Server Framework application specified as the `timertask.manager.processid` invokes the classname at application initialization.

The following properties are used to configure automated user audit reporting:

Property	Description
<code>report.userauditlog.loc</code>	The file path for the user audit report.
<code>report.userauditlog.name</code>	The name of the user audit report.
<code>report.userauditlog.offset.days</code>	The number of days prior to the current day to use for obtaining user activity for the report.
<code>report.userauditlog.report.starttime</code> <i>ACI Worldwide Inc.</i>	The time at which the report is generated.

For example, if today is Wednesday and the time is 9:00 AM, the offset is one day, and the report start time is 2:00 AM, then the most recent audit information available is that for 2:00 AM Tuesday to 2:00 AM Wednesday.

Refer to the *ACI Java Server Framework Reference Guide* for more information about the above properties.

ACI Worldwide Inc.


6: Version Checker

The desktop provides a way for clients to keep the desktop configuration current. This configuration support is provided by the Version Checker, which is a utility that manages the versions of JavaTM Archive (JAR) files of desktop components that are distributed to ACI desktop clients. The Version Checker automatically runs during startup of the desktop at which time it compares the current version of the client files to new versions, which reside in a predetermined location (i.e., repository). The location of the Version Checker repository is defined during installation. New files that are to be distributed to clients are placed in this location.

The Version Checker automatically runs when a desktop is started per commands located in the **RunDesktop.bat** file. Desktop shortcuts specified during installation point to this batch file. Whether a user is prompted to accept any new files or the files are automatically downloaded is dependent upon configuration settings as discussed in this section.

The files on the repository for which the version differs from that of the client are displayed in the Version Checker Client window. This window provides a list of the files along with the version number of each file on the repository and the version number of the file on the client. If automatic file updating is enabled (discussed later in this section), then this window is not displayed.

To download new files from the repository, select the applicable files and click Update. This update process can be skipped or canceled.



The **Select All** option can be used to select all listed files on the Version Checker Client window. Individual files can be selected by deselecting the Select All option and then clicking in the row for each desired file to download. Only selected files are downloaded.

If the **Close When Done** option is selected, the Version Checker Client window will automatically close after completion of the download of all selected files.

By selecting **Mirror Repository** on the Version Checker Client window, verification is initiated to ensure that no jars reside on the client that are not also on the server repository. That is, any files that exist on the client that do not exist on the current version of the server repository are deleted from the client.

The Version Checker can be configured to download updated and new files automatically. This automatic file updating (called VC quiet mode) is an option presented during installation of the ACI desktop.

Including the parameter “-Q” in the Version Checker command line located in the **RunDesktop.bat** file enables automatic file updating. Note that the “-Q” is added during installation when the VC quiet mode option is selected.

For example:

```
call "C:\ACI\VersionChecker\verChk" -Q
```


7: Online Help

The ACI desktop provides online help for windows (screens) and window components (e.g., fields). This help is displayed in a Java-based HTML browser, called the **Helpset Viewer**:



The components of the Helpset Viewer are:

- 1** — The **Title Bar** in which the name of the helpset is displayed.
- 2** — The **Toolbar** that contains various menu and button functions.
- 3** — The **Navigation Pane** in which are located Contents and Index tabs useful for navigating to desired help content, and a Search tab for searching content.
- 4** — The **Content Pane** in which help content is displayed.
- 5** — The **Contents** tab that provides structured access to window-level help files.
- 6** — The **Index** tab that provides alphabetical access to all help topics.
- 7** — The **Search** tab for searching help content.

Access to JavaHelp from the ACI Desktop

JavaHelp content can be accessed with or without context. These two methods are explained below.

With Context

Accessing online help with context displays the Helpset Viewer with content displayed in the Content Pane that is specific to a window or window component. To display help with context from the ACI desktop, select **Help > Context Help** or click  on the toolbar. Either of these actions display the Help Pointer  to use for clicking in a general area of a window for window-level help or on a window field for field-level help.

If a window is not open, help with context is not available because an active window in the Application Area of the ACI desktop is necessary to provide context. When context help is not available, the Context Help function and the button are inactive.

Note that the traditional way to access field-level help by placing the cursor in the field and pressing the **F1** key can also be used.

Without Context

To display online help without context from the ACI desktop, select **Help > Help Topics** from the Menu Bar or click  on the Toolbar. A window does not need to be open to access online help without context. When online help is accessed using this method, the Helpset Viewer is displayed with the default home page provided in the content pane and the default TOC view in the navigation pane.

If the Help Topics function and the button are not enabled, then the ACI desktop does not have access to online help. Check with a System Administrator to obtain ACI online help.

JavaHelp Files

The following files together are referred to as a **JavaHelp helpset**:

- The **helpset file** (ACI_Help.hs), which is identified by the .hs file extension, defines the name of the helpset displayed in the Title Bar, the JavaHelp components used, the name of the map file, the names of the table of contents and index files, and the ID of the default content file to display in the Content Pane when help is accessed without context. The helpset file is the top-level file in the JavaHelp helpset.

Be careful not to confuse the term “JavaHelp helpset” with the helpset (.hs) file. *JavaHelp helpset* refers to a collection of JavaHelp files as discussed on this page. Whereas the helpset (.hs) file is a single file (see following page).

- The **map file** is an XML file identified by the .jhm file extension that corresponds identifiers to HTML content files. This file is necessary to provide context-sensitive help for windows and window components as discussed later in this section.
- The **table of contents file** that defines the structure and links of the text entries of the Contents tab.
- The **index file** that defines the structure and links of the text entries of the Index tab located in the Navigation Pane of the Helpset Viewer.
- **HTML files** in which help content resides.
- **Cascading Style Sheets (CSS)** define the style rules applied to content.
- The **images** displayed within HTML content files. Images used in content are in Graphical Interchange Format (GIF) and Joint Photographic Experts Group (JPEG or JPG) formats.

JavaHelp Packages

ACI online help is packaged and distributed in the following Java™ Archive (JARs) files:

- **ACI_Help_es.jar** — For BASE24-es
- **ACI_Help_tss.jar** — For Transaction Security Services (TSS)
- **ACI_Help_pm.jar** — For ACI Payments Manager (PM)

Helpset File

The helpset file defines the Java components used, home page, map file, TOC, index, and views. Below is an example helpset file. Comments between “<!--” and “-->” have been added to provide additional information.

```
<?xml version='1.0' encoding='ISO-8859-1' ?>
<!DOCTYPE helpset
  PUBLIC "-//Sun Microsystems Inc.//DTD JavaHelp HelpSet Version 2.0//EN"
  "http://java.sun.com/products/javahelp/helpset_2_0.dtd">
<helpset version="2.0">

  <!-- The title displayed in the Title Bar -->
  <title>ACI Online Help</title>

  <!-- Map information -->
  <maps>
    <homeID>splash</homeID> <!-- The map ID of the splash page -->
    <mapref location="map.jhm" /> <!-- The map file -->
  </maps>

  <!-- Each view represents a tab on the Helpset viewer -->
  <!-- This helpset has 3 views. -->
  <!-- Immediately below is the TOC view -->
  <view>
    <name>TOC</name>
    <label>Contents</label> <!-- The popup (flyover) text of the tab -->
    <type>javax.help.TOCView</type> <!-- The JavaHelp TOC component -->
    <data>toc.xml</data> <!-- The name of the table of contents file -->
  </view>

  <!-- This is the index view -->
  <view>
    <name>Index</name>
    <label>Index</label>
    <type>javax.help.IndexView</type> <!--
    <data>ix.xml</data> <!-- The name of the index file -->
  </view>

  <!-- This is the search view -->
  <view>
    <name>Search</name>
    <label>Search</label>
    <type>javax.help.SearchView</type>
    <data engine="com.sun.java.help.search.DefaultSearchEngine">
      JavaHelpSearch
    </data> <!-- The search engine defined by the engine attribute -->
    <!-- And, the search database. In this case, the search -->
    <!-- database is located in a folder named JavaHelpSearch -->
  </view>


</helpset>
```

How Context is Implemented in JavaHelp

Help context is implemented in JavaHelp by the use of unique identifiers. Each identifier (referred to as a map ID or help ID) appears as necessary in the following files:

- The property (.properties) file for a window (desktop application)
Note: Most application windows have their own properties file. Also, some properties common among all windows are located in common property files that are shared among the window properties files.
- The JavaHelp map file, map.jhm (pmdesktop.jhm for ACI Payments Manager)
- The table of contents file, toc.xml (ACI_Help_pmtoc.xml for ACI Payments Manager)
- The index file, ix.xml (all applications)

The use and relationship of the identifiers in the above files is shown in the following illustration.




Search the Helpset for a Text String

The Search tab provides a text entry field (Find) to locate up to 100 occurrences of a text string within a helpset.

Note: Search is not case sensitive.

Enter the text string in the Find text entry field and press the **Enter** key. JavaHelp searches through the helpset and displays a list of topics in which the text string is found. This list is displayed in the Navigation Area by topic title and in descending order of number of matches. Select the desired topic to display the topic's content in the Content area.



Custom Help Content

Online help can be modified in a number of different ways depending on the level of modification desired.

- Content files can be modified.
- Cascading style sheets can be modified to change display formats.
- Images referenced in content files can be edited.

Note: Modifying the JavaHelp configuration files can adversely affect the performance of JavaHelp and is not discussed in this manual.

If an installed version of JavaHelp is customized, care must be taken to avoid overwriting the customized JavaHelp files when accepting an updated help JAR file for placement on the Version Checker repository. Therefore, the following guidelines can be used to establish procedures for maintaining and protecting customized JavaHelp:

- Always keep a backup of both original and customized files.
- Consider appending an identifier (e.g., “custom”) to the name of customized files. If a help file name is changed, the change must also be made to the map.jhm file. For example, a file named f_connection.htm file is customized and renamed to f_connection_custom.htm. The url attribute in the map.jhm file must be changed as follows:

From:

```
<mapID target="f_connection"
      url="f_connection.htm"/>
```

To:

```
<mapID target="f_connection"
      url="f_connection_custom.htm"/>
```

- Another option is to keep the same name of the file but place the customized file into a separate directory as follows:

```
<mapID target="f_connection"
      url="custom/f_connection.htm"/>
```

Customization of HTML Content Files

All content files within the JavaHelp JAR files are in compliance with the W3C HTML revision 3.2 format. This format is required for content files to display properly within the Helpset Viewer. Certain parts of the HTML revision 4.0 format can be used since it shares most markup tag elements with 3.2; however, care should be taken when implementing revision 4.0 features into content files destined for JavaHelp because certain revision 4.0 features might not be supported. To ensure proper behavior of content files in JavaHelp, always test the display characteristics of HTML files in JavaHelp before releasing the help files.

One advantage of the content files being in HTML format is that common editors can be used to modify help content. The specifics of editing HTML files are not discussed here since these depend on the editor; however, the following general always apply:

1. Before an HTML content file within a JAR file can be edited, the file must be extracted to a working location using a tool, such as WinZip. The extracted HTML file is a copy of the original file. Make a backup of the original file and place it in a specified archive directory for later retrieval. All editing should be done on the extracted copy.
2. Select an appropriate HTML editor. Note that some HTML editors automatically add embedded XML, HTML and other types of objects to HTML code. Such objects can adversely affect the display of the content within JavaHelp. As a result, editing tools that do not automatically add objects are recommended. Such tools include Macromedia's Dreamweaver and ASCII editors, such as Notepad.
3. Save the modified HTML file to the working location.
4. Add the modified file to the applicable JAR file replacing the original file in the JAR (the original being maintained in the archive directory location). Do not change the file extension.
5. If the name of the HTML file is changed to reflect customization, such as from `f_connection.htm` to `f_connection_custom.htm`, the URL attribute of the `map.jhm` file needs to be updated to reflect the name change. The `.jhm` file can be updated using an ASCII editor.

Change the Display of Content

The format and style of the content displayed in the Helpset Viewer can be modified by altering the values of the style properties in the applicable cascading style sheet (CSS) file. CSS files are defined in the <head>...</head> section of each HTML file used in the ACI online help using <link> tags as follows:

```
<link rel="StyleSheet" href="Templates/forScreen.css" type="text/css"
media="screen">
```

```
<link rel="StyleSheet" href="Templates/forPrint.css" type="text/css"
media="print">
```

CSS files are located in the Templates folder within the applicable helpset JAR (ACI_Help_es.jar, ACI_Help_tss.jar, and ACI_Help_pm.jar).

Note: For ACI Payments Manager, the name of the CSS is document.css for both screen and print media.

To ensure that content displays properly in the Helpset Viewer, always test before releasing the modified CSS files.

Install JavaHelp for Stand-alone Use

JavaHelp can be installed for direct access to helpset (.hs) files without the need to have the ACI desktop open. Note that Java must be already installed. The remainder of this topic discusses installing JavaHelp on a Java enabled Windows-based PC.

1. Download the latest version of JavaHelp from:


<http://java.sun.com/products/javahelp>

Note: JavaHelp is distributed as a zip file such as **Javahelp 2.0_02.zip** (a more current version might be available).


2. Open the zip file and extract all files to an easily accessible location, such as (e.g., C:\jh2.0). Among the files extracted is the **hsvviewer.jar** file that is needed later in this procedure.
3. Find java.exe and create a shortcut to the file. Java.exe must be already installed. Cut and paste the shortcut to an easily accessible location.

For the illustrations used in the remainder of this procedure, the shortcut name JavaHelp 2.0 is used.

4. Right click on the shortcut and select Properties on the drop-down menu:



The properties for the JavaHelp 2.0 shortcut are available in the Properties window:




5. In the Target field located on the Shortcut tab, enter the path to java.exe, followed by a space, the string “-jar”, another space, and then the path to the installed location of hsviewer.jar. In the illustration above, the full text of the Target field is partially obscured, but is:

C:\jdk1.3\bin\java.exe -jar c:\jh2.0\demos\bin\hsviewer.jar

6. Click OK.

7. Test by clicking on the shortcut, after which the following Set HelpSet... window should display that can be used to browse to a helpset file (.hs extension) that you want to open.



If the above window does not display, a number of problems could exist. For example, either Java, JavaHelp, or both are not installed properly. Also, the target path in the shortcut could be incorrect. Verify that the paths in the shortcut reflect the actual paths for both java.exe and hsvviewer.jar.

A: Task IDs, Windows, and Permissions

The term *window* is used in documentation and online help. This term relates to a collection of graphical user interface (GUI) components (i.e., buttons, fields, field names, tabs, buttons, tables, trees, and messages) that provide access to a particular application, function and data source(s).

Each window is managed by a particular application server on the host. The applications available (therefore, the windows available) depend on the ACI desktop configuration and user security access permissions.

An application (and the corresponding window) is identified by a task ID. Tasks available on a desktop can be viewed in the Task ID selectable field located on the Permissions tab of the User Security Role Configuration window (**Configure > User Security > Role**).

The following table lists default Task IDs and the corresponding ACI desktop window names and permissions.

BASE24-es	TSS	Task IDs	Window	Permissions
✓		AcquirerIssuerRelationConfig	Routing Configuration - Destination/Source Relationship) Help ID: w_destination_source_relationship	FullAcqIssRelatnCfg Permission
✓		AcquirerProfileConfiguration	Source Routing Profile Configuration Help ID: w_source_routing_profile_ configuration	FullAcqProfileConfig Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓		AcquirerTransactionsAllowed	Acquirer Transactions Allowed Profile Configuration Help ID: w_acquirer_transactions_allowed_profile_configuration	FullAcqTransAllowed Permission
✓		ActionCode	Action Code Profile Configuration Help ID: w_action_code	FullActionCode Permission
✓		ActiveScript	Active Script Statistics and Management Help ID: w_active_script_statistics_and_management	FullActiveScript Permission
✓		AdministrativeCardManagement	Administrative Card Configuration Help ID: w_administrative_card_configuration	FullAdminCardMgmt Permission
✓		APMSInterfaceConfiguration	Application Parameter Management System Interface Configuration Help ID: w_apms_interface_configuration	FullAPMSIFCfgr Permission
✓		ApplctnManagement	Application Management Help ID: w_application_configuration	FullApplctnManagement

BASE24-es	TSS	Task IDs	Window	Permissions
✓		ApplctnManagement Summary	Application Management Comms Handler ¹ Application Management Message Router Summary ² Application Management Process Summary ³ Application Management Queue Summary ⁴ Application Management Queue Manager Summary ⁵ Application Management Station Summary ⁶ Help IDs: ¹ w_appmanage_comms_ handler_summary ² w_appmanage_message_ router_summary ³ w_appmanage_process_ summary ⁴ w_appmanage_queue_ summary ⁵ w_appmanage_queue_ manager_summary ⁶ w_appmanage_station_ summary	FullApplctnManagement Summary
✓		ATMB24CompatProfile	ATM BASE24 Compatability Profile Help ID: w_atm_base24_compatibility_ profile_configuration	FullATMB24CompatPrf Permission
✓		ATMChanMgmtSelectedChannels	ATM Channel Management Help ID: w_atm_channel_management	FullATMChanMgmtSC Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓		ATMChannel	ATM Channel Configuration Help ID: w_atm_channel_configuration	FullATMChannel Permission
✓		ATMChannelAdministration	ATM Channel Administration Help ID: w_atm_channel_administration	FullATMChannelAdmin Permission
✓		ATMChannelManagement	ATM Channel Management - All Channels Help ID: w_atm_channel_all_channels	FullATMChannelMgmt Permission
✓		ATMChannelProfile	ATM Channel Profile Configuration Help ID: w_atm_channel_profile_ configuration	FullATMChannelPrfl Permission
✓		ATMDHInterfaceConfiguration	ATM Device Handler Interface Configuration Help ID: w_atm_device_handler_ interface_configuration	FullATMDHIFCfg Permission
✓		ATMDieboldChannelOperatorID	ATM Diebold Channel Operator ID Configuration Help ID: w_atm_diebold_channel_id_ configuration	FullATMDbldChanOprID Permission
✓		ATMEmvPrfl	ATM EMV Profile Help ID: w_atm_emv_profile_ configuration	FullATMEMVProfile Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓		ATMFastCashProfile	ATM Fast Cash Profile Help ID: w_atm_fast_cash_profile_ configuration	ATMFastCashPrfl Permission
✓		ATMHardwareStatus	ATM Hardware Status Help ID: w_atm_hardware_status	FullATMHardwareStat Permission
✓		ATMHopperProfile	ATM Hopper Profile Configuration Help ID: w_atm_hopper_profile_ configuration	FullATMHopperPrfl Permission
✓		ATMInactivityProfile	ATM Inactivity Alert Profile Help ID: w_atm_inactivity_alert_profile_ configuration	FullATMInactivePrfl Permission
✓		ATMLdTmtProfile	ATM Load Timeout Profile Help ID: w_atm_load_timeout_profile_ configuration	FullATMLoadTimerPrfl Permission
✓		ATMLoadProfile	ATM Load Profile Help ID: w_atm_load_profile	FullATMLoadProfile Permission
✓		ATMMacProfile	ATM MAC Profile w_atm_mac_profile_ configuration	FullATMMACProfile Permission
✓		ATMOptionalReceiptProfile	ATM Optional Receipt Profile Help ID: w_atm_optional_receipt_profile	FullATMOptnRcptPrfl Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓		ATMReceiptFormat	ATM Receipt Format Configuration Help ID: w_atm_receipt_format_profile_configuration	FullATMReceiptFormat Permission
✓		ATMReceiptRequiredType	ATM Receipt Required Type Configuration Help ID: w_atm_receipt_required_type_configuration	FullATMRcptReqType Permission
✓		ATMReloadMaps	ATM Reload Map Request Help ID: w_atm_reload_map_request	FullATMReloadMaps Permission
✓		ATMStatementPrintProfile	ATM Statement Print Help ID: w_atm_statement_print_profile_configuration	FullATMStmtPrntPrfl Permission
✓		ATMStatusQuery	ATM Status Query Help ID: w_atm_status_query	FullATMStatusuery Permission
✓		ATMSurcharge	ATM Surcharge Profile Help ID: w_atm_surcharge_profile_configuration	FullATMSurcharge Permission
✓		ATMSurcharge	Surcharge Profile Configuration Help ID: w_surcharge_profile_configuration	FullATMSurcharge Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓	✓	AuditSAFConfig	Audit Store and Forward (SAF) Configuration Help ID: w_audit_store_and_forward_configuration	FullAuditSAFConfig Permission
✓	✓	AuthenticationConfiguration	Authentication Profile Configuration Help ID: w_authentication_profile_configuration	FullAuthentConfig Permission
✓		AuthScript	Authorization Script Configuration Help ID: w_authorization_script_configuration	FullAuthScript Permission
✓		B24HISOInterfaceConfig	BASE24 ISO8583 Host Interface Configuration Help ID: w_base24_iso8583_host_interface_configuration	FullB24HISOIFConfig Permission FullHISO
✓	✓	B24KEYFSecurity	BASE24 KEYF Configuration Help ID: w_base24_keyf_configuration	FullB24KEYFSecurity Permission
✓	✓	B24SPDHDKPTDerivationKey	DUKPT Derivation Key Profile Configuration Help ID: w_dukpt_derivation_key_profile_configuration	FullB24SPDHDKPTDKey Permission
✓		BanknetInterface	BankNet ISO Interface Configuration Help ID: w_banknet_iso_interface_configuration	FullBanknetInterface Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓	✓	BNTngHeaderConfig	BNTng Key Header Configuration Help ID: w_bntng_key_header_configuration	FullBNTngHeader Configuration
✓		CardConfiguration	Card Management Help ID: w_card_management	FullCardConfig Permission
✓	✓	Certificate	Certificate Management Help ID: w_certificate_management	FullCertificate Permission
✓	✓	ChannelPKPerusal	Channel Public Key Perusal Help ID: w_channel_public_key_perusal	FullChannelPKPerusal Permission
✓	✓	ChannelSecurity	Channel Security Configuration Help ID: w_channel_security_configuration	FullChannelSecurity Permission
✓		ContextConfiguration	Context Profile Configuration Help ID: w_context_profile_configuration	FullContextConfig Permission
✓		CurrencyConvRateConfiguration	Currency Conversion Rate Configuration Help ID: w_currency_conversion_rate_configuration	FullCrncyConvRateCfg Permission
✓	✓	EnvironmentManagement	Environment Configuration Help ID: w_environment_configuration	FullEnvironmentMgmt Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓	✓	EPPSerialNumberConfig	EPP Serial Number Configuration Help ID: w_epp_serial_number_configuration	FullEPPSerialNumCfg Permission
✓		EPSNetInstitution	EPS-Net Institution Help ID: w_epsnet_institution_configuration	FullEPSNetInst Permission
✓		EPSNetInterfaceConfiguration	EPS-Net ISO Interface Configuration Help ID: w_epsnet_iso_interface_configuration	FullEPSNetInterface Permission
✓		EuroOptedCurencyConfiguration	Euro Opted Currency Configuration Help ID: w_euro_opted_currency_configuration	FullEuroOptedCurrCfg Permission
✓	✓	EventConfiguration	Event Configuration and Management Help ID: w_integrated_server_event_configuration	FullEventConfig Permission
✓	✓	EventSubsystemConfiguration	Event Subsystem ID Configuration Help ID: w_event_subsystem_id_configuration	FullEventSubConfig Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓		ExportedOperator	Exported Operators Configuration Help ID: w_exported_operators_configuration	FullExportedOperator Permission
✓	✓	FilePartition	File Partition Configuration Help ID: w_file_partition_configuration	FullFilePartition Permission
✓		FileUpdateRouterConfig	File Update Router Help ID: w_file_update_router_configuration	FullFileUpdateRouterConfig Perm
✓	✓	HostPKPerusal	Host Public Key Perusal Help ID: w_host_public_key_perusal	FullHostPKPerusal Permission
✓		IFXHostActionCode	IFX Host Action Code Profile Configuration Help ID: w_ifx_host_action_code_profile_configuration	FullIFXHostActionCode Perm
✓		IFXHostInterface	IFX Host Configuration Help ID: w_ifx_host_interface_configuration	FullIFXHostInterfacePerm
✓		IMTATMTransactionMapping	Internal Message Translation (IMT) Transaction Mapping - ATM Help ID: w_imt_transaction_mapping_atm	FullIMTATMTransMap Permission
✓		IMTInterface	IMT Interface Configuration Help ID: w_imt_interface_configuration	FullIMTInterface Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓		IMTPOSTransactionMapping	Internal Message Translation (IMT) Transaction Mapping - POS Help ID: w_imt_transaction_mapping_pos	FullIMTPOSTransMap Permission
✓		InstitutionConfiguration	Institution Configuration Help ID: w_institution_configuration	FullInstConfig Permission
✓		InstrStatusMappingProfile	Instrument Status Mapping Profile Configuration Help ID: w_instrument_status_mapping_profile_configuration	FullInstStatMapPrfl Permission
✓		InstrumentTypeIchgRelation	Instrument Type/Interchange Relationship Help ID: w_instrument_type_interchange_relationship_configuration	FullInstTypIchgRel Permission
✓		InterchangePrefixConfiguration	Interchange Prefix Configuration Help ID: w_interchange_prefix_configuration	FullIchgPrefixConfig Permission
✓	✓	InterfaceSecurityConfiguration	Interface Security Configuration Help ID: w_interface_security_configuration	FullIFSecurityConfig Permission
✓		InterfaceTerm	Interface Terminal Help ID: w_interface_terminal_configuration	FullInterfaceTerm Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓		InterpayInterface	Interpay (BIM) Interface Configuration Help ID: w_interpay_bim_interface_configuration	FullInterpayIFPermission
✓		ISO93InterfaceConfiguration	ISO 93 Host Interface Configuration Help ID: w_iso_93_host_interface_configuration	FullISO93IFConfig Permission
✓		ISOFrameworkConfiguration	ISO Message Profile Configuration Help ID: w_iso_framework_configuration	FullISOFrameworkCfgr Permission
✓		ISOTranMapping	ISO Transaction Mapping Profile Configuration Help ID: w_iso_transaction_mapping_profile_configuration	FullISOTranMap Permission
✓		IssuerProfileConfig	Destination Routing Profile Configuration Help ID: w_destination_routing_profile_configuration	FullIssProfConfig Permission
✓		IssuerTransactionsAllowed	Issuer Transactions Allowed Profile Configuration Help ID: w_issuer_transactions_allowed_profile_configuration	FullIssTransAllowed Permission
✓	✓	IWTApplicationConfig	Application Configuration Help ID: w_application_configuration	FullIWTApplCfgr Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓	✓	IWTCacheAdministration	Cache Administration Help ID: w_cache_administration	FullIWTCacheAdmin Permission
✓	✓	IWTConfigurationAdministration	Configuration Properties Help ID: w_configuration_properties	FullIWTConfigAdmin Permission
✓	✓	IWTConnectionConfig IWTPProcessConfig	External Connection Configuration Help ID: w_external_connection_ configuration	FullIWTConnectionCfg Permission
✓	✓	IWTDatabaseAdministration	Database Administration Help ID: w_database_administration	FullIWTDatabaseAdmin Permission
✓	✓	IWTListenerConfig	Listener Configuration Help ID: w_listener_configuration	FullIWTListenerCfg Permission
✓	✓	IWTProcessConfig	Process Configuration Help ID: w_process_configuration	FullIWTProcessCfg Permission
✓	✓	IWTSocketAdministration	Socket Administration Help ID: w_socket_administration	FullIWTSocketAdmin Permission
✓	✓	IWTSystemMonitor	System Monitor Help ID: w_system_monitor	FullIWTSystemMonitor Permission
✓	✓	IWTSystemProperties	System Properties Help ID: w_system_properties	FullIWTSysProperties Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓		JournalConfigurationMapping	Journal Issuer Profile Relationship Configuration Help ID: w_journal_issuer_profile_relationship_configuration	FullJrnlCfgMapping Permission
✓		JournalProfileConfiguration	Journal Profile Configuration Help ID: w_journal_profile_configuration	FullJrnlProfileCfg Permission
✓		JournalQueryConfiguration	Journal Query Configuration Help ID: w_journal_query_configuration	FullJrnlQueryConfig Permission
✓		JournalQueryExecution	Query Execute Help ID: w_query_execute	FullJrnlQueryExecute Permission
✓		JournalTDESuppression	Journal TDE Suppression Configuration Help ID: w_journal_tde_suppression	FullJrnlTDESuppress Permission
✓	✓	KEYGENLockdown	Disable KEYGEN Help ID: w_disable_keygen	FullKEYGENLockdown Permission
✓		LinkedCurrencyConfiguration	Linked Currency Configuration Help ID: w_linked_currency_configuration	FullLinkedCurrCfg Permission
✓		LIS5Interface	LINK ISO Interface (LIS5) Configuration Help ID: w_link_lis5_interface_configuration	FullLIS5Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓		LogFilePerusal	Journal Perusal Help ID: w_journal_perusal	FullLogFilePerusal Permission
✓		MaestroDebitSwitch	MasterCard Debit Switch (MDS) Interface Configuration Help ID: w_mastercard_debit_switch_ configuration	FullMaestro Permission
✓		MerchantChannel	Merchant Channel Configuration and Statistics Help ID: w_merchant_channel_ configuration	FullMerchantChannel Permission
✓		MerchantChannelProfile	Merchant Channel Profile Help ID: w_merchant_channel_profile_ configuration	FullMerchantChnlPrfl Permission
✓		MerchantConfiguration	Merchant Configuration and Statistics Help ID: w_merchant_configuration_and_ statistics	FullMerchantConfig Permission
✓	✓	MFKConverter	Master File Key Conversion Help ID: w_master_file_key_conversion	FullMFKConverter Permission
✓	✓	OltpWarmbootManagement	OLTP Warmboot Management Help ID: w_oltp_warmboot_management	FullOLTPWarmbootMgmt Permission
✓		PaymentLimitConfig	Limit Profile Management Help ID: w_limit_profile_configuration	FullPmtLimitConfig Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓		PerusalConfiguration	Perusal Profile Configuration Help ID: w_perusal_profile_configuration	FullPerusalConfig Permission
✓		PositiveBalance	Positive Balance Management Help ID: w_positive_balance_ management	FullPositiveBalance Permission
✓		PreAuthHold	Preauthorization Hold Management Help ID: w_preauthorization_hold_ management	FullPreAuthHold Permission
✓		PrefixConfiguration	On-Us Prefix Configuration Help ID: w_prefix_configuration	FullPrefixConfig Permission
✓	✓	ProcessControl	Process Control Help ID: w_process_control	FullProcContrl FullProcessControl
✓		RealTimeFeedInterface	Real Time Feed Window Help ID: w_realtimefeed_interface_ configuration	FullRealTimeFeedIF Permission
✓		RoutingConfiguration	Routing Configuration - Destination Help ID: w_routing_configuration_ destination	FullRoutingConfig Permission
✓		ScriptEditor	Script Editor Help ID: w_script_editor	FullScriptEditor Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓		ScriptRepository	Script Repository Help ID: w_script_repository	FullScriptRepository Permission
✓	✓	SecurityDeviceConfiguration	Security Device Configuration Help ID: w_security_device_configuration	FullSecurityDevCfg Permission
✓		SPDHDeviceConfig	SPDH Device Profile Configuration Help ID: w_spdh_device_profile_ configuration	FullSPDHDeviceConfig Permission
✓		StarInstitution	STAR Institution Help ID: w_star_institution_configuration	FullStarInstitution Permission
✓		StarInterface	STAR ISO Interface Configuration Help ID: w_star_iso_interface_ configuration	FullStarInterface Permission
✓		StarNetworkIdRelationship	STAR Network Identifier/ Instrument Type Relationship Help ID: w_star_network_identifier_ instrument_type_relationship_ configuration	FullStarNtwkIdRelation Perm
✓		SystemAlgorithm	System Algorithm Configuration Help ID: w_system_algorithm	FullSystemAlgoritm Permission
✓		SystemPrefix	System Prefix Configuration Help ID: w_system_prefix_configuration	FullSystemPrefix Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓		TermLnFiidMap	Terminal Logical Network/FIID Mapping Help ID: w_terminal_logical_network_fiid_mapping	FulltermLnFiidMapPerm
✓		TokenProfile	Token Profile Configuration Help ID: w_token_profile_configuration	FullTokenProfilePermission
✓	✓	TraceConfiguration	Trace Configuration Help ID: w_trace_configuration	FullTraceConfig Permission
✓	✓	TraceFilterConfiguration	Trace Filter Profile Configuration Help ID: w_trace_filter_profile_configuration	FullTraceFilterCfg Permission
✓		Usages	Usages Management Help ID: w_usages_management	FullUsages Permission
✓	✓	UserAuditReport	Audit Report Wizard Help ID: w_audit_report_wizard	FullUserAuditRpt Permission
✓		UserProfileRelation	User Profile Relationship Help ID: w_user_profile_relationship	FullUserProfRelation Permission
✓	✓	UserSecurityControl	User Security Control Management Help ID: w_user_security_control_management	FullUSCtl Permission

BASE24-es	TSS	Task IDs	Window	Permissions
✓	✓	UserSecurityGroupConfig	User Security Group Configuration Help ID: w_user_security_group_configuration	FullUSGCfg Permission
✓	✓	UserSecurityProfile	User Security Profile Configuration Help ID: w_user_security_profile_configuration	FullUSP Permission
✓	✓	UserSecurityRoleConfig	User Security Role Configuration Help ID: w_user_security_role_configuration	FullUSRCfg Permission
✓		VisaAcquirers	Visa Acquirers Configuration Help ID: w_visa_acquirers_configuration	FullVisaAcquirers Permission
✓		VisaDPSAcquirers	Visa DPS Acquirers Configuration	FullDPSVisaAcquirers Permission
✓		VisaDPSInterface	Visa DPS Interface Configuration Help ID: w_visa_dps_interface_configuration	FullVisaDPSInterface Permission
✓		VisanetInterfaceConfig	VisaNet ISO Interface Configuration Help ID: w_visanet_iso_interface_configuration	FullVisanetIFConfig Permission

ACI Worldwide Inc.

Index

A

Access user security windows, [3-2](#)
Active sessions (maximum allowed), [3-6](#)
Active user sessions, [4-3](#)
Application Area, [1-1](#)
Audit_Store_and_Forward data source, [5-1](#)
Automatic file updating, [6-2](#)

C

Cascading Style Sheets (CSS), JavaHelp, [7-3](#)
Concurrent active sessions, [2-3](#)
Confirm deletes check box, [2-7](#)
Confirm updates check box, [2-7](#)
Content files, JavaHelp, [7-3](#)
Context sensitive help, [7-5](#)
Currency format locale, [2-7](#)
Custom online help, [7-7](#)

D

Desktop layout (areas), [1-1](#)
DeskTop.log file, [2-11](#)
Distributed Security Administration (DSA), [3-7](#)
DSA (Distributed Security Administration), [3-7](#)

F

Filter settings, [3-15](#)
Frame open indicator, [2-7](#)

G

Get Info function, [3-19](#)

H

Help IDs, [7-5](#)
Helpset file, JavaHelp, [7-3](#)
Helpset Viewer, [7-1](#)
hsvviewer.jar, [7-10](#)

I

Images, JavaHelp, [7-3](#)

J

JAR files for JavaHelp, [7-3](#)
JAR versions, [2-12](#)
JavaHelp, [7-1](#)
JavaHelp configuration files, [7-3](#)
JavaHelp viewer, [7-1](#)

L

local.cfg, [1-2](#)

M

Map file, JavaHelp, [7-3](#)
Map IDs, [7-5](#)
Maximum number of allowed active sessions, [3-6](#)
Menu Bar, [1-1](#)
Mirror the repository, [6-2](#)

N

Navigation tree, [1-1](#)
Navigation tree check box, [2-7](#)
Node controllers
 selecting, [2-4](#)

O

Online help viewer (JavaHelp), [7-1](#)
OwnerIDSupport property, [3-7](#)

P

Packaging of online help, [7-3](#)
Password group, [3-4](#)
Passwords, [3-4](#)
 change by a user, [2-5](#)
 change by an administrator, [4-5](#)
 restrictions, [3-4](#)
Permission groups, [3-3](#)
Permissions, [3-3](#)

P continued

Pre-show frame indicator, [2-8](#)

Print Screen Orientation, [2-8](#)

Procedures

- Access online help from the desktop, [7-2](#)
- Access user security windows, [3-2](#)
- Assign a security group, [3-21](#)
- Assign a system administration role filter, [3-12](#)
- Assign roles to a user, [3-23](#)
- Change a password (by a user), [2-5](#)
- Change a user password (by admin), [4-5](#)
- Change the display of JavaHelp content, [7-9](#)
- Configure a password group, [3-9](#)
- Configure a security group, [3-10](#)
- Configure a user role, [3-13](#)
- Configure field filters, [3-14](#)
- Configure permission groups, [3-19](#)
- Configure permissions, [3-17](#)
- Connect to a node controller, [2-4](#)
- Connect to a web server, [2-4](#)
- Create custom JavaHelp content HTML files, [7-8](#)
- Create custom online help, [7-7](#)
- Display the user interface framework version, [2-12](#)
- Display user password history, [4-5](#)
- Expire a user password, [4-5](#)
- Hide or show the navigation tree, [2-7](#)
- Install JavaHelp, [7-10](#)
- Log off (out), [2-5](#)
- Log off a user, [4-4](#)
- Mirror the repository, [6-2](#)
- Search the helpset, [7-6](#)
- Send a snapshot, [2-11](#)
- Set a user status, [4-2](#)
- Set Error Notification settings, [2-9](#)
- Set sound preferences, [2-10](#)
- Set user preferences, [2-6](#)
- Terminate an active user session, [4-4](#)
- View active user sessions (refreshing, updating), [4-4](#)
- View password change history, [4-5](#)

R

REPORT.USERAUDITLOG.LOC environment attribute, [5-2](#)

Roles, [3-3](#)

RunDesktop.bat, [2-1](#), [6-1](#)

S

- Search the helpset, [7-6](#)
- Secure Sockets Layer (SSL) protocol, [1-3](#)
- Security domains, [3-7](#)
- Security error alert message, [2-2](#)
- Security groups (users), [3-5](#)
- Security warning alert message, [2-3](#)
- Session timeout, [3-6](#), [3-11](#)
- Sessions (active), [4-3](#)

Snapshots, [2-11](#)

sound.cfg, [2-10](#)

Status Pane, [1-1](#)

Status pane, [2-8](#)

SysAdmin Profile, [3-12](#)

System Administration Profile, [3-12](#)

T

Table of contents, JavaHelp, [7-3](#)

Timeouts

session, [3-11](#)

UI, [3-11](#)

Title Bar, [1-1](#)

Toolbar, [1-1](#), [2-8](#)

Tooltip text (display errors in tooltip text), [2-9](#)

U

UI timeout, [3-6](#), [3-11](#)

User authentication, [1-4](#)

User authorization, [1-4](#)

User interface framework, [1-2](#)

User interface framework version, [2-12](#)

User Preferences window

Error Notification tab, [2-9](#)

Sound tab, [2-10](#)

User roles, [3-3](#)

User Securit Group Configuration window

Password Group tab, [3-9](#)

User Security Control Management window

Active Sessions tab, [4-3](#), [4-4](#)

Password Maintenance tab, [4-5](#)

User Security Group Configuration window

Security Group tab, [3-10](#)

User Security Profile Configuration window

Active Sessions tab, [4-3](#), [4-4](#)

General tab, [3-20](#), [4-2](#)

User Security Profile window

Password tab, [4-5](#)

Roles tab, [3-23](#)

User Security Role Configuration window

Permission Groups tab, [3-19](#)

Permissions tab, [3-17](#)

Roles tab, [3-13](#)

User security server

overview, [1-4](#)

User sessions, [4-3](#)

User status, [4-2](#)

USRAULOG data source, [5-1](#)

V

VC quiet mode, [6-2](#)

Version Checker, [6-1](#)

Version Checker Client window, [6-2](#)

Versions, [2-12](#)

W

Web servers

 selecting, [2-4](#)

 user interface framework, [1-2](#)

X

XML index file, JavaHelp, [7-3](#)

ACI Worldwide Inc.