

ACI Desktop User Interface Manual

BASE24-eps[™]



© 2009 by ACI Worldwide, Inc. All rights reserved.

All information contained in this documentation, as well as the software described in it, is confidential and proprietary to ACI Worldwide, Inc., or one of its subsidiaries, is subject to a license agreement, and may be used or copied only in accordance with the terms of such license. Except as permitted by such license, no part of this documentation may be reproduced, stored in a retrieval system, or transmitted in any form or by electronic, mechanical, recording, or any other means, without the prior written permission of ACI Worldwide, Inc., or one of its subsidiaries.

ACI, ACI Worldwide, and the ACI product names used in this documentation are trademarks or registered trademarks of ACI Worldwide, Inc., or one of its subsidiaries.

Other companies' trademarks, service marks, or registered trademarks and service marks are trademarks, service marks, or registered trademarks and service marks of their respective companies.

Contents

Preface	vii
Conventions Used in This Manual	xi
1: Introduction	1-1
Communication Security	1-3
User Security	1-4
ACI Desktop Modules List	1-4
2: Getting Started and Basic Functions	2-1
Enable SSL for the BASE24-eps	2-2
Additional Information on the RunDesktop.bat File	2-4
Connection Information	2-5
Log In (Log On)	2-5
Connect to an Application Server	2-7
Display Name of the User that is Logged On to the Desktop	2-7
Change a Password	2-8
Log Out (Log Off) and Exit	2-9
User Preferences	2-10
General Preferences	2-10
Error Notification Preferences	2-13
Sound Preferences	2-14
Logging (Debug and Trace) Preferences	2-15
Display Framework Version Information	2-17

3: User Configuration	3-1
User Security Configuration Window Usage	3-2
User Profiles	3-3
Roles	3-3
Passwords and Password Groups	3-4
Security Groups	3-5
Distributed Security Administration (DSA)	3-7
Steps to Add a User	3-8
4: User Management	4-1
Set the Status of a User	4-2
Active User Session Management	4-3
Terminate Active User Sessions (Log off a User)	4-4
Password Management	4-5
User Status Window	4-6
User Status Detail Properties	4-7
User Status Detail Example	4-8
User Permissions Window	4-9
User Status Detail Properties	4-10
5: User Auditing	5-1
Audit Report XML Format	5-2
User Audit Activity Report Process	5-3
Example Report on the ACI Desktop	5-7
Automated User Auditing	5-9
6: Version Checker	6-1

7: Online Help	7-1
Access to JavaHelp from the ACI Desktop	7-2
With Context	7-2
Without Context	7-2
JavaHelp Files	7-3
JavaHelp Packages	7-3
Helpset File	7-4
How Context is Implemented in JavaHelp	7-5
Search the Helpset for a Text String	7-6
Custom Help Content	7-7
Customization of HTML Content Files	7-8
Change the Display of Content	7-9
Install JavaHelp for Stand-alone Use	7-10
A: BASE24-eps Window (UI) Information	A-1
B: Desktop.cfg File	B-1
C: SSL Keystore Password Manager	C-1
Sample Passwords.bin File	C-2
Run the Password Manager from the Command Prompt	C-3
Run the Password Manager from the PswdMgrUI Window	C-5
PswdMgrUI Window	C-5
Add a New User-Defined Password Token	C-6
Delete a User-Defined Password Token	C-6
D: Multibyte Character Data Support	D-1
Configuration	D-1
Multibyte Data Fields	D-3
ATM Consumer Media and Receipts	D-4
Instrument Type Descriptions	D-4
Scripts	D-5

E: Open Source Software License Agreements	E-1
JDOM Java XML API	E-1
Apache Ant 1.6.2	
Apache AXIS 1.4	
Apache Commons Codec 1.3	
Apache Jakarta Commons Net 1.3	
Apache Tomcat Versions 5.5 and 6.0	
Apache Xerces C++ 2.8.0	
SourceForge Piccolo XML Parser for Java	E-3
ICU License - ICU 1.8.1 and later	E-3
JAVA™ AUTHENTICATION AND AUTHORIZATION SERVICE	
VERSION 1.0	
JAVAHELP™ VERSION 2.0	E-4
JAVA™ 2 PLATFORM STANDARD EDITION RUNTIME ENVIRONMENT,	
VERSION 5.0	E-5
JAXB Component of JAVA™ Web Services Developer Pack	
JAVA™ Secure Socket Extension	
JavaBeans Activation Framework	
JavaMail API	E-5
Sun Java Graphics Repository	E-6
EXOLAB Castor, Exolab Core, Open JMS	E-6
The Legion of the Bouncy Castle	E-7
STLport	E-8
MX4J	E-9
Jython	E-10
JPython	E-10
Jetty	E-11
JCheckTree	E-14
JSpinner	E-14
JSch	E-14
ICEFaces	E-16
 Index.	 Index-1

Preface

The ACI desktop is the user access to the following ACI applications for configuration, operation, and management functions:

- BASE24-eps
- Enhanced authorization for BASE24 applications
- Transaction Security Services (TSS)
- ACI Payments Manager
- ACI Smart Chip Manager
- ACI Card Management System
- ACI Token Manager

Audience

This manual is written for all users of the ACI desktop, primarily system administration personnel.

Prerequisites

Readers must know basic graphical user interface (GUI) functionality and procedures, such as using hyperlinks and buttons. The ACI desktop is organized by tasks (i.e., configure, system operations, and customer management) that require basic understanding of managing payment systems and applications.

Referenced Documents

The *ACI Java Infrastructure Java Server Reference Guide* provides detailed information on the data sources and facilities used to configure remote destinations for Java processes.

Software

This manual documents standard processing as of its publication date. Software that is not current and custom software modifications (CSMs) may result in processing that differs from the material presented in this manual.

Manual Summary

Section 1, “Introduction,” provides an overview of the ACI desktop, windows, communication security, and information about default users. Also included is information about the user interface framework and user security.

Section 2, “Getting Started and Basic Functions,” describes how to log in and log out and perform other functions available from the File menu.

Section 3, “User Configuration,” provides an overview of user security, distributed security administration (DSA), and how to configure a user of the ACI desktop.

Section 4, “User Management,” describes how to manage and monitor users of the ACI desktop. Includes information about user status and user permission information available on the View menu.

Section 5, “User Auditing,” provides an overview of user auditing of the ACI desktop, including generating audit reports.

Section 6, “Version Checker,” describes how the Version Checker manages and updates ACI desktop versions.

Section 7, “Online Help,” describes the desktop online help (JavaHelp) and how to use online help. Provides information about localizing the ACI desktop and customizing online help.

Appendix A, “BASE24-eps Window (UI) Information,” provides a list of each BASE24-eps window and for each window the task ID, permissions, help ID, impacted data sources, ACI desktop menu access information, and server messages.

Appendix B, “Desktop.cfg File,” provides key-value pair information about the Desktop.cfg file.

Appendix C, “SSL Keystore Password Manager,” provides information about using the Password Manager to manage SSL keystore passwords.

Appendix E, “Multibyte Character Data Support,” provides information about the BASE24-eps Multibyte Character Set Service module and the multibyte data fields that are available on ACI desktop windows.

Appendix E, “Open Source Software License Agreements,” provides OSS license agreements applicable to the ACI desktop.

Publication Identification

The following information appears at the bottom of each page to identify this manual:

- ❑ Publication date (Sep-2009)
- ❑ Release and version number (R1.0v09.2)
- ❑ Publication number (CF-CS000-01ES)

ACI Worldwide, Inc.

Conventions Used in This Manual




This manual uses the symbol shown at the left to alert to cross-industry best practices information for protecting sensitive data that is stored, processed, or transmitted in ACI applications. Carefully review such information to implement compliance to cross-industry best practices for securing data.

Refer to the product-specific Security Best Practices manual for more information about configuring an ACI product to comply with cross-industry best practices.

ACI Worldwide, Inc.

1: Introduction

The user interface of the ACI desktop consists of distinctive areas identified below.



- 1** – The **Title Bar** displays the name of the desktop.
- 2** – The **Menu Bar** provides access to available functions and application windows.
- 3** – The **Toolbar** contains buttons for common functions, such as log in, log out, display help topics and display context help.
- 4** – The **Navigation Tree** provides a hierarchical view of the menu bar.
- 5** – The **Application Area** contains opened application windows. Note that the text “LOGGING SENSITIVE DATA” is displayed if the debugging option on the User Preferences window is set, or if tracing of client messages exchanged with the server has been activated by a system administrator.

- 6** – The **Status Pane** contains informational messages about the activity between the desktop and servers. Right click on this pane to see the full detail of a message. Left click to see a list of previously received messages.
- 7** – The **Icon Area** provides informational icons. Place the cursor over an icon to display a popup message.

The key component of the ACI desktop is the **user interface framework**, which is a collection of Java classes, interface applications, rules, guidelines, recommendations, and styles that are used as a template for building and supporting ACI desktop applications. The components of the user interface framework include:

- User interface clients for which common functions, such as logging on and off the desktop, are available through the File menu
- Application Servers, such as Apache Tomcat or IBM WebSphere Application Server

Each application server is responsible for managing communication among desktop clients. Multiple application servers can be available in groups and are configured for the desktop using the local.cfg file. By defining groups, users can select application servers as applicable.

- Version Checker for automatic client version checking and updating
- Online help that is context sensitive

These components communicate with each other and with applications running on the application host server using a variety technologies. XML messages are passed to application servers on the host using Transmission Control Protocol/Internet Protocol (TCP/IP).

Hypertext Transfer Protocol Secure Sockets Layer (HTTPS) is used for ACI desktops to communicate with web servers clients.

Communication Security

Connections among ACI desktops, web servers, and application servers on the host can be configured to be secured using Secure Sockets Layer (SSL).

Certificates are used to authenticate servers to desktop clients, and optionally authenticate clients to servers. Public key cryptography is used to encrypt messages sent among clients and servers.

Note: SSL is configured using SSL specific properties defined using the Application Configuration window (**System Operations > Server Management > Application**). Refer to the *ACI Java Infrastructure Java Server Reference Guide* for more information.

The following Java™ Archive files provide the support needed for SSL:

- Jcert.jar
- Jnet.jar
- Jsse.jar
- UIFSSLKeys.jar, which contains the default keystores.

Certificates and private keys used for encryption and authentication are maintained in protected files called keystores. These files vary by application and are identified by .sto.



Note: Custom communication developed and implemented for TCP/IP lines outside of the ACI desktop must be secured using SSL.

User Security

User security (USEC server) consists of the authentication of users, authorization of user activity, management of active user sessions, and the logging of user activity. The `user.security.version` property provides the USEC server version.

For authentication, an individual must provide a user ID and password. This information is checked the user security database to determine whether the individual can access the application. This authentication includes the requirement that the user ID be defined in the user security database and the password must match that recorded for the ID. In addition, the user's security group and password group restrictions are checked.

User authorization is the validating of each activity initiated by a user. During user authorization the activity initiated by a user is compared to the user's security profile, which defines the functions (i.e., Delete, Save, and View) that a user can perform. A user can only perform those functions that have been assigned to the user's profile. This ensures that a user does not perform an activity not authorized by the user's security configuration.

See section 3 (User Configuration), section 4 (User Management), and section 5 (User Auditing) for more information.


ACI Desktop Modules List

A `modules.lst` (modules list) is included with the install of the ACI desktop. This modules list is required because it contains module identifiers related to user interface windows, or more specifically, ACI desktop functionality. If additional functionality is added to the desktop after an install, the `modules.lst` file must be updated to include the new module ID(s) pertaining to the new functionality, and the desktop must be restarted to activate the new functionality.

On all platforms, the `modules.lst` file is located in the `<eshome./ESWeb/ESConfig` folder.

2: Getting Started and Basic Functions

Each desktop session is started by running the **RunDesktop.bat** batch file, which is usually configured during installation to be accessed through a shortcut located on a client desktop or a menu. For example:



After the desktop establishes contact with the applicable servers and JAR files have been downloaded (see the next page for more information), the desktop displays the Log In window for entry of a user ID (name) and password. The desktop opens after a valid user ID (name) and password combination has been provided and authenticated. The file menu functions (e.g., Configure) and windows that are presented are dependent upon the user's configuration settings.

This section discusses logging on to the desktop, connecting to application servers, setting user preferences, and viewing version information.

Enable SSL for the BASE24-eps

An SSL enabled desktop has the  lock image displayed at the lower right. Use the following procedure to enable SSL for a BASE24-eps desktop.

1. Access and open the desktop.cfg (local.cfg) file.
2. Add the following line to the [Desktop] section:

```
SSLEnabled=true
```

For example:

```
[Desktop]
.....
SSLEnabled=true
Host=TomcatServerName
.....
```

3. Add the https port entry in the hosts section, setting the port to the value configured in the server's application server configuration file. In a default deployment this is the Tomcat server.xml file. (The servlet name and port may vary by product release; match the one used in your vanilla deployment).

```
[Hosts]

TomcatServerName=<tomcat_machine_name>:8443/ESServer/
ESGenericServlet
```

4. Add the following SSL section if not already present

```
[SSL]
#
# The provider and protocol handler package need to be
# specified unless otherwise defined in the java.security
# file. They should be set to sun's implementation(s).
# Provider=com.sun.net.ssl.internal.ssl.Provider
# ProtocolHandlerPkgs=com.sun.net.ssl.internal.www.protocol
#
# If auto update is true, the specified key store file below
# will automatically be extracted by locating it in any jar
# in the classpath. This typically would come from the
# UIFSSLKeys.jar. If the keystore should not be extracted
# upon startup, then set thisproperty to false.
#

KeyStoreAutoUpdate=true
KeyStorePassword=defaultDT
KeyStore=dtKS.sto
KeyStoreType=JKS
```

5. Import the server's certificate into the keystore.
6. Restart the Desktop. You should have:
 - ❑ No URL connections errors in the desktop.err file. This means that there was a HTTP SSL connection established between the desktop and Tomcat.
 - ❑ You should see a lock icon on the right hand bottom corner of the desktop application frame. This confirms that the desktop is started with `SSLEnabled=true`
 - ❑ Logon to the desktop and test.

Additional Information on the RunDesktop.bat File

The install program names the RunDesktop.bat file. When the RunDesktop.bat is run, it starts up a JVM and launches the VersionChecker Client program which determines whether new and updated JAR files are available from the Server Repository (see section 6 for more information). When the Version Checker is completed, the batch file calls the DesktopLauncher.exe that starts up the Desktop. The DesktopLauncher.exe also accesses a file named DesktopLauncher.lax.

For support purposes, ACI does not recommend that the above files be renamed. However, if it is desired to rename the files, the following considerations apply:


- The RunDesktop.bat file can be renamed after install. Any shortcuts pointing to this file will need to be modified to reflect the name change.
- If the DesktopLauncher.exe file is renamed, the RunDesktop.bat file will need to be modified to reflect the name change. Also, the DesktopLauncher.lax will need to be renamed to the same name as the new name for DesktopLauncher.exe.

Connection Information

This topic provides information for logging on, concurrent sessions, connecting to an application server, changing passwords, and logging off.

Log In (Log On)


To log in, select the Log In function located on the File menu (**File > Log In**), the Log In button () on the toolbar, or navigation tree.




After a successful log-on attempt (authenticated user), the desktop provides access to those applications (windows) that system administration has assigned to the user (i.e., the permissions and permission groups of the user's profile). Each session is assigned a unique session number used for authorization purposes.

In addition to the above, session and window (UI) timeout values are initiated and tracked during a session. A timeout is a defined period of inactivity. Timeout limits are defined in the security groups assigned to users.

If the user name and password are not correct or the user name has been disabled or does not have valid access at the time of login, the user is not given access to the desktop. In this case a security error message (shown below) is displayed. The error message is purposely vague so not to indicate which information (name or password or both) is incorrect.




A **security warning**, such as the example below, is displayed upon a successful log-on attempt if there were one or more unsuccessful log-on attempts before the user successfully logged on.




Concurrent Sessions

The number of **concurrent active sessions** allowed for a user is limited to a maximum as defined in the security group of the user's profile. A possible scenario in which a user might have concurrent active sessions is by logging on from another terminal without logging off from an active session that was started at another terminal, or in a browser session.

This version of the Session Information dialog is displayed if a user has one or more existing active sessions when logging on, and this number of sessions is fewer than the maximum number as defined in the user's security group.



This version of the Session Information dialog is displayed if a user, upon startup, has already reached the maximum number of allowed active sessions defined in the user's security group.



Connect to an Application Server

During startup, the ACI desktop attempts to connect to the default (or most recently used) application server. If multiple application servers are available, a user can access the Connection window (**File > Connection**) to select an alternate. The Connection window displays a selectable list of available application servers from which one can be selected.

If the one selected accesses a different shared user security database, any existing active sessions for the user are terminated. Also, the port used must be available (i.e., not used by another system or application); otherwise, a connection error is encountered.

A system administrator can configure the list of supported hosts using the host variable in the desktop.cfg file. See Appendix B.

Display Name of the User that is Logged On to the Desktop


To obtain the name of the user currently logged on to the ACI desktop, mouse over the user icon () that is located at the bottom right of the desktop. For example:



If this icon is not displayed, access the desktop.cfg file and set the **ShowLoggedOnUser** property, which is located in the [desktop] section of the file, to true. This property can be added if it is not present. The desktop will need to be restarted if a change is made to the desktop.cfg file.

Change a Password

To change a password, log in to the desktop and select the Change Password function (**File > Change Password**) to display the Change Password window:



Note: This dialog box will not be available when you are using a third-party authenticator other than the one provided with this application. Contact your security administrator for details.

Certain password restrictions and requirements apply. See section 3 for more information.

Log Out (Log Off) and Exit

To log out, select the Log Out function located either on the File menu (**File > Log Out**), the Log Out button () on the toolbar, or navigation tree.

Logging out does not close the desktop. To close the desktop, select **File > Exit**.


Note: A user does not need to be logged in to exit. Also, if a user exits without logging out, the user is automatically logged out from the desktop.

User Preferences

Each user can set desktop characteristics to desired preferences by accessing **File > Preferences**. These preferences are discussed below.

General Preferences

Use the General tab of the User Preferences window to set the following user preferences.




Descriptions of general preferences are discussed below.

Preference	Description
Calendar starts on	Indicates what day of the week calendars start on in the windows. For example, if this is set to Wednesday, all of the windows that have calendars will start on Wednesday, rather than the standard Sunday.
Confirm deletes	Indicates whether the desktop displays a confirmation dialog box before a delete function is processed.
Confirm non-editable row paste	Displays a dialog box indicating that an attempt was made to paste a copied table row onto a non-editable row.
Confirm non-matching row paste	Displays a dialog box indicating that an attempt was made to paste a copied table row onto a table row that has a different number of table cells.
Confirm updates	Indicates whether the desktop displays a confirmation dialog box that requires a response before an update function is processed.
Currency format locale	Sets whether the default currency is obtained from the desktop configuration or user configuration settings.
Frame open indicator	Indicates whether a frame open indicator (which is the phrase “Opening window...”) is displayed in the desktop toolbar while a window is opening.
Language	Displays menu functions, dialog box text, messages, and field names in the selected language, if the selected language is defined in the properties file for a window. This also allows access to available localized online help (online help provided in a different language or dialect). Note: If the locale property is not set, the language is the default locale of the JRE (Java Runtime Environment) installed on the client’s workstation.

Preference	Description
Navigation tree	Sets whether the navigation tree is displayed upon desktop startup. If checked, the navigation tree is initially displayed. If not checked, it is initially hidden.
New window position	Sets the position of a window when opened as follows: • Bottom • Cascaded • Centered • Frame specified • Left • Right • Top • Top left
Pre-show frame	Indicates whether a blank window is shown while a window is initializing (being opened).
Print screen orientation	Sets the default print orientation to either portrait or landscape.
Status pane	Indicates whether the status pane is displayed.
Toolbar	Indicates whether the toolbar is displayed.

Error Notification Preferences


Use the Error Notification tab to set error notification preferences.



Preference	Description
Border Color	Sets the border color of fields that are in error.
Status	Indicates whether error text is displayed in the status pane of windows.
Tooltip	Indicates whether error messages are displayed in tooltip text. Tooltip text is text that appears in a pop-up window over a field or button.
Dialog	Indicates whether error messages are displayed in a dialog box.
Trap Focus	Makes error messages modal; that is, a user is required to resolve an error before focus can be changed to another window or tab.

Sound Preferences

Use the Sound tab to set the sound played during certain events (as selected in the Events field).




Preference	Description
Themes	Sets the sound group to apply to the selected event(s). Themes are defined in the sound.cfg configuration file located in the desktop.jar. The theme selected is stored in the configuration file of the logged on user.
Events	An event to be associated with a sound file.
Location	The location of the sound file, such as a .AU file (Java) and .WAV file (Windows), to associate with the selected event.

Logging (Debug and Trace) Preferences



Per PCI requirements, the ACI desktop will not log sensitive data to a client's computer unless configured to do so using the Logging tab of the User Preferences window.



Though the User Preferences window and the Logging tab are available from the File menu and can be altered before a user logs on to the ACI desktop, the changes are only activated after the user logs on to the desktop and the user is determined to have the permission to make the change. If the user does not have permission to set debugging and trace levels, the change is not made.

Debugging



When the Debugging enabled option is selected, debug messages are written to DeskTop.dbg debug file and the text “LOGGING SENSITIVE DATA” is displayed on the background of the application area.

Note: An ACI desktop user can only enable debugging if the view function of the **allowPostLogonDebug** task ID has been associated with the user’s profile.

Trace

Three options are provided on the Logging tab for enabling tracing:

- Trace message headers
- Trace full message content
- Trace connection and full message content



If one of the above options are selected, trace messages written to the DeskTop.log file and the text “LOGGING SENSITIVE DATA” is displayed on the background of the application area. By default and per settings in the LogScrubber.cfg file, the following information is scrubbed (i.e., information is masked with asterisk (*) characters):

- Passwords
- Client IP address
- Session information


Note: An ACI desktop user can only set the tracing level if the view function of the **allowPostLogonTrace** task ID has be associated with the a user’s profile.

Display Framework Version Information

Access **Help > About** to display desktop version information as shown below:




Click **Versions** to display detailed version information as shown below:



ACI Worldwide, Inc.

3: User Configuration


The ACI desktop provides access to an integrated user security environment in which each user must be defined in a user security database. This section consists of two parts: an overview of user security and steps about how to add a user. It also discusses the user profile which is central to establishing a user's access level to the ACI desktop. Each profile defines the integral components of user security, some of which, such as security and password groups, can be shared among multiple users. The hierarchy of a user profile is shown below.



Note: The user.security.version property in the APPLCNFG table is configured to use the USEC 1.2 mode (the BASE24-eps default). This mode enables filters to be tied directly to user profiles, thereby improving the performance of user security.

User Security Configuration Window Usage

User profiles are maintained from the ACI desktop using various user security windows. The hierarchy of a user profile from the previous page is shown below with the names and usage of the user security windows added.



All user security windows are accessed at **Configure > User Security**. A comprehensive hierarchical view of the relationships among tasks IDs, permissions, permission groups, and roles can be accessed at **View > User Permissions**.

User Profiles

Each user is assigned a **user profile** consisting of the following configuration components:

- User ID — A unique character string used to identify a user.
- General user information — Name and contact information about a user.
- Filters — Filter IDs directly assigned to the user.
- User status — In response to certain events, such as too many bad log-on attempts, a user's status can be changed (i.e. disabled) programmatically or by security administrative personnel.
- Role(s) — One or more sets of permission groups.
- Security group — A unique ID that defines a set of common user security access restrictions.
- Password group — A unique ID that defines a set of common user password restrictions.

Roles

A role defines the level of a user's access to the desktop. Each role identifies a job function, such as security administrator, system administrator, manager, and end user. Roles apply a set of permissions, tasks, and functions to users.

A role can contain one or more permission groups. A permission group can contain one or more permissions. Each permission is associated with a task (window application) and defines the functions (e.g., delete, save, send, and view) allowed for that task.

Permission Groups

A permission group is a collection of selected permissions that is assigned a unique identifier (the permission group ID) and a description of the purpose or use of the group.

Permissions

Permissions define specific access to a window. Each permission consists of a single task (task ID), the functions that can be performed within the task, a unique ID (the permission ID), and a description of the purpose or use of the permission.

Field Filters

Field filters restrict a user's access to field values by defining either a single value, multiple values, or a range of values allowed.

Note: The filter IDs available vary by application. However, a common example is to restrict a user to see only data for a single institution.

Task IDs

Each task consists of a unique identifier and a group of functions (e.g., delete, save, send, and view) and corresponds to a window on the ACI desktop. Available task IDs and functions for each task ID are provided on the Permissions tab of the User Security Role Configuration window and are used to create permission IDs. Task IDs can be used in multiple permissions.

Passwords and Password Groups



Beginning with version 08.2, a user's password is stored in the user security database in encrypted form using a Secure Hash Algorithm with Randomized Salt Hash (SHA-256) that is not reversible. This ensures that passwords cannot be extracted in clear form from the database. Only SHA-1 is supported for 07.4 and earlier versions. SHA-1 is also supported in version 08.2 for backward compatibility.

Note: When a new user is added, the option to force the new user to change his or her password on first use can be selected as described in step 4.4 later in this section.

Passwords comply with Payment Card Industry complex password requirements as follows:

- Passwords are case sensitive.
- Alphabetic, numeric, and special characters are permitted.
- Password history is maintained.
- Passwords cannot be shared.
- Characters cannot be repeated sequentially. For example, a password with the string “BB” appearing anywhere in the password is not valid.

- The password cannot be the same as the user ID. For example, a user with the ID “enduser02” cannot use “enduser02” as the password.
- A user’s password must meet the requirements (discussed below) defined in the password group assigned to the user.

Password Group Requirements

Password groups consist of password requirements that are imposed on all user passwords assigned the group. A password group consists of the following password requirements as configured using the Password Groups tab on the User Security Group Configuration window.



- The number of days prior to a password expiration on which the desktop displays a warning dialog prompting a user to change the password.
- The maximum number of days a user can use a password.
- The minimum password length (4 characters or more).
Note: Payment card cross-industry best practices specify a minimum length of 7 or more characters.
- The maximum password length.
- The minimum number of numeric characters required in each password.
- The minimum number of alphabetic characters required in each password.
- The maximum number of old passwords retained for each user (users cannot use retained old passwords).
- The maximum number of password changes allowed during a 24-hour period.

Security Groups

Each user must be assigned one and only one security group. However, since a security group can be assigned to multiple users, the security group simplifies the management of user security, assigns passwords by group, and assists in implementing distributed security administration, which is discussed later in this section.

Each user security group consists of the following common user security access restrictions that apply to all users assigned the security group:

- The time each day a user can log on to the desktop.

- The time each day a user must be logged off the desktop and, after which, can no longer log on to the desktop.
- The days of the week on which a user can log on to the desktop.
- The maximum number of invalid log-on attempts allowed for each user. If this value is exceeded, the user's status is disabled.

If the environment variable is false (the default), then the user must wait the required 300 seconds before they can once again attempt to log on with their user ID. If the environment variable is true, the system administrator must intervene and manually reset the user status to Active. Refer to the *ACI Java Infrastructure Java Server Reference Guide* for more information about the `isDisableUserOnFailedLogonAttempts` property.

- The number of seconds, if set, after which the number of invalid log-on attempts is reset to zero.
- The maximum number of active sessions allowed for a user.

When a user fails to log off correctly from the desktop or if a system outage occurs during a user's active session, the user security database still maintains a record of the active session. Therefore, if the maximum number of active sessions has been reached by a user attempting to log on to the desktop, the user is presented with an option to stop one or more of the active sessions.


- The number of seconds of user inactivity after which the user is automatically logged off the desktop (this is called a **session timeout**).
- The number of seconds of terminal inactivity after which the desktop is disabled and any logged on user is logged off (this is called a **UI timeout**).
- The number of days a user's ID can be inactive (not used) after which the user ID status is disabled.
- The password group ID defining password requirements applied to all users of the security group.

Distributed Security Administration (DSA)

Each installation is configured with a system administrator and security administrator. The system administrator has access to all applications of the desktop. The security administrator has access to the user security windows. Distributed security administration involves the security administrator configuring other, lower-level, administrators that are assigned a limited set of permissions.

Distributed security is implemented by the top-level security administrator by configuring applicable roles, assigning these roles as necessary to security groups, and assigning the security groups to other, lower-level, system administrators.

The top-level security administrator can set up tiers of other system administrators who are limited to a **security domain**, which is a set containing a security group, password group, roles, and permissions as defined by a security role ID. At this level, a role ID is used to restrict users within the domain to a defined set of permissions (including permission groups), tasks and filters. This methodology can be used to create system administrator groups and departments as shown in the illustration below.



For example, the system administrator assigned Role1 can create user profiles or groups of user profiles having roles that can contain only those permissions, permission groups, tasks, and filters defined for Role1. With distributed security administration, users, including administrators, cannot access the users and roles of other security domains.

Steps to Add a User

Note: Some steps have additional steps (i.e., steps 3.1 – 3.3 and 4.1 – 4.5). Whether these additional steps are required depends on the extent to which a complete user security system has been configured.

- ❑ Step 1.0: Configure a Password Group
- ❑ Step 2.0: Configure a Security Group
- ❑ Step 3.0: Configure a User Role
 - Step 3.1: Configure Field Filters
 - Step 3.2: Configure Permissions
 - Step 3.3: Configure Permission Groups
- ❑ Step 4.0: Configure the User's Profile
 - Step 4.1: Set the User's Status
 - Step 4.2: Assign a Security Group
 - Step 4.3: Enter Information about the User
 - Step 4.4: Set the User's Password
 - Step 4.5: Assign Roles
 - Step 4.6: Assign Filters

Usage Note: To ensure that changes are implemented in the user security database, click Save () each time a step has been completed.

Tip: If a new user is to be based on an existing user profile, that is, the password group, security group, and roles are already configured, go directly to step 4.0 and read the Tip provided in the step.

Step 1.0: Configure a Password Group

Use the Password Group tab on the User Security Group Configuration window to configure a password group.

The screenshot shows the 'User Security Group Configuration' window with the 'Password Group' tab selected. The 'Password Gr...' dropdown is set to 'SysAdminPswdGrp'. The 'Description' field contains 'Default password params for system administrators.' Below this, there are two columns of settings, each with a label and a numeric input field with up/down arrows:

Minimum Length	6	Lifetime Days	0
Maximum Length	16	Old Password Cache	6
Required Numeric Characters	1	Expire Pre-Warn Days	0
Required Alpha Characters	2	Changes Per Day	6

In the example above, the password group **SysAdminPswdGrp** is shown. This group is described as the default password group for system administrators. The password requirements are set in the fields provided on the tab.

Password groups are assigned to users (their profiles) through security groups. Therefore, a password group must be assigned to a security group using the Security Group tab of the User Security Group Configuration window. The security group is then used in user profiles.

Step 2.0: Configure a Security Group

Topics in this step to consider are listed below and are discussed on the following pages.

- ❑ UI and Session Timeout Considerations
- ❑ System Administration Role Filter (Owner ID)

Use the Security Group tab on the User Security Group Configuration window to configure a security group.

The screenshot shows the 'User Security Group Configuration' window with the 'Security Group' tab selected. The configuration is as follows:

- Security Group:** SysAdminSecurityGrp
- Description:** Default security params for system administrators..
- Password Group:** SysAdminPswdGrp
- SysAdmin Profile:** (Empty)
- Allowed Time and Days:**
 - Begin:** 08:00 am
 - End:** 05:00 pm
 - Days:** Sun, Mon, Tue, Wed, Thu, Fri, Sat (all checked)
- Bad Logins Allowed:** 4
- Reset Bad Logins:** 300 seconds
- Sessions Allowed:** 5
- UI Timeout:** 1200 seconds
- Inactive Days Allowed:** 60
- Session Timeout:** 0 seconds

In the example above, the configuration for the **SysAdminSecurityGrp** security group is shown. This group defines standard authentication requirements for system administration user. The password group **SysAdminPswdGrp** is assigned to this security group. As a result, the password requirements defined by **SysAdminPswdGrp** apply to all users of this security group.

UI and Session Timeout Considerations

A security group defines both UI and session timeouts. These timeouts are defined in units of seconds using the Security Group tab of the User Security Group Configuration window.

A UI timeout occurs after a duration of desktop inactivity defined in the UI Timeout field. When a UI timeout event occurs, the user no longer has access to the desktop and any open windows. However, the user's session and the open windows are not closed, and the desktop displays the Verify Password dialog in which the user must provide a valid password to restore access to the desktop and any open windows. If the user does not provide a valid password in three attempts, they will be logged out automatically. Otherwise, the user can log out at this time without reentering a valid password. Keep in mind the Verify Password dialog differs from the Bad Logins Allowed field of the User Security Group Configuration window. The Bad Logins Allowed field is also based on the number of invalid log-on attempts allowed, but this field accepts a greater range of values and can be set from 1-100.

UI timeouts only occur if the security group to which the user belongs has a configured UI timeout limit greater than zero. Entering a zero ('0') in the UI Timeout field implies no limit of desktop inactivity.

A session timeout occurs after a duration of desktop inactivity defined in the Session Timeout field. When a session timeout event occurs, the user is automatically logged off the desktop and the user must log on (open the Log In window and provide a valid user name and password combination) to obtain access to the desktop. Any windows open upon a session timeout are closed.

If the user's session expires while the Verify Password dialog is displayed and the user has not provided input, the user is still logged out and the user is no longer able to verify the password. All windows are closed, but the desktop remains open.

Session timeouts only occur if the security group to which the user belongs has a configured session timeout limit greater than zero. Entering a zero ('0') in the Session Timeout field implies no limit of desktop inactivity.

To use UI timeouts in an effective manner, the session timeout must be greater than the UI timeout. This is because if the session timeout is less than the UI timeout, users in the security group will be logged off the desktop (upon a session timeout event) prior to a UI timeout event.

A UI timeout event should occur first so that a user can be alerted and take necessary action to save work. Having a session timeout less than the UI timeout negates the purpose of the UI timeout.


System Administration Role Filter (Owner ID)

An existing role ID can be assigned to a security group using the SysAdmin Profile field. Since a role defines a set of permissions (permission groups), tasks IDs and field filters, the role ID at this level limits access to permissions and permission groups that can be configured for users by administrators assigned the security group. To assign a role ID as a filter for a security group, select the role ID in the SysAdmin Profile field.

If a system administration role profile is selected for a security group, only those permission groups, permissions, and tasks defined for the role are accessible to users assigned the security group.

Step 3.0: Configure a User Role

To configure a user role, use the Roles tab on the User Security Role Configuration window.



If the available permission groups meet existing needs, enter or select the role ID in the Role field, add or modify the description of the purpose of the role, and select the applicable permissions groups (permission groups can be selected and deselected using the check boxes for each group), then go to Step 4.0: Configure the User's Profile. **Note:** Permissions not defined within your security domain are not available.

If one or more permission groups need to be configured, the following steps might also need to be performed.

- ❑ Step 3.1: Configure Field Filters
- ❑ Step 3.2: Configure Permissions
- ❑ Step 3.3: Configure Permission Groups

Step 3.1: Configure Field Filters

Note: The functionality of field filtering is the same among applications, but the implementation can vary.

Field filters are configured using the Filters tab on the User Security Role Configuration window, and are applied to a user's profile through permissions.

The screenshot shows the 'User Security Role Configuration' window with the 'Filters' tab selected. The window has a blue title bar and standard Windows window controls. Below the title bar is a toolbar with icons for save, print, refresh, and delete. The main area contains the following fields and controls:

- Filter ID:** A dropdown menu.
- Filter Type:** A dropdown menu.
- Description:** A text input field.
- Filter Value Settings:** A section containing:
 - A text input field for adding values.
 - An 'Add' button.
 - Available Values:** A large empty box on the left.
 - Assigned Values:** A large empty box on the right.
 - Four arrow buttons (right, right, left, left) for moving values between the two boxes.

Note: The Add button and filter value text box is visible only when debugging is enabled and is intended for ACI use only.

Field filters consist of the following elements:

- ❑ Unique identification (the Filter ID field)
- ❑ The type of filter (the Filter Type field)

- ❑ A description of the purpose and use of the filter
- ❑ Multiple field values

The values available in the Available Values field are those that have been configured using the applicable configuration window. For example, for the InstitutionID filter type, the values shown in the Filter Value Settings area are those institution IDs that have been configured using the Institution Configuration window.

Tip: Use the asterisk (*) to select all current and future field values.

To add or remove field values, use the following buttons provided on the tab to perform the desired task:

Button	Task
	Move the selected field value(s) from the Available Values field to the Assigned Values field.
	Add all available field values from the Available Values field to the Assigned Values field.
	Remove the selected field(s) value from Assigned Values field back to the Available Values field.
	Remove all selected field(s) values from Assigned Values field back to the Available Values field.

To select a value, click on the value. Selected values have a modified background color. To select multiple values, press down the **Ctrl** key while selecting values.

To add a value not available in the Available Values field, enter the value in the text entry field below the Filter Value Settings area and click the Add button.

Step 3.2: Configure Permissions

Use the Permissions tab on the User Security Role Configuration window to create permissions and permission group IDs.

The screenshot shows the 'User Security Role Configuration' window with the 'Permissions' tab selected. The window has a title bar with standard OS controls. Below the title bar is a toolbar with icons for save, delete, and other actions. The main area contains four tabs: 'Roles', 'Permission Groups', 'Permissions' (selected), and 'Filters'. The 'Permissions' tab has three input fields: 'Permission ID' with a dropdown menu showing 'FullUSCtlPermission', 'Task ID' with a dropdown menu showing 'UserSecurityControl', and a 'Description' text box containing 'Full User Security Control permission set.'. Below these fields is a tree view under the 'Functions' folder, which is expanded. The tree view shows four sub-items: 'ExpireAll', 'ExpireSelected', 'LogoutAll', and 'LogoutSelected', each with a checked checkbox. The status bar at the bottom left shows '3 - Permission read.' and a small upward arrow icon on the right.

Permission IDs

A new permission ID can be created (entered) or an existing permission ID can be selected. Permissions are available on the Permissions Group tab for selection when configuring a permission group.

The description is to state the purpose of the permission and any special information.

Tasks IDs

Each task ID corresponds to an ACI desktop window.

Note: Task IDs cannot be created using the ACI desktop.

Functions

The functions that a user can perform on a window (task) are defined for each permission on the Permissions tab. A function is selected by entering a check mark in the functions check box. Functions include, but are not limited to, Delete, Save, Send, and View. The available functions vary by task ID.


Field Filters

If a task ID refers to a window that contains a field or fields that are filterable, the Permissions tab will list the field ID(s) and provide a selectable list of filter IDs that can be selected and applied to the permission.

Note: The actual filterable fields varies by application. See the boxed note in step 3.1 for more information.

Step 3.3: Configure Permission Groups

To configure a new or existing permission group, use the Permission Groups tab on the User Security Role Configuration window. This tab provides a Permission Group field in which a new permission group ID can be entered or an existing permission group can be selected.



Available permissions, as defined per your security domain, are provided on the tab. Permissions are added or removed from a permission group by selecting (entering a check mark) or deselecting (removing a check mark) in the appropriate checkbox.

Permission Information

A description of each permission along with the Task ID assigned to the permission and the allowed functions can be displayed in the Permission Description section of the Permissions Groups tab. To display this information, right click on the desired permission and select Get Info on the pop-up menu.

Step 4.0: Configure the User's Profile

To configure a new user (user profile), display the General tab of the User Security Profile Configuration window, enter the user's unique ID in the User ID field and perform the following steps:

- ❑ Step 4.1: Set the user's status
- ❑ Step 4.2: Assign a security group
- ❑ Step 4.3: Enter information about the user
- ❑ Step 4.4: Set the user's password
- ❑ Step 4.5: Assign roles to the user
- ❑ Step 4.6: Assign filters

Note: The User Security Profile Configuration window will not be available when you are using a third-party authenticator other than the one provided with this application. Contact your security administrator for details.

Tip: To add a new user whose profile is based on an existing user profile, display the user profile that is to be used as a template and replace the text in the User ID field with the new user ID. In addition, when the Save button is clicked for a new user, the desktop displays the New User's Password window, which is described in Step 4.4.

Step 4.1: Set the User's Status

User status options:

Active	= Open and active.
Closed/Admin	= Closed without incident.
Closed/Inactive	= Closed due to inactivity.
Disabled/Admin	= Disabled, for security reasons, by authorized personnel.
Disabled/System	= Disabled automatically for security reasons (e.g., maximum number of log-on attempts has been exceeded).
Note: This status is set programmatically.	
Temporary	= User can access the desktop for a predefined amount of time.

Step 4.2: Assign a Security Group

Security groups are provided in the selectable field next to the Security Group link. If a desired security group is not available, click on the link to access the User Security Group Configuration window to review existing security groups or configure a new security group. Only those security groups defined for your security domain are available.

Step 4.3: Enter Information about the User

Information about the user includes:

- ❑ Complete name information
- ❑ Contact information, such as phones, Fax and email address
- ❑ Employment information, such as department, manager and location

Step 4.4: Set the User's Password

To set a new user's password, click Save, after which the desktop displays the New User's Password window.

Note: The Password tab of the User Security Profile Configuration window is used for management of existing users. See the User Management section for more information.

For users assigned a status other than Temporary, the desktop displays the version of the New User's Password window shown below. Indicate whether the user must change the assigned password during the next log-on attempt (or upon the first log-on attempt for a new user), and the start date on which the user can log on to the desktop.



The dialog box titled "New User's Password" has a blue title bar with a red triangle icon and a close button. It contains two password input fields: "New Password" and "Verify Password", both filled with asterisks. Below these is a checkbox labeled "Require password change" which is checked. Underneath is a date selection field labeled "New User Start" showing "Thursday, January 11, 2007". At the bottom are "Ok" and "Cancel" buttons.


When a new temporary user (i.e., user status being set to temporary) is created, the desktop displays the New User's Password window, shown below, for indicating whether the user must change the password on logging on, and for setting the start and expiration dates for which the user is active.



The dialog box titled "New User's Password" has a blue title bar with a red triangle icon and a close button. It contains two empty password input fields: "New Password" and "Verify Password". Below these is an unchecked checkbox labeled "Require password change". Underneath is a date selection field labeled "New User Start" showing "Thursday, January 11, 2007". Below that is another date selection field labeled "New User Expire" showing "Friday, January 11, 2008". At the bottom are "Ok" and "Cancel" buttons.

Step 4.5: Assign Roles

Use the Roles tab on the User Security Profile window to assign (and remove) the roles defined for a user.



This tab displays all the user roles available within your security domain on the ACI desktop. Roles not defined within your security domain are not displayed. User roles assigned to a user are shown in the User Roles field. Available user roles not assigned to a user are shown in the All Roles field. To add or remove user roles from a user profile, select the role or roles and use the buttons provided on the tab to perform the desired task. The buttons are:

Button	Task
	Add the selected role(s) to the user profile (move from the All Roles field to the User Roles field).
	Add all available roles to the user profile (move from the All Roles field to the User Roles field).

Button	Task
	Remove the selected role(s) from the user profile (move from the User Roles field to the All Roles field).
	Remove all assigned roles from the user profile (move from the User Roles field to the All Roles field).


To select a role, click on the role. Selected roles have a modified background color. To select multiple roles, press down the **Ctrl** key while selecting roles.

If a particular role is not available or an existing role needs to be changed, click on the Configure Roles link to access the User Security Role Configuration window to configure a new or existing role.

Note: A user cannot change the role configuration for the profile (User ID) that was used to log on. In such situations, when the Roles tab is accessed for that User ID, the All Roles field and User Roles fields are inactive.

Step 4.6: Assign Filters

Use the Filters tab on the User Security Profile window to assign (and remove) the filters defined for a user.



To add or remove filters from a user profile, select the filter or filters and use the buttons provided on the tab to perform the desired task. The buttons are:

Button	Task
	Add the selected filter(s) to the user profile (move from the All Filters (Field ID) Filter ID field to the User Filters (FieldID) Filter ID field).


Button	Task
	Add all available filters to the user profile (move from the All Filters (Field ID) Filter ID field to the User Filters (FieldID) Filter ID field).
	Remove the selected filter(s) from the user profile (move from the User Filters (FieldID) Filter ID field to the All Filters (Field ID) Filter ID field).
	Remove all assigned filters from the user profile (move from the User Filters (FieldID) Filter ID field to the All Filters (Field ID) Filter ID field).

ACI Worldwide, Inc.

4: User Management

Security administrators can set the status, display and terminate active sessions, and expire passwords by password group of users within the administrator's security domain. This activity is performed from the user security windows as described in this section.

The illustration below shows the user profile and includes the name of the applicable windows used to manage user profiles.



The User Security Profile Configuration window is used for configuring a user profile; however, it can be used to view a user's active sessions, to change an existing user's status and to manage a user's password.

The User Security Control Management window is used to view and manage the active sessions for all users. The window can also be used to expire passwords by password group.

To assist system administrators and other authorized users, two additional windows are available and are discussed in this section:

- User Status window
- User Permissions window

Set the Status of a User

A user's status can be changed automatically if security and password group requirements have been violated. A user's status can also be changed by authorized users.

Use the General tab on the User Security Profile Configuration window to view and set a user's status.

The screenshot shows the 'User Security Profile Configuration' window with the 'General' tab selected. The 'User ID' is 'systemUser01'. The 'User Status' dropdown is open, showing options: Active, Closed/Admin, Closed/Inactive, Disabled/Admin, Disabled/System, and Temporary. The 'Security Group' is 'Level1SecurityGroup'. Other fields include First Name, Middle Name, Last Name, Department, Location, Manager, Email, Work Phone, Mobile Phone, Fax, Create Time (1/11/07 1:00 PM), Last Login (6/12/07 12:43 PM), Last Failed Login (4/18/07 7:58 AM), and Bad Login Tries (1).

Authorized users can assign the following status codes to a user:

- Active = Open and active.
 - Closed/Admin = Closed without incident.
 - Closed/Inactive = Closed due to inactivity.
 - Disabled/Admin = Disabled, for security reasons, by authorized personnel.
 - Disabled/System = Disabled automatically for security reasons (e.g., maximum number of log-on attempts has been exceeded).
- Note:** This status is set programmatically.
- Temporary = User can access the desktop for a predefined amount of time.

Active User Session Management

When a user has logged on to the desktop by providing a valid user ID and password, an active session is created for the user. An active session contains the following information:

- ❑ The user's ID.
- ❑ The unique session number assigned to the user's session.
- ❑ The workstation ID, such as a network ID or URL, from which the user has logged on to the desktop.
- ❑ The date and time the user began the session.
- ❑ The date and time the current session expires.


Information about active user sessions is available on two separate Active Sessions tabs. One tab is provided on the User Security Profile Configuration window and displays the active sessions for a selected user. The other Active Sessions tab is located on the User Security Control Management window and displays active user sessions for all users within a security administrator's security domain (security group to which the administrator has access).

Active User Session for a Selected User:

The screenshot shows a window titled "User Security Profile Configuration" with a blue header bar. Below the header is a toolbar with icons for save, print, refresh, and delete. A "User ID" dropdown menu is set to "systemUser01". Below this are five tabs: "General", "Roles", "Filters", "Password", and "Active Sessions". The "Active Sessions" tab is selected, displaying a table with two columns: "Workstation ID" and "Logged in time". The table contains one row with the values "Network/URL" and "2007-6-12 12:43:11.39". Below the table is a "Password" label and a "Logout Selected" button. At the bottom of the tab area, there is a link labeled "All Active Sessions" in blue text.

Workstation ID	Logged in time
Network/URL	2007-6-12 12:43:11.39

Active User Sessions for All Users:



Note: The active sessions of the application can change at any time; therefore, to update the list of active sessions, click Refresh ().

Terminate Active User Sessions (Log off a User)

One or more active user sessions can be terminated (i.e., logged off) from either one of the two windows that are used to display active user sessions — the User Security Profile Configuration window and the User Security Control Management window. To log off one or more user sessions, display and select the user session(s) and click Logout Selected.

Password Management

Authorized users can view a user's password change history, add or change a user's password, and expire the user's current password by accessing the Password tab on the User Security Profile window and selecting the user's ID.

To change a user's password, display the Password tab on the User Security Profile Configuration window and select the user ID. Enter the new password in both the New Password and Verify Password text boxes and click Save (). If the change is successful, a confirmation message appears in the status pane of the window. Otherwise, an appropriate error message is displayed.

To expire a user's password, display the Password tab on the User Security Profile Configuration window, select the user ID, and click Expire Password. If a user's password has been expired but a new password has not been defined, the user is prompted to create a new password on the next log-on attempt.

Authorized users can access a table that shows the password groups that have been assigned to security groups, and can expire all user passwords of users assigned to a password group.

Use the Password Maintenance tab on the User Security Control Management window to view password group usage and expire password groups.


A summary of password changes for all users can be displayed on the User Status window (**View > User Status**) as discussed on the following page.

User Status Window

The User Status window (**View > User Status**) lists summary information for users.

Note: The User Status window will not be available when you are using a third-party authenticator other than the one provided with this application. Contact your security administrator for details.

Example User Status window:



When this window is accessed, a list of user IDs with user role and login information is displayed.

This window allows quick identification of users with specific status exceptions and stale (i.e., idle) accounts. To identify such users, if the **More** button is active, click the button to retrieve additional users. The button remains active until all user accounts have been retrieved. The users can be sorted by login information by clicking the **Last Logged In** column. Other columns can be used to sort the users by different criteria. A secondary sort can be obtained by holding down the CTRL key and selecting another column header.

To display a detail report for a user, select the row of the user and click **Detail**. The summary information displayed in the text area can be printed using the Print function available on the File menu.

User Status Detail Properties



In support of PCI compliance, a recurring report of the information shown on this window can be configured using the following properties documented in the *ACI Java Infrastructure Java Server Reference Guide*:

report.userdetail.loc


report.userdetail.name

report.userdetail.timeperiod.hours

report.userdetail.starttime

User Status Detail Example

Below is an example of the detail information available on the User Status window.




User Permissions Window

The User Permissions window (**View > User Permissions**) provides hierarchical information for users, roles, permission groups, permissions, tasks, and field filters.

Note: The User Permissions window will not be available when you are using a third-party authenticator other than the one provided with this application. Contact your security administrator for details.

Example User Permission window:



When this window is accessed, hierarchical user security information lists are provided and accessible on the various tabs of the window. For example, select the Tasks tab to identify all task IDs and the role, permissions, permission groups, and users assigned a given task.

Note: Distributed Security Administration filters do not apply to the information displayed on the User Permissions window. Therefore, user security access to the window should only be provided to System-level security administrators.

User Status Detail Properties



In support of PCI compliance, a recurring report of the information shown on this window can be configured using the following properties documented in the *ACI Java Infrastructure Java Server Reference Guide*:

report.userpermissions.loc

report.userpermissions.name

report.userpermissions.timeperiod.hours

report.userpermissions.starttime

5: User Auditing

User audit is the logging of user activity to a data source for the purpose of reporting and monitoring the user activity.

Whenever a user of the desktop initiates and completes an activity (e.g., log in, log out, change password, delete, or save) from a window, a message that contains information about the user activity is written to the User Audit Log data source.

The audit message sent to the log data source can be one of the following:

- Header information only about the changes to affected records
- Header information and detail information about the before and after data images of affected records

The application server writes audit messages directly to the USRAULOG data source or to the Audit_Store_and_Forward data source depending on the middle ware capabilities of the hardware platform.

For information about enabling user auditing and setting the audit level for a desktop window, refer to the *ACI Java Infrastructure Java Server Reference Guide* for information about audit properties, such as:

- db.audited
- db.audited.*table-name*, where *table-name* is the physical table name

Audit Report XML Format

The information stored in the extracted audit reports is in XML format. The following example is an XML-formatted message containing user activity information.


```
<?xml version="1.0" encoding="UTF-8" ?>
<AuditReport>
  <AuditDetails row="0">
    <Audit_LoggingRq>
      <Timestamp>TimeStamp Info</Timestamp>
      <ContextDescr>InsertRq</ContextDescr>
      <Ticket>
        <UserID>User Profile ID</UserID>
        <SessionNumber>1</SessionNumber>
        <TerminalID>OMAUUSER/ip_addr</TerminalID>
      </Ticket>
      <ActivityGroup>
        <ActivityType>Table Function</ActivityType>
        <TableGroup>
          <TableName>Table</TableName>
          <KeyGroup>
            <Column>
              <ColumnName>Table Element</ColumnName>
              <BeforeValue />
              <AfterValue>New Value</AfterValue>
            </Column>
            <Key>
              <KeyColumn>
                <ColumnName>Key</ColumnName>
                <AfterValue>New Value</AfterValue>
              </KeyColumn>
            </Key>
          </KeyGroup>
        </TableGroup>
      </ActivityGroup>
    </Audit_LoggingRq>
  </AuditDetails>
</AuditReport>
```

The root element of the XML message is `<AuditReport>` that includes one or more `<AuditDetails></AuditDetails>` sections. `<AuditDetails>` contains important information: a time stamp (`<Timestamp>`), Context information (`<ContextDescr>`), ticket information (`<Ticket>`), and activity information (`<ActivityGroup>`). Information related to the user and the user's session is included in the ticket. Information about the activity performed and the data source (table) affected is included in the activity group.

Note: Use an XML reporting tool such as XML Spy, MS-Access 2002, or Crystal Reports to evaluate and format the XML information as well as to generate reports.

User Audit Activity Report Process

Activity reports for selected users can be initiated by accessing User Audit on the View menu. User activity is extracted from the USRAULOG data source for a specified user ID between a start date and time and an end date and time. This information can be viewed on the ACI desktop or sent to a designated file.



The reports provide the following information:


- Date and time of action.
- User ID performing the action.
- Terminal location from which action was performed.
- Type of action performed.
- File and field name affected by the action, if applicable.
- Before and after image of data modification action, if full auditing is set.

The location where the report file is saved is specified by the **report.userauditlog.loc** environment attribute, which defines the directory location. See the previous page for an example report file.

Click **Next** to proceed.

Selection

Below is the Selection step of the User Audit function.



1. Select whether to have the report sent to the screen or written to a file (the file name is specified in the next step window).
2. Click **Next**.

Search Filter

Below is the Search Filter step of the User Audit function.


The screenshot shows a software window titled "User Audit" with a standard Windows-style title bar. Inside the window, on the left, is a vertical navigation pane with four items: "Welcome", "Selection", "Search Filter" (which is highlighted with a blue arrow icon), and "Summary". The main area of the window is titled "Search Filter" and contains the following elements:

- A prompt: "Please enter the desired audit report filter:"
- Two date/time selection fields:
 - "Start date/time:" with a date field showing "October 24, 2007" and a time field showing "12:00:00 am CDT".
 - "End date/time:" with a date field showing "October 24, 2007" and a time field showing "02:25:16 pm CDT".
- A "User ID:" text field containing an asterisk (*), with a note below it: "(Specify '*' to select all users.)"
- An "Extract file name:" text field containing "AudExt_071024_142836.xml", with a note below it: "(The extracted report will be stored on the server.)"
- At the bottom, four buttons: "Back" (with a left arrow), "Next" (with a right arrow and a dotted border), "Cancel" (with a red X), and "Help" (with a question mark icon).

1. Select the start and end date/time fields.
2. Enter a specific user ID or an asterisk (*) to report on all users.
3. Select the file name of the extract XML report file.
4. Click **Next**.

Summary

Below is the Summary of the User Audit function.



1. Review the summary information provided.
2. If the summary information is incorrect, click **Back** to step back through the process to make changes.
3. If the summary information is correct, click **Finish** to begin building the report, whether for screen or written to file.

Example Report on the ACI Desktop

When a report is completed, the results are shown in the Audit Report Viewer for which an example is shown on the following page.

If the **More** button is active, click the button to retrieve additional users. Note that the **More** button remains active until all user accounts have been retrieved. The user information displayed in the table can be sorted using the column headers. Additional column headers can be selected by pressing the **Ctrl** key.

To display detail information for a user, select a summary role and click the **Detail** button. Double clicking in a summary row also initiates the display of detail information for a user.

Audit Report Viewer

Audit Summary

#	Local Date/Time	User ID	Workstation	Activity Type	Activity Detail	Result	Service
1	Sep 21, 2007 1...	systemuser01	oma2ui1	Logoff	USEC		
2	Sep 21, 2007 2...	systemuser	SystemProcess	View	SecurityReport...		USERSECURIT...
3	Sep 21, 2007 ...	systemuser03	oma2ui1	Logon	LoginComma...	OK	USERSECURI...
4	Sep 21, 2007 2...	SysAdmin	oma2ui1	View	ISOMsgPrflListRq		
5	Sep 21, 2007 2...	SecAdmin	oma2ui1	View	InterfaceListR...		
6	Sep 21, 2007 2...	systemuser07	oma2ui1	View	InstConfigGetI...		

Detail More

Audit Detail

Find:

AuditReport :

- AuditDetails :
 - row : 3
 - Audit_JoggingRq :
 - Timestamp : 2007-09-21T07:30:11.734Z
 - ContextDescr : LoginCommand
 - Ticket :
 - UserID : systemuser03
 - SessionNumber : 48
 - TerminalID : oma2ui1/172.17.1.177
 - ErrorData : OK
 - ActivityGroup :
 - ActivityType : Logon

Automated User Auditing

User audit extracts to file can be performed automatically by specifying the `com.aciworldwide.common.timertask.UserAuditReport` classname for the configuration properties file `timertask.function.n.classname` configuration parameter. The Java Server Framework application specified as the `timertask.manager.processid` invokes the classname at application initialization.

The following properties are used to configure automated user audit reporting:

Property	Description
<code>report.userauditlog.loc</code>	The file path for the user audit report.
<code>report.userauditlog.name</code>	The name of the user audit report.
<code>report.userauditlog.offset.days</code>	The number of days prior to the current day to use for obtaining user activity for the report.
<code>report.userauditlog.report.starttime</code>	The time at which the report is generated.

For example, if today is Wednesday and the time is 9:00 AM, the offset is one day, and the report start time is 2:00 AM, then the most recent audit information available is that for 2:00 AM Tuesday to 2:00 AM Wednesday.

Refer to the *ACI Java Infrastructure Java Server Reference Guide* for more information about the above properties.

ACI Worldwide, Inc.


6: Version Checker

The desktop provides a way for clients to keep the desktop configuration current. This configuration support is provided by the Version Checker, which is a utility that manages the versions of JavaTM Archive (JAR) files of desktop components that are distributed to ACI desktop clients. The Version Checker automatically runs during startup of the desktop at which time it compares the current version of the client files to new versions, which reside in a predetermined location (i.e., repository). The location of the Version Checker repository is defined during installation. New files that are to be distributed to clients are placed in this location.

The Version Checker automatically runs when a desktop is started per commands located in the **RunDesktop.bat** file. Desktop shortcuts specified during installation point to this batch file. Whether a user is prompted to accept any new files or the files are automatically downloaded is dependent upon configuration settings as discussed in this section.

The files on the repository for which the version differs from that of the client are displayed in the Version Checker Client window. This window provides a list of the files along with the version number of each file on the repository and the version number of the file on the client. If automatic file updating is enabled (discussed later in this section), then this window is not displayed.

To download new files from the repository, select the applicable files and click Update. This update process can be skipped or canceled.



The **Select All** option can be used to select all listed files on the Version Checker Client window. Individual files can be selected by deselecting the Select All option and then clicking in the row for each desired file to download. Only selected files are downloaded.

If the **Close When Done** option is selected, the Version Checker Client window will automatically close after completion of the download of all selected files.

By selecting **Mirror Repository** on the Version Checker Client window, verification is initiated to ensure that no jars reside on the client that are not also on the server repository. That is, any files that exist on the client that do not exist on the current version of the server repository are deleted from the client.

The Version Checker can be configured to download updated and new files automatically.

Including the parameter “-Q” in the Version Checker command line located in the **RunDesktop.bat** file enables automatic file updating.

For example:

```
call "C:\ACI\VersionChecker\verChk" -Q
```

7: Online Help

The ACI desktop provides online help for windows (screens) and window components (e.g., fields). This help is displayed in a Java-based HTML browser, called the **Helpset Viewer**:



The components of the Helpset Viewer are:

- 1** — The **Title Bar** in which the name of the helpset is displayed.
- 2** — The **Toolbar** that contains various menu and button functions.
- 3** — The **Navigation Pane** in which are located Contents and Index tabs useful for navigating to desired help content, and a Search tab for searching content.
- 4** — The **Content Pane** in which help content is displayed.
- 5** — The **Contents** tab that provides structured access to window-level help files.
- 6** — The **Index** tab that provides alphabetical access to all help topics.
- 7** — The **Search** tab for searching help content.

Access to JavaHelp from the ACI Desktop

JavaHelp content can be accessed with or without context. These two methods are explained below.

With Context

Accessing online help with context displays the Helpset Viewer with content displayed in the Content Pane that is specific to a window or window component. To display help with context from the ACI desktop, select **Help > Context Help** or click  on the toolbar. Either of these actions display the Help Pointer  to use for clicking in a general area of a window for window-level help or on a window field for field-level help.

If a window is not open, help with context is not available because an active window in the Application Area of the ACI desktop is necessary to provide context. When context help is not available, the Context Help function and the button are inactive.

Note that the traditional way to access field-level help by placing the cursor in the field and pressing the **F1** key can also be used.

Without Context

To display online help without context from the ACI desktop, select **Help > Help Topics** from the Menu Bar or click  on the Toolbar. A window does not need to be open to access online help without context. When online help is accessed using this method, the Helpset Viewer is displayed with the default home page provided in the content pane and the default TOC view in the navigation pane.

If the Help Topics function and the button are not enabled, then the ACI desktop does not have access to online help. Check with a System Administrator to obtain ACI online help.

JavaHelp Files

The following files together are referred to as a **JavaHelp helpset**:

- The **helpset file** (ACI_Help.hs), which is identified by the .hs file extension, defines the name of the helpset displayed in the Title Bar, the JavaHelp components used, the name of the map file, the names of the table of contents and index files, and the ID of the default content file to display in the Content Pane when help is accessed without context. The helpset file is the top-level file in the JavaHelp helpset.

Be careful not to confuse the term “JavaHelp helpset” with the helpset (.hs) file. *JavaHelp helpset* refers to a collection of JavaHelp files as discussed on this page. Whereas the helpset (.hs) file is a single file (see following page).

- The **map file** is an XML file identified by the .jhm file extension that corresponds identifiers to HTML content files. This file is necessary to provide context-sensitive help for windows and window components as discussed later in this section.
- The **table of contents file** that defines the structure and links of the text entries of the Contents tab.
- The **index file** that defines the structure and links of the text entries of the Index tab located in the Navigation Pane of the Helpset Viewer.
- **HTML files** in which help content resides.
- **Cascading Style Sheets (CSS)** define the style rules applied to content.
- The **images** displayed within HTML content files. Images used in content are in Graphical Interchange Format (GIF) and Joint Photographic Experts Group (JPEG or JPG) formats.

JavaHelp Packages

ACI online help is packaged and distributed in the following Java™ Archive (JARs) files:

- **ACI_Help_apf.jar** — For APF-Admin ACI desktop windows
- **ACI_Help_es.jar** — For BASE24-eps
- **ACI_Help_tss.jar** — For Transaction Security Services (TSS)
- **ACI_Help_pm.jar** — For ACI Payments Manager (PM)

Helpset File

The helpset file defines the Java components used, home page, map file, TOC, index, and views. Below is an example helpset file. Comments between “<!--” and “-->” have been added to provide additional information.

```
<?xml version='1.0' encoding='ISO-8859-1' ?>
<!DOCTYPE helpset
  PUBLIC "-//Sun Microsystems Inc.//DTD JavaHelp HelpSet Version 2.0//EN"
  "http://java.sun.com/products/javahelp/helpset_2_0.dtd">
<helpset version="2.0">

  <!-- The title displayed in the Title Bar -->
  <title>ACI Online Help</title>

  <!-- Map information -->
  <maps>
    <homeID>splash</homeID> <!-- The map ID of the splash page -->
    <mapref location="map.jhm" /> <!-- The map file -->
  </maps>

  <!-- Each view represents a tab on the Helpset viewer -->
  <!-- This helpset has 3 views. -->
  <!-- Immediately below is the TOC view -->
  <view>
    <name>TOC</name>
    <label>Contents</label> <!-- The popup (flyover) text of the tab -->
    <type>javax.help.TOCView</type> <!-- The JavaHelp TOC component -->
    <data>toc.xml</data> <!-- The name of the table of contents file -->
  </view>

  <!-- This is the index view -->
  <view>
    <name>Index</name>
    <label>Index</label>
    <type>javax.help.IndexView</type> <!--
    <data>ix.xml</data> <!-- The name of the index file -->
  </view>

  <!-- This is the search view -->
  <view>
    <name>Search</name>
    <label>Search</label>
    <type>javax.help.SearchView</type>
    <data engine="com.sun.java.help.search.DefaultSearchEngine">
      JavaHelpSearch
    </data> <!-- The search engine defined by the engine attribute -->
    <!-- And, the search database. In this case, the search -->
    <!-- database is located in a folder named JavaHelpSearch -->
  </view>


</helpset>
```

How Context is Implemented in JavaHelp

Help context is implemented in JavaHelp by the use of unique identifiers. Each identifier (referred to as a map ID or help ID) appears as necessary in the following files:

- The property (.properties) file for a window (desktop application)
Note: Most application windows have their own properties file. Also, some properties common among all windows are located in common property files that are shared among the window properties files.
- The JavaHelp map file, map.jhm (pmdesktop.jhm for ACI Payments Manager)
- The table of contents file, toc.xml (ACI_Help_pmtoc.xml for ACI Payments Manager)
- The index file, ix.xml (all applications)

The use and relationship of the identifiers in the above files is shown in the following illustration.




Search the Helpset for a Text String

The Search tab provides a text entry field (Find) to locate up to 100 occurrences of a text string within a helpset.

Note: Search is not case sensitive.

Enter the text string in the Find text entry field and press the **Enter** key. JavaHelp searches through the helpset and displays a list of topics in which the text string is found. This list is displayed in the Navigation Area by topic title and in descending order of number of matches. Select the desired topic to display the topic's content in the Content area.



Custom Help Content

Online help can be modified in a number of different ways depending on the level of modification desired.

- Content files can be modified.
- Cascading style sheets can be modified to change display formats.
- Images referenced in content files can be edited.

Note: Modifying the JavaHelp configuration files can adversely affect the performance of JavaHelp and is not discussed in this manual.

If an installed version of JavaHelp is customized, care must be taken to avoid overwriting the customized JavaHelp files when accepting an updated help JAR file for placement on the Version Checker repository. Therefore, the following guidelines can be used to establish procedures for maintaining and protecting customized JavaHelp:

- Always keep a backup of both original and customized files.
- Consider appending an identifier (e.g., “custom”) to the name of customized files. If a help file name is changed, the change must also be made to the map.jhm file. For example, a file named f_connection.htm file is customized and renamed to f_connection_custom.htm. The url attribute in the map.jhm file must be changed as follows:

From:

```
<mapID target="f_connection"
      url="f_connection.htm"/>
```

To:

```
<mapID target="f_connection"
      url="f_connection_custom.htm"/>
```

- Another option is to keep the same name of the file but place the customized file into a separate directory as follows:

```
<mapID target="f_connection"
      url="custom/f_connection.htm"/>
```

Customization of HTML Content Files

All content files within the JavaHelp JAR files are in compliance with the W3C HTML revision 3.2 format. This format is required for content files to display properly within the Helpset Viewer. Certain parts of the HTML revision 4.0 format can be used since it shares most markup tag elements with 3.2; however, care should be taken when implementing revision 4.0 features into content files destined for JavaHelp because certain revision 4.0 features might not be supported. To ensure proper behavior of content files in JavaHelp, always test the display characteristics of HTML files in JavaHelp before releasing the help files.

One advantage of the content files being in HTML format is that common editors can be used to modify help content. The specifics of editing HTML files are not discussed here since these depend on the editor; however, the following general always apply:

1. Before an HTML content file within a JAR file can be edited, the file must be extracted to a working location using a tool, such as WinZip. The extracted HTML file is a copy of the original file. Make a backup of the original file and place it in a specified archive directory for later retrieval. All editing should be done on the extracted copy.
2. Select an appropriate HTML editor. Note that some HTML editors automatically add embedded XML, HTML and other types of objects to HTML code. Such objects can adversely affect the display of the content within JavaHelp. As a result, editing tools that do not automatically add objects are recommended. Such tools include Macromedia's Dreamweaver and ASCII editors, such as Notepad.
3. Save the modified HTML file to the working location.
4. Add the modified file to the applicable JAR file replacing the original file in the JAR (the original being maintained in the archive directory location). Do not change the file extension.
5. If the name of the HTML file is changed to reflect customization, such as from `f_connection.htm` to `f_connection_custom.htm`, the URL attribute of the `map.jhm` file needs to be updated to reflect the name change. The `.jhm` file can be updated using an ASCII editor.

Change the Display of Content

The format and style of the content displayed in the Helpset Viewer can be modified by altering the values of the style properties in the applicable cascading style sheet (CSS) file. CSS files are defined in the <head>...</head> section of each HTML file used in the ACI online help using <link> tags as follows:

```
<link rel="StyleSheet" href="Templates/forScreen.css" type="text/css"
media="screen">
```

```
<link rel="StyleSheet" href="Templates/forPrint.css" type="text/css"
media="print">
```

CSS files are located in the Templates folder within the applicable helpset JAR (ACI_Help_es.jar, ACI_Help_tss.jar, and ACI_Help_pm.jar).

Note: For ACI Payments Manager, the name of the CSS is document.css for both screen and print media.

To ensure that content displays properly in the Helpset Viewer, always test before releasing the modified CSS files.

Install JavaHelp for Stand-alone Use


JavaHelp can be installed for direct access to helpset (.hs) files without the need to have the ACI desktop open. Note that Java must be already installed. The remainder of this topic discusses installing JavaHelp on a Java enabled Windows-based PC.

1. Download the latest version of JavaHelp from:


<http://java.sun.com/products/javahelp>

Note: JavaHelp is distributed as a zip file such as **Javahelp 2.0_02.zip** (a more current version might be available).

2. Open the zip file and extract all files to an easily accessible location, such as (e.g., C:\jh2.0). Among the files extracted is the **hsvviewer.jar** file that is needed later in this procedure.
3. Find java.exe and create a shortcut to the file. Java.exe must be already installed. Cut and paste the shortcut to an easily accessible location.
4. Right click on the shortcut and select Properties on the drop-down menu:



The properties for the shortcut are available in the Properties window:




5. In the Target field located on the Shortcut tab, enter the path to java.exe, followed by a space, -jar, another space, and then the path to the installed location of hviewer.jar. In the illustration above, the full text of the Target field is partially obscured, but contains:

"C:\\Program Files\\jdk1.5.0_05\\bin\\java.exe" -jar "C:\\jh2.0\\demos\\bin\\hviewer.jar"

Note: If a blank space is located in a file path (e.g., C:\\Program Files\\...), enclose the path in quotes, as shown above.

6. Click OK.

7. Test the install by clicking on the shortcut, after which the following Set HelpSet window should display that can be used to browse to a helpset file (.hs extension) that you want to open.



If the above window does not display, a number of problems could exist. For example, either Java, JavaHelp, or both are not installed properly. Also, the target path in the shortcut could be incorrect. Verify that the paths in the shortcut reflect the actual paths for both java.exe and hswviewer.jar.

A: BASE24-eps Window (UI) Information

The term *window* is used in documentation and online help. This term relates to a collection of graphical user interface (GUI) components (i.e., buttons, fields, field names, tabs, buttons, tables, trees, and messages) that provide access to a particular application, function and data source(s).

Each window, which can also be called a UI, is managed by a particular application server on the host. The applications available (therefore, the windows available) depend on the ACI desktop configuration and user security access permissions.

An application (and the corresponding window) is identified by a task ID. Tasks available on a desktop can be viewed in the Task ID selectable field located on the Permissions tab of the User Security Role Configuration window (**Configure > User Security > Role**).

Window information is presented alphabetically by window name. Information is structured as follows:

Task ID:	The unique task ID for the window.
Permissions:	Full access and view access permissions, as applicable.
Help ID:	The unique ID for context sensitive help between the desktop and the online help system.
Data Sources:	A list of data sources possibly updated by the window. The actual data source(s) impacted by a change made at a window can vary by application configuration. Verify impacted data sources using the OLTP Warmboot Management window.
Desktop Access:	How the window is accessed on the ACI desktop.
Messages:	Messages exchanged with the server.

Interface Profile Permissions

FullAcqProfileConfigPermission
ViewAcquirerProfileConfig

FullAcqTransAllowedPermission
ViewAcqTransAllowedPermission

FullIssTransAllowedPermission
ViewIssTransAllowedPermission

FullContextConfigPermission
ViewContextConfigPermission

FullISOFrameworkCfgPermission
ViewISOFrameworkCfgPermission

FullActionCodePermission
ViewActionCodePermission

FullATMSurchPrflPermission
ViewATMSurchPrflPermission

FullISOTranMapPermission
ViewISOTranMapPermission

ABI (Italian Banking Association) ISO Interface Configuration Window

Task ID:	AbiIsoInterface
Permissions:	FullAbiIsoInterfacePermission ViewAbiIsoInterfacePermission
Help ID:	n/a
Data Sources:	ABI_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > ABI (Italian Banking Association) > ABI ISO Interface
Messages:	AbiKeyListRq AbiKeyViewRq AbiKeyInsertRq AbiKeyUpdateRq AbiKeyDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

ABI (Italian Banking Association) MAC Key Configuration Window

Task ID:	AbiKeyConfig
Permissions:	FullAbiKeyConfigPermission ViewAbiKeyConfigPermission
Help ID:	n/a
Data Sources:	ABI_Key
Desktop Access:	Configure > Interface > Network > ABI (Italian Banking Association) > ABI MAC Key
Messages:	AbiKeylistRq AbiKeyViewRq AbiKeyInsertRq AbiKeyUpdateRq AbiKeyDeleteRq

Accel/Exchange Interface Configuration Window

Task ID:	AccelInterface
Permissions:	FullAccelInterfacePermission ViewAccelInterfacePermission
Help ID:	n/a
Data Sources:	ACCEL_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Accel/Exchange > Accel/ Exchange Interface
Messages:	IfAccelViewRq IfAccelInsertRq IfAccelUpdateRq IfAccelDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Accel-Exchange Network ID/Instrument Type Relationship Configuration Window

Task ID:	AccelBrandInstrmRelation
Permissions:	FullAccelBrandInstrmRelnPerm ViewAccelBrandInstrmRelnPerm FullInstrumentTypePermission ViewInstrumentTypePermission
Related Permissions:	FullAccelInterfacePermission ViewAccelInterfacePermission
Help ID:	n/a
Data Sources:	Netwk_Brand_Instrm_Reln
Desktop Access:	Configure > Interface > Network > Accel/Exchange > ACCEL-Exchange Network ID/Instrument Type Relationship
Messages:	NetwkBrandInstrmRelnViewRq NetwkBrandInstrmRelnInsertRq NetwkBrandInstrmRelnUpdateRq NetwkBrandInstrmRelnDeleteRq

Account Routing Configuration Window

Task ID:	AccountRouting
Permissions:	FullAccountRoutingPermission ViewAccountRoutingPermission
Help ID:	w_account_routing_configuration
Data Sources:	ACCOUNT_ROUTING
Desktop Access:	Configure > Account Routing
Messages:	AccountRoutingRttnListRq AccountRoutingListRq AccountRoutingViewRq AccountRoutingInsertRq AccountRoutingUpdateRq AccountRoutingDeleteRq

Account Status Mapping Profile Configuration Window

Task ID:	AcctStatusMappingProfile
Permissions:	FullAcctStatusMappingProfile ViewAcctStatusMappingProfile
Help ID:	w_account_status_mapping_profile_configuration
Data Sources:	Acct_Status_Extrn_to_Intrn Acct_Status_Intrn_to_Extrn
Desktop Access:	Configure > Account Status Mapping Profile
Messages:	AcctStatusMappingListRq AcctStatusMappingViewRq AcctStatusMappingInsertRq AcctStatusMappingUpdateRq AcctStatusMappingDeleteRq AcctStatusMappingGenericDeleteRq

Acquirer/Instrument Type Relationship Profile Configuration Window

Task ID:	AcquirerInstrumTypeRelation
Permissions:	FullAcqInstRelationPermission ViewAcqInstRelationPermission
Help ID:	w_acquirer_instrument_type_relationship_profile_configuration
Data Sources:	ACQ_INSTRM_TYP_REL
Desktop Access:	Configure > Acquirer/Instrument Type Relationship Profile
Messages:	AcqInstRelationViewRq AcqInstRelationListRq AcqInstRelationInsertRq AcqInstRelationUpdateRq AcqInstRelationDeleteRq

Acquirer Transactions Allowed Profile Configuration Window

Task ID:	AcquirerTransactionsAllowed
Permissions:	FullAcqTransAllowedPermission ViewAcqTransAllowedPermission
Help ID:	w_acquirer_transactions_allowed_profile_configuration
Data Sources:	Acquirer_Txn_Allowed
Desktop Access:	Configure > Transactions Allowed > Acquirer Transactions Profile
Messages:	ATAPrflListRq ATAPrflInsertRq ATAPrflViewRq ATAPrflUpdateRq ATAPrflDeleteRq ATAPrflGenericDeleteRq

Action Code Profile Configuration Window

Task ID:	ActionCode
Permissions:	FullActionCodePermission FullIFXHostActCdPermission ViewActionCodePermission ViewIFXHostActCdPermission
Help ID:	w_action_code
Data Sources:	Action_Code_Extrn_to_Intrn Action_Code_Intrn_to_Extrn
Desktop Access:	Configure > Action Code Profile
Messages:	ActionCodeIntInsertRq ActionCodeExtInsertRq ActionCodeListRq ActionCodeIntViewRq ActionCodeIntUpdateRq ActionCodeExtViewRq ActionCodeExtUpdateRq ActionCodeIntDeleteRq ActionCodeExtDeleteRq ActionCodeGenericDeleteRq

Active Script Statistics and Management Window

Task ID:	ActiveScript
Permissions:	FullActiveScriptPermission ViewActiveScriptPermission
Help ID:	w_active_script_statistics_and_management
Data Sources:	Active_Script_Statistics
Desktop Access:	System Operations > Active Script Statistics
Messages:	ActiveScriptListRq ActiveScriptMsgTypeListRq AuthScriptDataRq ActiveScriptViewRq ActiveScriptResetDataRq

Administrative Card Configuration Window

Task ID:	AdministrativeCardManagement
Permissions:	FullAdminCardMgmtPermission ViewAdminCardMgmtPermission
Help ID:	w_administrative_card_configuration
Data Sources:	Admin_Card
Desktop Access:	Configure > Administrative Card
Messages:	AdminCardInsertRq AdminCardViewRq AdminCardUpdateRq AdminCardDeleteRq

American Express CAPN Interface Configuration Window

Task ID:	AmexCAPNInterface
Permissions:	FullAmexCAPNInterfacePerm ViewAmexCAPNInterfacePerm
Help ID:	n/a
Data Sources:	AMEX_CAPN_INTF INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > American Express > American Express CAPN Interface
Messages:	IfAmexCAPNViewRq IfAmexCAPNInsertRq IfAmexCAPNUpdateRq IfAmexCAPNDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

American Express Global Network Services Interface Configuration Window

Task ID:	AmexGNSInterface
Permissions:	FullAmexGNSInterfacePermission
Help ID:	w_aegn_interface_configuration
Data Sources:	AEGN_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > American Express > American Express Global Network Interface
Messages:	IfAmexGNSViewRq IfAmexGNSInsertRq IfAmexGNSUpdateRq IfAmexGNSDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Application Configuration Window

Task ID:	IWTApplicationConfig
Permissions:	FullIWTAppCfgPermission ViewIWTAppCfgPermission
Help ID:	w_application_configuration
Data Sources:	APPLCNFG
Desktop Access:	System Operations > Server Management > Application
Messages:	IWTAppCfgInsertRq IWTAppCfgGetPropertyRq IWTAppCfgListRq IWTAppCfgUpdateRq IWTAppCfgDeleteRq

Application Management Comms Handler Window

Task ID:	ApplctnManagementSummary
Permissions:	FullApplctnManagementSummary ViewApplctnManagementSummary
Data Sources:	n/a
Help ID:	w_appmanage_comms_handler_summary
Desktop Access:	System Operations > Application Management > Application Management Summary > Comms Handler Summary
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

Application Management Message Router Summary Window

Task ID:	ApplctnManagementSummary
Permissions:	FullApplctnManagementSummary ViewApplctnManagementSummary
Data Sources:	n/a
Help ID:	w_appmanage_message_router_summary
Desktop Access:	System Operations > Application Management > Application Management Summary > Message Router Summary
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

Application Management Process Summary Window

Task ID:	ApplctnManagementSummary
Permissions:	FullApplctnManagementSummary ViewApplctnManagementSummary
Data Sources:	n/a
Help ID:	w_appmanage_process_summary
Desktop Access:	System Operations > Application Management > Application Management Summary > Process Summary
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

Application Management Queue Manager Summary Window

Task ID:	ApplctnManagementSummary
Permissions:	FullApplctnManagementSummary ViewApplctnManagementSummary
Data Sources:	n/a
Help ID:	w_appmanage_queue_manager_summary
Desktop Access:	System Operations > Application Manager > Application Management Summary > Queue Manager Summary
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

Application Management Queue Summary Window

Task ID:	ApplctnManagementSummary
Permissions:	FullApplctnManagementSummary ViewApplctnManagementSummary
Data Sources:	n/a
Help ID:	w_appmanage_queue_summary
Desktop Access:	System Operations > Application Management > Application Management Summary > Queue Summary
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

Application Management Station Summary Window

Task ID:	ApplctnManagementSummary
Permissions:	FullApplctnManagementSummary ViewApplctnManagementSummary
Data Sources:	n/a
Help ID:	w_appmanage_station_summary
Desktop Access:	System Operations > Application Management > Application Management Summary > Station Summary
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

Application Management Window

Task ID:	ApplctnManagement
Permissions:	FullApplctnManagement ViewApplctnManagement
Data Sources:	n/a
Help ID:	t_appmanage_detail
Desktop Access:	System Operations > Application Management > Application Management
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

Application Parameter Management System Interface Configuration Window

Task ID:	APMSInterfaceConfiguration
Permissions:	FullAPMSIFCfgPermission
Help ID:	w_apms_interface_configuration
Data Sources:	INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Host > Application Parameter Management Interface
Messages:	InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Armed Forces Financial Network (AFFN) Institution Configuration Window

Task ID:	AffnInstitution
Permissions:	FullAffnInstitutionPermission ViewAffnInstitutionPermission
Help ID:	n/a
Data Sources:	B53_INSTITUTION
Desktop Access:	Configure > Interface > Network > Armed Forces Financial Network (AFFN) > Armed Forces Financial Network (AFFN) Institution
Messages:	B53InstitutionListRq B53InstitutionViewRq B53InstitutionInsertRq B53InstitutionUpdateRq B53InstitutionDeleteRq

Armed Forces Financial Network (AFFN) Interface Configuration Window

Task ID:	AffnInterface
Permissions:	FullAffnInterfacePermission
Help ID:	n/a
Data Sources:	INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Armed Forces Financial Network (AFFN) > Armed Forces Financial Network (AFFN) Interface
Messages:	InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Artajasa Interface Configuration Window

Task ID:	ArtajasaInterface
Permissions:	FullArtajasaInterfacePerm ViewArtajasaInterfacePerm
Help ID:	n/a
Data Sources:	INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Artajasa Interface
Messages:	InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

AS2805 ISO Interface Configuration Window

Task ID:	As2805Interface
Permissions:	FullAs2805InterfacePerm ViewAs2805InterfacePerm
Help ID:	w_as2805_iso_interface_configuration
Data Sources:	AS2805_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > AS2805 ISO Interface
Messages:	IfAs28ViewRq IfAs28InsertRq IfAs28UpdateRq IfAs28DeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

ATM BASE24 Compatibility Profile Configuration Window

Task ID:	ATMB24CompatProfile
Permissions:	FullATMB24CompatPrflPermission ViewATMB24CompatPrflPermission
Help ID:	w_atm_base24_compatibility_profile_configuration
Data Sources:	CMPTPRFL
Desktop Access:	Configure > ATM (Java) > ATM BASE24 Compatibility Profile
Messages:	ATMB24CompatProfileInsertRq ATMB24CompatProfileListRq ATMB24CompatProfileViewRq ATMB24CompatProfileUpdateRq ATMB24CompatProfileDeleteRq

ATM Channel Administration Window

Task ID:	ATMChannelAdministration
Permissions:	FullATMChannelAdminPermission ViewATMChannelAdminPermission
Help ID:	w_atm_channel_administration_java
Data Sources:	ATDCNFG ESATDD1 ESATDS1 HPRPRFL
Desktop Access:	System Operations > ATM (Java) > ATM Channel Administration
Messages:	ATM Channel Administration ATMChannelAdminListRq ATMChannelAdminViewRq ATMChannelAdminUpdateRq ATMChannelAdminSubmitRq

ATM Channel Administration Window

Task ID:	ATMDHChannelAdministration
Permissions:	FullATMDHChannelAdminPerm ViewATMDHChannelAdminPerm
Help ID:	w_atm_channel_administration_cplus
Data Sources:	ATDCNFG ESATDD1 ESATDS1
Data Sources:	HPRPRFL
Desktop Access:	System Operations > ATM > ATM Channel Administration
Messages:	ATMChannelAdminListRq ATMChannelAdminViewRq ATMChannelAdminUpdateRq ATMChannelAdminSubmitRq

ATM Channel Configuration Window

Task ID:	ATMChannel
Permissions:	FullATMChannelPermission FullATMChannelAdminPermission FullATMChannelMgmtPermission FullATMChannelPrflPermission ViewATMChannelPermission ViewATMChannelAdminPermission ViewATMChannelMgmtPermission ViewATMChannelPrflPermission
Help ID:	w_atm_channel_configuration_java
Data Sources:	ATM_DS1
Desktop Access:	Configure > ATM (Java) > ATM Channel
Messages:	ATMChannelListRq ATMChannelViewRq ATMChannelInsertRq ATMChannelUpdateRq ATMChannelDeleteRq

ATM Channel Configuration Window

Task ID:	ATMDHChannel
Permissions:	FullATMDHChannelPermission FullATMDHChannelAdminPerm FullATMDHChannelMgmtPermission FullATMDHChannelPrflPermission ViewATMDHChannelPermission ViewATMDHChannelAdminPerm ViewATMDHChannelMgmtPermission ViewATMDHChannelPrflPermission
Help ID:	w_atm_channel_configuration_cplus
Data Sources:	ATM_DS1
Desktop Access:	Configure > ATM > ATM Channel
Messages:	ATMDHChannelListRq ATMDHChannelViewRq ATMDHChannelInsertRq ATMDHChannelUpdateRq ATMDHChannelDeleteRq

ATM Channel Management - All Channels Window

Task ID:	ATMChannelManagement
Permissions:	FullATMChannelMgmtPermission ViewATMChannelMgmtPermission
Help ID:	w_atm_channel_management_all_java
Data Sources:	ESATDD1 ESATDS1
Desktop Access:	System Operations > ATM (Java) > ATM Channel Management > All Channels
Messages:	ATMChannelMgmtAllSubmitRq

ATM Channel Management - All Channels Window

Task ID:	ATMDHChannelManagement
Permissions:	FullATMDHChannelMgmtPermission ViewATMDHChannelMgmtPermission
Help ID:	w_atm_channel_management_all_cplus
Data Sources:	ESATDD1 ESATDS1
Desktop Access:	System Operations > ATM > ATM Channel Management > All Channels
Messages:	ATMChannelMgmtAllSubmitRq

ATM Channel Management - Selected Channels Window

Task ID:	ATMDHChanMgmtSelectedChannels
Permissions:	FullATMDHChanMgmtSCPermission ViewATMDHChanMgmtSCPermission
Help ID:	w_atm_channel_management_selected_cplus
Data Sources:	ESATDD1 ESATDS1
Desktop Access:	System Operations > ATM > ATM Channel Management > Selected Channels
Messages:	ATMChannelMgmtViewRq ATMChannelMgmtSubmitRq

ATM Channel Management - Selected Channels Window

Task ID:	ATMChanMgmtSelectedChannels
Permissions:	FullATMChanMgmtSCPermission ViewATMChanMgmtSCPermission
Help ID:	w_atm_channel_management_selected_java
Data Sources:	ESATDD1 ESATDS1
Desktop Access:	System Operations > ATM (Java) > ATM Channel Management > Selected Channels
Messages:	ATMChannelMgmtViewRq ATMChannelMgmtSubmitRq

ATM Channel Profile Configuration Window

Task ID:	ATMChannelProfile
Permissions:	FullATMChannelPrflPermission ViewATMChannelPrflPermission
Help ID:	w_atm_channel_profile_configuration
Data Sources:	ATM_PRFL
Desktop Access:	Configure > ATM (Java) > ATM Channel Profile
Messages:	ATMConfigProfileInsertRq ATMConfigProfileListRq ATMConfigProfileViewRq ATMConfigProfileUpdateRq ATMConfigProfileDeleteRq

ATM Channel Profile Configuration Window

Task ID:	ATMDHChannelProfile
Permissions:	FullATMDHChannelPrflPermission ViewATMDHChannelPrflPermission
Help ID:	w_atm_channel_profile_cplus
Data Sources:	ATM_PRFL
Desktop Access:	Configure > ATM > ATM Channel Profile
Messages:	ATMConfigProfileInsertRq ATMConfigProfileListRq ATMConfigProfileViewRq ATMConfigProfileUpdateRq ATMConfigProfileDeleteRq

ATM Consumer Media Configuration Window

Task ID:	ATMDHConsumerMedia
Permissions:	FullATMDHConsumerMediaPerm ViewATMDHConsumerMediaPerm
Help ID:	w_consumer_media_configuration
Data Sources:	ATM_CONSUMER_MEDIA
Desktop Access:	Configure > ATM > ATM Consumer Media
Messages:	ATMDHConsumerMediaInsertRq ATMDHConsumerMediaListRq ATMDHConsumerMediaViewRq ATMDHConsumerMediaUpdateRq ATMDHConsumerMediaDeleteRq ATMDHConsumerMediaGenericDeleteRq

ATM Depository Bin Profile Configuration Window

Task ID:	ATMDHDepositoryBinProfile
Permissions:	FullATMDHDepBinPrflPermission ViewATMDHDepBinPrflPermission
Help ID:	w_atm_depository_bin_profile_configuration
Data Sources:	ATM_SSB_BIN
Desktop Access:	Configure > ATM > ATM Depository Bin Profile
Messages:	ATMDHDepBinProfileInsertRq ATMDHDepBinProfileListRq ATMDHDepBinProfileViewRq ATMDHDepBinProfileUpdateRq ATMDHDepBinProfileDeleteRq ATMDHDepBinProfileGenericDeleteRq

ATM Device Handler Interface Configuration Window

Task ID:	ATMDHInterfaceConfiguration
Permissions:	FullATMDHIFCfgPermission ViewATMDHIFCfgPermission
Help ID:	w_atm_device_handler_interface_configuration
Data Sources:	n/a
Desktop Access:	Configure > Interface > Host > ATM Device Handler
Messages:	n/a

ATM Dial-Up Channel Management Window

Task ID:	ATMDHDialUpChannelMgmt
Permissions:	FullATMDHDialChMgmtPermission ViewATMDHDialChMgmtPermission
Help ID:	w_atm_dial-up_channel_management
Data Sources:	ATMDH_DIAL_UP_CHANNEL_MGMT
Desktop Access:	System Operations > ATM > ATM Dial-Up Channel Management
Messages:	ATMDHChnlDialupMgmt ListRq ATMDHChnlDialupMgmt ViewRq ATMDHChnlDialupMgmt InsertRq ATMDHChnlDialupMgmt ResetErrorsRq ATMDHChnlDialupMgmt DeleteRq ATMDHChnlDialupMgmt GenericDeleteRq

ATM Diebold Channel Operator Configuration Window

Task ID:	ATMDHDieboldChannelOperatorID
Permissions:	FullATMDHDbldChanOpIDPerm ViewATMDHDbldChanOpIDPerm
Help ID:	w_atm_diebold_channel_operator_configuration
Data Sources:	ATM_OPER
Desktop Access:	Configure > ATM > ATM Diebold Channel Operator
Messages:	ATMDHOperIdInsertRq ATMDHOperIdListRq ATMDHOperIdViewRq ATMDHOperIdUpdateRq ATMDHOperIdDeleteRq ATMDHOperIdGenericDeleteRq

ATM Diebold Channel Operator ID Configuration Window

Task ID:	ATMDieboldChannelOperatorID
Permissions:	FullATMDbldChanOprIDPermission ViewATMDbldChanOprIDPermission
Help ID:	w_atm_diebold_channel_id_configuration
Data Sources:	ATM_OPER
Desktop Access:	Configure > ATM (Java) > ATM Diebold Channel Operator
Messages:	ATMDHOperIdInsertRq ATMDHOperIdListRq ATMDHOperIdViewRq ATMDHOperIdUpdateRq ATMDHOperIdDeleteRq ATMDHOperIdGenericDeleteRq

ATM DKM Profile Window

Task ID:	ATMDHDkmProfile
Permissions:	FullATMDHDkmProfilePermission ViewATMDHDkmProfilePermission
Help ID:	w_atm_dkm_profile
Data Sources:	ATM_DKM
Desktop Access:	Configure > ATM > ATM DKM Profile
Messages:	ATMDHDkmProfileListRq ATMDHDkmProfileViewRq ATMDHDkmProfileInsertRq ATMDHDkmProfileUpdateRq ATMDHDkmProfileDeleteRq

ATM EMV Profile Configuration Window

Task ID:	ATMEmvProfile
Permissions:	FullATMEMVProfilePermission ViewATMEMVProfilePermission
Help ID:	w_atm_emv_profile_configuration
Data Sources:	ATM_EMV
Desktop Access:	Configure > ATM (Java) > ATM EMV Profile
Messages:	ATMEmvProfileInsertRq ATMEmvProfileListRq ATMEmvProfileViewRq ATMEmvProfileUpdateRq ATMEmvProfileDeleteRq

ATM Fast Cash Profile Configuration Window

Task ID:	ATMDHFastCashProfile
Permissions:	FullATMDHFastCashPrflPerm ViewATMDHFastCashPrflPerm
Help ID:	w_atm_fast_cash_profile_configuration
Data Sources:	ATM_FAST_CASH
Desktop Access:	Configure > ATM > ATM Fast Cash Profile
Messages:	ATMFastCashProfileInsertRq ATMFastCashProfileListRq ATMFastCashProfileViewRq ATMFastCashProfileUpdateRq ATMFastCashProfileDeleteRq

ATM Fast Cash Profile Configuration Window

Task ID:	ATMFastCashProfile
Permissions:	FullATMFastCashPrflPermission ViewATMFastCashPrflPermission
Help ID:	w_atm_fast_cash_profile_configuration
Data Sources:	ATM_FAST_CASH
Desktop Access:	Configure > ATM (Java) > ATM Fast Cash Profile
Messages:	ATMFastCashProfileInsertRq ATMFastCashProfileListRq ATMFastCashProfileViewRq ATMFastCashProfileUpdateRq ATMFastCashProfileDeleteRq

ATM Flow Configuration

Task ID:	ATMDHFlowconfig
Permissions:	FullATMDHFlowConfigPermission ViewATMDHFlowConfigPermission
Help ID:	w_atm_flow_configuration
Data Sources:	ATM_FLOW_CNTL
Desktop Access:	Configure > ATM > ATM Flow > ATM Flow Configuration
Messages:	ATMDHFlowInsertRq ATMDHFlowListRq ATMDHFlowGetControlInfoRq ATMDHFlowViewRq ATMDHFlowUpdateRq ATMDHFlowDeleteRq ATMDHFlowCreateWorkingRq ATMDHFlowCheckInWorkingRq ATMDHFlowSequenceControlListRq ATMDHFlowGenericDeleteRq ATMDHFlowWorkingListRq ATMDHFlowActiveListRq

ATM Flow Management

Task ID:	ATMDHFlowManagement
Permissions:	FullATMDHFlowMgmtPermission ViewATMDHFlowMgmtPermission
Help ID:	w_atm_flow_management
Data Sources:	ATM_FLOW_CNTL
Desktop Access:	Configure > ATM > ATM Flow > ATM Flow Management
Messages:	ATMDHFlowInsertRq ATMDHFlowListRq ATMDHFlowGetControlInfoRq ATMDHFlowViewRq ATMDHFlowUpdateRq ATMDHFlowDeleteRq ATMDHFlowCreateWorkingRq ATMDHFlowCheckInWorkingRq ATMDHFlowSequenceControlListRq ATMDHFlowGenericDeleteRq ATMDHFlowWorkingListRq ATMDHFlowActiveListRq

ATM Flow Perusal

Task ID:	ATMDHFlowPerusal
Permissions:	FullATMDHFlowPerusalPermission ViewATMDHFlowPerusalPermission
Help ID:	w_atm_flow_perusal
Data Sources:	ATM_FLOW_CNTL
Desktop Access:	Configure > ATM > ATM Flow > ATM Flow Perusal
Messages:	ATMDHFlowInsertRq ATMDHFlowListRq ATMDHFlowGetControlInfoRq ATMDHFlowViewRq ATMDHFlowUpdateRq ATMDHFlowDeleteRq ATMDHFlowCreateWorkingRq ATMDHFlowCheckInWorkingRq ATMDHFlowSequenceControlListRq ATMDHFlowGenericDeleteRq ATMDHFlowWorkingListRq ATMDHFlowActiveListRq

ATM Hardware Status Window

Task ID:	ATMHardwareStatus
Permissions:	FullATMHardwareStatPermission ViewATMHardwareStatPermission
Help ID:	w_atm_hardware_status
Data Sources:	ESATDD1
Desktop Access:	System Operations > ATM (Java) > ATM Hardware Status
Messages:	ATMHardwareStatusListRq ATMHardwareStatusViewRq

ATM Hopper Profile Configuration Window

Task ID:	ATMDHHopperProfile
Permissions:	FullATMDHHopperPrflPermission ViewATMDHHopperPrflPermission
Help ID:	w_atm_hopper_profile_configuration_cplus
Data Sources:	ATM_HOPR
Desktop Access:	Configure > ATM > ATM Hopper Profile
Messages:	ATMHopperProfileInsertRq ATMHopperProfileListRq ATMHopperProfileViewRq ATMHopperProfileUpdateRq ATMHopperProfileDeleteRq

ATM Hopper Profile Configuration Window

Task ID:	ATMHopperProfile
Permissions:	FullATMHopperPrflPermission ViewATMHopperPrflPermission
Help ID:	w_atm_hopper_profile_configuration_java
Data Sources:	ATM_HOPR
Desktop Access:	Configure > ATM (Java) > ATM Hopper Profile
Messages:	ATMHopperProfileInsertRq ATMHopperProfileListRq ATMHopperProfileViewRq ATMHopperProfileUpdateRq ATMHopperProfileDeleteRq

ATM Inactivity Alert Profile Configuration Window

Task ID:	ATMDHInactivityProfile
Permissions:	FullATMDHInactiveAlertPrflPerm ViewATMDHInactiveAlertPrflPerm
Help ID:	w_atm_inactivity_alert_profile_configuration
Data Sources:	ATM_INACT
Desktop Access:	Configure > ATM > ATM Inactivity Alert Profile
Messages:	ATMInactProfileInsertRq ATMInactProfileListRq ATMInactProfileViewRq ATMInactProfileUpdateRq ATMInactProfileDeleteRq

ATM Inactivity Alert Profile Configuration Window

Task ID:	ATMInactivityProfile
Permissions:	FullATMInactivePrflPermission ViewATMInactivePrflPermission
Help ID:	w_atm_inactivity_alert_profile_configuration
Data Sources:	ATM_INACT
Desktop Access:	Configure > ATM (Java) > ATM Inactivity Alert Profile
Messages:	ATMInactProfileInsertRq ATMInactProfileListRq ATMInactProfileViewRq ATMInactProfileUpdateRq ATMInactProfileDeleteRq

ATM Load Configuration Administration Window

Task ID:	ATMDHLoadConfigAdmin
Permissions:	FullATMDHLoadCnfgAdminPerm ViewATMDHLoadCnfgAdminPerm
Help ID:	w_atm_load_configuration_administration
Data Sources:	ATM_CONF
Desktop Access:	System Operations > ATM > ATM Load Configuration Administration
Messages:	ATMDHConfUtilSubmitRq

ATM Load Profile Window

Task ID:	ATMDHLoadProfile
Permissions:	FullATMDHLoadPrflPermission ViewATMDHLoadPrflPermission
Help ID:	w_atm_load_profile
Data Sources:	ATMCNFG
Desktop Access:	Configure > ATM > ATM Load Profile
Messages:	ATMLoadProfileDeleteRq ATMLoadProfileListRq ATMLoadProfileViewRq

ATM Load Profile Window

Task ID:	ATMLoadProfile
Permissions:	FullATMLoadProfilePermission ViewATMLoadProfilePermission
Help ID:	w_atm_load_profile
Data Sources:	ATMCNFG
Desktop Access:	Configure > ATM (Java) > ATM Load Profile
Messages:	ATMLoadProfileDeleteRq ATMLoadProfileListRq ATMLoadProfileViewRq

ATM Load Timeout Profile Configuration Window

Task ID:	ATMLdTmtProfile
Permissions:	FullATMLoadTimerPrflPermission ViewATMLoadTimerPrflPermission
Help ID:	w_atm_load_timeout_profile_configuration
Data Sources:	LTMRPRFL
Desktop Access:	Configure > ATM (Java) > ATM Load Timeout Profile
Messages:	ATMLdTmtProfileInsertRq ATMLdTmtProfileListRq ATMLdTmtProfileViewRq ATMLdTmtProfileUpdateRq ATMLdTmtProfileDeleteRq

ATM MAC Profile Configuration Window

Task ID:	ATMDHMacProfile
Permissions:	FullATMDHMacProfilePermission ViewATMDHMacProfilePermission
Help ID:	w_atm_mac_profile_configuration_cplus
Data Sources:	ATM_MAC
Desktop Access:	Configure > ATM > ATM MAC Profile
Messages:	ATMMacProfileInsertRq ATMMacProfileListRq ATMMacProfileViewRq ATMMacProfileUpdateRq ATMMacProfileDeleteRq

ATM MAC Profile Configuration Window

Task ID:	ATMMacProfile
Permissions:	FullATMMACProfilePermission ViewATMMACProfilePermission
Help ID:	w_atm_mac_profile_configuration_java
Data Sources:	ATM_MAC
Desktop Access:	Configure > ATM (Java) > ATM MAC Profile
Messages:	ATMMacProfileInsertRq ATMMacProfileListRq ATMMacProfileViewRq ATMMacProfileUpdateRq ATMMacProfileDeleteRq

ATM Multi-byte Translation Configuration Window

Task ID:	ATMMultibyteTranslation
Permissions:	FullATMMbyteTransPermission ViewATMMbyteTransPermission
Help ID:	w_multibyte_translation_cfg
Data Sources:	ATM_MBYTE_XLATE
Desktop Access:	Configure > ATM > ATM Multi-byte Translation
Messages:	ATMDHMMultibyteXLateListRq ATMDHMMultibyteXLateViewRq ATMDHMMultibyteXLateInsertRq ATMDHMMultibyteXLateUpdateRq ATMDHMMultibyteXLateDeleteRq

ATM Operation Code Configuration Window

Task ID:	ATMDHOpCodeMapping
Permissions:	FullATMDHOpCodeMapPermission ViewATMDHOpCodeMapPermission
Help ID:	w_atm_operation_code_configuration
Data Sources:	ATM_OP_CDE
Desktop Access:	Configure > ATM > ATM Operation Code
Messages:	ATMDHOpCodeInsertRq ATMDHOpCodeListRq ATMDHOpCodeViewRq ATMDHOpCodeUpdateRq ATMDHOpCodeDeleteRq

ATM Optional Receipt Profile Window

Task ID:	ATMOptionalReceiptProfile
Permissions:	FullATMOptnRcptPrflPermission ViewATMOptnRcptPrflPermission
Help ID:	w_atm_optional_receipt_profile
Data Sources:	OPTRCPT
Desktop Access:	Configure > ATM (Java) > ATM Optional Receipt Profile
Messages:	ATMOptnRcptPrflInsertRq ATMOptnRcptPrflListRq ATMOptnRcptPrflViewRq ATMOptnRcptPrflUpdateRq ATMOptnRcptPrflDeleteRq

ATM Peak Load Profile Window

Task ID:	ATMDHPeakLoadProfile
Permissions:	FullATMDHPeakLoadProfilePerm ViewATMDHPeakLoadProfilePerm
Help ID:	w_atm_peak_load_profile_configuration
Data Sources:	ATM_PEAK_LOAD
Desktop Access:	Configure > ATM > ATM Peak Load Profile
Messages:	ATMDHPeakLoadProfileViewRq ATMDHPeakLoadProfileUpdateRq

ATM Receipt Format Profile Configuration Window

Task ID:	ATMDHReceiptFormat
Permissions:	FullATMDH RcptFrmtPrflPerm ViewATMDH RcptFrmtPrflPerm
Help ID:	w_atm_receipt_format_profile_configuration_cplus
Data Sources:	ATM_RECEIPT
Desktop Access:	Configure > ATM > ATM Receipt Format Profile
Messages:	ATMDHReceiptFormatInsertRq ATMDHReceiptFormatListRq ATMDHReceiptFormatViewRq ATMDHReceiptFormatUpdateRq ATMDHReceiptFormatDeleteRq ATMDHReceiptFormatGenericDeleteRq

ATM Receipt Format Profile Configuration Window

Task ID:	ATMReceiptFormat
Permissions:	FullATMReceiptFormatPermission ViewATMReceiptFormatPermission
Help ID:	w_atm_receipt_format_profile_configuration_java
Data Sources:	ATM_RECEIPT
Desktop Access:	Configure > ATM (Java) > ATM Receipt Format
Messages:	ATMDHReceiptFormatInsertRq ATMDHReceiptFormatListRq ATMDHReceiptFormatViewRq ATMDHReceiptFormatUpdateRq ATMDHReceiptFormatDeleteRq ATMDHReceiptFormatGenericDeleteRq

ATM Receipt Required Profile Configuration Window

Task ID:	ATMDHReceiptRequiredType
Permissions:	FullATMDHRCptRqdTypPrflPerm ViewATMDHRCptRqdTypPrflPerm
Help ID:	w_atm_receipt_required_profile_configuration
Data Sources:	ATM_REQ_RCPT
Desktop Access:	Configure > ATM > ATM Receipt Required Profile
Messages:	ATMReceiptReqTypeInsertRq ATMReceiptReqTypeListRq ATMReceiptReqTypeViewRq ATMReceiptReqTypeUpdateRq ATMReceiptReqTypeTableDeleteRq ATMReceiptReqTypeDeleteRq

ATM Receipt Required Profile Configuration Window

Task ID:	ATMReceiptRequiredType
Permissions:	FullATMRcptReqTypePermission ViewATMRcptReqTypePermission
Help ID:	w_atm_receipt_required_profile_configuration
Data Sources:	ATM_REQ_RCPT
Desktop Access:	Configure > ATM (Java) > ATM Receipt Required Profile
Messages:	ATMReceiptReqTypeInsertRq ATMReceiptReqTypeListRq ATMReceiptReqTypeViewRq ATMReceiptReqTypeUpdateRq ATMReceiptReqTypeTableDeleteRq ATMReceiptReqTypeDeleteRq

ATM Reload Map Request Window

Task ID:	ATMReloadMaps
Permissions:	FullATMReloadMapsPermission
Help ID:	w_atm_reload_map_request
Data Sources:	n/a
Desktop Access:	System Operations > ATM (Java) > ATM Reload Map
Messages:	ATMReloadMapSubmitRq

ATM State and Screen Configuration Window

Task ID:	CurrencyConvRateConfiguration
Permissions:	FullCrncyConvRateCfgPermission ViewCrncyConvRateCfgPermission
Help ID:	w_atm_state_and_screen_configuration
Data Sources:	ATM_STATE_SCRN
Desktop Access:	Configure > ATM > ATM State and Screen
Messages:	ATMDHStateScreenInsertRq ATMDHStateScreenListRq ATMDHStateScreenViewRq ATMDHStateScreenUpdateRq ATMDHStateScreenGenericDeleteRq

ATM Statement Print Profile Configuration Window

Task ID:	ATMDHStatementPrintProfile
Permissions:	FullATMDHStmntPrntPrflPerm ViewATMDHStmntPrntPrflPerm
Help ID:	w_atm_statement_print_profile_configuration
Data Sources:	ATM_STMNT_PRNT
Desktop Access:	Configure > ATM > ATM Statement Print Profile
Messages:	ATMStmntPrntProfileInsertRq ATMStmntPrntProfileListRq ATMStmntPrntProfileViewRq ATMStmntPrntProfileUpdateRq ATMStmntPrntProfileDeleteRq

ATM Statement Print Profile Configuration Window

Task ID:	ATMStatementPrintProfile
Permissions:	FullATMStmtPrntPrflPermission ViewATMStmtPrntPrflPermission
Help ID:	w_atm_statement_print_profile_configuration
Data Sources:	ATM_STMNT_PRNT
Desktop Access:	Configure > ATM (Java) > ATM Statement Print Profile
Messages:	ATMStmntPrntProfileInsertRq ATMStmntPrntProfileListRq ATMStmntPrntProfileViewRq ATMStmntPrntProfileUpdateRq ATMStmntPrntProfileDeleteRq

ATM Status Window

Task ID:	ATMHardwareStatus
Permissions:	FullATMHardwareStatPermission ViewATMHardwareStatPermission
Help ID:	w_atm_status
Data Sources:	ATM_DD1
Desktop Access:	System Operations > ATM > ATM Status
Messages:	ATMDHStatusListRq ATMDHStatusViewRq

ATM Status Query Window

Task ID:	ATMDHStatusQuery
Permissions:	FullATMDHStatusQueryPermission ViewATMDHStatusQueryPermission
Help ID:	w_atm_status_query_cplus
Data Sources:	n/a
Desktop Access:	System Operations > ATM > ATM Status Query
Messages:	ATMStatusViewRq

ATM Status Query Window

Task ID:	ATMStatusQuery
Permissions:	FullATMStatusQueryPermission
Help ID:	w_atm_status_query_java
Data Sources:	ESATDD1 ESATDS1
Desktop Access:	System Operations > ATM (Java) > ATM Status Query
Messages:	ATMStatusViewRq

ATM Surcharge Profile Configuration Window

Task ID:	ATMDHSurchargeProfile
Permissions:	FullATMDHSurchargePrflPerm ViewATMDHSurchargePrflPerm
Help ID:	w_atm_surcharge_profile_configuration_cplus
Data Sources:	ATM_SUR
Desktop Access:	Configure > ATM > ATM Surcharge Profile
Messages:	ATMSurchargeProfileInsertRq ATMSurchargeProfileListRq ATMSurchargeProfileViewRq ATMSurchargeProfileUpdateRq ATMSurchargeProfileDeleteRq

ATM Surcharge Profile Configuration Window

Task ID:	ATMSurchargeProfile
Permissions:	FullATMSurchPrflPermission ViewATMSurchPrflPermission
Help ID:	w_atm_surcharge_profile_configuration_java
Data Sources:	ATM_SUR
Desktop Access:	Configure > ATM (Java) > ATM Surcharge Profile
Messages:	ATMSurchargeProfileInsertRq ATMSurchargeProfileListRq ATMSurchargeProfileViewRq ATMSurchargeProfileUpdateRq ATMSurchargeProfileDeleteRq

ATM Totals Window

Task ID:	ATMDHTotals
Permissions:	FullATMDHTotalsPermission ViewATMDHTotalsPermission
Help ID:	w_atm_totals
Data Sources:	ATM_DD1 ATM_DS1 ATM_HOPR ATM_PREV_TTL ATM_PRFL
Desktop Access:	System Operations > ATM > ATM Totals
Messages:	ATMDHTotalsCurViewRq ATMDHTotalsPrvViewRq

Audit Store and Forward (SAF) Configuration Window

Task ID:	AuditSAFConfig
Permissions:	FullAuditSAFConfigPermission ViewAuditSAFConfigPermission
Help ID:	w_audit_store_and_forward_configuration
Data Sources:	Audit_Store_and_Forward
Desktop Access:	System Operations > Audit SAF
Messages:	AuditSAFViewRq AuditSAFUpdateRq

Authentication Profile Configuration Window

Task ID:	AuthenticationConfiguration
Permissions:	FullAuthentConfigPermission ViewAuthentConfigPermission
Help ID:	w_authentication_profile_configuration
Data Sources:	Card_Verification Diebold_Number_Table Dynamic_Card_Verification EMV_Security IBM_DES Identikey NCR_PIN_Verification Visa_PVV Dual_PIN_Verification
Desktop Access:	Configure > Transaction Security > Authentication Profile
Messages:	AuthentCnfgCardProfilesRq AuthentCnfgIdentikeyProfilesRq AuthentCnfgPinProfilesRq AuthentCnfgInsertDNTRq AuthentCnfgSummaryViewRq AuthentCnfgViewDNTRq AuthentCnfgUpdateDNTRq AuthentCnfgViewDNTRq AuthentCnfgDeleteRq AuthentCnfgProfileDeleteRq AuthentCnfgInsertNCRRq AuthentCnfgNCRProfilesRq AuthentCnfgViewNCRRq AuthentCnfgUpdateNCRRq AuthentCnfgInsertEMVRq AuthentCnfgEMVProfilesRq AuthentCnfgViewEMVRq AuthentCnfgUpdateEMVRq AuthentCnfgInsertIdentikeyRq AuthentCnfgViewIdentikeyRq AuthentCnfgUpdateIdentikeyRq AuthentCnfgInsertRq AuthentCnfgViewRq AuthentCnfgUpdateRq AuthentCnfgDeleteDPPPProfileRq AuthentCnfgDeleteDPPRq

AuthentCnfgDPPProfilesRq
AuthentCnfgInsertDPPRq
AuthentCnfgUpdateDPPRq
AuthentCnfgViewDPPRq
AuthentCnfgViewDPPSummaryRq

Authorization Script Configuration Window

Task ID:	AuthScript
Permissions:	FullAuthScriptPermission ViewAuthScriptPermission
Related Permissions:	FullScriptRepository ViewScriptRepository
Help ID:	w_authorization_script_configuration
Data Sources:	Authorization_Script
Desktop Access:	Configure > Script > Authorization Script
Messages:	AuthScriptListRq AuthScriptInsertRq AuthScriptViewRq AuthScriptUpdateRq AuthScriptDeleteRq AuthScriptGenericDeleteRq

Bank of America MultiLink Services (BAMS) Interface Configuration Window

Task ID:	BamsInterface
Permissions:	FullBamsInterfacePerm ViewBamsInterfacePerm
Help ID:	n/a
Data Sources:	INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Bank of America MultiLink Services (BAMS) Interface
Messages:	InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Banknet Acquirers Configuration Window

Task ID:	BanknetAcquirers
Permissions:	FullBanknetAcquirersPermission ViewBanknetAcquirersPermission
Help ID:	w_banknet_acquirers_configuration
Data Sources:	Banknet_Institution_Id
Desktop Access:	Configure > Interface > Network > Banknet > Banknet Acquirers
Messages:	BanknetInstitutionInsertRq BanknetInstitutionDeleteRq BanknetInstitutionUpdateRq BanknetInstitutionViewRq

Banknet/EPS-Net Program ID/Instrument Type Relationship Configuration Window

Task ID:	BepsBrandInstrmRelation
Permissions:	FullBepsBrandInstrmRelnPerm ViewBepsBrandInstrmRelnPerm FullInstrumentTypePermission ViewInstrumentTypePermission
Help ID:	w_banknet_epsnet_program_id_instrument_type_ relationship_configuration
Data Sources:	Netwk_Brand_Instrm_Reltn
Desktop Access:	Configure > Interface > Network > Banknet > Banknet/EPS- Net Program ID/Instrument Type Relationship
Messages:	NetwkBrandInstrmRelnViewRq NetwkBrandInstrmRelnInsertRq NetwkBrandInstrmRelnUpdateRq NetwkBrandInstrmRelnDeleteRq

Banknet ISO Interface Configuration Window

Task ID:	BanknetInterface
Permissions:	FullBanknetInterfacePermission ViewBanknetInterfacePermission
Help ID:	w_banknet_iso_interface_configuration
Data Sources:	Banknet_Configuration INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Banknet > Banknet ISO Interface
Messages:	BanknetMerchantProgramInsertRq BanknetMerchantProgramViewRq BanknetMerchantProgramUpdateRq BanknetMerchantProgramDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

(Banknet) Merchant Programs Configuration Window

Task ID:	BanknetMerchantProgram
Permissions:	FullBanknetMerchProgPermission
Help ID:	w_merchant_programs_configuration
Data Sources:	Banknet_Merchant_Program
Desktop Access:	Configure > Interface > Network > Banknet > Merchant Programs
Messages:	BanknetMerchantProgramInsertRq BanknetMerchantProgramDeleteRq BanknetMerchantProgramUpdateRq BanknetMerchantProgramViewRq

BASE24 ISO8583 (87) Host Interface Configuration Window

Task ID:	B24HISOInterfaceConfig
Permissions:	FullB24HISOIFConfigPermission ViewB24HISOIFConfigPermission
Help ID:	w_base24_iso8583_host_interface_configuration
Data Sources:	HISO87_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Host > ISO8583 (87) > BASE24 ISO8583 (87) Host Interface
Messages:	HISO87InsertRq HISO87ViewRq HISO87UpdateRq HISO87DeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

BASE24 ISO8583 (87) IMS/CICS Mapping Configuration Window

Task ID:	ImsCicsMapping
Permissions:	FullImsCicsMappingPermission ViewImsCicsMappingPermission
Help ID:	w_base24_iso8583_ims_cics_mapping_configuration
Data Sources:	HISO87_PROC_TXN
Desktop Access:	Configure > Interface > Host > ISO8583 (87) > BASE24 ISO8583 (87) IMS/CICS Mapping
Messages:	IMSCICSMapListRq IMSCICSMapViewRq IMSCICSMapInsertRq IMSCICSMapUpdateRq IMSCICSMapDeleteRq IMSCICSMapGenericDeleteRq

BASE24 KEYF Configuration Window

Task ID:	B24KEYFSecurity
Permissions:	FullB24KEYFSecuritPermission ViewB24KEYFSecuritPermission
Help ID:	w_base24_keyf_configuration
Data Sources:	BASE24_KEYF
Desktop Access:	Configure > BASE24 > KEYF
Messages:	B24KEYFGetFIIDListRq B24KEYFInsertRq B24KEYFGetSymbolicNameListRq

BASE24-atm Transaction Mapping Profile Configuration Window

Task ID:	B24AtmTranMapping
Permissions:	FullB24ATMTranMapPermission ViewB24ATMTranMapPermission
Help ID:	w_base24atm_transaction_mapping_profile
Data Sources:	ATM_TC_Proc_Code Proc_Code_ATM_TC
Desktop Access:	Configure > BASE24 > Transaction Mapping > ATM
Messages:	B24AtmTranMappingListRq B24AtmTranMappingInbInsertRq B24AtmTranMappingOutInsertRq B24AtmTranMappingInbViewRq B24AtmTranMappingInbUpdateRq B24AtmTranMappingOutViewRq B24AtmTranMappingOutUpdateRq B24AtmTranMappingInbDeleteRq B24AtmTranMappingOutDeleteRq B24AtmTranMappingGenericDeleteRq

BASE24-pos Transaction Mapping Profile Configuration Window

Task ID:	B24PosTranMapping
Permissions:	FullB24POSTranMapPermission ViewB24POSTranMapPermission
Help ID:	w_base24pos_transaction_mapping_profile
Data Sources:	POS_TC_Proc_Code Proc_Code_POS_TC
Desktop Access:	Configure > BASE24 > Transaction Mapping > POS
Messages:	B24PosTranMappingListRq B24PosTranMappingInbInsertRq B24PosTranMappingOutInsertRq B24PosTranMappingInbViewRq B24PosTranMappingInbUpdateRq B24PosTranMappingOutViewRq B24PosTranMappingOutUpdateRq B24PosTranMappingInbDeleteRq B24PosTranMappingOutDeleteRq B24PosTranMappingGenericDeleteRq

Batch Authorization Configuration Window

Task ID:	BatchAuth
Permissions:	FullBatchAuthPermission ViewBatchAuthPermission
Help ID:	w_batch_authorization_configuration
Data Sources:	BATCH_AUTH
Desktop Access:	Configure > Interface > Host > Batch Authorization > Batch Authorization
Messages:	BatchAuthListRq BatchAuthViewRq BatchAuthInsertRq BatchAuthUpdateRq BatchAuthDeleteRq

Batch Authorization ISO8583 (93) Host Interface Configuration Window

Task ID:	BatchAuthHISO93
Permissions:	FullBatchAuthHISO93Permission ViewBatchAuthHISO93Permission
Help ID:	w_iso_93_host_interface_configuration
Data Sources:	BATCH_AUTH_HISO93 INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Host > Batch Authorization > Batch Authorization ISO8583 (93) Host
Messages:	HISO93InsertRq HISO93ViewRq HISO93UpdateRq HISO93DeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq

Benefit Interface Configuration Window

Task ID:	BenefitInterface
Permissions:	FullBenefitInterfacePermission ViewBenefitInterfacePermission
Help ID:	n/a
Data Sources:	BNFT_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Benefit ISO Interface
Messages:	IfBenefitViewRq IfBenefitInsertRq IfBenefitUpdateRq IfBenefitDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

BIC ISO (87) Interface Configuration Window

Task ID:	BicIsoInterface
Permissions:	FullBicIsoInterfacePermission
Help ID:	w_bic_iso_87_interface_configuration
Data Sources:	BIC_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > BIC ISO (87) Interface
Messages:	IfBicIsoViewRq IfBicIsoInsertRq IfBicIsoUpdateRq IfBicIsoDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

BNTng Key Header Configuration Window

Task ID:	BNTngHeaderConfig
Permissions:	FullBNTngHdrCnfgPermission ViewBNTngHdrCnfgPermission
Help ID:	w_bntng_key_header_configuration
Data Sources:	BNTng_Header
Desktop Access:	Configure > Transaction Security > BNTng Header
Messages:	BNTngHeaderInsertRq BNTngHeaderListRq BNTngHeaderViewRq BNTngHeaderUpdateRq BNTngHeaderDeleteRq

Cache Administration Window

Task ID:	IWTCacheAdministration
Permissions:	FullIWTCacheAdminPermission ViewIWTCacheAdministration
Help ID:	w_cache_administration
Data Sources:	n/a
Desktop Access:	System Operations > Server Management > Server Administration > Cache Administration
Messages:	IWTFCacheAdminListRq IWTFCacheAdminResetRq

Card Block Configuration Window

Task ID:	CardBlockConfig
Permissions:	FullCardBlockConfigPerm ViewCardBlockConfigPerm
Help ID:	w_card_block_configuration
Data Sources:	Card_Block
Desktop Access:	Customer Management > Card Block
Messages:	CardBlockConfigGenericDeleteRq CardBlockConfigDeleteRq CardBlockConfigInsertRq CardBlockConfigListRq CardBlockConfigUpdateRq CardBlockConfigViewRq

Card Management Window

Task ID:	CardConfiguration CardAccount CardLimits CardStatus FindCard
Permissions:	FullCardConfigPermission ViewCardConfigPermission FullCardAccountPermission ViewCardAccountPermission FullCardAddressPermission ViewCardAddressPermission FullCardLimitsPermission ViewCardLimitsPermission FullCardStatusPermission ViewCardStatusPermission FullFindCardPermission ViewFindCardPermission
Help ID:	w_card_management
Data Sources:	Card Card_Account Environment
Desktop Access:	Customer Management > Card
Messages:	CardEnvParamRq CardInsertRq CardPANListRq CardAcctInsertRq CardViewRq CardUpdateRq CardAcctViewRq CardAcctUpdateRq CardAcctDeleteRq CardDeleteRq

Certificate Management Window

Task ID:	Certificate
Permissions:	FullCertificatePermission ViewCertificatePermission
Help ID:	w_certificate_management
Data Sources:	n/a
Desktop Access:	Configure > Transaction Security > Automated Key Distribution > Certificate Management
Messages:	CertGenMesgDigestRq CertGetPublicKeyDataRq CertValidateRq

Channel Public Key Perusal Window

Task ID:	ChannelPKPerusal
Permissions:	FullChannelPKPerusalPermission ViewChannelPKPerusalPermission
Help ID:	w_channel_public_key_perusal
Data Sources:	Channel_Public_Key_Security
Desktop Access:	View > Automated Key Distribution > Channel Public Key Perusal
Messages:	ChannelPubKeyListRq

Channel Security Configuration Window

Task ID:	ChannelSecurity
Permissions:	FullChannelSecurityPermission ViewChannelSecurityPermission
Help ID:	w_channel_security_configuration
Data Sources:	Channel_Security
Desktop Access:	Configure > Transaction Security > Channel
Messages:	ChannelIDSecurListGetRq ChannelListGetRq

Check Management Window

Task ID:	Check
Permissions:	FullCheckPermission ViewCheckPermission
Help ID:	w_check_management
Data Sources:	Check
Desktop Access:	Customer Management > Check
Messages:	CheckRttnListRq CheckAccountListRq CheckViewRq CheckInsertRq CheckUpdateRq CheckDeleteRq CheckGenericDeleteRq

Check Type Configuration Window

Task ID:	CheckType
Permissions:	FullCheckTypePermission ViewCheckTypePermission
Help ID:	w_check_type_configuration
Data Sources:	CHECK_TYPE
Desktop Access:	Configure > Check Type
Messages:	CheckTypeListRq CheckTypeViewRq CheckTypeInsertRq CheckTypeUpdateRq CheckTypeDeleteRq CheckTypeGenericDeleteRq

China Union Pay (CUP) Interface Configuration Window

Task ID:	CupInterface
Permissions:	FullCupInterfacePermission ViewCupInterfacePermission
Help ID:	n/a
Data Sources:	CUP_INTERFACE INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > China Union Pay (CUP) Interface
Messages:	IfCupViewRq IfCupInsertRq IfCupUpdateRq IfCupDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Circuit Interface Configuration Window

Task ID:	CircuitInterface
Permissions:	FullCircuitInterfacePermission ViewCircuitInterfacePermission
Help ID:	n/a
Data Sources:	CIRCUIT_INTERFACE INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Circuit Interface
Messages:	IfCircuitViewRq IfCircuitInsertRq IfCircuitUpdateRq IfCircuitDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Cirrus/Maestro Brand ID/Instrument Type Relationship Configuration Window

Task ID:	MasterCardIpF
Permissions:	FullMasterCardIpFPermission ViewMasterCardIpFPermission FullInstrumentTypePermission ViewInstrumentTypePermission
Help ID:	w_cirrus_maestro_brand_id_instrument_type_relationship_configuration
Data Sources:	Netwk_Brand_Instrm_Reln
Desktop Access:	Configure > Interface > Network > MasterCard > Cirrus/ Maestro Brand ID/Instrument Type Relationship
Messages:	n/a

Configuration Properties Window

Task ID:	IWTConfigurationAdministration
Permissions:	FullIWTConfigAdminPermission ViewIWTConfigurationAdmin
Help ID:	w_configuration_properties
Data Sources:	n/a
Desktop Access:	System Operations > Server Management > Server Administration > Configuration Properties
Messages:	IWTFCfgPropertiesListRq IWTFCfgPropertiesReloadRq

Context Profile Configuration Window

Task ID:	ContextConfiguration
Permissions:	FullContextConfigPermission ViewContextConfigPermission
Help ID:	w_context_profile_configuration
Data Sources:	Context_Configuration
Desktop Access:	Configure > Interface > Context Profile
Messages:	ContextConfigInsertRq ContextConfigListRq ContextConfigViewRq ContextConfigUpdateRq ContextConfigDeleteRq

Contingency Interface Configuration Window

Task ID:	ContingencyInterface
Permissions:	FullContingencyInterface
Help ID:	w_contingency_interface_configuration
Data Sources:	Contingency_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Host > Contingency
Messages:	IntffworkContingencyViewRequest IntffworkContingencyUpdateRequest IntffworkContingencyInsertRequest IntffworkContingencyDeleteRequest InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Contingency Store and Forward (SAF) Configuration Window

Task ID:	ContingencySAF
Permissions:	FullContingencySAFPermission ViewContingencySAFPermission
Help ID:	w_contingency_store_and_forward
Data Sources:	Store_and_Forward
Desktop Access:	System Operations > Contingency SAF
Messages:	ContingencySAFCnfgViewRq ContingencySAFCnfgUpdateRq

COOP Interface Configuration Window

Task ID:	CoopInterface
Permissions:	FullCoopInterfacePermission
Help ID:	n/a
Data Sources:	EFunds_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > COOP Interface
Messages:	IfEFundsViewRq IfEFundsInsertRq IfEFundsUpdateRq IfEFundsDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Credit Union 24 (CU24) Institution Configuration Window

Task ID:	Cu24Institution
Permissions:	FullCu24InstitutionPermission
Help ID:	n/a
Data Sources:	B53_INSTITUTION
Desktop Access:	Configure > Interface > Network > Credit Union 24 (CU24) > Credit Union 24 (CU24) Institution
Messages:	B53InstitutionListRq B53InstitutionViewRq B53InstitutionInsertRq B53InstitutionUpdateRq B53InstitutionDeleteRq

Credit Union 24 (CU24) Interface Configuration Window

Task ID:	Cu24Interface
Permissions:	FullCu24InterfacePermission
Help ID:	n/a
Data Sources:	INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Credit Union 24 (CU24) > Credit Union 24 (CU24) Interface
Messages:	InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

CSC Interface Configuration Window

Task ID:	CSC
Permissions:	FullCSCPermission ViewCSCPermission
Help ID:	w_iso_93_host_interface_configuration
Data Sources:	HISO93_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Host > CSC Interface
Messages:	IntffworkHISO93ViewRq IntffworkHISO93InsertRq IntffworkHISO93UpdateRq IntffworkHISO93DeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Currency Conversion Rate Configuration Window

Task ID:	CurrencyConvRateConfiguration
Permissions:	FullCrncyConvRateCfgPermission ViewCurrencyConvRateConfig
Help ID:	w_currency_conversion_rate_configuration
Data Sources:	Currency_Conversion_Rate
Desktop Access:	Configure > Currency Conversion > Currency Conversion Rate
Messages:	CurrConvRateInsertRq CurrConvRateListRq CurrConvRateUpdateRq CurrConvRateDeleteRq CurrConvRateGenericDeleteRq

Database Administration Window

Task ID:	IWTDatabaseAdministration
Permissions:	FullIWTDatabaseAdminPermission ViewIWTDatabaseAdministration
Help ID:	w_database_administration
Data Sources:	n/a
Desktop Access:	System Operations > Server Management > Server Administration > Database Administration
Messages:	IWTFDBConnectionAdminViewRq

Destination Routing Profile Configuration Window

Task ID:	IssuerProfileConfig
Permissions:	FullIssProfConfigPermission ViewIssurerProfileConfig
Help ID:	w_destination_routing_profile_configuration
Data Sources:	Issuer_Route_Profile
Desktop Access:	Configure > Routing > Profile Description > Destination Routing Profile
Messages:	DestinationRoutingProfileViewRq DestinationRoutingProfileInsertRq DestinationRoutingProfileUpdateRq DestinationRoutingProfileDeleteRq

DIAS Interface Configuration Window

Task ID:	DiasInterface
Permissions:	FullDiasInterfacePermission ViewDiasInterfacePermission
Help ID:	n/a
Data Sources:	DIAS_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > DIAS Interface
Messages:	IfDiasViewRq IfDiasInsertRq IfDiasUpdateRq IfDiasDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Disable KEYGEN Window

Task ID:	KEYGENLockdown
Permissions:	FullKEYGENLockdownPermission ViewKEYGENLockdownPermission
Help ID:	w_disable_keygen
Data Sources:	n/a
Desktop Access:	Configure > Transaction Security > Automated Key Distribution > Disable KEYGEN
Messages:	DisableKeyGenViewRq DisableKeyGenUpdateRq

Discover Acquirers Configuration Window

Task ID:	DiscoverAcquirers
Permissions:	FullDiscoverAcquirersPerm ViewDiscoverAcquirersPerm
Help ID:	w_discover_acquirers_configuration
Data Sources:	DISCOVER_INST
Desktop Access:	Configure > Interface > Network > Discover > Discover Acquirers
Messages:	n/a

Discover Interface Configuration Window

Task ID:	DiscoverInterface
Permissions:	FullDiscoverInterfacePerm ViewDiscoverInterfacePerm
Help ID:	w_discover_interface_configuration
Data Sources:	DISCOVER_INTF
Desktop Access:	Configure > Interface > Network > Discover > Discover Interface
Messages:	IfDiscoverViewRq IfDiscoverInsertRq IfDiscoverUpdateRq IfDiscoverDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

DUKPT Derivation Key Profile Configuration Window

Task ID:	B24SPDHDDUKPTDerivationKey
Permissions:	FullB24SPDHDDUKPTDKeyPermission ViewB24SPDHDDUKPTDKeyPermission
Help ID:	w_dukpt_derivation_key_profile_configuration
Data Sources:	Derivation_Key
Desktop Access:	Configure > Transaction Security > DUKPT Derivation Key Profile
Messages:	DrvKeyInsertRq DrvKeyProfileListRq DrvKeyViewRq DrvKeyUpdateRq DrvKeyDeleteRq

EFD (eFunds) Interface Configuration Window

Task ID:	EFundsInterface
Permissions:	FullEFundsInterfacePermission ViewEFundsInterfacePermission FullEFundsInterfaceUIPerm ViewEFundsInterfaceUIPerm
Help ID:	n/a
Data Sources:	EFunds_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > EFD (eFunds) Interface
Messages:	IfEFundsViewRq IfEFundsInsertRq IfEFundsUpdateRq IfEFundsDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

(EFD (eFunds)) Interface Terminal Configuration Window

Task ID:	EfundsInterfaceTerminal
Permissions:	FullEfundsInterfaceTermPerm ViewEfundsInterfaceTermPerm
Help ID:	n/a
Data Sources:	Interface_Terminal
Desktop Access:	Configure > Interface > Network > EFD (eFunds) Interface Terminal
Messages:	InterfaceTerminalListRq InterfaceTerminalViewRq InterfaceTerminalInsertRq InterfaceTerminalUpdateRq InterfaceTerminalDeleteRq

ELAN Acquirers Configuration Window

Task ID:	ElanInsitution
Permissions:	FullElanInstitutionPermission ViewElanInstitutionPermission
Help ID:	n/a
Data Sources:	Elan_Institution
Desktop Access:	Configure > Interface > Network > ELAN > ELAN Acquirers
Messages:	ElanInstitutionListRq ElanInstitutionViewRq ElanInstitutionInsertRq ElanInstitutionUpdateRq ElanInstitutionDeleteRq

ELAN ISO Interface Configuration Window

Task ID:	ElanInterface
Permissions:	FullElanInterfacePermission ViewElanInterfacePermission
Help ID:	n/a
Data Sources:	Interface Interface_SAF Interface_Station
Desktop Access:	Configure > Interface > Network > ELAN > ELAN ISO Interface
Messages:	InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

EMV Card Verification Results (CVR) Results Status Window

Task ID:	EMVCardVerifResultsStatusUI
Permissions:	FullEMVCrdVrfRsItsStatUIPerm
Help ID:	w_emv_card_verification_results_status_configuration
Data Sources:	EMV_Card_Vrfrn_Results_Status
Desktop Access:	Configure > EMV > Card Verification Results Status
Messages:	EMVCardVerifResultsDetailListRq EMVCardVerifResultsDetailInsertRq EMVCardVerifResultsDetailUpdateRq EMVCardVerifResultsDetailDeleteRq

EMV Issuer Authentication Configuration Window

Task ID:	EMVIssAuthConfig
Permissions:	FullEMVIssAuthConfigPermission ViewEMVIssAuthConfigPermission
Help ID:	w_emv_issuer_authentication_configuration
Data Sources:	EMV_Iss_Auth_Dta
Desktop Access:	Configure > Transaction Security > Automated Key Distribution > EMV Issuer Authentication
Messages:	EMVIssuerAuthDeleteRq EMVIssuerAuthInsertRq EMVIssuerAuthListRq EMVIssuerAuthUpdateRq EMVIssuerAuthViewRq

EMV Reason Online Code (ROC) Description Configuration

Task ID:	EMVReasonOnlineCodeDescrUI
Permissions:	FullEMVReasonOnlCdeDscrUIPerm
Help ID:	w_emv_reason_online_code_description_configuration
Data Sources:	Reason_Online_Code_Description
Desktop Access:	Configure > EMV > Reason Online Code Description
Messages:	EMVReasonOnlineCodeDescrViewRq EMVReasonOnlineCodeDescrInsertRq EMVReasonOnlineCodeDescrInsertRqEntry EMVReasonOnlineCodeDescrUpdateRq EMVReasonOnlineCodeDescrUpdateRqEntry EMVReasonOnlineCodeDescrDeleteRq EMVReasonOnlineCodeDescrDeleteRqEntry

EMV Reason Online Code Status Window

Task ID:	EMVReasonOnlineCodeStatusUI
Permissions:	FullEMVReasonOnlCdeStatUIPerm
Help ID:	w_emv_reason_online_code_status_configuration
Data Sources:	EMV_Reason_Online_Code_Status
Desktop Access:	Configure > EMV > Reason Online Code Status
Messages:	EMVReasonOnlineCodeViewRq EMVReasonOnlineCodeInsertRq EMVReasonOnlineCodeInsertRqEntry EMVReasonOnlineCodeUpdateRq EMVReasonOnlineCodeUpdateRqEntry EMVReasonOnlineCodeDeleteRqEntry EMVReasonOnlineCodeDeleteRqEntry

EMV Terminal Verification Results Status Window

Task ID:	EMVTermVerifResultsStatusUI
Permissions:	FullEMVTrmVrfRsItsStatUIPerm
Help ID:	w_emv_terminal_verification_results_status_configuration
Data Sources:	EMV_Terminal_Vrfrn_Results_Status
Desktop Access:	Configure > EMV > EMV Terminal Verification Results Status
Messages:	EMVTerminalVerifResultsDetailListRq EMVTerminalVerifResultsInsertRq EMVTerminalVerifResultsInsertRqEntry EMVTerminalVerifResultsUpdateRq EMVTerminalVerifResultsDeleteRq

Environment Configuration Window

Task ID:	EnvironmentManagement
Permissions:	FullEnvironmentMgmtPermission ViewEnvironmentMgmtPermission
Help ID:	w_environment_configuration
Data Sources:	Environment
Desktop Access:	System Operations > Environment
Messages:	EnvironmentInsertRq EnvironmentViewRq EnvironmentUpdateRq EnvironmentDeleteRq

EPP Serial Number Configuration Window

Task ID:	EPPSerialNumberConfig
Permissions:	FullEPPSerialNumCfgPermission ViewEPPSerialNumCfgPermission
Help ID:	w_epp_serial_number_configuration
Data Sources:	EPP_Serial_Number
Desktop Access:	Configure > Transaction Security > Automated Key Distribution > EPP Serial Number
Messages:	EPPSerNumInsertRq EPPSerNumViewRq EPPSerNumUpdateRq EPPSerNumDeleteRq

EPS-Net Institution Configuration Window

Task ID:	EPSNetInstitution
Permissions:	FullEPSNetInstPermission ViewEPSNetInstPermission
Help ID:	w_epsnet_institution_configuration
Data Sources:	EPSNET_Inst
Desktop Access:	Configure > Interface > Network > EPS-Net > EPS-Net Institution
Messages:	EPSNetInstitutionInsertRq EPSNetInstitutionListRq EPSNetInstitutionViewRq EPSNetInstitutionUpdateRq EPSNetInstitutionDeleteRq

EPS-Net ISO Interface Configuration Window

Task ID:	EPSNetInterfaceConfiguration
Permissions:	FullEPSNetInterfacePermission ViewEPSNetInterfacePermission
Help ID:	w_epsnet_iso_interface_configuration
Data Sources:	EPSNET_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > EPS-Net > EPS-Net ISO Interface
Messages:	EPSNetInsertRq EPSNetViewRq EPSNetUpdateRq EPSNetDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Equens BIM Instrument Type Mapping Profile Configuration Window

Task ID:	EquensInstrumentType
Permissions:	FullEquensInstrumentTypePerm ViewEquensInstrumentTypePerm
Help ID:	n/a
Data Sources:	EQUENS_INSTRM_TYP_EXTRN EQUENS_INSTRM_TYP_INTRN
Desktop Access:	Configure > Interface > Network > Equens BIM > Equens BIM Instrument Type Mapping
Messages:	EquensInstrumentTypeMappingInbViewRq EquensInstrumentTypeMappingInbInsertRq EquensInstrumentTypeMappingInbUpdateRq EquensInstrumentTypeMappingInbDeleteRq EquensInstrumentTypeMappingOutViewRq EquensInstrumentTypeMappingOutInsertRq EquensInstrumentTypeMappingOutUpdateRq EquensInstrumentTypeMappingOutDeleteRq

Equens BIM Interface Configuration Window

Task ID:	EquensInterface
Permissions:	FullEquensInterfacePermission ViewEquensInterfacePermission
Help ID:	n/a
Data Sources:	EQUENS_INTERFACE INTERFACE INTERFACE_STA INTERFACE_MGR INTERFACE_SAF
Desktop Access:	Configure > Interface > Network > Equens BIM > Equens BIM Interface
Messages:	IfEquensViewRq IfEquensInsertRq IfEquensUpdateRq IfEquensDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkInsertRq InterfaceFrameworkUpdateRq InterfaceFrameworkDeleteRq

E-RSB ISO Interface Configuration Window

Task ID:	ERsbInterface
Permissions:	FullERsbInterfacePerm ViewERsbInterfacePerm
Help ID:	n/a
Data Sources:	ERSB_INTERFACE INTERFACE INTERFACE_STA INTERFACE_MGR INTERFACE_SAF
Desktop Access:	Configure > Interface > Network > E-RSB ISO Interface
Messages:	IfErsbViewRq IfErsbInsertRq IfErsbUpdateRq IfErsbDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkInsertRq InterfaceFrameworkUpdateRq InterfaceFrameworkDeleteRq

Euro Opted Currency Configuration Window

Task ID:	EuroOptedCurrencyConfiguration
Permissions:	FullEuroOptedCurrCfgPermission ViewEuroOptedCurrencyConfig
Help ID:	w_euro_opted_currency_configuration
Data Sources:	Euro_Opted_Currency
Desktop Access:	Configure > Currency Conversion > Euro Opted Currency
Messages:	EuroOptCurrInsertRq EuroOptCurrListRq EuroOptCurrUpdateRq EuroOptCurrDeleteRq

Event Configuration and Management Window

Task ID:	EventConfiguration
Permissions:	FullEventConfigPermission ViewEventConfiguration
Help ID:	w_integrated_server_event_configuration
Data Sources:	Event
Desktop Access:	System Operations > Event > Event Management
Messages:	EventListRq EventViewRq EventInsertRq EventUpdateRq EventDeleteRq

Event Perusal Window

Note: This window is only available on IBM System z and Unix platforms.

Task ID:	EventPerusal
Permissions:	FullEventPerusalPermission ViewEventPerusalPermission
Help ID:	w_event_perusal
Data Sources:	EVNTLOG
Desktop Access:	System Operations > Event > Event Perusal
Messages:	EventPerusalViewRq

Event Subsystem ID Configuration Window

Task ID:	EventSubsystemConfiguration
Permissions:	FullEventSubConfigPermission ViewEventSubsystemConfig
Help ID:	w_event_subsystem_id_configuration
Data Sources:	Event_Document
Desktop Access:	System Operations > Event > Subsystem ID
Messages:	n/a

Exported Operators Configuration Window

Task ID:	ExportedOperator
Permissions:	FullExportedOperatorPermission ViewExportedOperatorPermission
Help ID:	w_exported_operators_configuration
Data Sources:	Exported_Operator_Documentation
Desktop Access:	Configure > Script > Exported Operators
Messages:	ExpOperListRq ExpOperInsertRq ExpOperViewRq ExpOperUpdateRq ExpOperDeleteRq

External Connection Configuration Window

Task ID:	IWTConnectionConfig
Permissions:	FullIWTConnectionCfgPermission ViewIWTConnectionCfgPermission
Help ID:	w_external_connection_configuration
Data Sources:	EXTRCNCT
Desktop Access:	System Operations > Server Management > External Connection
Messages:	IWTFCConnectionListRq IWTFCConnectionInsertRq IWTFCConnectionViewRq IWTFCConnectionUpdateRq IWTFCConnectionDeleteRq

FDR ISO Interface Configuration Window

Task ID:	FDRInterface
Permissions:	FullFDRInterfacePermission ViewFDRInterfacePermission
Help ID:	n/a
Data Sources:	Interface Interface_SAF Interface_Station
Desktop Access:	Configure > Interface > Network > FDR ISO Interface
Messages:	InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Fifth Third Institution Configuration Window

Task ID:	B53Institution
Permissions:	FullB53InstitutionPermission ViewB53InstitutionPermission FullInstConfigPermission ViewInstConfigPermission FullInterfaceConfigPermission ViewInterfaceConfigPermission
Help ID:	n/a
Data Sources:	B53_INSTITUTION
Desktop Access:	Configure > Interface > Network > Fifth Third > Fifth Third Institution
Messages:	B53InstitutionListRq B53InstitutionViewRq B53InstitutionInsertRq B53InstitutionUpdateRq B53InstitutionDeleteRq InstConfigGetIDListRq InstConfigGetIDListFilteredRq InterfaceFrameworkListRq

Fifth Third ISO Interface Configuration Window

Task ID:	B53IsoInterface
Permissions:	FullB53IsoInterfacePermission ViewB53IsoInterfacePermission
Help ID:	n/a
Data Sources:	FIFTH_THIRD_INTF
Desktop Access:	Configure > Interface > Network > Fifth Third > Fifth Third ISO Interface
Messages:	IfB53IsoViewRq IfB53IsoInsertRq IfB53IsoUpdateRq IfB53IsoDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkInsertRq InterfaceFrameworkUpdateRq InterfaceFrameworkDeleteRq

File Partition Configuration Window

Task ID:	FilePartition
Permissions:	FullFilePartitionPermission ViewFilePartitionPermission
Help ID:	w_file_partition_configuration
Data Sources:	file_part_fields file_part_list
Desktop Access:	System Operations > Database Management > File Partition
Messages:	FilePartAssgnFieldsListRq FilePartAssgnListRq FilePartCatalogInsertRq FilePartCatalogUpdateRq FilePartCatalogViewRq FilePartGenericDeleteRq

File Update Router Configuration Window

Task ID:	FileUpdateRouterConfig
Permissions:	FullFileUpdateRouterConfigPerm ViewFileUpdateRouterConfigPerm
Help ID:	w_file_update_router_configuration
Data Sources:	File_Update_Route
Desktop Access:	Configure > Routing > File Update Router
Messages:	FilUpdRtrInsertRq FilUpdRtrListRq FilUpdRtrViewRq FilUpdRtrDeleteRq FilUpdRtrGenericDeleteRq

German BLZ Mapping Window

Task ID:	BLZMapping
Permissions:	FullBLZMappingPermission ViewBLZMappingPermission
Help ID:	w_german_blz_mapping
Data Sources:	BLZ_Map
Desktop Access:	Configure > German BLZ Mapping
Messages:	BLZMappingViewRq BLZMappingInsertRq BLZMappingUpdateRq BLZMappingDeleteRq

German ISO Credit Card (GICC) Interface Configuration Window

Task ID:	GICCInterface
Permissions:	FullGiccInterfacePermission ViewGiccInterfacePermission
Help ID:	n/a
Data Sources:	GICC_Interface Interface Interface_SAF Interface_Station
Desktop Access:	Configure > Interface > Network > German
Messages:	IfGiccViewRq IfGiccInsertRq IfGiccUpdateRq IfGiccDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

GICC POS Channel Configuration Window

Task ID:	GICCPOSChannel
Permissions:	FullGICCPOSChannelPerm ViewGICCPOSChannelPerm
Help ID:	w_gicc_pos_channel_configuration
Data Sources:	GICC_Channel
Desktop Access:	Configure > Merchant Processing > German ISO Credit Card > GICC POS Channel
Messages:	GICCPOSChannelGenericDeleteRq GICCPOSChannelDeleteRq GICCPOSChannelInsertRq GICCPOSChannelListRq GICCPOSChannelUpdateRq GICCPOSChannelViewRq

Host Public Key Perusal Window

Task ID:	HostPKPerusal
Permissions:	FullHostPKPerusalPermission ViewHostPKPerusalPermission
Help ID:	w_host_public_key_perusal
Data Sources:	HOST_Public_Key_Security_Primary HOST_Public_Key_Security_Secondary
Desktop Access:	View > Automated Key Distribution > Host Public Key Perusal
Messages:	HostPubKeyListRq

Hypercom NAC Profile Window

Task ID:	HypercomNac
Permissions:	FullHypercomNacPermission
Help ID:	w_hypercom_nac_profile_configuration
Data Sources:	HPDH_NAC_Term
Data Sources:	Configure > Merchant Processing > Hypercom NAC Profile
Messages:	HypercomNacViewRq HypercomNacInsertRq HypercomNacUpdateRq HypercomNacDeleteRq

Hypercom NMS Profile Window

Task ID:	HypercomNms
Permissions:	FullHypercomNmsPermission
Help ID:	w_hypercom_nms_profile_configuration
Data Sources:	HPDH_NMS_Term
Desktop Access:	Configure > Merchant Processing > Hypercom NMS Profile
Messages:	HypercomNmsViewRq HypercomNmsInsertRq HypercomNmsUpdateRq HypercomNmsDeleteRq

IFX Host Action Code Profile Configuration Window

Task ID:	IFXHostActionCode
Permissions:	FullIFXHostActCdPermission ViewIFXHostActCdPermission
Help ID:	w_ifx_host_action_code_profile_configuration
Data Sources:	IFX_Host_Action_Cod_Int_Ext
Desktop Access:	Configure > Interface > Host > IFX Host > IFX Host Action Code Profile
Messages:	IFX Host Action Code Profile IFXHostActionCodeListRq IFXHostActionCodeInsertRq IFXHostActionCodeViewRq IFXHostActionCodeUpdateRq IFXHostActionCodeDeleteRq IFXHostActionCodeGenericDeleteRq

IFX Host Interface Configuration Window

Task ID:	IFXHostInterface
Permissions:	FullIFXHostIntfPermission ViewIFXHostIntfPermission
Help ID:	w_ifx_host_interface_configuration
Data Sources:	IFX_Host_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Host > IFX Host > IFX Host Interface
Messages:	IFXHostInterfaceInsertRq IFXHostInterfaceViewRq IFXHostInterfaceUpdateRq IFXHostInterfaceDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Institution Configuration Window

Task ID:	InstitutionConfiguration
Permissions:	FullInstConfigPermission ViewInstConfigPermission
Help ID:	w_institution_configuration
Data Sources:	Institution
Desktop Access:	Configure > Institution
Messages:	InstConfigGetIDListRq InstConfigGetIDListFilteredRq InstConfigInsertRq InstConfigViewRq InstConfigUpdateRq InstConfigDeleteRq

Instrument Status Mapping Profile Configuration Window

Task ID:	InstrStatusMappingProfile
Permissions:	FullInstStatMapPrflPermission ViewInstStatMapPrflPermission
Help ID:	w_instrument_status_mapping_profile_configuration
Data Sources:	Instrm_Status_Extrn_to_Intrn
Desktop Access:	Configure > Instrument Type > Instrument Status Mapping Profile
Messages:	InstrumentStatusMappingInsertRq InstrumentStatusMappingListRq InstrumentStatusMappingViewRq InstrumentStatusMappingUpdateRq InstrumentStatusMappingDeleteRq InstrumentStatusMappingGenericDeleteRq

Instrument Type Window

Task ID:	InstrumentTypeCnfg
Permissions:	FullInstrumentTypePermission
Help ID:	w_instrument_type_configuration
Data Sources:	Instrument_Type
Desktop Access:	Configure > Instrument Type > Instrument Type
Messages:	InstrumentTypeViewRq InstrumentTypeInsertRq InstrumentTypeUpdateRq InstrumentTypeDeleteRq

Instrument Type/Interchange Relationship Configuration Window

Task ID:	InstrumentTypeIchgRelation
Permissions:	FullInstTypIchgRelPermission ViewInstTypIchgRelPermission
Help ID:	w_instrument_type_interchange_relationship_configuration
Data Sources:	Instrum_Typ_Interchange_Rel
Desktop Access:	Configure > Instrument Type > Instrument Type/Interchange Relationship
Messages:	InstrumentTypeRelationListRq InstrumentTypeRelationInsertRq InstrumentTypeRelationUpdateRq InstrumentTypeRelationDeleteRq

Interac Global Parameter Configuration Window

Task ID:	InteracBase
Permissions:	FullInteracBasePermission ViewInteracBasePermission
Help ID:	w_interac_global_parameter_configuration
Data Sources:	Interac_Base
Desktop Access:	Configure > Interface > Network > Interac > Interac Global Parameters
Messages:	InteracBaseViewRq InteracBaseInsertRq InteracBaseUpdateRq InteracBaseDeleteRq

Interac Institution ID Routing Configuration Window

Task ID:	InteracLinRouting
Permissions:	FullInteracLinRoutingPerm ViewInteracLinRoutingPerm
Help ID:	w_interac_institution_id_routing_configuration
Data Sources:	Interac_IIN
Desktop Access:	Configure > Interface > Network > Interac > Interac IIN Routing
Messages:	InteracIINRoutingViewRq InteracIINRoutingInsertRq InteracIINRoutingUpdateRq InteracIINRoutingDeleteRq

Interac Interface Configuration Window

Task ID:	InteracInterface
Permissions:	FullInteracInterfacePermission ViewInteracInterfacePermission
Help ID:	w_interac_interface_configuration
Data Sources:	Interac_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Interac > Interac Interface
Messages:	IfInteracViewRq IfInteracInsertRq IfInteracUpdateRq IfInteracDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Interchange Prefix Configuration Window

Task ID:	InterchangePrefixConfiguration
Permissions:	FullIchgPrefixConfigPermission ViewIchgPrefixConfigPermission
Help ID:	w_interchange_prefix_configuration
Data Sources:	System_Prefix
Desktop Access:	Configure > Prefix > Not-On-Us > Interchange Prefix
Messages:	InterchangePrefixInsertRq InterchangePrefixGetFileRq InterchangePrefixViewRq InterchangePrefixUpdateRq InterchangePrefixDeleteRq

Interface Security Configuration Window

Task ID:	InterfaceSecurityConfiguration
Permissions:	FullIFSecurityConfigPermission ViewIFSecurityConfigPermission
Help ID:	n/a
Data Sources:	Interchange_Security
Desktop Access:	Configure > Transaction Security > Interface
Messages:	InterfaceSafInsertRq InterfaceSafViewRq InterfaceListRequest InterfaceInsertRequest InterfaceStationInsertRq InterfaceSecInsertRq InterfaceViewRequest InterfaceUpdateRequest InterfaceStationListRq InterfaceStationUpdateRq InterfaceSecViewRq InterfaceSecUpdateRq InterfaceSecDeleteRq InterfaceStationDeleteRq InterfaceDeleteRequest

Interface Status Window

Task ID:	InterfaceStatus
Permissions:	FullInterfaceStatusPermission ViewInterfaceStatusPermission
Help ID:	w_interface_status
Data Sources:	n/a
Desktop Access:	System Operations > Interface > Interface Status
Messages:	InterfaceStatusAllInterfacesViewRq InterfaceStatusAllStationsViewRq InterfaceStationListRq

Interface Totals Window

Task ID:	InterfaceTotals
Permissions:	FullInterfaceTotalsPermission
Help ID:	w_interface_totals
Data Sources:	Totals
Desktop Access:	System Operations > Interface > Interface Totals
Messages:	InterfaceTotalsViewRq

Internal Message Translator (IMT) Interface Configuration Window

Task ID:	IMTInterface
Permissions:	FullIMTInterfacePermission ViewIMTInterfacePermission
Help ID:	w_imt_interface_configuration
Data Sources:	IMT_Interface Interface Interface_SAF Interface_Station
Desktop Access:	Configure > BASE24 > Internal Message Translator (IMT)
Messages:	IMTInsertRequest IMTViewRequest IMTUpdateRequest IMTDeleteRequest InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Interpay BIM Interface Configuration Window

Task ID:	InterpayInterface
Permissions:	FullInterpayIntfPermission ViewInterpayIntfPermission
Help ID:	w_interpay_bim_interface_configuration
Data Sources:	Ipay_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Interpay BIM
Messages:	InterPayInsertRq InterPayViewRq InterPayUpdateRq InterPayDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

ISO Message Profile Configuration Window

Task ID:	ISOFrameworkConfiguration
Permissions:	FullISOFrameworkCfgPermission ViewISOFrameworkCfgPermission
Help ID:	w_iso_message_profile_configuration
Data Sources:	ISO_Field ISO_Message
Desktop Access:	Configure > ISO > Message Profile
Messages:	ISOMsgPrflListRq ISOFldInsertRq ISOMsgInsertRq ISOFldViewRq ISOFldUpdateRq ISOMsgDataListRq ISOMsgUpdateRq ISOMsgDeleteRq ISOFldDeleteRq

ISO Transaction Mapping Profile Configuration Window

Task ID:	ISOTranMapping
Permissions:	FullISOTranMapPermission ViewISOTranMapPermission
Help ID:	w_iso_transaction_mapping_profile_configuration
Data Sources:	ISO_PROC_CODE PROC_CODE_ISO
Desktop Access:	Configure > ISO > Transaction Mapping
Messages:	IsoTranMappingListRq IsoTranMappingInbInsertRq IsoTranMappingOutInsertRq IsoTranMappingInbViewRq IsoTranMappingInbUpdateRq IsoTranMappingOutViewRq IsoTranMappingOutUpdateRq IsoTranMappingInbDeleteRq IsoTranMappingOutDeleteRq IsoTranMappingGenericDeleteRq

ISO8583 (93) Host Interface Configuration Window

Task ID:	B24HISO93InterfaceConfig
Permissions:	FullB24HISO93IFCnfgPermission ViewB24HISO93IFCnfgPermission
Help ID:	w_iso_93_host_interface_configuration
Data Sources:	HISO93_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Host > ISO8583 (93) Host
Messages:	HISO93InsertRq HISO93ViewRq HISO93UpdateRq HISO93DeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Issuer Transactions Allowed Profile Configuration Window

Task ID:	IssuerTransactionsAllowed
Permissions:	FullIssTransAllowedPermission ViewIssTransAllowedPermission
Help ID:	w_issuer_transactions_allowed_profile_configuration
Data Sources:	Issue_Txn_Allowed
Desktop Access:	Configure > Transactions Allowed > Issuer Transaction Profile
Messages:	IssuerTransAllowedInsertRq IssuerTransAllowedListRq IssuerTransAllowedViewRq IssuerTransAllowedUpdateRq IssuerTransAllowedDeleteRq IssuerTransAllowedGenericDeleteRq

JCB Acquirers Configuration Window

Task ID:	JcbAcquirers
Permissions:	FullJcbAcquirersPermission ViewJcbAcquirersPermission FullInstConfigPermission ViewInstConfigPermission FullInterfaceConfigPermission ViewInterfaceConfigPermission
Help ID:	n/a
Data Sources:	JCB_INSTITUTION
Desktop Access:	Configure > Interface > Network > JCB Acquirers
Messages:	JcbAcquirersListRq JcbAcquirersViewRq JcbAcquirersInsertRq JcbAcquirersUpdateRq JcbAcquirersDeleteRq InstConfigGetIDListRq InstConfigGetIDListFilteredRq InterfaceFrameworkListRq

JCB Interface Configuration Window

Task ID:	JcbInterface
Permissions:	FullJcbInterfacePermission
Help ID:	n/a
Data Sources:	JCB_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > JCB > JCB Interface
Messages:	IfJcbViewRq IfJcbInsertRq IfJcbUpdateRq IfJcbDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

JEANIE Institution Configuration Window

Task ID:	JeanieInstitution
Permissions:	FullJeanieInstPermission
Help ID:	n/a
Data Sources:	n/a
Desktop Access:	Configure > Interface > Network > JEANIE > JEANIE Institution
Messages:	n/a

JEANIE Interface Configuration Window

Task ID:	JeanieInterface
Permissions:	FullJeanieInterfacePermission
Help ID:	n/a
Data Sources:	INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > JEANIE > JEANIE Interface
Messages:	InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Journal Issuer Profile Relationship Configuration Window

Task ID:	JournalConfigurationMapping
Permissions:	FullJrnlCfgMappingPermission ViewJrnlCfgMappingPermission
Help ID:	w_journal_issuer_profile_relationship_configuration
Data Sources:	Issuer_Profile_Map
Desktop Access:	Configure > Journal > Issuer Profile Relationship
Messages:	IssuerPrflRelationViewRq IssuerPrflRelationInsertRq IssuerPrflRelationGenericDeleteRq IssuerPrflRelationUpdateRq

Journal Perusal Window

Task ID:	LogFilePerusal
Permissions:	FullLogFilePerusalPermission ViewLogFilePerusalPermission
Help ID:	w_journal_perusal
Data Sources:	n/a
Desktop Access:	View > Journal Perusal
Messages:	LFPGetSummaryScriptRq LFPGetDetailScriptRq LFPQuerySummaryRq LFPQueryDetailRq

Journal Profile Configuration Window

Task ID:	JournalProfileConfiguration
Permissions:	FullJrnlProfileCfgPermission ViewJrnlProfileCfgPermission
Help ID:	w_journal_profile_configuration
Data Sources:	Journal_Profile_Group Journal_Profile_Group_Assign
Desktop Access:	Configure > Journal > Journal Profile
Messages:	JournalCnfgListRq JournalCnfgGrpListRq JournalCnfgUpdateRq JournalCnfgInsertRq JournalCnfgGenericDeleteRq

Journal Query Configuration Window

Task ID:	JournalQueryConfiguration
Permissions:	FullJrnlQueryConfigPermission ViewJournalQueryConfiguration
Help ID:	w_journal_query_configuration
Data Sources:	Journal_Query_Config
Desktop Access:	Configure > Journal > Journal Query
Messages:	JournalQueryListRq JournalQueryInsertRq JournalQueryPositionViewRq JournalQueryViewRq JournalQueryUpdateRq JournalQueryDeleteRq

Journal TDE Suppression Configuration Window

Task ID:	JournalTDESuppression
Permissions:	FullJrnlTDESuppressPermission ViewJrnlTDESuppressPermission
Help ID:	w_journal_tde_suppression
Data Sources:	Journal_Data_Suppression
Desktop Access:	Configure > Journal > Journal TDE Suppression
Messages:	JrnlTdeSpInsertRq JrnlTdeSpListRq JrnlTdeSpViewRq JrnlTdeSpUpdateRq JrnlTdeSpDeleteRq JrnlTdeSpGenericDeleteRq

KEYGEN Command Configuration and Submission Window

Task ID:	KEYGENCommand
Permissions:	FullKEYGENCommandPermission
Help ID:	w_keygen_command_configuration_and_submission
Data Sources:	n/a
Desktop Access:	Configure > Transaction Security > Automated Key Distribution > KEYGEN Command Configuration and Submission
Messages:	KeyGenSubmitRq

KNET ISO Interface Configuration Window

Task ID:	KnetInterface
Permissions:	FullKnetInterfacePermission ViewKnetInterfacePermission
Help ID:	n/a
Data Sources:	BIC_Interface HISO87_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE Totals_Configuration
Desktop Access:	Configure > Interface > Network > KNET ISO Interface
Messages:	IfBicIsoViewRq IfBicIsoInsertRq IfBicIsoUpdateRq IfBicIsoDeleteRq HISO7InsertRq HISO87ViewRq HISO87UpdateRq HISO87DeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Limit Profile Management Window

Task ID:	PaymentLimitConfig
Permissions:	FullPmtLimitConfigPermission ViewPmtLimitConfigPermission
Help ID:	w_limit_profile_configuration
Data Sources:	Limits
Desktop Access:	Customer Management > Limit Profile
Messages:	LimitListRq LimitInsertRq LimitDetailRq LimitUpdateRq LimitDeleteRq LimitDeletePrflRq

LINK ISO Interface (LIS5) Configuration Window

Task ID:	LIS5Interface
Permissions:	FullLIS5InterfacePermission ViewLIS5InterfacePermission
Help ID:	w_link_lis5_interface_configuration
Data Sources:	LIS5_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > LINK ISO Interface
Messages:	Lis5InsertRq Lis5ViewRq Lis5UpdateRq Lis5DeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Linked Currency Configuration

Task ID:	LinkedCurrencyConfiguration
Permissions:	FullLinkedCurrCfgPermission ViewLinkedCurrencyConfig
Help ID:	w_linked_currency_configuration
Data Sources:	Linked_Currency
Desktop Access:	Configure > Currency Conversion > Linked Currency
Messages:	LinkedCurrencyInsertRq LinkedCurrencyListRq LinkedCurrencyDeleteRq

Listener Configuration Window

Task ID:	IWTListenerConfig
Permissions:	FullIWTListenerCfgPermission ViewIWTListenerCfgPermission
Help ID:	w_listener_configuration
Data Sources:	LISTENER
Desktop Access:	System Operations > Server Management > Listener
Messages:	IWTFLListenerInsertRq IWTFLListenerListRq IWTFLListenerViewRq IWTFLListenerUpdateRq IWTFLListenerDeleteRq

Locale Content Configuration Window

Task ID:	MultibyteConfiguration
Permissions:	FullMultibyteConfigPerm ViewMultibyteConfigPerm
Help ID:	w_locale_content_configuration
Data Sources:	MULTIBYTE_ENCODING
Desktop Access:	Configure > Locale Content
Messages:	MultibyteConfigInsertRq MultibyteConfigUpdateRq MultibyteConfigDeleteRq

Master File Key Conversion Window

Task ID:	MFKConverter
Permissions:	FullMFKConverterPermission ViewMFKConverterPermission
Help ID:	w_master_file_key_conversion
Data Sources:	n/a
Desktop Access:	Configure > Transaction Security > Master File Key Conversion
Messages:	MFKConv_ConvertKeysRq

MasterCard Brand/Instrument Type Relationship Configuration Window

Task ID:	MasterCardIpF
Permissions:	FullMasterCardIpFPermission
Help ID:	w_mastercard_brand_instrument_type_relationship_configuration
Data Sources:	MDS_Brand_Rel
Desktop Access:	Configure > Interface > Network > MasterCard > MasterCard Brand/Instrument Type Relationship
Messages:	MdsBrandRelViewRq MdsBrandRelInsertRq MdsBrandRelUpdateRq MdsBrandRelDeleteRq

MasterCard Debit Switch (MDS) Interface Configuration Window

Task ID:	MaestroDebitSwitch
Permissions:	FullMaestroPermission ViewMaestroPermission
Help ID:	w_mastercard_debit_switch_configuration
Data Sources:	MDS_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > MasterCard > MasterCard Debit Switch (MDS) Interface
Messages:	MdsInsertRequest MdsViewRequest MdsUpdateRequest MdsDeleteRequest InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

(MasterCard) Merchant Programs Configuration Window

Task ID:	BanknetMerchantProgram
Permissions:	FullBanknetMerchProgPermission
Help ID:	w_merchant_programs_configuration
Data Sources:	Banknet_Merchant_Program
Desktop Access:	Configure > Interface > Network > MasterCard > Merchant Programs
Messages:	BanknetMerchantProgramInsertRq BanknetMerchantProgramDeleteRq BanknetMerchantProgramUpdateRq BanknetMerchantProgramViewRq

Merchant Channel Configuration Window

Task ID:	MerchantChannel
Permissions:	FullMerchantChannelPermission FullMerchantChnlPrflPermission ViewMerchantChannelPermission ViewMerchantChnlPrflPermission
Help ID:	w_merchant_channel_configuration_and_statistics
Data Sources:	Merchant_Delivery_Channel_Profile
Desktop Access:	Configure > Merchant Processing > Merchant Channel
Messages:	MerchantChannelViewRq MerchantChannelInstrmTypeViewRq MerchantChannelFindListRq MerchantChannelGetMrchIdRq MerchantChannelGetChanPrflRq MerchantChannelInsertRq MerchantChannelResetMACSubmitRq MerchantChannelUpdateRq MerchantChannelDeleteRq MerchantOnlyFindListRq

Merchant Channel Profile Window

Task ID:	MerchantChannelProfile
Permissions:	FullMerchantChnlPrflPermission ViewMerchantChnlPrflPermission
Help ID:	w_merchant_channel_profile_configuration
Data Sources:	APACS_Configuration Chan_Profile_Instrm_Typ_Relation Merchant_Delivery_Channel
Desktop Access:	Configure > Merchant Processing > Merchant Channel Profile
Messages:	MerchantChannelProfileFindListRq MerchantChannelProfileViewRq MerchantChannelProfileInsertRq MerchantChannelProfileUpdateRq MerchantChannelProfileDeleteRq APACSViewRq APACSUpdateRq APACSInsertRq APACSDeleteRq MerchantChannelProfileInstrmTypesViewRq MerchantChannelProfileInstrmTypesInsertRq MerchantChannelProfileInstrmTypesUpdateRq MerchantChannelProfileInstrmTypesDeleteRq SPDHViewRq SPDHInsertRq SPDHUpdateRq SPDHDeleteRq HPDHViewRq HPDHInsertRq HPDHUpdateRq HPDHDeleteRq

Merchant Configuration Window

Task ID:	MerchantConfiguration
Permissions:	FullMerchantConfigPermission ViewMerchantConfigPermission
Help ID:	w_merchant_configuration_and_statistics
Data Sources:	Merchant Merch_Instr_Typ_Relation
Desktop Access:	Configure > Merchant Processing > Merchant
Messages:	MerchantInstrmTypeInsertRq MerchantInstrmTypeViewRq MerchantInstrmTypeUpdateRq MerchantInstrmTypeDeleteRq

Merchant Programs

Note: See (Banknet) Merchant Programs Configuration and (MasterCard) Merchant Programs Configuration Windows.

MNET ISO Interface Configuration Window

Task ID:	MnetInterface
Permissions:	FullMnetInterfacePermission ViewMnetInterfacePermission
Help ID:	n/a
Data Sources:	MNET_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > MNET ISO Interface
Messages:	IfMnetViewRq IfMnetInsertRq IfMnetUpdateRq IfMnetDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

NetWorks (NETS) Interface Configuration Window

Task ID:	NetsInterface
Permissions:	FullNetsInterfacePermission
Help ID:	n/a
Data Sources:	INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Networks (NETS) > Networks (NETS) ISO Interface
Messages:	InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

(Networks (NETS)) Interface Terminal Configuration Window

Task ID:	NetsInterfaceTerminal
Permissions:	FullNetsInterfaceTermPerm
Help ID:	w_interface_terminal_configuration
Data Sources:	Interface_Terminal
Desktop Access:	Configure > Interface > Network > Networks (NETS) > Networks (NETS) Interface Terminal
Messages:	InterfaceTerminalInsertRq InterfaceTerminalListRq InterfaceTerminalFindListRq InterfaceTerminalViewRq InterfaceTerminalUpdateRq InterfaceTerminalDeleteRq

NYCE Acquirers Configuration Window

Task ID:	NyceAcquirers
Permissions:	FullNyceAcquirersPermission
Help ID:	n/a
Data Sources:	NYCE_Institution
Desktop Access:	Configure > Interface > Network > NYCE > NYCE Acquirers
Messages:	NyceAcquirersListRq NyceAcquirersViewRq NyceAcquirersInsertRq NyceAcquirersUpdateRq NyceAcquirersDeleteRq

(NYCE) Interface Terminal Configuration Window

Task ID:	NyceInterfaceTerminal
Permissions:	FullNyceInterfaceTermPerm
Help ID:	w_interface_terminal_configuration
Data Sources:	Interface_Terminal
Desktop Access:	Configure > Interface > Network > NYCE > NYCE Interface Terminal
Messages:	InterfaceTerminalInsertRq InterfaceTerminalListRq InterfaceTerminalFindListRq InterfaceTerminalViewRq InterfaceTerminalUpdateRq InterfaceTerminalDeleteRq

NYCE ISO Interface Configuration

Task ID:	NyceInterface
Permissions:	FullNyceInterfacePermission
Help ID:	n/a
Data Sources:	NYCE_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > NYCE > NYCE ISO Interface
Messages:	IntffworkNyceViewRq IntffworkNyceInsertRq IntffworkNyceUpdateRq IntffworkNyceDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

OLTP Warmboot Management Window

Task ID:	OltpWarmbootManagement
Permissions:	FullOLTPWarmbootMgmtPermission ViewOLTPWarmbootMgmtPermission
Help ID:	w_oltp_warmboot_management
Data Sources:	OLTP_Warmboot
Desktop Access:	System Operations > OLTP Warmboot Management
Messages:	OltpWarmbootMngmntViewRq OltpWarmbootMngmntUpdateRq OltpWarmbootMngmntDeleteRq

On-Us Prefix Configuration Window

Task ID:	PrefixConfiguration
Permissions:	FullIchgPrefixConfigPermission FullPrefixConfigPermission ViewIchgPrefixConfigPermission ViewPrefixConfigPermission
Help ID:	w_prefix_configuration
Data Sources:	Prefix
Desktop Access:	Configure > Prefix > On-Us
Messages:	PrefixListRq PrefixConfigInsertRq PrefixConfigViewRq PrefixConfigUpdateRq PrefixConfigDeleteRq

Perusal Profile Configuration Window

Task ID:	PerusalConfiguration
Permissions:	FullPerusalConfigPermission ViewPerusalConfiguration
Help ID:	w_perusal_profile_configuration
Data Sources:	Perusal_Script
Desktop Access:	Configure > Journal > Perusal > Perusal Profile
Messages:	PerusalPrflListRq PerusalPrflInsertRq PerusalPrflViewRq PerusalPrflUpdateRq PerusalPrflDeleteRq PerusalPrflGenericDeleteRq PerusalUserIDListRq

PIN Transport Key Profile Window

Task ID:	PINTransportKeyUI
Permissions:	FullPINTransportKeyUIPerm
Help ID:	w_pin_transport_key_configuration
Data Sources:	Transport_Key
Desktop Access:	Configure > Transaction Security > PIN Transport Key Profile
Messages:	TransportKeyInsertRq

Positive Balance Management Window

Task ID:	PositiveBalance PositiveBalanceActivity PositiveBalanceBalances PositiveBalanceGeneral PositiveBalanceLimits PositiveBalanceStatus FindAccount
Permissions:	FullPositiveBalancePermission ViewPositiveBalancePermission FullPositiveBalActivityPerm ViewPositiveBalActivityPerm FullPositiveBalBalancesPerm ViewPositiveBalBalancesPerm FullPositiveBalGeneralPerm ViewPositiveBalGeneralPerm FullPositiveBalLimitsPerm ViewPositiveBalLimitsPerm FullPositiveBalStatusPerm ViewPositiveBalStatusPerm FullFindAccountPermission ViewFindAccountPermission
Help ID:	w_positive_balance_management
Data Sources:	Institution Positive_Balance
Desktop Access:	Customer Management > Positive Balance
Messages:	PositiveBalanceAcctListRq PositiveBalanceInsertRq PositiveBalanceViewRq PositiveBalanceUpdateRq PositiveBalanceDeleteRq

Preauthorization Hold Management Window

Task ID:	PreAuthHold
Permissions:	FullPreAuthHoldPermission ViewPreAuthHoldPermission
Help ID:	w_preauthorization_hold_management
Data Sources:	Pre_Auth_Hold
Desktop Access:	Customer Management > Preauthorization Hold
Messages:	PreAuthHoldUITblInsertRq PreAuthHoldUIListRq PreAuthHoldUITblViewRq PreAuthHoldUITblUpdateRq PreAuthHoldUITblDeleteRq PreAuthHoldUIDeleteRq

Prefix Block Configuration Window

Task ID:	PrefixBlockConfig
Permissions:	FullPrefixBlockConfigPerm ViewPrefixBlockConfigPerm
Help ID:	w_prefix_block_configuration
Data Sources:	Prefix_Block
Desktop Access:	Customer Management > Prefix Block
Messages:	PrefixBlockConfigDeleteRq PrefixBlockConfigInsertRq PrefixBlockConfigListRq PrefixBlockConfigUpdateRq PrefixBlockConfigViewRq CardBlockConfigGenericDeleteRq

Presto Interface Configuration Window

Task ID:	PrestoInterface
Permissions:	FullPrestoInterfacePermission
Help ID:	n/a
Data Sources:	Presto_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Presto Interface
Messages:	IfPrestoViewRq IfPrestoInsertRq IfPrestoUpdateRq IfPrestoDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

PRICE Interface Configuration Window

Task ID:	PriceInterface
Permissions:	FullPriceInterfacePermission ViewPriceInterfacePermission
Help ID:	n/a
Data Sources:	PRICE_INTERFACE INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > PRICE Interface
Messages:	IfPriceViewRq IfPriceInsertRq IfPriceUpdateRq IfPriceDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Proactive Risk Manager (PRM) Credit/Debit Near Real-Time (NRT) Interface Configuration Window

Task ID:	PRMCreditDebitNRT
Permissions:	FullPRMCreditDebitNRTPerm ViewPRMCreditDebitNRTPerm
Help ID:	w_prm_credit_debit_near_real_time_interface_configuration
Data Sources:	PRM_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Host > Proactive Risk Manager (PRM) > Credit/Debit > Near Real-Time (NRT) Interface
Messages:	PRMViewRq PRMInsertRq PRMUpdateRq PRMDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Proactive Risk Manager (PRM) Credit/Debit Real-Time (RT) Interface Configuration Window

Task ID:	PRMCreditDebitRT
Permissions:	FullPRMCreditDebitRTPerm ViewPRMCreditDebitRTPerm
Help ID:	w_prm_credit_debit_real_time_interface_configuration
Data Sources:	PRM_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Host > Proactive Risk Manager (PRM) > Credit/Debit > Real-Time (RT) Interface
Messages:	PRMViewRq PRMInsertRq PRMUpdateRq PRMDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Proactive Risk Manager (PRM) Enterprise Near Real-Time (NRT) Interface Configuration Window

Task ID:	PRMEnterpriseNRT
Permissions:	FullPRMEnterpriseNRTPerm ViewPRMEnterpriseNRTPerm
Help ID:	w_prm_enterprise_near_real_time_interface_configuration
Data Sources:	PRM_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Host > Proactive Risk Manager (PRM) > Enterprise Risk > Near Real-Time (NRT) Interface
Messages:	PRMViewRq PRMInsertRq PRMUpdateRq PRMDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Proactive Risk Manager (PRM) Enterprise Real-Time (RT) Interface Configuration Window

Task ID:	PRMEnterpriseRT
Permissions:	FullPRMEnterpriseRTPerm ViewPRMEnterpriseRTPerm
Help ID:	w_prm_enterprise_real_time_interface_configuration
Data Sources:	PRM_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Host > Proactive Risk Manager (PRM) > Enterprise Risk > Real-Time (RT) Interface
Messages:	PRMViewRq PRMInsertRq PRMUpdateRq PRMDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Process Configuration Window

Task ID:	IWTProcessConfig
Permissions:	FullIWTProcessCfgPermission ViewIWTProcessCfgPermission
Help ID:	w_process_configuration
Data Sources:	PROCESS
Desktop Access:	System Operations > Server Management > Process
Messages:	IWTFProcessListRq IWTFProcessInsertRq IWTFProcessViewRq IWTFProcessUpdateRq IWTFProcessDeleteRq

Process Control Window

Task ID:	ProcessControl
Permissions:	FullProcessControl ViewProcessControl
Help ID:	w_process_control
Data Sources:	n/a
Desktop Access:	System Operations > Process Control
Messages:	ProcessControlRq

Pulse Institution Configuration Window

Task ID:	PulseInstitution
Permissions:	FullPulseInstitutionPermission
Help ID:	n/a
Data Sources:	Pulse_Institution
Desktop Access:	Configure > Interface > Network > Pulse > Pulse Institution
Messages:	PulseInstitutionListRq PulseInstitutionViewRq PulseInstitutionInsertRq PulseInstitutionUpdateRq PulseInstitutionDeleteRq

Pulse Interface Configuration Window

Task ID:	PulseInterface
Permissions:	FullPulseInterfacePermission
Help ID:	n/a
Data Sources:	Pulse_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Pulse > Pulse Interface
Messages:	PulseViewRq PulseInsertRq PulseUpdateRq PulseDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

(Pulse) Interface Terminal Configuration Window

Task ID:	PulseInterfaceTerminal
Permissions:	FullPulseInterfaceTermPerm
Help ID:	w_interface_terminal_configuration
Data Sources:	Interface_Terminal
Desktop Access:	Configure > Interface > Network > Pulse > Pulse Interface Terminal
Messages:	InterfaceTerminalInsertRq InterfaceTerminalListRq InterfaceTerminalFindListRq InterfaceTerminalViewRq InterfaceTerminalUpdateRq InterfaceTerminalDeleteRq

Pulse Network ID/Instrument Type Relationship Configuration Window

Task ID:	PulseBrandInstrmRelation
Permissions:	FullPulseBrandInstrmReInPerm FullInstrumentTypePermission ViewInstrumentTypePermission
Help ID:	n/a
Data Sources:	Netwk_Brand_Instrm_ReIn
Desktop Access:	Configure > Interface > Network > Pulse > Pulse Network ID/ Instrument Type Relationship
Messages:	NetwkBrandInstrmReInViewRq NetwkBrandInstrmReInInsertRq NetwkBrandInstrmReInUpdateRq NetwkBrandInstrmReInDeleteRq

Query Execute Window

Task ID:	JournalQueryExecution
Permissions:	FullJrnlQueryExecutePermission ViewJrnlQueryExecutePermission
Help ID:	w_query_execute
Data Sources:	n/a
Desktop Access:	System Operations > Query Execution
Messages:	n/a

Real Time Feed Interface Configuration Window

Task ID:	RealTimeFeedInterface
Permissions:	FullRealTimeFeedIFPermission ViewRealTimeFeedIFPermission
Help ID:	w_realtimefeed_interface_configuration
Data Sources:	Real_Time_Feed_Config INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Host > Real Time Feed
Messages:	RealTimeFeedInsertRq RealTimeFeedViewRq RealTimeFeedUpdateRq RealTimeFeedDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Routing Configuration - Destination Window

Task ID:	RoutingConfiguration
Permissions:	FullRoutingConfigPermission ViewRoutingConfiguration
Help ID:	w_routing_configuration_destination
Data Sources:	Acquirer_Route_Profile Issuer_Route_Profile Route Acquirer_Issuer_Relation
Desktop Access:	Configure > Routing > Destinations
Messages:	RoutingListRq RoutingViewRq RoutingInsertRq RoutingUpdateRq RoutingDeleteRq

Routing Configuration - Destination/Source Relationship Window

Task ID:	AcquirerIssuerRelationConfig
Permissions:	FullAcqIssRelatnCfgPermission ViewRoutingConfiguration
Help ID:	w_destination_source_relationship
Data Sources:	Acquirer_Route_Profile Issuer_Route_Profile Route Acquirer_Issuer_Relation
Desktop Access:	Configure > Routing > Destination/Source
Messages:	AIRFListRq AIRFViewRq AIRFInsertRq AIRFUpdateRq AIRFDeleteRq

SAMA Saudi Payments Network (SPAN2) ISO Interface Configuration Window

Task ID:	Span2Interface
Permissions:	FullSpan2InterfacePermission
Help ID:	n/a
Data Sources:	SPAN2_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > SAMA Saudi Payments Network (SPAN2) > Saudi Payments Network (SPAN2) ISO Interface
Messages:	IfSpan2IsoViewRq IfSpan2IsoInsertRq IfSpan2IsoUpdateRq IfSpan2IsoDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

(SAMA Saudi Payments Network (SPAN2)) Interface Terminal Configuration Window

Task ID:	Span2InterfaceTerminal
Permissions:	FullSpan2InterfaceTerminalPerm ViewSpan2InterfaceTerminalPerm
Help ID:	n/a
Data Sources:	SPAN2_Interface_Terminal
Desktop Access:	Configure > Interface > Network > SAMA Saudi Payments Network (SPAN2) > Saudi Payments Network (SPAN2) Interface Terminal
Messages:	InterfaceTerminalListRq InterfaceTerminalViewRq InterfaceTerminalInsertRq InterfaceTerminalUpdateRq InterfaceTerminalDeleteRq

Script Editor Window

Task ID:	ScriptEditor
Permissions:	FullScriptEditorPermission
Help ID:	w_script_editor
Data Sources:	Script Script_Configuration Script_Source
Desktop Access:	Configure > Script > Editor
Messages:	ScriptListRetrvRq ScriptInsertRq ScriptSourceRetrvRq ScriptUpdateRq ScriptCompileRq ScriptDeleteRq

Script Repository Window

Task ID:	ScriptRepository
Permissions:	FullScriptRepository ViewScriptRepository
Help ID:	w_script_repository
Data Sources:	Script Script_Configuration Script_Source
Desktop Access:	Configure > Script > Repository
Messages:	ScriptListRetrvRq ScriptInsertRq ScriptSourceRetrvRq ScriptUpdateRq ScriptCompileRq ScriptDeleteRq

Security Device Configuration Window

Task ID:	SecurityDeviceConfiguration
Permissions:	FullSecurityDevCfgPermission ViewSecurityDevCfgPermission
Help ID:	w_security_device_configuration
Data Sources:	Security_Device_Config
Desktop Access:	Configure > Transaction Security > Security Device
Messages:	SDC_DevListRq SDC_InsertRq SDC_DetailRq SDC_UpdateRq SDC_DeleteRq

Shazam Interface Configuration Window

Task ID:	ShazamInterface
Permissions:	FullShazamInterfacePermission
Help ID:	n/a
Data Sources:	INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Shazam Interface
Messages:	InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

SIBS Acquirer Interface Configuration Window

Task ID:	SIBAInterface
Permissions:	FullSIBAInterfacePermission ViewSIBAInterfacePermission
Help ID:	w_prm_credit_debit_real_time_interface_configuration
Data Sources:	INTERFACE_MGR INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Merchant > SIBS Acquirer Interface
Messages:	InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

SIBS Issuer Interface Configuration Window

Task ID:	SIBIInterface
Permissions:	FullSIBIInterfacePermission ViewSIBIInterfacePermission
Help ID:	w_prm_credit_debit_real_time_interface_configuration
Data Sources:	INTERFACE_MGR INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Merchant > SIBS Issuer Interface
Messages:	InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Socket Administration Window

Task ID:	IWTSocketAdministration
Permissions:	FullIWTSocketAdminPermission ViewIWTSocketAdministration
Help ID:	w_socket_administration
Data Sources:	n/a
Desktop Access:	System Operations > Server Management > Server Administration > Socket Administration
Messages:	IWTFSocketAdminViewRq IWTFSocketInClientListRq IWTFSocketInClientUpdateRq IWTFSocketInServerListRq IWTFSocketInServerUpdateRq IWTFSocketOutClientListRq IWTFSocketOutClientUpdateRq IWTFSocketOutServerListRq IWTFSocketOutServerUpdateRq

Source Routing Profile Configuration Window

Task ID:	AcquirerProfileConfiguration
Permissions:	FullAcqProfileConfigPermission ViewAcqProfileConfigPermission
Help ID:	w_source_routing_profile_configuration
Data Sources:	Acquirer_Route_Profile Issuer_Route_Profile Route Acquirer_Issuer_Relation
Desktop Access:	Configure > Routing > Profile Description > Source Routing Profile
Messages:	AcquirerProfileListRq AcquirerProfileInsertRq AcquirerProfileViewRq AcquirerProfileUpdateRq AcquirerProfileDeleteRq

SPDH Device Profile Configuration Window

Task ID:	SPDHDeviceConfig
Permissions:	FullSPDHDeviceConfigPermission ViewSPDHDeviceConfigPermission
Help ID:	w_spdh_device_profile_configuration
Data Sources:	SPDH_act_cde_descr SPDH_Configuration SPDH_Message SPDH_opt_resp_data SPDH_txn_cde_descr
Desktop Access:	Configure > Merchant Processing > SPDH Device Profile
Messages:	SPDHActCodesDescrsInsertAllRq SPDHActCodesDescrsGetAllRq SPDHActCodesDescrsUpdateAllRq SPDHActCodesDescrsDeleteAllRq SPDHActionCodesInsertAllRq SPDHActionCodesGetAllRq SPDHActionCodesUpdateAllRq SPDHActionCodesDeleteAllRq SPDHMessagesInsertAllRq SPDHMessagesGetAllRq SPDHMessagesUpdateAllRq SPDHMessagesDeleteAllRq SPDHTranCodesDescrsInsertAllRq SPDHTranCodesDescrsGetAllRq SPDHTranCodesDescrsUpdateAllRq SPDHTranCodesDescrsDeleteAllRq

STAR Institution Configuration Window

Task ID:	StarInstitution
Permissions:	FullStarInstitutionPermission ViewStarInstitutionPermission
Help ID:	w_star_institution_configuration
Data Sources:	Star_Institution
Desktop Access:	Configure > Interface > Network > STAR > STAR Institution
Messages:	StarInstitutionInsertRq StarInstitutionListRq StarInstitutionViewRq StarInstitutionUpdateRq StarInstitutionDeleteRq

(STAR) Interface Terminal Configuration Window

Task ID:	InterfaceTerm
Permissions:	FullInterfaceTermPermission ViewInterfaceTermPermission
Help ID:	w_interface_terminal_configuration
Data Sources:	Interface_Terminal
Desktop Access:	Configure > Interface > Network > STAR > STAR Interface Terminal
Messages:	InterfaceTerminalInsertRq InterfaceTerminalListRq InterfaceTerminalFindListRq InterfaceTerminalViewRq InterfaceTerminalUpdateRq InterfaceTerminalDeleteRq

STAR ISO Interface Configuration Window

Task ID:	StarInterface
Permissions:	FullStarInterfacePermission ViewStarInterfacePermission
Help ID:	w_star_iso_interface_configuration
Data Sources:	Star_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > STAR > STAR ISO Interface
Messages:	StarInsertRquest StarViewRequest StarUpdateRequest StarDeleteRequest InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

STAR NE Network ID/Instrument Type Relationship Configuration Window

Task ID:	StarNEIpF
Permissions:	FullStarNEIpFPermission FullInstrumentTypePermission ViewInstrumentTypePermission
Help ID:	w_star_network_id_instrument_type_relationship_configuration
Data Sources:	Netwk_Brand_Instrm_Reln
Desktop Access:	Configure > Interface > Network > STAR > STAR NE Network ID/Instrument Type Relationship
Messages:	NetwkBrandInstrmRelnViewRq NetwkBrandInstrmRelnInsertRq NetwkBrandInstrmRelnUpdateRq NetwkBrandInstrmRelnDeleteRq

STAR SE/W Network ID/Instrument Type Relationship Configuration Window

Task ID:	StarNetworkIdRelationship
Permissions:	FullStarNtwkIdRelationPerm ViewStarNtwkIdRelationPerm FullInstrumentTypePermission ViewInstrumentTypePermission
Help ID:	w_star_network_identifier_instrument_type_relationship_configuration
Data Sources:	Netwk_Brand_Instrm_Reln
Desktop Access:	Configure > Interface > Network > STAR > STAR SE/W Network ID/Instrument Type Relationship
Messages:	NetwkBrandInstrmRelnViewRq NetwkBrandInstrmRelnInsertRq NetwkBrandInstrmRelnUpdateRq NetwkBrandInstrmRelnDeleteRq

Stop Payment Management Window

Task ID:	StopPayment
Permissions:	FullStopPaymentPermission ViewStopPaymentPermission
Help ID:	w_stop_payment_management
Data Sources:	STOP_PAYMENT
Desktop Access:	Customer Management > Stop Payment
Messages:	StopPaymentAccountFindRq StopPaymentViewRq StopPaymentInsertRq StopPaymentUpdateRq StopPaymentDeleteRq StopPaymentGenericDeleteRq

Surcharge Country Code Configuration Window

Task ID:	SurchargeCntryCdeCnfg
Permissions:	FullSurchCntryCdePermission
Help ID:	w_surcharge_country_code_configuration
Data Sources:	Surcharge_Country_Code
Desktop Access:	Configure > Surcharge Country Code
Messages:	SurchCountryCodeViewRq SurchCountryCodeInsertRq SurchCountryCodeInsertRqEntry SurchCountryCodeUpdateRq SurchCountryCodeUpdateRqEntry SurchCountryCodeDeleteRq SurchCountryCodeDeleteRqEntry

Surcharge Profile Configuration Window

Task ID:	ATMSurcharge
Permissions:	FullATMSurchargePermission FullATMSurchPrflPermission ViewATMSurchargePermission ViewATMSurchPrflPermission
Help ID:	w_surcharge_profile_configuration
Data Sources:	Surcharge
Desktop Access:	Configure > Surcharge Profile
Messages:	SrchgPrflInsRq SrchgPrflListRq SrchgPrflViewTypeRq SrchgPrflUpdRq SrchgPrflDelRq SrchgPrflGenericDeleteRq

System Algorithm Configuration Window

Task ID:	SystemAlgorithm
Permissions:	FullSystemAlgorithmPermission ViewSystemAlgorithm
Help ID:	w_system_algorithm
Data Sources:	System_Alogrithm_Config
Desktop Access:	Configure > Prefix > Not-On-Us > System Algorithm
Messages:	SysAlgoInsertRq SysAlgoListRq SysAlgoViewRq SysAlgoUpdateRq SysAlgoDeleteRq SysAlgoGenericDeleteRq

System Monitor Window

Task ID:	IWTSystemMonitor
Permissions:	FullIWTSystemMonitorPermission ViewIWTSystemMonitor
Help ID:	w_system_monitor
Data Sources:	n/a
Desktop Access:	System Operations > Server Management > Server Administration > System Monitor
Messages:	n/a

System Prefix Configuration Window

Task ID:	SystemPrefix
Permissions:	FullSystemPrefixPermission ViewSystemPrefix
Help ID:	w_system_prefix_configuration
Data Sources:	SYSTEM_PREFIX
Desktop Access:	Configure > Prefix > Not-On-Us > System Prefix
Messages:	SysPrfxInsertRq SysPrfxPrflListRq SysPrfxDetailListRq SysPrfxUpdateRq SysPrfxDeleteRq SysPrfxDeletePrflRq

System Properties Window

Task ID:	IWTSystemProperties
Permissions:	FullIWTSystemPropertiesPermission ViewIWTSystemProperties
Help ID:	w_system_properties
Data Sources:	n/a
Desktop Access:	System Operations > Server Management > Server Administration > System Properties
Messages:	n/a

Terminal Logical Network/FIID Mapping Window

Task ID:	TermLnFiidMap
Permissions:	FulltermLnFiidMapPermission ViewtermLnFiidMapPermission
Help ID:	w_terminal_logical_network_fiid_mapping
Data Sources:	TERM_LN_FIID_MAP
Desktop Access:	Configure > Interface > Host > Terminal Logical Network/ FIID Mapping
Messages:	TermLnFiidMapListRq TermLnFiidMapViewRq TermLnFiidMapInsertRq TermLnFiidMapUpdateRq TermLnFiidMapDeleteRq

Token Profile Configuration Window

Task ID:	TokenProfile
Permissions:	FullTokenProfilePermission ViewTokenProfilePermission
Help ID:	w_token_profile_configuration
Data Sources:	Token_Config Token_Id_List
Desktop Access:	Configure > BASE24 > Token Profile
Messages:	TokenDescListRq TokenProfileInsertRq TokenProfileListRq TokenProfileViewRq TokenProfileUpdateRq TokenProfileDeleteRq

Totals Tag Documentation Configuration Window

Task ID:	TotalsTagDocumentation
Permissions:	FullTotalsTagDocPermission
Help ID:	w_totals_tag_documentation_configuration
Data Sources:	Totals_Tag_Documentation
Desktop Access:	Configure > Interface > Totals Tag Documentation
Messages:	TotalsTagsListRq TotalsTagsViewRq TotalsTagsInsertRq TotalsTagsUpdateRq TotalsTagsDeleteRq

Trace Configuration Window

Task ID:	TraceConfiguration
Permissions:	FullTraceConfigPermission ViewTraceConfigPermission
Help ID:	w_trace_configuration
Data Sources:	Trace_Config
Desktop Access:	System Operations > Trace > Trace Configuration
Messages:	TraceConfigInsertRq TraceConfigListRq TraceConfigViewRq TraceConfigUpdateRq TraceConfigDeleteRq

Trace Filter Profile Configuration Window

Task ID:	TraceFilterConfiguration
Permissions:	FullTraceFilterCfgPermission ViewTraceFilterCfgPermission
Help ID:	w_trace_filter_profile_configuration
Data Sources:	Trace_Filter
Desktop Access:	System Operations > Trace > Trace Filter Profile
Messages:	TraceFilterInsertRq TraceFilterListRq TraceFilterViewRq TraceFilterUpdateRq TraceFilterDeleteRq TraceFilterGenericDeleteRq

United Arab Emirates (UAE) Interface Configuration Window

Task ID:	UaeInterface
Permissions:	FullUaeInterfacePerm ViewUaeInterfacePerm
Help ID:	n/a
Data Sources:	INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE TOTALS_CONFIGURATION
Desktop Access:	Configure > Interface > Network > United Arab Emirates (UAE) Interface
Messages:	InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkInsertRq InterfaceFrameworkUpdateRq InterfaceFrameworkDeleteRq

Usages Management Window

Task ID:	Usages
Permissions:	FullUsagesPermission ViewUsagesPermission
Help ID:	w_usages_management
Data Sources:	Usage
Desktop Access:	Customer Management > Usages
Messages:	UsagesUIListRq UsagesUITblViewRq

User Audit Window

Task ID:	UserAuditReport
Permissions:	FullUserAuditRptPermission
Help ID:	w_audit_report_wizard
Data Sources:	n/a
Desktop Access:	View > User Audit
Messages:	n/a

User Permissions Window

Task ID:	UserSecurityProfile
Permissions:	ViewUSPPermission
Help ID:	w_user_permissions
Data Sources:	n/a
Desktop Access:	View > User Permissions
Messages:	n/a

User Profile Relationship Window

Task ID:	UserProfileRelation
Permissions:	FullUserProfRelationPermission ViewUserProfileRelation
Help ID:	w_user_profile_relationship
Data Sources:	User_Perusal_Prfl_Relation
Desktop Access:	Configure > Journal > Perusal > User Profile Relationship
Messages:	UserRelationshipInsertRq UserRelationshipViewRq UserRelationshipUpdateRq UserRelationshipDeleteRq

User Security Control Management Window

Task ID:	UserSecurityControl
Permissions:	FullUSCtlPermission
Help ID:	w_user_security_control_management
Data Sources:	Users
Desktop Access:	Configure > User Security > Control
Messages:	n/a

User Security Group Configuration Window

Task ID:	UserSecurityGroupConfig
Permissions:	FullUSGCfgPermission ViewUSGCfgPermission
Help ID:	w_user_security_group_configuration
Data Sources:	SecGrp
Desktop Access:	Configure > User Security > Group
Messages:	n/a

User Security Profile Configuration Window

Task ID:	UserSecurityProfile
Permissions:	FullUSPPPermission ViewUSPPPermission
Help ID:	w_user_security_profile_configuration
Data Sources:	Users
Desktop Access:	Configure > User Security > Profile
Messages:	n/a

User Security Role Configuration Window

Task ID:	UserSecurityRoleConfig
Permissions:	FullUSRCfgPermission ViewUSRCfgPermission
Help ID:	w_user_security_role_configuration
Data Sources:	UsrXRole
Desktop Access:	Configure > User Security > Role
Messages:	n/a

User Status Window

Task ID:	UserSecurityProfile
Permissions:	FullUserAuditRptPermission
Help ID:	w_user_status
Data Sources:	UsrStat
Desktop Access:	View > User Status
Messages:	n/a

Visa Acquirers Configuration Window

Task ID:	VisaAcquirers
Permissions:	FullVisaAcquirersPermission ViewVisaAcquirersPermission
Help ID:	w_visa_acquirers_configuration
Data Sources:	Visa_Institution
Desktop Access:	Configure > Interface > Network > VisaNet > Visa Acquirers
Messages:	VisaInstitutionListRq VisaInstitutionViewRq VisaInstitutionInsertRq VisaInstitutionUpdateRq VisaInstitutionDeleteRq

Visa Brand/Instrument Type Relationship Configuration Window

Task ID:	VisaIpf
Permissions:	FullVisaIpfPermission ViewVisaIpfPermission FullInstrumentTypePermission ViewInstrumentTypePermission
Help ID:	w_visa_brand_instrument_type_relationship_configuration
Data Sources:	Netwk_Brand_Instrm_Reltn
Desktop Access:	Configure > Interface > Network > VisaNet > Visa Brand ID/ Instrument Type Relationship
Messages:	VisaBrandRelViewRq VisaBrandRelInsertRq VisaBrandRelUpdateRq VisaBrandRelDeleteRq

Visa DPS Acquirers Configuration Window

Task ID:	VisaDPSAcquirers
Permissions:	FullVisaDPSAcquirersPermission ViewVisaDPSAcquirersPermission
Help ID:	w_visa_dps_acquirers_configuration
Data Sources:	Visa_DPS_Institution
Desktop Access:	Configure > Interface > Network > Visa DPS > Visa DPS Acquirers
Messages:	VisaDPSInstitutionInsertRq VisaDPSInstitutionListRq VisaDPSInstitutionViewRq VisaDPSInstitutionUpdateRq VisaDPSInstitutionDeleteRq

Visa DPS Interface Configuration Window

Task ID:	VisaDPSInterface
Permissions:	FullVisaDPSInterfacePermission ViewVisaDPSInterfacePermission
Help ID:	w_vis_a_dps_interface_configuration
Data Sources:	Visa_DPS_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > Visa DPS > Visa DPS Interface
Messages:	VisaDPSInsertRq VisaDPSViewRq VisaDPSUpdateRq VisaDPSDeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Visa DPS Network ID/Instrument Type Relationship Configuration Window

Task ID:	VdpsBrandInstrmRelation
Permissions:	FullVdpsBrandInstrmRelnPerm ViewInstrumentTypePermission
Help ID:	w_vis_a_brand_instrument_type_relationship_configuration
Data Sources:	Netwk_Brand_Instrm_Reltn
Desktop Access:	Configure > Interface > Network > Visa DPS > Visa DPS Network ID/Instrument Type Relationship
Messages:	NetwkBrandInstrmRelnViewRq NetwkBrandInstrmRelnInsertRq NetwkBrandInstrmRelnUpdateRq NetwkBrandInstrmRelnDeleteRq

VisaNet ISO Interface Configuration Window

Task ID:	VisanetInterfaceConfig
Permissions:	FullVisanetIFConfigPermission ViewVisanetIFConfigPermission
Help ID:	w_visanet_iso_interface_configuration
Data Sources:	Visa_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Network > VisaNet > VisaNet ISO Interface
Messages:	VisaInsertRequest VisaViewRequest VisaUpdateRequest VisaDeleteRequest InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

Voice Authorization Interface Configuration Window

Task ID:	VoiceAuthInterface
Permissions:	FullVoiceAuthInterfacePerm ViewVoiceAuthInterfacePerm
Help ID:	w_iso_93_host_interface_configuration
Data Sources:	HISO93_Interface INTERFACE_MGR INTERFACE_SAF INTERFACE_STA INTERFACE
Desktop Access:	Configure > Interface > Host > Voice Authorization Interface
Messages:	HISO93InsertRq HISO93ViewRq HISO93UpdateRq HISO93DeleteRq InterfaceFrameworkListRq InterfaceFrameworkViewRq InterfaceFrameworkUpdateRq InterfaceFrameworkInsertRq InterfaceFrameworkDeleteRq

ZKA Key Gen Keys Configuration Window

Task ID:	ZKAKeyGenKeys
Permissions:	FullZKAKeyGenKeysPermission ViewZKAKeyGenKeysPermission
Help ID:	w_zka_key_gen_keys_configuration
Data Sources:	ZKA_KGK
Desktop Access:	Configure > Transaction Security > Automated Key Distribution > ZKA Key Gen Keys
Messages:	ZKAKeyGenKeysGenericDeleteRq ZKAKeyGenKeysDeleteRq ZKAKeyGenKeysInsertRq ZKAKeyGenKeysListRq ZKAKeyGenKeysUpdateRq ZKAKeyGenKeysViewRq

B: Desktop.cfg File

The **desktop.cfg** configuration property file defines parameters for ACI Desktop user interface and Web clients. This file should be configured once for all users associated with a version checker server. Configuration files are created for each user of the desktop (*username.cfg*) and contain user-specific definitions. The properties of desktop.cfg file are divided into logical sections and are discussed below.

[Desktop] section

The **AppPath** property specifies the location of the UI application jars and must contain a valid directory location.

The **SSLEnabled** property is a boolean value indicating whether the desktop is to use an HTTPS connection for SSL support. This property only applies to those desktop connections to a webserver over HTTP.

The **CachePermissions** property is a boolean value indicating whether permissions are maintained in memory during user sessions.

The **EnableUSECReloadCacheCmd** property is a boolean value that if set to true enables those users who can access the User Security Role Configuration window to reload the user security authorization cache on demand by clicking the Reload Cache button. If this property is set to false, the Reload Cache button is not presented on the window.

The **Host** property specifies the name of the host group currently selected (last used) by the user. The host group specified by the value of the host property is used by the desktop to determine the connectivity parameters of the host server. The Host property is required.

The **HostTimeout** property specifies the amount of time, in seconds, that can elapse after a host request has been sent without a response being received. This property is optional and if specified must be a positive number. If the value is zero, or this property is missing, host requests waits 60 seconds for a response.

The **ShowLoggedOnUser** property is used to activate the user icon located at the lower right of the desktop. When this icon is moused over, the desktop displays the name of the user currently logged onto the desktop in a popup message. Set this property to true to activate this functionality.

[Hosts] section

The [Hosts] section contains definitions for host groups used by the Host property above.

Each group (e.g., ProdServer) key entry within the [Hosts] section represents a logical host which consists of one or more physical hosts which are mirrors of each other and available for load balancing and fail over. The actual key name of each group entry is listed in the host selection list on the desktop. The value of a group entry consists of one or more URL entries in the form of 'host:port/path' separated by commas ','. The currently selected group name key entry is set in the Host property of the [Desktop] section.

Example:

```
ProdServer=prod1:9023,prod2:8079
TestServer=test1:7765
```

[OnlineHelp] section

The **ACI Help** property identifies the default JavaHelp helpset (e.g., ACI_Help.hs) for the desktop.

[Common] section

The **Debug** property specifies whether or not debug messages are enabled for the desktop. Debug messages are sent to the debug log file identified by the **LogFileName** property located at the location specified by the **LogPath** property. Valid values are true or false (the default). This property can be specified at run time by setting the Debug system property on the command line. Setting the command line property overrides this property value.

The **TPA** property refers to Third Party Authentication. It specifies the type of third party authentication. If set to true then DEFAULT is implied. If set to false then NONE is implied.

The **ChangePasswordAllowed** property contains a boolean value that identifies whether the desktop allows password change capability. Typically used in conjunctions with the TPA property above. By default, this property is true. It can be set to false to disable the change password dialog of the desktop.

PasswordProperty defines the name and location of the SSL keystore encrypted password binary file.

The **ChannelTrace** is a boolean value. If true then connectivity and messaging between the desktop and server will be traced and logged to the log entry file configured for the desktop. If false, then no tracing will be logged. The default value, if not present, is false. If the system property - DChannelTrace is present it will be overridden by the setting from this property.

The **ChannelTraceLevel** property is a numerical value indicating the level of tracing that is performed. This value is only effective if the ChannelTrace property is set to true. Valid values are:

- 0 = Trace connection and all messages
- 4 = Trace all messages (default)
- 5 = Trace channel message header content only
- 6 = Trace summary information (this setting is only used until the user is authenticated after which the user's trace flag is used. See user preferences in section 2)

[SSL] section

Refer to Appendix C for more information.

Note: The SSL properties only apply if SSL enabled (i.e., the SSLEnabled property in the [Desktop] section is set to true).

If the **KeyStoreAutoUpdate** property is a boolean value that if set to true, the desktop automatically extracts the specified KeyStore file by identifying its location in the classpath. The extracted file will replace the local KeyStore file at the time this component is started. If this property is not present, it defaults to false. The KeyStore file name is found in the **KeyStore** property below.

The **KeyStore** property contains the key store file name used for retrieving private key information and any trusted certificates and associated keys. It must be built correctly in order for the SSL implementation to properly function. The default if not present is defaultKS.sto. Any specified file that is not present locally or if KeyStoreAutoUpdate is set to true, causes the component to search the classpath for the specified key store. If found, it is extracted and stored in the specified location (local).

The **KeyStorePassword** property specifies the password value that allows access to the KeyStore private and trusted certificate public keys. The default is "default".

The **KeyStoreType** property specifies the type of KeyStore file generated. The default, is JKS (Java Key Store). If a client implements a different type of keystore then it must be specified in this property.

The **TrustStore** property identifies the trust store where trusted certificates are accessed. By default, a separate trust store is not needed. This is an optional property and if not present, defaults to the value of the **KeyStore** property.

For the **TrustStoreType** property, refer to the KeyStoreType property above. If not present, it defaults to the KeyStoreType specified.

For the **TrustStorePassword** property, refer to the KeyStorePassword property above. If not present, it defaults to the KeyStorePassword specified.

The **Protocol** property defines the cryptographic protocol used, such as TLS (Transport Layer Protocol) or SSL (Secure Sockets Layer).

The **KeyMgmtAlgo** property specifies certificates standard and how keys are managed in regards to the trusted certificates. The default value, if not present, is “SunX509”.

The **Provider** property specifies the Provider class that is used as the SSL implementation. The default value, if not present, is “com.sun.net.ssl.internal.ssl.Provider”.

The **ProtocolHandlerPkgs** property specifies the protocol handler package that is required in conjunction with the provider implementation. The default value, if not present, is “com.sun.net.ssl.internal.www.protocol”.

C: SSL Keystore Password Manager

The ACI desktop accesses SSL keystore passwords during secure communication with servers. These passwords are referenced (not stored) for the ACI desktop in the desktop.cfg configuration file. The keystore passwords are not stored in the desktop.cfg because passwords cannot be encrypted within the desktop.cfg file (see the PCI note below). Therefore, the encrypted passwords are placed in a binary file (e.g., passwords.bin) that is referenced within the desktop.cfg file in the [COMMON] section of file using the PasswordProperty property.

The Password Manager is provided to assist users in managing and encrypting SSL keystore password binary files. There are two types of passwords used: system and user-defined. The Password Manager can be used to manage both types. Passwords are associated with token IDs and descriptions.

Password values are encrypted using a proprietary bit encryption algorithm that the code base can cipher and decipher. The password properties file is made up of *tokens* (i.e., properties) that contain a password value. Thus, each password token is associated with a password value. It is the token IDs that are acted upon when using the Password Manager.



Payment Card Industry (PCI) Note: For security, stored password values must be encrypted. Cross-industry best practices recommend that vendor-supplied default passwords not be used, that passwords contain both numeric and alphabetic characters with a minimum password length of at least seven characters, that passwords be changed at least every 90 days, and that a new password not be the same as any of the last four passwords used.

Sample Passwords.bin File

The example below is an ASCII-format representation of a passwords.bin file. The actual information is stored on disk encrypted and in binary format.

```
[UserTokens]
```

```
# This section is for user specific tokens (if any)
```

```
[SystemTokens]
```

```
ESF.password=USEC Database password token
```

```
EAF.password=UAUD Database password token
```

```
KeyStorePassword=SSL Key store password token for USEC/UAUD
```

```
TrustStorePassword=SSL Trust store password token for USEC/  
UAUD
```

```
[Password]
```

```
ESF.password=657e1f6fecea9ea8
```

```
EAF.password=657e1f6fecea9ea8
```

```
KeyStorePassword=512bb47f6f7206e90d0d440da775982b
```

```
TrustStorePassword=512bb47f6f7206e90d0d440da775982b
```

Run the Password Manager from the Command Prompt

When the Password Manager is initiated from a command prompt, both system and user-defined password tokens can be added and deleted.

To run the Password Manager from a command prompt, enter the following command syntax at the command prompt:

Syntax:

```
java -classpath {uif-jar} [-DPasswordProperty=password-bin-filename]
    framework.cipher.PswdMgr -keyword argument
```

where:

uif-jar is any one of the following JARs:

- uif_dt.jar
- uif_sh.jar
- uif_verchk.jar

password-bin-filename is the optional name of the password bin file entered as a system property. If it is not specified, it defaults to a value of “Password.bin”. If the password bin file is entered as a run argument, it overrides this value.

keyword argument is one of the following formats:

```
-SetPW token password password [password-bin-filename]
-VerifyPW token password [password-bin-filename]
-SetTKN token description [password-bin-filename]
-SetSYSTKN token description [password-bin-filename]
-RemoveTKN token password [password-bin-filename]
-RemoveSYSTKN token password [password-bin-filename]
-RemovePW token password [password-bin-filename]
```

where:

- SetPW — To set or change a password value and associate it to an existing token.

Note: A password cannot be changed unless the associated token for the password already exists. Therefore, use SetTKN first to add a user-defined or system password token.

- ❑ VerifyPW — To verify a password value.
- ❑ SetTKN — To add a user-defined password token.
- ❑ SetSYSTKN — To add a system password token.
- ❑ RemoveTKN — To remove a user-defined password token and the password associated with the token.
- ❑ RemoveSYSTKN — To remove a system password token and the password associated with the token.
- ❑ RemovePW — To remove a password value, but retains the token and description.

token is the name of a password property in the desktop.cfg (or local.cfg) file.

password is a clear password value. For the SetPW command function, you must enter the password twice to ensure it is entered correctly.

password-bin-filename is the optional name of the password bin file. If it is not specified, the value for the PasswordProperty system property is used.

description is a text description of a token. If the description contains spaces, it must be enclosed within quotes (“USEC database password key/token”).

Run the Password Manager from the PswdMgrUI Window

When running the Password Manager from the PswdMgrUI window, user-defined password tokens can be added and deleted. However, system password tokens cannot be added or deleted from the window, these tokens can only be changed.

To run Password Manager from the PswdMgrUI window, enter the following command syntax at the Command prompt. Tokens, descriptions, and password values can be edited using this window.

Syntax:

```
Java -classpath {framework-jar} framework.cipher.PswdMgrUI  
      [password-bin-filename]
```

where:

framework-jar is any one of the following JARs:


- uif_dt.jar
- uif_sh.jar
- uif_verchk.jar

password-bin-filename is the optional name of the password bin file. If it is not specified, it defaults to a value of “Password.bin”.

PswdMgrUI Window

The following is an example of the PswdMgrUI window. If the specified password bin file already exists, the window reads the file and displays all of the token/password entries in the file. System passwords are displayed in black text while

user-defined passwords are displayed in blue text. In addition, all passwords values are masked with asterisk characters for security reasons. If the password bin file does not yet exist, no table rows are displayed.



Add a New User-Defined Password Token

Use the following procedures to add a new user-defined password token.

1. Click the New button to insert a new empty row into the table.
2. In the empty row, enter a token ID, description, and password value.
3. Click the Store button to save the new information to the password binary file (e.g., password.bin).
4. Click the Exit button to stop the Password Manager.

Delete a User-Defined Password Token

Use the following procedures to delete a password token.

1. Click on the row of the token that you want to delete. A selected row has a modified background color.
2. Click the Delete button to delete the token.
3. Click the Store button to save the change to the password binary file (e.g., password.bin).
4. Click the Exit button to stop the Password Manager.

D: Multibyte Character Data Support

The BASE24-eps Multibyte Character Set Service module provides support for different alphabets, syllabic languages, and character sets that require two or more (multiple) bytes of data to represent a single character. This module provides support for additional languages and character sets independent of the number of bytes required to represent each character. The BASE24-eps Multibyte Character Set Service module enables BASE24-eps to store, display, and print user-entered data in local/native character sets such as Arabic, Han Chinese, Japanese, and Korean.

Configuration

You must have licensed the Multibyte Character Set Service module before you can configure its use.

Content Encoding Field

You configure use of the Multibyte Character Set Service module by setting the Content Encoding field on the Locale Content Configuration window (accessed from **Configure > Locale Content**) to a value of UTF-8.

Encoding Properties

When you click Save on the Locale Content Configuration window, the value of the Content Encoding field is used to set both the MULTIBYTE_ENCODING Environment attribute in the Environment data source (Environment) and the MULTIBYTE_ENCODING Java property value in the Application Configuration data source (APPLCNFG). The MULTIBYTE_ENCODING Java property specifies how multibyte messages are encoded in the ACI desktop client and in the User Interface Framework (UIF) for messages containing multibyte fields.

Also note that the file.encoding Java system property must be set to a value of “ISO8859-1” when the ESWEB Java Server process is started (e.g., -Dfile.encoding=ISO8859-1) and to a value of “UTF-8” when an ACI desktop client is started (e.g., -Dfile.encoding=UTF-8 system property in the DesktopLauncher.lax file).

Because the MULTIBYTE_ENCODING Environment attribute and MULTIBYTE_ENCODING Java property must always be set to the same value, you cannot enter them on the Environment Configuration window or Application Configuration window. Refer to the ***BASE24-eps Environment Management User Guide*** for a detailed description of the MULTIBYTE_ENCODING Environment attribute and the ***ACI Java Infrastructure Java Server Reference Guide*** for a detailed description of the MULTIBYTE_ENCODING Java property and file.encoding Java system property.

Warmbooting the ESWEB Server Process

After you save the value on the Locale Content Configuration window, you must either restart the ESWEB Server process or reload the configuration properties for the ESWEB Server process (e.g., P92^ESWEB) on the Configuration Properties window. You can access this window directly from the Locale Content Configuration window by clicking the “Reload Server Configuration Properties” link or you can manually navigate to the Configuration Properties window (accessed from **System Operations > Server Management > Server Administration > Configuration Properties**). To reload the configuration properties on the Configuration Properties window, enter the symbolic name of the ESWEB Server process in the Process ID field and click Reload.

Language Preference

The locale you enter in the Language field on the General tab of the User Preferences window has no impact on multibyte character data fields. This setting only determines whether localized property files are used for the display of field labels, tooltips, screen messages, etc., on the ACI desktop. The values displayed in the selectable list for the Language field are controlled by the LocaleManager. language properties in the Desktop.properties file. Currently, only the U.S. English locale is configured for the BASE24-eps product.

Multibyte Data Fields

Once you have configured the ACI desktop to use a multibyte encoding value (e.g., UTF-8), multibyte fields are displayed on the windows, tabs, and fields listed in the following table. You can enter and display multibyte characters in these fields. These multibyte fields automatically determine whether text is displayed in a left to right or right to left direction based on the type of characters entered. Multibyte data fields are stored in multibyte data elements within existing data sources or in data sources that only contain multibyte data.

Window	Tab	Field	Data Source
Action Code Profile Configuration	Inbound Mapping	External Action Code Description (Locale)	Action Code External to Internal (ACT_CDE_EXT_INT)
	Outbound Mapping		Action Code Internal to External (ACT_CDE_EXT_INT)
ATM Channel Configuration	Location (Locale)	All	ATM Static Data Table 1 (ATM_DS1)
	Migration (Locale)	All	
Card Management	General	Customer ID (Locale)	Card Account Multibyte (CARD_ACCT_MBYTE)
	Address (Locale)	Address (line 1 and 2) Postal Code	
	Accounts	Description (Locale)	
Institution Configuration	Address and Contacts (Locale)	All	Institution (INSTITUTION)
Merchant Channel Configuration	N/A	Merchant Name (Locale) (Display only)	Merchant Delivery Channel (CARD_ACCT_MBYTE)
	Terminal Information (Locale)	Terminal Location (Locale) Terminal Service Representative (Locale)	

Window	Tab	Field	Data Source
Merchant Configuration	N/A	Merchant Name (Locale)	Merchant (MERCHANT)
	Contact Information (Locale)	All	

ATM Consumer Media and Receipts

After the ACI desktop is configured to use a multibyte encoding, you can enter multibyte data on the ATM Consumer Media Configuration window, ATM Multi-byte Translation Configuration window, and on the ATM Receipt Format Profile Configuration window. This support is described in the ***BASE24-eps ATM Configuration and Management Guide***.

Note: You do not actually enter multibyte characters on the ATM Multi-byte Translation Configuration window. The ATM Multibyte Translation data source (ATM_MBYTE_XLATE) maintained by this window is used to translate/map multibyte data to the corresponding single byte elements that the ATM is configured for in its language pages.

Instrument Type Descriptions


Multibyte instrument type descriptions are not supported on the Instrument Type Configuration window or in the Instrument Type data source (INSTRUMENT_TYPE). You can, however, override these descriptions with multibyte instrument type descriptions through the configuration of InstrumentTypeOverride properties in the CommonCodeValues property file. These override properties are in the format of InstrumentTypeOverride.<instrument-type-value>.text, where <instrument-type-value> is the two-character instrument type for which the description from the INSTRUMENT_TYPE is overridden.

When an InstrumentTypeOverride property is provided for an instrument type, then wherever that instrument type description is displayed on an ACI desktop window or browser page, it will contain the multibyte locale description from the property file rather than the ASCII description from the INSTRUMENT_TYPE.

The Instrument Type selectable list field on the Instrument Types tab of the Merchant Configuration window below depicts the display of multibyte instrument type descriptions using the localization override support entries in the CommonCodeValues property file. In the example shown, override entries are used for the AB and AC instrument types.

InstrumentTypeOverride.AB.text=醫藥費

InstrumentTypeOverride.AC.text=醫藥費伊斯坦堡



Scripts

After the ACI desktop is configured to use a multibyte encoding, you can add comments to scripts in a multibyte language and select the reading order of scripts (right to left instead of left to right) on the Script Editor window. You can also use certain exported operators in scripts to extract or report on multibyte data. This support is described in the *BASE24-eps Scripting Manual*.

ACI Worldwide, Inc.

E: Open Source Software License Agreements

This ACI Software Product is licensed to you or your company or organization (“You”) under the terms of the written license agreement in place between You and ACI (the “License Agreement”). In addition to the License Agreement, the third party license terms displayed below govern ACI’s distribution to You and Your use of the individual third party software components included with or in the ACI Software Product, but do NOT supersede or limit the terms and conditions of the License Agreement for use of the ACI Software Product. The following third party license terms shall be deemed to apply exclusively to the applicable third party software associated with such third party license and NOT to the ACI Software Product, or any portion thereof, with which such third party software is used or distributed. Any of the following third party license terms that differ from or conflict with the License Agreement shall not affect the License Agreement or your license thereunder in the ACI Software Product. As between You and ACI, the ACI Software Product shall not be deemed to be a derivative work or modification of, or a contribution to, any of the third party software used or distributed with such ACI Software Product. The following third party license terms are excerpted from the license file for the applicable third party software component; see the full license terms included with the Software Product for specific language governing permissions and limitations under the third party license for each such third party software component.

JDOM Java XML API

Copyright (C) 2001 Brett McLaughlin & Jason Hunter. All rights reserved.

“This product includes software developed by the JDOM Project (<http://www.jdom.org/>).”

The name “JDOM” must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact license@jdom.org.

Products derived from this software may not be called “JDOM”, nor may “JDOM” appear in their name, without prior written permission from the JDOM Project Management (pm@jdom.org).

THIS SOFTWARE IS PROVIDED BY JDOM “AS IS” AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE JDOM AUTHORS OR THE PROJECT CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Apache Jakarta Common Language Version 2.0
Apache Jakarta Project Java Regular Expression Parser Version 1.2
Apache Jakarta Project ORO 2.0
Apache log4j Version 1.2
Apache XML Project Xerces Java Parser Versions 1.0 and 2.4
Apache XML Project Xerces C++ Parser Version 3.3, formerly licensed as IBM XML4C

The Apache Software License, Version 1.1

Copyright (c) 1999 The Apache Software Foundation. All rights reserved.

“This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>).”

The names “Xerces”, “The Jakarta Project”, “Commons”, “log4j”, “Tomcat”, “Jakarta-Regexp”, and “Apache Software Foundation” must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org.

Products derived from this software may not be called “Apache” nor may “Apache” appear in their names without prior written permission of the Apache Group.

THIS SOFTWARE IS PROVIDED "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Apache Ant 1.6.2

Apache AXIS 1.4

Apache Commons Codec 1.3

Apache Jakarta Commons Net 1.3

Apache Tomcat Versions 5.5 and 6.0

Apache Xerces C++ 2.8.0

SourceForge Piccolo XML Parser for Java

Copyright © 2004 The Apache software Foundation. All Rights reserved.

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for specific language governing permissions and limitations under the License.

ICU License - ICU 1.8.1 and later

COPYRIGHT AND PERMISSION NOTICE

Copyright (c) 1995-2005 International Business Machines Corporation and others

All rights reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, provided that the above copyright notice(s) and this permission notice appear in all copies of the Software and that both the above copyright notice(s) and this permission notice appear in supporting documentation.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR HOLDERS INCLUDED IN THIS NOTICE BE LIABLE FOR ANY CLAIM, OR ANY SPECIAL INDIRECT OR CONSEQUENTIAL DAMAGES, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

JAVA™ AUTHENTICATION AND AUTHORIZATION SERVICE VERSION 1.0 JAVAHELP™ VERSION 2.0

Sun Microsystems, Inc. Binary Code License

Copyright ©2000 by Sun Microsystems Inc. All Rights Reserved.

Java Technology Restrictions. You may not modify the Java Platform Interface (“JPI”, identified as classes contained within the “java” package or any sub-packages of the “java” package), by creating additional classes within the JPI or otherwise causing the addition to or modification of the classes in the JPI. In the event that you create an additional class and associated API(s) which (i) extends the functionality of the Java platform, and (ii) is exposed to third party software developers for the purpose of developing additional software which invokes such additional API, you must promptly publish broadly an accurate specification for

such API for free use by all developers. You may not create, or authorize your licensees to create, additional classes, interfaces, or sub-packages that are in any way identified as "java", "javax", "sun" or similar convention as specified by Sun in any naming convention designation.

JAVA™ 2 PLATFORM STANDARD EDITION RUNTIME ENVIRONMENT, VERSION 5.0

Sun Microsystems, Inc. Binary Code License

Copyright © 2009 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, U.S.A. All rights reserved. U.S.

Java Technology Restrictions. You may not modify the Java Platform Interface ("JPI", identified as classes contained within the "java" package or any sub-packages of the "java" package), by creating additional classes within the JPI or otherwise causing the addition to or modification of the classes in the JPI. In the event that you create an additional class and associated API(s) which (i) extends the functionality of the Java platform, and (ii) is exposed to third party software developers for the purpose of developing additional software which invokes such additional API, you must promptly publish broadly an accurate specification for such API for free use by all developers. You may not create, or authorize your licensees to create, additional classes, interfaces, or sub-packages that are in any way identified as "java", "javax", "sun" or similar convention as specified by Sun in any naming convention designation.

JAXB Component of JAVA™ Web Services Developer Pack JAVA™ Secure Socket Extension JavaBeans Activation Framework JavaMail API

License

Copyright 1994-2004 Sun Microsystems, Inc. All Rights Reserved.

Java Technology Restrictions. You may not modify the Java Platform Interface ("JPI", identified as classes contained within the "java" package or any sub-packages of the "java" package), by creating additional classes within the JPI or otherwise causing the addition to or modification of the classes in the JPI. In the

event that you create an additional class and associated API(s) which (i) extends the functionality of the Java platform, and (ii) is exposed to third party software developers for the purpose of developing additional software which invokes such additional API, you must promptly publish broadly an accurate specification for such API for free use by all developers. You may not create, or authorize your licensees to create, additional classes, interfaces, or sub-packages that are in any way identified as "java", "javax", "sun" or similar convention as specified by Sun in any naming convention designation.

This software is provided “AS IS,” without a warranty of any kind. ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE HEREBY EXCLUDED. SUN MICROSYSTEMS, INC. (“SUN”) AND ITS LICENSORS SHALL NOT BE LIABLE FOR ANY DAMAGES SUFFERED BY LICENSEE AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THIS SOFTWARE OR ITS DERIVATIVES. IN NO EVENT WILL SUN OR ITS LICENSORS BE LIABLE FOR ANY LOST REVENUE, PROFIT OR DATA, OR FOR DIRECT, INDIRECT, SPECIAL, CONSEQUENTIAL, INCIDENTAL OR PUNITIVE DAMAGES, HOWEVER CAUSED AND REGARDLESS OF THE THEORY OF LIABILITY, ARISING OUT OF THE USE OF OR INABILITY TO USE THIS SOFTWARE, EVEN IF SUN HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

You acknowledge that this software is not designed, licensed or intended for use in the design, construction, operation or maintenance of any nuclear facility.

“This product includes code licensed from RSA Data Security”

Additional copyright notices and license terms applicable to portions of the software are set forth in the THIRDPARTYLICENSEREADME file.

Sun Java Graphics Repository

Copyright 2000 by Sun Microsystems, Inc. All Rights Reserved

EXOLAB Castor, Exolab Core, Open JMS

Copyright 2000-2002 © Intalio Inc. All Rights Reserved.

The ExoLab Project: <http://www.exolab.org/>

The name “ExoLab” must not be used to endorse or promote products derived from this Software without prior written permission of Intalio Inc. For written permission, please contact info@exolab.org.

Products derived from this Software may not be called “Castor” nor may “Castor” appear in their names without prior written permission of Intalio Inc. Exolab, Castor and Intalio are trademarks of Intalio Inc.

THIS SOFTWARE IS PROVIDED BY INTALIO AND CONTRIBUTORS “AS IS” AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL INTALIO OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

The Legion of the Bouncy Castle

Copyright (c) 2000 The Legion Of The Bouncy Castle (<http://www.bouncycastle.org>)

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM,

DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

STLport

License Agreement

Boris Fomitchev grants **Licensee** a non-exclusive, non-transferable, royalty-free license to use **STLport** and its documentation without fee.

By downloading, using, or copying STLport or any portion thereof, Licensee agrees to abide by the intellectual property laws and all other applicable laws of the United States of America, and to all of the terms and conditions of this Agreement.

Licensee shall maintain the following copyright and permission notices on **STLport** sources and its documentation unchanged:

Copyright 1999,2000 Boris Fomitchev

This material is provided “as is”, with absolutely no warranty expressed or implied. Any use is at your own risk.

Permission to use or copy this software for any purpose is hereby granted without fee, provided the above notices are retained on all copies. Permission to modify the code and to distribute modified code is granted, provided the above notices are retained, and a notice that the code was modified is included with the above copyright notice.

The Licensee may distribute binaries compiled with STLport (whether original or modified) without any royalties or restrictions.

The **Licensee** may distribute original or modified **STLport** sources, provided that:

The conditions indicated in the above permission notice are met;

The following copyright notices are retained when present, and conditions provided in accompanying permission notices are met:

Copyright 1994 Hewlett-Packard Company

Copyright 1996,97 Silicon Graphics Computer Systems, Inc.

Copyright 1997 Moscow Center for SPARC Technology.

Permission to use, copy, modify, distribute and sell this software and its documentation for any purpose is hereby granted without fee, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation. Hewlett-Packard Company makes no representations about the suitability of this software for any purpose. It is provided "as is" without express or implied warranty.

Permission to use, copy, modify, distribute and sell this software and its documentation for any purpose is hereby granted without fee, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation. Silicon Graphics makes no representations about the suitability of this software for any purpose. It is provided "as is" without express or implied warranty.

Permission to use, copy, modify, distribute and sell this software and its documentation for any purpose is hereby granted without fee, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation. Moscow Center for SPARC Technology makes no representations about the suitability of this software for any purpose. It is provided "as is" without express or implied warranty.

MX4J

License Version 1.0. Copyright © 2001 MX4J. All Rights Reserved.

This product includes software developed by the MX4J project (<http://mx4j.sourceforge.net>).

THIS SOFTWARE IS PROVIDED ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL CARLOS QUIROZ OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Jython

Copyright © 2000, Jython Developers. All Rights Reserved.

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

- Neither the name of the Jython Developers nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS ``AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

JPYthon

Copyright © 1995-2001 Corporation for National Research Initiatives.

JPYthon (Version 1.1.x) is made available subject to the terms and conditions in CNRI's License Agreement. This Agreement may be located on the Internet using the following unique, persistent identifier (known as a handle): 1895.22/1006. The License may also be obtained from a proxy server on the Web using the following URL: <http://hdl.handle.net/1895.22/1006>.

CNRI is making the Software available to Licensee on an "AS IS" basis. CNRI MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF EXAMPLE, BUT NOT LIMITATION, CNRI MAKES

NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF THE SOFTWARE WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.

CNRI SHALL NOT BE LIABLE TO LICENSEE OR OTHER USERS OF THE SOFTWARE FOR ANY INCIDENTAL, SPECIAL OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THE SOFTWARE, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF. SOME STATES DO NOT ALLOW THE LIMITATION OR EXCLUSION OF LIABILITY SO THE ABOVE DISCLAIMER MAY NOT APPLY TO LICENSEE.

Jetty

Copyright Mort Bay Consulting Pty. Ltd. (Australia)

\$Revision: 1.1 \$

Preamble:

The intent of this document is to state the conditions under which the Jetty Package may be copied, such that the Copyright Holder maintains some semblance of control over the development of the package, while giving the users of the package the right to use, distribute and make reasonable modifications to the Package in accordance with the goals and ideals of the Open Source concept as described at <http://www.opensource.org>.

It is the intent of this license to allow commercial usage of the Jetty package, so long as the source code is distributed or suitable visible credit given or other arrangements made with the copyright holders.

Definitions:

* “Jetty” refers to the collection of Java classes that are distributed as a HTTP server with servlet capabilities and associated utilities.

* “Package” refers to the collection of files distributed by the Copyright Holder, and derivatives of that collection of files created through textual modification.

* “Standard Version” refers to such a Package if it has not been modified, or has been modified in accordance with the wishes of the Copyright Holder.

* “Copyright Holder” is whoever is named in the copyright or copyrights for the package. Mort Bay Consulting Pty. Ltd. (Australia) is the “Copyright Holder” for the Jetty package.

* “You” is you, if you're thinking about copying or distributing this Package.

* “Reasonable copying fee” is whatever you can justify on the basis of media cost, duplication charges, time of people involved, and so on. (You will not be required to justify it to the Copyright Holder, but only to the computing community at large as a market that must bear the fee.)

* “Freely Available” means that no fee is charged for the item itself, though there may be fees involved in handling the item. It also means that recipients of the item may redistribute it under the same conditions they received it.

0. The Jetty Package is Copyright (c) Mort Bay Consulting Pty. Ltd. (Australia) and others. Individual files in this package may contain additional copyright notices. The javax.servlet packages are copyright Sun Microsystems Inc.

1. The Standard Version of the Jetty package is available from <http://jetty.mortbay.org>.

2. You may make and distribute verbatim copies of the source form of the Standard Version of this Package without restriction, provided that you include this license and all of the original copyright notices and associated disclaimers.

3. You may make and distribute verbatim copies of the compiled form of the Standard Version of this Package without restriction, provided that you include this license.

4. You may apply bug fixes, portability fixes and other modifications derived from the Public Domain or from the Copyright Holder. A Package modified in such a way shall still be considered the Standard Version.

5. You may otherwise modify your copy of this Package in any way, provided that you insert a prominent notice in each changed file stating how and when you changed that file, and provided that you do at least ONE of the following:

- a) Place your modifications in the Public Domain or otherwise make them Freely Available, such as by posting said modifications to Usenet or an equivalent medium, or placing the modifications on a major archive site such as [ftp.uu.net](ftp://ftp.uu.net), or by allowing the Copyright Holder to include your modifications in the Standard Version of the Package.

- b) Use the modified Package only within your corporation or organization.
- c) Rename any non-standard classes so the names do not conflict with standard classes, which must also be provided, and provide a separate manual page for each non-standard class that clearly documents how it differs from the Standard Version.
- d) Make other arrangements with the Copyright Holder.

6. You may distribute modifications or subsets of this Package in source code or compiled form, provided that you do at least ONE of the following:

- a) Distribute this license and all original copyright messages, together with instructions (in the about dialog, manual page or equivalent) on where to get the complete Standard Version.
- b) Accompany the distribution with the machine-readable source of the Package with your modifications. The modified package must include this license and all of the original copyright notices and associated disclaimers, together with instructions on where to get the complete Standard Version.
- c) Make other arrangements with the Copyright Holder.

7. You may charge a reasonable copying fee for any distribution of this Package. You may charge any fee you choose for support of this Package. You may not charge a fee for this Package itself. However, you may distribute this Package in aggregate with other (possibly commercial) programs as part of a larger (possibly commercial) software distribution provided that you meet the other distribution requirements of this license.

8. Input to or the output produced from the programs of this Package do not automatically fall under the copyright of this Package, but belong to whomever generated them, and may be sold commercially, and may be aggregated with this Package.

9. Any program subroutines supplied by you and linked into this Package shall not be considered part of this Package.

10. The name of the Copyright Holder may not be used to endorse or promote products derived from this software without specific prior written permission.

11. This license may change with each release of a Standard Version of the Package. You may choose to use the license associated with version you are using or the license of the latest Standard Version.

12. THIS PACKAGE IS PROVIDED “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

13. If any superior law implies a warranty, the sole remedy under such shall be, at the Copyright Holders option either a) return of any price paid or b) use or reasonable endeavors to repair or replace the software.

14. This license shall be read under the laws of Australia.

JCheckTree

Duguay, Claude, “Visual Components: Swinging on a JCheckTree, JAVAPro Magazine, January 2001, Fawcette Technical Publications, Copyright 1999.

JSpinner

Duguay, Claude, “Widget Factory: JSpinner,” Java Developer’s Journal, Volume 04, Issue 04, SYS-CON Media, Inc., Copyright 2001.

JSch

Copyright (c) 2002, 2003, 2004, 2005, 2006, 2007 Atsuhiko Yamanaka, JCraft, Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

The names of the authors may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED “AS IS” AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL JCRAFT, INC. OR ANY CONTRIBUTORS TO THIS SOFTWARE BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

ICEFaces

ICESoft's open source products are licensed under the Mozilla Public License 1.1 (MPL), or a derivative thereof. The official copy of the Mozilla Public License Version 1.1 can be found at <http://www.mozilla.org/MPL/>

Software distributed under the License is distributed on an "AS IS" basis, WITHOUT WARRANTY OF ANY KIND, either express or implied. See the License for the specific language governing rights and limitations under the License.

Index

A

Access user security windows, [3-2](#)
Active sessions (maximum allowed), [3-6](#)
Active user sessions, [4-3](#)
allowPostLogonDebug task ID, [2-16](#)
allowPostLogonTrace task ID, [2-16](#)
Application Area, [1-1](#)
Audit report XML format, [5-2](#)
Audit_Store_and_Forward data source, [5-1](#)
Automatic file updating, [6-2](#)

C

Calendar starts on, [2-11](#)
Cascading Style Sheets (CSS), JavaHelp, [7-3](#)
Complex password requirements, [3-4](#)
Concurrent active sessions, [2-6](#)
Confirm deletes check box, [2-11](#)
Confirm non-editable row paste check box, [2-11](#)
Confirm non-matching row paste check box, [2-11](#)
Confirm updates check box, [2-11](#)
Content files, JavaHelp, [7-3](#)
Context sensitive help, [7-5](#)
Currency format locale, [2-11](#)
Custom online help, [7-7](#)

D

Desktop layout (areas), [1-1](#)
desktop.cfg file, [B-1](#)
Distributed Security Administration (DSA), [3-7](#)
DSA (Distributed Security Administration), [3-7](#)

F

Frame open indicator, [2-11](#)

G

Get Info function, [3-18](#)

H

Help IDs, [7-5](#)
Helpset file, JavaHelp, [7-3](#)
Helpset Viewer, [7-1](#)
hsvviewer.jar, [7-10](#)

I

Icon area, [1-2](#)
Images, JavaHelp, [7-3](#)

J

JAR files for JavaHelp, [7-3](#)
JAR versions, [2-17](#)
JavaHelp, [7-1](#)
JavaHelp configuration files, [7-3](#)
JavaHelp viewer, [7-1](#)

L

Language, [2-11](#)
local.cfg, [1-2](#)
Logging sensitive data, [1-1](#)
LogScrubber.cfg file, [2-16](#)

M

Map file, JavaHelp, [7-3](#)
Map IDs, [7-5](#)
Maximum number of allowed active sessions, [3-6](#)
Menu Bar, [1-1](#)
Mirror the repository, [6-2](#)
modules.lst file (Modules list), [1-4](#)
Multibyte character data support, [D-1](#)

N

Navigation tree, [1-1](#)
Navigation tree check box, [2-12](#)
New window position, [2-12](#)

O

Online help viewer (JavaHelp), [7-1](#)

P

Packaging of online help, [7-3](#)

Password group, [3-4](#)

Password manager (PswdMgr) utility
 running directly from a Java prompt, [C-3](#)
 running from a user interface window, [C-5](#)

PasswordProperty, [C-1](#)

Passwords, [3-4](#)
 change by a user, [2-8](#)
 change by an administrator, [4-5](#)
 restrictions, [3-4](#)

Permission groups, [3-3](#)

Permissions, [3-3](#)

Pre-show frame indicator, [2-12](#)

Print Screen Orientation, [2-12](#)

Procedures

- Access online help from the desktop, [7-2](#)
- Access user security windows, [3-2](#)
- Assign a security group, [3-20](#)
- Assign a system administration role filter, [3-12](#)
- Assign filters to a user, [3-24](#)
- Assign roles to a user, [3-22](#)
- Change a password (by a user), [2-8](#)
- Change a user password (by admin), [4-5](#)
- Change the display of JavaHelp content, [7-9](#)
- Configure a password group, [3-9](#)
- Configure a security group, [3-10](#)
- Configure a user role, [3-13](#)
- Configure field filters, [3-14](#)
- Configure permission groups, [3-18](#)
- Configure permissions, [3-16](#)
- Connect to a web server, [2-7](#)
- Create custom JavaHelp content HTML files, [7-8](#)
- Create custom online help, [7-7](#)
- Display the name of the user logged on to the desktop, [2-7](#)
- Display the user interface framework version, [2-17](#)
- Display user password history, [4-5](#)
- Enable SSL, [2-2](#)
- Expire a user password, [4-5](#)
- Hide or show the navigation tree, [2-12](#)
- Install JavaHelp, [7-10](#)
- Log off (out), [2-9](#)
- Log off a user, [4-4](#)
- Mirror the repository, [6-2](#)
- Search the helpset, [7-6](#)
- Set a user status, [4-2](#)
- Set Error Notification settings, [2-13](#)
- Set sound preferences, [2-14](#)
- Set user preferences, [2-10](#)
- Terminate an active user session, [4-4](#)
- View active user sessions (refreshing, updating), [4-4](#)
- View password change history, [4-5](#)

R

report.userauditlog.loc environment attribute, [5-3](#)

report.userdetail.xxx properties, [4-7](#)

report.userpermissions.xxx properties, [4-10](#)

Roles, [3-3](#)

RunDesktop.bat, [2-1](#), [6-1](#)

S

Search the helpset, [7-6](#)

Secure Sockets Layer (SSL) protocol, [1-3](#)
 enable, [2-2](#)

Security domains, [3-7](#)

Security error alert message, [2-5](#)

Security groups (users), [3-5](#)

Security warning alert message, [2-6](#)

Session timeout, [3-6](#), [3-11](#)

Sessions (active), [4-3](#)

sound.cfg, [2-14](#)

Status Pane, [1-2](#)

Status pane, [2-12](#)

SysAdmin Profile, [3-12](#)

System Administration Profile, [3-12](#)

T

Table of contents, JavaHelp, [7-3](#)

Timeouts
 session, [3-11](#)
 UI, [3-11](#)

Title Bar, [1-1](#)

Toolbar, [1-1](#), [2-12](#)

Tooltip text (display errors in tooltip text), [2-13](#)

U

UI timeout, [3-6](#), [3-11](#)

User authentication, [1-4](#)

User authorization, [1-4](#)

User interface framework, [1-2](#)

User interface framework version, [2-17](#)

User logged on information, [2-7](#)

User Permissions window, [4-9](#)

User Preferences window
 Error Notification tab, [2-13](#)
 Sound tab, [2-14](#)

User roles, [3-3](#)

User Security Control Management window
 Active Sessions tab, [4-3](#), [4-4](#)
 Password Maintenance tab, [4-5](#)

- User Security Group Configuration window
 - Password Group tab, [3-9](#)
 - Security Group tab, [3-10](#)
- User security overview, [1-4](#)
- User Security Profile Configuration window
 - Active Sessions tab, [4-3](#), [4-4](#)
 - General tab, [3-19](#), [4-2](#)
- User Security Profile window
 - Password tab, [4-5](#)
 - Roles tab, [3-22](#), [3-24](#)
- User Security Role Configuration window
 - Permission Groups tab, [3-18](#)
 - Permissions tab, [3-16](#)
 - Roles tab, [3-13](#)
- User sessions, [4-3](#)
- User status, [4-2](#)
- User Status window, [4-6](#)
- USRAULOG data source, [5-1](#)

V

- Version Checker, [6-1](#)
- Version Checker Client window, [6-2](#)
- Versions, [2-17](#)

W

- Web servers
 - selecting, [2-7](#)
 - user interface framework, [1-2](#)

X

- XML audit message format, [5-2](#)
- XML index file, JavaHelp, [7-3](#)

ACI Worldwide, Inc.