

ACI Desktop User Interface Manual

BASE24-esTM



© 2006 by ACI Worldwide Inc. All rights reserved.

All information contained in this documentation is confidential and proprietary to ACI Worldwide Inc., and has been delivered for use pursuant to license. No part of this documentation may be photocopied, electronically transferred, modified, or reproduced in any manner that is contrary to license without the prior written consent of ACI Worldwide Inc.

Access Control Server, ACI Automated Case Management System, ACI Card Management System, ACI Claims Manager, ACI Commerce Gateway, ACI Debit Card System, ACI e-Courier, ACI Host Link, ACI Merchant Accounting System, ACI Payments Manager, ACI Proactive Risk Manager, ACI Smart Chip Manager, BASE24, BASE24-atm, BASE24-card, BASE24-check auth, BASE24-configuration manager, BASE24-es, BASE24-frequent shopper, BASE24-infobase, BASE24-pos, BASE24-refunds, BASE24-remote banking, BASE24-teller, NET24, and WINPAY24 are trademarks or registered trademarks of ACI Worldwide Inc., Transaction Systems Architects, Inc., or their subsidiaries.

Other companies' trademarks, service marks, or registered trademarks and service marks are trademarks, service marks, or registered trademarks and service marks of their respective companies.

Contents

Preface	v
Conventions Used in This Manual	vii
1: Introduction	1-1
Communication Security	1-3
User Security Server	1-4
2: Getting Started and Basic Functions	2-1
Connection Information	2-2
Log On	2-2
Connect to a Web Server	2-4
Change a Password	2-5
Log Off and Exit	2-5
User Preferences	2-6
General Preferences	2-6
Error Notification Preferences	2-9
Sound Preferences	2-10
Snapshots	2-11
Display Framework Version Information	2-12
3: User Configuration	3-1
User Security Configuration Window Usage	3-2
User Profiles	3-3
Roles	3-3
Passwords and Password Groups	3-4
Security Groups	3-5
Distributed Security Administration (DSA)	3-7
Steps to Add a User	3-8

4: User Management	4-1
Set the Status of a User	4-2
Active User Session Management	4-3
Terminate Active User Sessions (Log off a User)	4-4
Password Management	4-5
User Status Window	4-6
User Status Detail Properties	4-7
User Status Detail Example	4-8
User Permissions Window	4-9
User Status Detail Properties	4-10
5: User Auditing	5-1
Audit Report XML Format	5-2
User Audit Activity Reports	5-3
Automated User Auditing	5-6
6: Version Checker	6-1
7: Online Help	7-1
Access to JavaHelp from the ACI Desktop	7-2
With Context	7-2
Without Context	7-2
JavaHelp Files	7-3
JavaHelp Packages	7-3
Helpset File	7-4
How Context is Implemented in JavaHelp	7-5
Search the Helpset for a Text String	7-6
Custom Help Content	7-7
Customization of HTML Content Files	7-8
Change the Display of Content	7-9
Install JavaHelp for Stand-alone Use	7-10
A: Window (UI) Information	A-1
Index	Index-1

Preface

The ACI desktop is the user access to the following ACI applications for configuration, operation, and management functions:

- BASE24-es
- Enhanced authorization for BASE24 applications
- Transaction Security Services (TSS)
- ACI Payments Manager

Audience

This manual is written for all users of the ACI desktop, including system administration personnel.

Prerequisites

Readers must know basic graphical user interface (GUI) functionality and procedures, such as using hyperlinks and buttons. The ACI desktop is organized by tasks (i.e., configure, system operations, and customer management) that require basic understanding of managing payment systems and applications.

Software

This manual documents standard processing as of its publication date. Software that is not current and custom software modifications (CSMs) may result in processing that differs from the material presented in this manual.

Manual Summary

Section 1, “Introduction,” provides an overview of the ACI desktop, windows, communication security, and information about default users. Also included is information about the user interface framework and user security servers.

Section 2, “Getting Started and Basic Functions,” describes how to log on and log off, set user preferences, and print, among other basic functions available from the File menu.

Section 3, “User Configuration,” provides an overview of user security, distributed security administration (DSA), and how to configure a user of the ACI desktop.

Section 4, “User Management,” describes how to manage and monitor users of the ACI desktop. Includes information about user status and user permission information available on the View menu.

Section 5, “User Auditing,” provides an overview of user auditing of the ACI desktop, including generating audit reports.

Section 6, “Version Checker,” describes how the Version Checker manages and updates ACI desktop versions.

Section 7, “Online Help,” describes the desktop online help (JavaHelp) and how to use online help. Provides information about localizing the ACI desktop and customizing online help.

Appendix A, “Window (UI) Information,” provides a list of each ACI desktop window and for each window the task ID, permissions, help ID, impacted data sources, ACI desktop menu access information, and server messages.

Publication Identification

Information appears at the bottom of each page to identify this manual. This information includes:

- ❑ Publication date (Dec-2006)
- ❑ BASE24-es release and version number (R1.0v06.4)
- ❑ Publication number (CF-CS000-01ES)

Conventions Used in This Manual




This manual uses the symbol shown at the left to alert to cross-industry best practices information for protecting sensitive data that is stored, processed, or transmitted in a BASE24-es system. Carefully review such information to implement compliance to cross-industry best practices for securing data. Refer to the *BASE24-es Security Best Practices* for more information about configuring the BASE24-es product to comply with cross-industry best practices.

ACI Worldwide Inc.

1: Introduction

The user interface of the ACI desktop consists of distinctive areas identified below.



- 1** – The **Title Bar** displays the name of the desktop.
- 2** – The **Menu Bar** provides access to available functions and application windows.
- 3** – The **Toolbar** contains buttons for common functions, such as logon, logoff, and online help.
- 4** – The **Navigation Tree** provides a hierarchical view of the menu bar.
- 5** – The **Application Area** contains opened application windows. Note that the text “LOGGING SENSITIVE DATA” is displayed if the debugging option on the User Preferences window is set, or if tracing of client messages exchanged with the server has been activated by a system administrator.
- 6** – The **Status Pane** contains informational messages about the activity between the desktop and servers. Right click on this pane to see the full detail of a message. Left click to see a list of previously received messages.

The key component of the ACI desktop is the **user interface framework**, which is a collection of Java classes, interface applications, rules, guidelines, recommendations, and styles that are used as a template for building and supporting ACI desktop applications. The components of the user interface framework include:

- User interface clients for which common functions, such as logging on and off the desktop, are available through the File menu
- User security server
- Web servers, such as WebGate

Each web server is responsible for managing communication among desktop clients and the user security server. Multiple web servers can be available in groups and are configured for the desktop using the local.cfg file. By defining groups, users can select web servers as applicable.

- Version Checker for automatic client version checking and updating
- Online help that is context sensitive

These components communicate with each other and with applications running on the application host server using a variety technologies. XML messages are passed to application servers on the host using Transmission Control Protocol/Internet Protocol (TCP/IP).

Hypertext Transfer Protocol (HTTP) is used for ACI desktops to communicate with web servers clients. Java-based Remote Method Invocation (RMI) is used to communicate with the user security server.

Communication Security

Connections among ACI desktops, web servers, user security servers, and application servers on the host can be configured to be secured using Secure Sockets Layer (SSL).

Certificates are used to authenticate servers to desktop clients, and optionally authenticate clients to servers. Public key cryptography is used to encrypt messages sent among clients and servers.

Note: SSL is configured using SSL specific properties defined using the Application Configuration window (**System Operations > Server Management > Application**). Refer to the *ACI Java Server Framework User Guide* for more information.

The following Java™ Archive files provide the support needed for SSL:

- Jcert.jar
- Jnet.jar
- Jsse.jar
- UIFSSLKeys.jar, which contains the default keystores.

Certificates and private keys used for encryption and authentication are maintained in protected files called keystores. These files vary by application and are identified by .sto.



Note: Custom communication developed and implemented for TCP/IP lines outside of the ACI desktop must be secured using SSL.

User Security Server

The user security server authenticates and authorizes users, creates and maintains active user sessions, and maintains the access level for each user. Host applications access the user security server to obtain authorization to complete a function initiated by an authenticated user of the ACI desktop.


For authentication, an individual must provide a user ID and password. This information is passed to the user security server, which checks the information against the user security database to determine whether the individual can access the application. This authentication includes the requirement that the user ID be defined in the user security database and the password must match that recorded for the ID. In addition, the user's security group and password group restrictions are checked.

User authorization is the validating of each activity initiated by a user. During user authorization the user security server compares the activity initiated by a user to the user's security profile, which defines the functions (i.e., Delete, Save, and View) that a user can perform. This ensures that a user does not perform an activity not authorized by the user's security configuration.

See section 3 (User Configuration) and section 4 (User Management) for more information.

2: Getting Started and Basic Functions

Each desktop session is started by running the **RunDesktop.bat** batch file, which is usually configured during installation to be accessed through a shortcut located on a client desktop or a menu. For example:



When the desktop is started, it contacts the applicable servers and configuration files and which point the Version Checker is accessed to determine whether new and updated JAR files are available from the Server Repository. If JAR files on the local desktop need updating, the Version Checker Client window is displayed for users to download new and updated JAR files (see section 6 for more information).

After the desktop establishes contact with the applicable servers and JAR files have been downloaded, the desktop displays the Log In window for entry of a user ID (name) and password. The desktop opens after a valid user ID (name) and password combination has been provided and authenticated by the user security server. The file menu functions (e.g., Configure) and windows that are presented are dependent upon the user's configuration settings.


This section discusses logging on to the desktop, connecting to web servers, setting user preferences, sending desktop snapshots, and viewing version information.

Connection Information

This topic provides information for logging on, concurrent sessions, connecting to a web server, changing passwords, and logging off.

Log On


To log on, select the Log In function located on the File menu (**File > Log In**), the Log In button () on the toolbar, or navigation tree.




After a successful logon (authenticated user) the desktop provides access to those applications (windows) that system administration has assigned to the user (i.e., the permissions and permission groups of the user's profile). Each session is assigned a unique session number used by the user security server for authorization purposes.

In addition to the above, session and window (UI) timeout values are initiated and tracked during a session. A timeout is a defined period of inactivity. Timeout limits are defined in the security groups assigned to users.

If the user name and password are not correct or the user name has been disabled or does not have valid access at the time of login, the user security server does not allow the user access to the desktop. In this case a security error message (shown below) is displayed. The error message is purposely vague so not to indicate which information (name or password or both) is incorrect.




A **security warning**, such as the example below, is displayed upon a successful logon if there were one or more unsuccessful logon attempts before the successful logon.




Concurrent Sessions

The number of **concurrent active sessions** allowed for a user is limited to a maximum as defined in the Security Group of the user's profile. A possible scenario in which a user might have concurrent active sessions is by logging on from another terminal without logging off from an active session that was started at another terminal.

This version of the Session Information dialog is displayed if a user has one or more existing active sessions when logging on, and this number of sessions is fewer than the maximum number as defined in the user's Security Group.



This version of the Session Information dialog is displayed if a user upon logon has already reached the maximum number of allowed active sessions defined in the user's Security Group.



Connect to a Web Server


During startup, the ACI desktop attempts to connect to the default (or most recently used) web server. If multiple web servers are available, a user can access the Connection window (**File > Connection**) to select an alternate.

The Connection window displays a selectable list of available web servers from which one can be selected.

If the one selected accesses a different shared user security database, any existing active sessions for the user are terminated. Also, the port used must be available (i.e., not used by another system or application); otherwise, a connection error is encountered.

Change a Password

To change a password, log on to the desktop and select the Change Password function (**File > Change Password**) to display the Change Password window:



Certain password restrictions and requirements apply. See section 3 for more information.

Log Off and Exit

To log off, select the Log Out function located either on the File menu (**File > Log Out**), the Log Out button () on the toolbar, or navigation tree.

Logging off does not close the desktop. To close the desktop, select **File > Exit**.


Note: A user does not need to be logged on to exit. Also, if a user exits without logging off, the user is automatically logged off from the desktop.

User Preferences

Each user can set desktop characteristics to desired preferences by accessing **File > Preferences**. These preferences are discussed below.

General Preferences

Use the General tab of the User Preferences window to set the following user preferences.




Descriptions of general preferences are discussed below.

Preference	Description
Confirm Deletes	Indicates whether the desktop displays a confirmation dialog box before a delete function is processed.
Confirm non-editable row paste	Displays a dialog box indicating that an attempt was made to paste a copied table row onto a non-editable row.
Confirm non-matching row paste	Displays a dialog box indicating that an attempt was made to paste a copied table row onto a table row that has a different number of table cells.
Confirm Updates	Indicates whether the desktop displays a confirmation dialog box that requires a response before an update function is processed.
Currency Format Locale	Sets whether the default currency is obtained from the desktop configuration or user configuration settings.
Debugging Enabled	Enables the writing of debug messages to a debug file (e.g., DeskTop.dbg). This activates the text “LOGGING SENSITIVE DATA” to be displayed on the background of the application area.
Frame Open Indicator	Indicates whether a Frame Open Indicator is displayed in the desktop toolbar while a window is opening.
Language	Displays menu functions, dialog box text, messages, and field names in the selected language, if the selected language is defined in the properties file for a window. This also allows access to available localized online help (online help provided in a different language or dialect).
Navigation Tree	Sets whether the navigation tree is displayed upon desktop startup. If checked, the navigation tree is initially displayed. If not checked, it is initially hidden.

Preference	Description
New Window Position	Sets the position of a window when opened as follows: • Bottom • Cascaded • Centered • Frame specified • Left • Right • Top • Top left
Pre-Show Frame	Indicates whether a blank window is shown while a window is initializing (being opened).
Screen Print Orientation	Sets the default print orientation to either portrait or landscape.
Status Pane	Indicates whether the status pane is displayed.
Toolbar	Indicates whether the toolbar is displayed.

Error Notification Preferences


Use the Error Notification tab to set error notification preferences.



Preference	Description
Border Color	Sets the border color of fields that are in error.
Status	Indicates whether error text is displayed in the status pane of windows.
Tooltip	Indicates whether error messages are displayed in tooltip text. Tooltip text is text that appears in a pop-up window over a field or button.
Dialog	Indicates whether error messages are displayed in a dialog box.
Trap Focus	Makes error messages modal, that is, a user is required to resolve an error before focus can be change to another window or tab.

Sound Preferences

Use the Sound tab to set the sound played during certain events (as selected in the Events field).



Preference	Description
Themes	Sets the sound group to apply to the selected event(s). Themes are defined in the sound.cfg configuration file located in the desktop.jar. The theme selected is stored in the configuration file of the logged on user.
Events	An event to be associated with a sound file.
Location	The location of the sound file, such as a .AU file (Java) and .WAV file (Windows), to associate with the selected event.

Snapshots

Use the Send Snapshot (**File > Send Snapshot**) function to send an E-mail message (using the Send Snapshot window shown below) about the desktop configuration and a log record (DeskTop.log) of desktop activity to system administrators. The DeskTop.log file is an ASCII text file that contains information about recent desktop activity that is pertinent to system administrators.

The configuration information is sent as a comma separated values (CSV) file that can be opened by many ASCII readers and spreadsheet applications. The configuration information contains the following information:


- User ID and machine (client workstation) ID
- JAR versions installed
- Local configuration settings
- Version Checker settings
- Global configuration settings
- User preferences
- Global preferences

Display Framework Version Information

Access **Help > About** to display desktop version information as shown below:




Click **Versions** to display detailed version information as shown below:




3: User Configuration

The ACI desktop provides access to an integrated user security environment in which each user must be defined in a user security database. This section consists of two parts: an overview of user security and steps about how to add a user. It also discusses the user profile which is central to establishing a user's access level to the ACI desktop. Each profile defines the integral components of user security, some of which, such as security and password groups, can be shared among multiple users. The hierarchy of a user profile is shown below.



User Security Configuration Window Usage

User profiles are maintained from the ACI desktop using various user security windows. The hierarchy of a user profile from the previous page is shown below with the names and usage of the user security windows added.



All user security windows are accessed at **Configure > User Security**.

User Profiles

Each user is assigned a **user profile** consisting of the following configuration components:

- User ID — A unique character string used to identify a user.
- General user information — Name and contact information about a user.
- User status — Set by the user security server in response to some action, such as too many bad logon attempts, or by security administrative personnel.
- Role(s) — One or more sets of permission groups.
- Security group — A unique ID that defines a set of common user security access restrictions.
- Password group — A unique ID that defines a set of common user password restrictions.

Roles

A role defines the level of a user's access to the desktop. Each role identifies a job function, such as security administrator, system administrator, manager, and end user. Roles apply a set of permissions, tasks, and functions to users.

A role can contain one or more permission groups. A permission group can contain one or more permissions. Each permission is associated with a task (window application) and defines the functions (e.g., delete, save, send, and view) allowed for that task.

Permission Groups

A permission group is a collection of selected permissions that is assigned a unique identifier (the permission group ID) and a description of the purpose or use of the group.

Permissions

Permissions define specific access to a window. Each permission consists of a single task (task ID), the functions that can be performed within the task, a unique ID (the permission ID), and a description of the purpose or use of the permission.

Field Filters

Field filters restrict a user's access to field values by defining either a single value, multiple values, or a range of values allowed.

Note: For BASE24-es, only the Institution ID and Issuer ID fields are filterable.

Task IDs

Each task consists of a unique identifier and a group of functions (e.g., delete, save, send, and view) and corresponds to a window on the ACI desktop. Available task IDs and functions for each task ID are provided on the Permissions tab of the User Security Role Configuration window and are used to create permission IDs. Task IDs can be used in multiple permissions.

Passwords and Password Groups



A user's password is stored in the user security database in encrypted form using a Secure Hash Algorithm (SHA1) that is not reversible ensuring that passwords cannot be extracted in clear form from the database.

Note: When a new user is added, the option to force the new user to change his or her password on first use can be selected as described in step 4.4 later in this section.

Passwords comply with Payment Card Industry complex password requirements as follows:

- Passwords are case sensitive.
- Alphabetic, numeric, and special characters are permitted.
- Password history is maintained.
- Passwords cannot be shared.
- Characters cannot be repeated sequentially. For example, a password with the string “BB” appearing anywhere in the password is not valid.
- The password cannot be the same as the user ID. For example, a user with the ID “enduser02” cannot use “enduser02” as the password.
- A user's password must meet the requirements (discussed below) defined in the password group assigned to the user.

Password Group Requirements

Password groups consist of password requirements that are imposed on all user passwords assigned the group. A password group consists of the following password requirements as configured using the Password Groups tab on the User Security Group Configuration window.



- The number of days prior to a password expiration on which the desktop displays a warning dialog prompting a user to change the password.
 - The maximum number of days a user can use a password.
 - The minimum password length (4 characters or more).
- Note:** Payment card cross-industry best practices specify a minimum length of 7 or more characters.
- The maximum password length.
 - The minimum number of numeric characters required in each password.
 - The minimum number of alphabetic characters required in each password.
 - The maximum number of old passwords retained for each user (users cannot use retained old passwords).
 - The maximum number of password changes allowed during a 24-hour period.

Security Groups

Each user must be assigned one and only one security group. However, since a security group can be assigned to multiple users, the security group simplifies the management of user security, assigns passwords by group, and assists in implementing distributed security administration, which is discussed later in this section.

Each user security group consists of the following common user security access restrictions that apply to all users assigned the security group:

- The time each day a user can log on to the desktop.
- The time each day a user must be logged off the desktop and, after which, can no longer log on to the desktop.
- The days of the week on which a user can log on to the desktop.
- The maximum number of invalid logon attempts allowed for each user. If this value is reached, the user's status is disabled by the user security server.

- The number of minutes, if set, after which the number of invalid logon attempts is reset to zero.
- The maximum number of active sessions allowed for a user.


When a user fails to log off correctly from the desktop or if a system outage occurs during a user's active session, the user security database still maintains a record of the active session. Therefore, if the maximum number of active sessions has been reached by a user attempting to log on to the desktop, the user is presented with an option to stop one or more of the active sessions.
- The number of seconds of user inactivity after which the user is automatically logged off the desktop (this is called a **session timeout**).
- The number of seconds of terminal inactivity after which the desktop is disabled and any logged on user is logged off (this is called a **UI timeout**).
- The number of days a user's ID can be inactive (not used) after which the user ID status is disabled by the user security server.
- The password group ID defining password requirements applied to all users of the security group.

Distributed Security Administration (DSA)

Each installation is configured with a system administrator and security administrator. The system administrator has access to all applications of the desktop. The security administrator has access to the user security windows. Distributed security administration involves the security administrator configuring other, lower-level, administrators that are assigned a limited set of permissions. Distributed security administration is enabled by setting the **OwnerIDSupport** property in the usec.cfg file to true.

Distributed security is implemented by the top-level security administrator by configuring applicable roles, assigning these roles as necessary to security groups, and assigning the security groups to other, lower-level, system administrators.

The top-level security administrator can set up tiers of other system administrators who are limited to a **security domain**, which is a set containing a security group, password group, roles, and permissions as defined by a security role ID. At this level, a role ID is used to restrict users within the domain to a defined set of permissions (including permission groups), tasks and filters. This methodology can be used to create system administrator groups and departments as shown in the illustration below.



For example, the system administrator assigned Role1 can create user profiles or groups of user profiles having roles that can contain only those permissions, permission groups, tasks, and filters defined for Role1. With distributed security administration, users, including administrators, cannot access the users and roles of other security domains.

Steps to Add a User

Note: Some steps have additional steps (i.e., steps 3.1 – 3.3 and 4.1 – 4.5). Whether these additional steps are required depends on the extent to which a complete user security system has been configured.

- ❑ Step 1.0: Configure a Password Group
- ❑ Step 2.0: Configure a Security Group
- ❑ Step 3.0: Configure a User Role
 - Step 3.1: Configure Field Filters
 - Step 3.2: Configure Permissions
 - Step 3.3: Configure Permission Groups
- ❑ Step 4.0: Configure the User's Profile
 - Step 4.1: Set the User's Status
 - Step 4.2: Assign a Security Group
 - Step 4.3: Enter Information about the User
 - Step 4.4: Set the User's Password
 - Step 4.5: Assign Roles

Usage Note: To ensure that changes are implemented in the user security database, click Save () each time a step has been completed.

Tip: If a new user is to be based on an existing user profile, that is, the password group, security group, and roles are already configured, go directly to step 4.0 and read the Tip provided in the step.

Step 1.0: Configure a Password Group

Use the Password Group tab on the User Security Group Configuration window to configure a password group.

The screenshot shows the 'User Security Group Configuration' window with the 'Password Group' tab selected. The 'Password Gr...' dropdown is set to 'pswd_grp_1'. The 'Description' field contains 'Default password group for end users.' Below this, there are two columns of settings, each with a label and a numeric input field with up/down arrows:

Minimum Length	7	Lifetime Days	30
Maximum Length	10	Old Password Cache	5
Required Numeric Characters	2	Expire Pre-Warn Days	7
Required Alpha Characters	2	Changes Per Day	3

In the example above, the password group **pswd_grp_1** is shown. This group is described as the default password group for end users. The password requirements are set in the fields provided on the tab.

Password groups are assigned to users (their profiles) through security groups. Therefore, a password group must be assigned to a security group using the Security Group tab of the User Security Group Configuration window. The security group is then used in user profiles.

Step 2.0: Configure a Security Group

Topics in this step to consider are listed below and are discussed on the following pages.

- ❑ UI and Session Timeout Considerations
- ❑ System Administration Role Filter (Owner ID)

Use the Security Group tab on the User Security Group Configuration window to configure a security group.

The screenshot shows the 'User Security Group Configuration' window with the 'Security Group' tab selected. The configuration includes the following fields and settings:

- Security Group:** end_user_sec_grp (selected from a dropdown)
- Description:** Security group for end users.
- Password Group:** pswd_grp_1 (selected from a dropdown)
- SysAdmin Profile:** (empty dropdown)
- Allowed Time and Days:**
 - Begin:** 08:00 am
 - End:** 05:00 pm
 - Days:** Sun (unchecked), Mon (checked), Tue (checked), Wed (checked), Thu (checked), Fri (checked), Sat (unchecked)
- Bad Logins Allowed:** 3
- Reset Bad Logins:** 3000 seconds
- Sessions Allowed:** 1
- UI Timeout:** 1800 seconds
- Inactive Days Allowed:** 60
- Session Timeout:** 3600 seconds

In the example above, the configuration for the **end_user_sec_grp** security group is shown. This group defines standard authentication requirements for users. The password group **pswd_grp_1** is assigned to this security group. As a result, the password requirements defined by **pswd_grp_1** apply to all users of this security group. Users assigned this security group cannot log on to the desktop before 8:00 am and must be logged off by 8:00 pm. Also, users cannot log on to the desktop on Sundays and Saturdays.

UI and Session Timeout Considerations

A security group defines both UI and session timeouts. These timeouts are defined in units of seconds using the Security Group tab of the User Security Group Configuration window.

A UI timeout occurs after a duration of desktop inactivity defined in the UI Timeout field. When a UI timeout event occurs, the user no longer has access to the desktop and any open windows; however, the user's session and the open windows are not closed but the desktop displays the Verify Password dialog in which the user must provide a valid password to restore access to the desktop and any open windows. The user also has the option to log out at this time.

UI timeouts only occur if the security group to which the user belongs has a configured UI timeout limit greater than zero. Entering a zero ('0') in the UI Timeout field implies no limit of desktop inactivity.

A session timeout occurs after a duration of desktop inactivity defined in the Session Timeout field. When a session timeout event occurs, the user is automatically logged off the desktop and the user must log on (open the Log In window and provide a valid user name and password combination) to obtain access to the desktop. Any windows open upon a session timeout are closed.

If the user's session expires while the Verify Password dialog is displayed and the user has not provided input, the user is still logged out and the user is no longer able to verify the password. All windows are closed, but the desktop remains open.

Session timeouts only occur if the security group to which the user belongs has a configured session timeout limit greater than zero. Entering a zero ('0') in the Session Timeout field implies no limit of desktop inactivity.

To use UI timeouts in an effective manner, the session timeout must be greater than the UI timeout. This is because if the session timeout is less than the UI timeout, users in the security group will be logged off the desktop (upon a session timeout event) prior to a UI timeout event.

A UI timeout event should occur first so that a user can be alerted and take necessary action to save work. Having a session timeout less than the UI timeout negates the purpose of the UI timeout.

System Administration Role Filter (Owner ID)


When the **OwnerIDSupport** property in the usec.cfg file is set to the true, the Security tab on the User Security Group Configuration window displays the SysAdmin Profile selectable field.

An existing role ID can be assigned to a security group using the SysAdmin Profile field. Since a role defines a set of permissions (permission groups), tasks IDs and field filters, the role ID at this level limits access to permissions and permission groups that can be configured for users by administrators assigned the security group. To assign a role ID as a filter for a security group, select the role ID in the SysAdmin Profile field.

If a system administration role profile is selected for a security group, only those permission groups, permissions, and tasks defined for the role are accessible to users assigned the security group.

Step 3.0: Configure a User Role

To configure a user role, use the Roles tab on the User Security Role Configuration window.



If the available permission groups meet existing needs, enter or select the role ID in the Role field, add or modify the description of the purpose of the role, and select the applicable permissions groups (permission groups can be selected and deselected using the check boxes for each group), then go to Step 4.0: Configure the User's Profile. **Note:** Permissions not defined within your security domain are not available.

If one or more permission groups need to be configured, the following steps might also need to be performed.

- ❑ Step 3.1: Configure Field Filters
- ❑ Step 3.2: Configure Permissions
- ❑ Step 3.3: Configure Permission Groups

Step 3.1: Configure Field Filters

Note: The functionality of field filtering is the same among applications, but the implementation can vary. For BASE24-es, only the Institution ID and Issuer ID fields are filterable.

Field filters are configured using the Filters tab on the User Security Role Configuration window, which is shown below, and are applied to a user's profile through permissions.

The screenshot shows the 'User Security Role Configuration' window with the 'Filters' tab selected. The window has a title bar with a red triangle icon and standard window controls. Below the title bar is a toolbar with icons for save, print, refresh, delete, and help. The main area contains the following fields and controls:


- Filter ID:** A dropdown menu with 'AllIssuer' selected.
- Field ID:** A dropdown menu with 'Issuer' selected.
- Description:** A text box containing 'All the issuers on the system.'
- Filter Type:** A group box containing three radio buttons: 'Range' (selected), 'Single Value', and 'Multi-Value'.
- Filter Settings:** A large container box containing two text boxes: 'Begin Value' and 'End Value', both of which are empty.

Field filters consist of the following elements:

- ❑ Unique identification (the Filter ID field)
- ❑ Field ID
- ❑ A description of the purpose and use of the filter
- ❑ One or more field values, which can be a single value, multiple values, or a range of values.


The format of the Filter Settings area is dependent upon the filter type selected, whether Range, Single Value, or Multi-Value.

If **Range** is selected, begin and end values must be entered:



The screenshot shows a 'Filter Type' section with three radio buttons: 'Range' (selected), 'Single Value', and 'Multi-Value'. Below this is a 'Filter Settings' section containing two text input fields labeled 'Begin Value' and 'End Value'.

If **Single Value** is selected, a single filter value must be selected or entered:



The screenshot shows a 'Filter Type' section with three radio buttons: 'Range', 'Single Value' (selected), and 'Multi-Value'. Below this is a 'Filter Settings' section containing a single dropdown menu labeled 'Filter Value'.

The values available in the Filter Value field are those that have been configured using the applicable configuration window. For example, for the InstitutionID field ID, the values shown in the Filter Settings area are those institution IDs that have been configured using the Institution Configuration window.

Tip: Use the asterisk (“*”) to select all current and future field values.

If **Multi-Value** is selected, values must be selected and moved from the All Field Values field to the Selected Field Values field.

To add or remove field values, use the following buttons provided on the tab to perform the desired task:

Button	Task
	Add the selected field value(s) from the All Field Values field to the Selected Field Values field.
	Add all available field values from the All Field Values field to the Selected Field Values field.
	Remove the selected field(s) value from Selected Field Values field back to the All Field Values field.
	Remove all field values from Selected Field Values field back to the All Field Values field.

To select a value, click on the value. Selected values have a modified background color. To select multiple values, press down the **Ctrl** key while selecting values.

The values shown in the All Field Values field are those that have been configured using the applicable configuration window. Use the asterisk (“*”) to select all current and future field values. For example, for the InstitutionID field ID, the values shown in the Filter Settings area are those institution IDs that have been configured using the Institution Configuration window.

To add a value not available in the All Field Values field, enter the value in the text entry field to the right of the Filter Type area and click the Add Value button.

Step 3.2: Configure Permissions

Use the Permissions tab on the User Security Role Configuration window to create permissions and permission group IDs.

The screenshot shows the 'User Security Role Configuration' window with the 'Permissions' tab selected. The window has a title bar with standard OS controls. Below the title bar is a toolbar with icons for file operations. The main area contains several fields and a tree view:

- Permission ID:** A dropdown menu showing 'FullAcctStatusMappingProfile'.
- Task ID:** A dropdown menu showing 'AcctStatusMappingProfile'.
- Description:** A text field containing 'FullAcctStatusMappingProfile'.
- Functions:** A tree view on the left showing a folder 'Functions' with three sub-items: 'Delete', 'Save', and 'View'. Each item has a checkbox and a small icon.
- Filter Description:** A text field containing 'Filter info'.

At the bottom of the window, there is a status bar with a message: 'Permission read.'

Permission IDs

A new permission ID can be created (entered) or an existing permission ID can be selected. Permissions are available on the Permissions Group tab for selection when configuring a permission group.

The description is to state the purpose of the permission and any special information.

Tasks IDs

Each task ID corresponds to an ACI desktop window. **Note:** Task IDs cannot be created using the ACI desktop.

Functions

The functions that a user can perform on a window (task) are defined for each permission on the Permissions tab. A function is selected by entering a check mark in the functions check box. Functions include, but are not limited to, Delete, Save, Send, and View. The available functions vary by task ID.

Field Filters

If a task ID refers to a window that contains a field or fields that are filterable, the Permissions tab will list the field ID(s) and provide a selectable list of filter IDs that can be selected and applied to the permission.

The field IDs **InstitutionID** and **Issuer** are shown in the example below for the Institution Configuration window.

Note: The actual filterable fields varies by application. See the boxed note in step 3.1 for more information.

The screenshot shows the 'User Security Role Configuration' window with the 'Permissions' tab selected. The window has a title bar with standard OS controls. Below the title bar is a toolbar with icons for save, delete, and other actions. The main area contains several fields and a list of functions.

Fields:

- Permission ID: FullInstConfigPermission
- Task ID: InstitutionConfiguration
- Description: Full Institution Configuration permission set.

Functions:

- Functions: A list of functions with checkboxes. The 'InstitutionID' function is checked.

Filter Information:

- Filter ID: InstitutionID
- Filter Value: AllInstitution
- Filter Description: Filter info

Footer: Permission read.

Step 3.3: Configure Permission Groups

To configure a new or existing permission group, use the Permission Groups tab on the User Security Role Configuration window. This tab provides a Permission Group field in which a new permission group ID can be entered or an existing permission group can be selected.

Available permissions, as defined per your security domain, are provided on the tab. Permissions are added or removed from a permission group by selecting (entering a check mark) or deselecting (removing a check mark) in the appropriate checkbox.

Permission Information

A description of each permission along with the Task ID assigned to the permission and the allowed functions can be displayed in the Permission Description section of the Permissions Groups tab. To display this information, right click on the desired permission and select Get Info on the pop-up menu.

Step 4.0: Configure the User's Profile

To configure a new user (user profile), display the General tab of the User Security Profile Configuration window, enter the user's unique ID in the User ID field and perform the following steps:

- ❑ Set the user's status
- ❑ Assign a security group
- ❑ Enter information about the user
- ❑ Set the user's password
- ❑ Assign roles to the user

The screenshot shows the 'User Security Profile Configuration' window with the 'General' tab selected. The 'User ID' field is set to 'end_user_1'. Below the tabs, there are two columns of fields. The left column includes 'User Status' (set to 'Active'), 'First Name' (placeholder '<given_name>'), 'Middle Name' (empty), 'Last Name' (placeholder '<family_name>'), 'Department' (placeholder '<department_id>'), 'Location' (empty), 'Manager' (empty), and 'Email' (empty). The right column includes 'Security Group' (set to 'end_user_sec_grp'), 'Work Phone' (empty), 'Mobile Phone' (empty), 'Fax' (empty), 'Create Time' (05/08/06 2:01 PM), 'Last Login' (05/18/06 9:01 AM), 'Last Failed Login' (05/09/06 9:05 AM), and 'Bad Login Tries' (1). The window has a standard Windows-style title bar and a toolbar with icons for save, refresh, and delete.

Tip: To add a new user whose profile is based on an existing user profile, display the user profile that is to be used as a template and replace the text in the User ID field with the new user ID.

Note: When the Save button is clicked for a new user, the desktop displays the New User's Password window, which is described in Step 4.4.

Step 4.1: Set the User's Status

User status options:

Active	= Open and active.
Closed/Admin	= Closed without incident.
Closed/Inactive	= Closed, by the user security server, due to inactivity.
Disabled/Admin	= Disabled, for security reasons, by authorized personnel.
Disabled/System	= Disabled, for security reasons, by the user security server (e.g., maximum number of log on attempts has been reached).
Temporary	= User can access the desktop for a predefined amount of time.

Step 4.2: Assign a Security Group

Security groups are provided in the selectable field next to the Security Group link. If a desired security group is not available, click on the link to access the User Security Group Configuration window to review existing security groups or configure a new security group. Only those security groups defined for your security domain are available.

Step 4.3: Enter Information about the User

Information about the user includes:

- ❑ Complete name information
- ❑ Contact information, such as phones, Fax and email address
- ❑ Employment information, such as department, manager and location

Step 4.4: Set the User's Password

To set a new user's password, click Save, after which the desktop displays the New User's Password window.

Note: The Password tab of the User Security Profile Configuration window is used for management of existing users, see the User Management section for more information.

For users assigned a status other than Temporary, the desktop displays the version of the New User's Password window shown below. Indicate whether the user must change the assigned password during the next logon (or first logon for a new user), and the start date on which the user can log on to the desktop.



The dialog box titled "New User's Password" has a blue title bar with a red triangle icon and a close button. It contains two password input fields labeled "New Password" and "Verify Password", both filled with asterisks. Below these is a checkbox labeled "Require password change" which is checked. Underneath is a date selection field labeled "New User Start" showing "Monday, March 15, 2006". At the bottom are "Ok" and "Cancel" buttons.


When a new temporary user (i.e., user status being set to temporary) is created, the desktop displays the New User's Password window, shown below, for indicating whether the user must change the password on logging on, and for setting the start and expiration dates for which the user is active.



The dialog box titled "New User's Password" has a blue title bar with a red triangle icon and a close button. It contains two empty password input fields labeled "New Password" and "Verify Password". Below these is an unchecked checkbox labeled "Require password change". Underneath is a date selection field labeled "New User Start" showing "Wednesday, March 31, 2006". Below that is another date selection field labeled "New User Expire" also showing "Wednesday, March 31, 2006". At the bottom are "Ok" and "Cancel" buttons.

Step 4.5: Assign Roles

Use the Roles tab on the User Security Profile window to assign (and remove) the roles defined for a user.



This tab displays all the user roles available within your security domain on the ACI desktop. Roles not defined within your security domain are not displayed. User roles assigned to a user are shown in the User Roles field. Available user roles not assigned to a user are shown in the All Roles field. To add or remove user roles from a user profile, select the role or roles and use the buttons provided on the tab to perform the desired task. The buttons are:

Button	Task
	Add the selected role(s) to the user profile (move from the All Roles field to the User Roles field).
	Add all available roles to the user profile (move from the All Roles field to the User Roles field).

Button	Task
	Remove the selected role(s) from the user profile (move from the User Roles field to the All Roles field).
	Remove all assigned roles from the user profile (move from the User Roles field to the All Roles field).

To select a role, click on the role. Selected roles have a modified background color. To select multiple roles, press down the **Ctrl** key while selecting roles.


If a particular role is not available or an existing role needs to be changed, click on the Configure Roles link to access the User Security Role Configuration window to configure a new or existing role.

Note: A user cannot change the role configuration for the profile (User ID) that was used to log on. In such situations, when the Roles tab is accessed for that User ID, the All Roles field and User Roles fields are inactive.

4: User Management

System administrators can set the status, display and terminate active sessions, and expire passwords by password group of users within the administrator's security domain. This activity is performed from the user security windows as described in this section.

The illustration below shows the user profile and includes the name of the applicable windows used to manage user profiles.



The User Security Profile Configuration window is used for configuring a user profile; however, it can be used to view a user's active sessions, to change an existing user's status and to manage a user's password.

The User Security Control Management window is used to view and manage the active sessions for all users. The window can also be used to expire passwords by password group.

To assist system administrators and other authorized users, two additional windows are available and are discussed in this section:

- User Status window
- User Permissions window

Set the Status of a User

The user security server maintains a status for each user. A user's status can be changed by the user security server if security and password group requirements have been violated. A user's status can also be changed by authorized users.

Use the General tab on the User Security Profile Configuration window to view and set a user's status.

User Security Profile Configuration

User ID: end_user

General | Roles | Password | Active Sessions

User Status: Active (dropdown menu open showing: Active, Closed/Admin, Closed/Inactive, Disabled/Admin, Disabled/System, Temporary)

Security Group: end_user_sec_grp

First Name: [text box]
Middle Name: [text box]
Last Name: [text box]
Department: [text box]
Location: [text box]
Manager: [text box]
Email: [text box]

Work Phone: [text box]
Mobile Phone: [text box]
Fax: [text box]
Create Time: 1/11/06 1:00 PM
Last Login: 3/15/06 4:55 PM
Last Failed Login: 2/2/06 2:07 PM
Bad Login Tries: 1

Authorized users can assign the following status codes to a user:

- | | |
|-----------------|---|
| Active | = Open and active. |
| Closed/Admin | = Closed without incident. |
| Closed/Inactive | = Closed, by the user security server, due to inactivity. |
| Disabled/Admin | = Disabled, for security reasons, by authorized personnel. |
| Disabled/System | = Disabled, for security reasons, by the user security server (e.g., maximum number of log on attempts has been reached). |
| Temporary | = User can access the desktop for a predefined amount of time. |

Active User Session Management

When a user has logged on to the desktop by providing a valid user ID and password, the user security server creates an active session for the user. An active session contains the following information:

- ❑ The user's ID.
- ❑ The unique session number assigned by the user security server.
- ❑ The workstation ID, such as a network ID or URL, from which the user has logged on to the desktop.
- ❑ The date and time the user began the session.
- ❑ The date and time the current session expires.


Information about active user sessions is available on two separate Active Sessions tabs. One tab is provided on the User Security Profile Configuration window and displays the active sessions for a selected user. The other Active Sessions tab is located on the User Security Control Management window and displays active user sessions for all users within a security administrator's security domain (security group to which the administrator has access).

Active User Session for a Selected User:

The screenshot shows a window titled "User Security Profile Configuration" with a blue header bar. Below the header, there are icons for file operations and a section labeled "Active Sessions". A "User ID" dropdown menu is set to "end_user". Below this, there are four tabs: "General", "Roles", "Password", and "Active Sessions", with the last one being selected. The "Active Sessions" tab contains a table with two columns: "Workstation ID" and "Logged in time". The table has one row with the values "Network/URL" and "2006-3-24 08:43:11.39". Below the table, there is a "Password" label and a "Logout Selected" button. At the bottom of the window, there is a link labeled "All Active Sessions".

Workstation ID	Logged in time
Network/URL	2006-3-24 08:43:11.39

Active User Sessions for All Users:



Note: The active sessions of the application can change at any time; therefore, to update the list of active sessions, click Refresh ().

Terminate Active User Sessions (Log off a User)

One or more active user sessions can be terminated (i.e., logged off) from either one of the two windows that are used to display active user sessions — the User Security Profile Configuration window and the User Security Control Management window. To log off one or more user sessions, display and select the user session(s) and click Logout Selected.

Password Management

Authorized users can view a user's password change history, add or change a user's password, and expire the user's current password by accessing the Password tab on the User Security Profile window and selecting the user's ID.

To change a user's password, display the Password tab on the User Security Profile Configuration window and select the user ID. Enter the new password in both the New Password and Verify Password text boxes and click Save (). If the change is successful, a confirmation message appears in the status pane of the window. Otherwise, an appropriate error message is displayed.


To expire a user's password, display the Password tab on the User Security Profile Configuration window, select the user ID, and click Expire Password. If a user's password has been expired but a new password has not been defined, the user is prompted to create a new password on the next logon attempt.

Authorized users can access a table that shows the password groups that have been assigned to security groups, and can expire all user passwords of users assigned to a password group.

Use the Password Maintenance tab on the User Security Control Management window to view password group usage and expire password groups.

User Status Window

The User Status window (**View > User Status**) lists summary information for users. Example User Status window:



When this window is accessed, a list of user IDs with user role and logon information is displayed.

This window allows quick identification of users with specific status exceptions and stale (i.e., idle) accounts. To identify such users, if the **More** button is active, click the button to retrieve additional users. The **More** button remains active until all user accounts have been retrieved. The users can be sorted by logon information by clicking the **Last Logged In** column. Other columns can be used to sort the users by different criteria.

To display a detail report for a user, select the row of the user and click **Detail**. The summary information displayed in the text area can be printed using the Print function available on the File menu.

User Status Detail Properties



In support of PCI compliance, a recurring report of the information shown on this window can be configured using the following properties documented in the *Java Server Framework Reference Guide*:

report.userdetail.loc


report.userdetail.name

report.userdetail.timeperiod.hours

report.userdetail.starttime


User Status Detail Example

Below is an example of the detail information available on the User Status window.



User Permissions Window

The User Permissions window (**View > User Permissions**) provides hierarchical information for users, roles, permission groups, permissions, tasks, and field filters. Example User Permission window:



When this window is accessed, hierarchical user security information lists are provided and accessible on the various tabs of the window. For example, select the Tasks tab to identify all task IDs and the role, permissions, permission groups, and users assigned a given task.

Note: Distributed Security Administration filters do not apply to the information displayed on the User Permissions window. Therefore, user security access to the window should only be provided to System-level security administrators.

User Status Detail Properties



In support of PCI compliance, a recurring report of the information shown on this window can be configured using the following properties documented in the ***Java Server Framework Reference Guide***:

report.userpermissions.loc

report.userpermissions.name

report.userpermissions.timeperiod.hours

report.userpermissions.starttime

5: User Auditing

User audit is the logging of user activity to a data source for the purpose of reporting and monitoring the user activity.

Whenever a user of the desktop initiates and completes an activity (e.g., logon, logoff, password changes, delete, or save) from a window, a message that contains information about the user activity is written to the User Audit Log data source.

The audit message sent to the log data source can be one of the following:

- Header information only about the changes to affected records
- Header information and detail information about the before and after data images of affected records

The application server writes audit messages directly to the USRAULOG data source or to the Audit_Store_and_Forward data source depending on the middle ware capabilities of the hardware platform.

For information about enabling user auditing and setting the audit level for a desktop window, refer to the *ACI Java Server Framework Reference Guide* for information about audit properties, such as:

- `db.audit.db-service-name`
- `db.audited`
- `db.audited.db-service-name`

Audit Report XML Format

The information stored in the extracted audit reports is in XML format. The following example is an XML-formatted message containing user activity information.


```
<?xml version="1.0" encoding="UTF-8" ?>
<AuditReport>
  <AuditDetails row="0">
    <Audit_LoggingRq>
      <TimeStamp>TimeStamp Info</TimeStamp>
      <ContextDescr>InsertRq</ContextDescr>
      <Ticket>
        <UserID>User Profile ID</UserID>
        <SessionNumber>1</SessionNumber>
        <TerminalID>OMAUUSER/ip_addr</TerminalID>
      </Ticket>
      <ActivityGroup>
        <ActivityType>Table Function</ActivityType>
        <TableGroup>
          <TableName>Table</TableName>
          <KeyGroup>
            <Column>
              <ColumnName>Table Element</ColumnName>
              <BeforeValue />
              <AfterValue>New Value</AfterValue>
            </Column>
            <Key>
              <KeyColumn>
                <ColumnName>Key</ColumnName>
                <AfterValue>New Value</AfterValue>
              </KeyColumn>
            </Key>
          </KeyGroup>
        </TableGroup>
      </ActivityGroup>
    </Audit_LoggingRq>
  </AuditDetails>
</AuditReport>
```

The root element of the XML message is `<AuditReport>` that includes one or more `<AuditDetails></AuditDetails>` sections. `<AuditDetails>` contains important information: a time stamp (`<TimeStamp>`), Context information (`<ContextDescr>`), ticket information (`<Ticket>`), and activity information (`<ActivityGroup>`). Information related to the user and the user's session is included in the ticket. Information about the activity performed and the data source (table) affected is included in the activity group.

Note: Use an XML reporting tool such as XML Spy, MS-Access 2002, or Crystal Reports to evaluate and format the XML information as well as to generate reports.

User Audit Activity Reports


Activity reports for selected users can be initiated accessing User Audit on the View menu. User activity is extracted from the USRAULOG data source for a specified user ID between a start date and time and an end date and time. This information can be viewed on the ACI desktop or sent to a designated file. The location where the file is saved is specified by the **report.userauditlog.loc** environment attribute, which defines the directory location.



The reports provide the following information:

- Date and time of action.
- User ID performing the action.
- Terminal location from which action was performed.
- Type of action performed.
- File and field name affected by the action, if applicable.
- Before and after image of data modification action, if full auditing is set.


When a report is completed, the results are shown in the Audit Report Viewer for which an example is shown below.



If the **More** button is active, click the button to retrieve additional users. Note that the **More** button remains active until all user accounts have been retrieved. The user information displayed in the table can be sorted using the column headers. Additional column headers can be selected by pressing the **Ctrl** key.

To display detail information for a user, select the user and click the **Detail** button.

Example detail report:



Automated User Auditing

User audit extracts to file can be performed automatically by specifying the `com.aciworldwide.common.timertask.UserAuditReport` classname for the configuration properties file `timertask.function.n.classname` configuration parameter. The Java Server Framework application specified as the `timertask.manager.processid` invokes the classname at application initialization.

The following properties are used to configure automated user audit reporting:

Property	Description
<code>report.userauditlog.loc</code>	The file path for the user audit report.
<code>report.userauditlog.name</code>	The name of the user audit report.
<code>report.userauditlog.offset.days</code>	The number of days prior to the current day to use for obtaining user activity for the report.
<code>report.userauditlog.report.starttime</code>	The time at which the report is generated.

For example, if today is Wednesday and the time is 9:00 AM, the offset is one day, and the report start time is 2:00 AM, then the most recent audit information available is that for 2:00 AM Tuesday to 2:00 AM Wednesday.

Refer to the *ACI Java Server Framework Reference Guide* for more information about the above properties.


6: Version Checker

The desktop provides a way for clients to keep the desktop configuration current. This configuration support is provided by the Version Checker, which is a utility that manages the versions of JavaTM Archive (JAR) files of desktop components that are distributed to ACI desktop clients. The Version Checker automatically runs during startup of the desktop at which time it compares the current version of the client files to new versions, which reside in a predetermined location (i.e., repository). The location of the Version Checker repository is defined during installation. New files that are to be distributed to clients are placed in this location.

The Version Checker automatically runs when a desktop is started per commands located in the **RunDesktop.bat** file. Desktop shortcuts specified during installation point to this batch file. Whether a user is prompted to accept any new files or the files are automatically downloaded is dependent upon configuration settings as discussed in this section.

The files on the repository for which the version differs from that of the client are displayed in the Version Checker Client window. This window provides a list of the files along with the version number of each file on the repository and the version number of the file on the client. If automatic file updating is enabled (discussed later in this section), then this window is not displayed.

To download new files from the repository, select the applicable files and click Update. This update process can be skipped or canceled.



The **Select All** option can be used to select all listed files on the Version Checker Client window. Individual files can be selected by deselecting the Select All option and then clicking in the row for each desired file to download. Only selected files are downloaded.

If the **Close When Done** option is selected, the Version Checker Client window will automatically close after completion of the download of all selected files.

By selecting **Mirror Repository** on the Version Checker Client window, verification is initiated to ensure that no jars reside on the client that are not also on the server repository. That is, any files that exist on the client that do not exist on the current version of the server repository are deleted from the client.

The Version Checker can be configured to download updated and new files automatically. This automatic file updating (called VC quiet mode) is an option presented during installation of the ACI desktop.

Including the parameter “-Q” in the Version Checker command line located in the **RunDesktop.bat** file enables automatic file updating. Note that the “-Q” is added during installation when the VC quiet mode option is selected.

For example:

```
call "C:\ACI\VersionChecker\verChk" -Q
```

7: Online Help

The ACI desktop provides online help for windows (screens) and window components (e.g., fields). This help is displayed in a Java-based HTML browser, called the **Helpset Viewer**:



The components of the Helpset Viewer are:

- 1** — The **Title Bar** in which the name of the helpset is displayed.
- 2** — The **Toolbar** that contains various menu and button functions.
- 3** — The **Navigation Pane** in which are located Contents and Index tabs useful for navigating to desired help content, and a Search tab for searching content.
- 4** — The **Content Pane** in which help content is displayed.
- 5** — The **Contents** tab that provides structured access to window-level help files.
- 6** — The **Index** tab that provides alphabetical access to all help topics.
- 7** — The **Search** tab for searching help content.

Access to JavaHelp from the ACI Desktop

JavaHelp content can be accessed with or without context. These two methods are explained below.

With Context

Accessing online help with context displays the Helpset Viewer with content displayed in the Content Pane that is specific to a window or window component. To display help with context from the ACI desktop, select **Help > Context Help** or click  on the toolbar. Either of these actions display the Help Pointer  to use for clicking in a general area of a window for window-level help or on a window field for field-level help.

If a window is not open, help with context is not available because an active window in the Application Area of the ACI desktop is necessary to provide context. When context help is not available, the Context Help function and the button are inactive.

Note that the traditional way to access field-level help by placing the cursor in the field and pressing the **F1** key can also be used.

Without Context

To display online help without context from the ACI desktop, select **Help > Help Topics** from the Menu Bar or click  on the Toolbar. A window does not need to be open to access online help without context. When online help is accessed using this method, the Helpset Viewer is displayed with the default home page provided in the content pane and the default TOC view in the navigation pane.

If the Help Topics function and the button are not enabled, then the ACI desktop does not have access to online help. Check with a System Administrator to obtain ACI online help.

JavaHelp Files

The following files together are referred to as a **JavaHelp helpset**:

- The **helpset file** (ACI_Help.hs), which is identified by the .hs file extension, defines the name of the helpset displayed in the Title Bar, the JavaHelp components used, the name of the map file, the names of the table of contents and index files, and the ID of the default content file to display in the Content Pane when help is accessed without context. The helpset file is the top-level file in the JavaHelp helpset.

Be careful not to confuse the term “JavaHelp helpset” with the helpset (.hs) file. *JavaHelp helpset* refers to a collection of JavaHelp files as discussed on this page. Whereas the helpset (.hs) file is a single file (see following page).

- The **map file** is an XML file identified by the .jhm file extension that corresponds identifiers to HTML content files. This file is necessary to provide context-sensitive help for windows and window components as discussed later in this section.
- The **table of contents file** that defines the structure and links of the text entries of the Contents tab.
- The **index file** that defines the structure and links of the text entries of the Index tab located in the Navigation Pane of the Helpset Viewer.
- **HTML files** in which help content resides.
- **Cascading Style Sheets (CSS)** define the style rules applied to content.
- The **images** displayed within HTML content files. Images used in content are in Graphical Interchange Format (GIF) and Joint Photographic Experts Group (JPEG or JPG) formats.

JavaHelp Packages

ACI online help is packaged and distributed in the following Java™ Archive (JARs) files:

- **ACI_Help_es.jar** — For BASE24-es
- **ACI_Help_tss.jar** — For Transaction Security Services (TSS)
- **ACI_Help_pm.jar** — For ACI Payments Manager (PM)

Helpset File

The helpset file defines the Java components used, home page, map file, TOC, index, and views. Below is an example helpset file. Comments between “<!--” and “-->” have been added to provide additional information.

```
<?xml version='1.0' encoding='ISO-8859-1' ?>
<!DOCTYPE helpset
  PUBLIC "-//Sun Microsystems Inc.//DTD JavaHelp HelpSet Version 2.0//EN"
  "http://java.sun.com/products/javahelp/helpset_2_0.dtd">
<helpset version="2.0">

  <!-- The title displayed in the Title Bar -->
  <title>ACI Online Help</title>

  <!-- Map information -->
  <maps>
    <homeID>splash</homeID> <!-- The map ID of the splash page -->
    <mapref location="map.jhm" /> <!-- The map file -->
  </maps>

  <!-- Each view represents a tab on the Helpset viewer -->
  <!-- This helpset has 3 views. -->
  <!-- Immediately below is the TOC view -->
  <view>
    <name>TOC</name>
    <label>Contents</label> <!-- The popup (flyover) text of the tab -->
    <type>javax.help.TOCView</type> <!-- The JavaHelp TOC component -->
    <data>toc.xml</data> <!-- The name of the table of contents file -->
  </view>

  <!-- This is the index view -->
  <view>
    <name>Index</name>
    <label>Index</label>
    <type>javax.help.IndexView</type> <!--
    <data>ix.xml</data> <!-- The name of the index file -->
  </view>

  <!-- This is the search view -->
  <view>
    <name>Search</name>
    <label>Search</label>
    <type>javax.help.SearchView</type>
    <data engine="com.sun.java.help.search.DefaultSearchEngine">
      JavaHelpSearch
    </data> <!-- The search engine defined by the engine attribute -->
    <!-- And, the search database. In this case, the search -->
    <!-- database is located in a folder named JavaHelpSearch -->
  </view>


</helpset>
```

How Context is Implemented in JavaHelp

Help context is implemented in JavaHelp by the use of unique identifiers. Each identifier (referred to as a map ID or help ID) appears as necessary in the following files:

- The property (.properties) file for a window (desktop application)
Note: Most application windows have their own properties file. Also, some properties common among all windows are located in common property files that are shared among the window properties files.
- The JavaHelp map file, map.jhm (pmdesktop.jhm for ACI Payments Manager)
- The table of contents file, toc.xml (ACI_Help_pmtoc.xml for ACI Payments Manager)
- The index file, ix.xml (all applications)

The use and relationship of the identifiers in the above files is shown in the following illustration.




Search the Helpset for a Text String

The Search tab provides a text entry field (Find) to locate up to 100 occurrences of a text string within a helpset.

Note: Search is not case sensitive.

Enter the text string in the Find text entry field and press the **Enter** key. JavaHelp searches through the helpset and displays a list of topics in which the text string is found. This list is displayed in the Navigation Area by topic title and in descending order of number of matches. Select the desired topic to display the topic's content in the Content area.



Custom Help Content

Online help can be modified in a number of different ways depending on the level of modification desired.

- Content files can be modified.
- Cascading style sheets can be modified to change display formats.
- Images referenced in content files can be edited.

Note: Modifying the JavaHelp configuration files can adversely affect the performance of JavaHelp and is not discussed in this manual.

If an installed version of JavaHelp is customized, care must be taken to avoid overwriting the customized JavaHelp files when accepting an updated help JAR file for placement on the Version Checker repository. Therefore, the following guidelines can be used to establish procedures for maintaining and protecting customized JavaHelp:

- Always keep a backup of both original and customized files.
- Consider appending an identifier (e.g., “custom”) to the name of customized files. If a help file name is changed, the change must also be made to the map.jhm file. For example, a file named f_connection.htm file is customized and renamed to f_connection_custom.htm. The url attribute in the map.jhm file must be changed as follows:

From:

```
<mapID target="f_connection"
      url="f_connection.htm"/>
```

To:

```
<mapID target="f_connection"
      url="f_connection_custom.htm"/>
```

- Another option is to keep the same name of the file but place the customized file into a separate directory as follows:

```
<mapID target="f_connection"
      url="custom/f_connection.htm"/>
```

Customization of HTML Content Files

All content files within the JavaHelp JAR files are in compliance with the W3C HTML revision 3.2 format. This format is required for content files to display properly within the Helpset Viewer. Certain parts of the HTML revision 4.0 format can be used since it shares most markup tag elements with 3.2; however, care should be taken when implementing revision 4.0 features into content files destined for JavaHelp because certain revision 4.0 features might not be supported. To ensure proper behavior of content files in JavaHelp, always test the display characteristics of HTML files in JavaHelp before releasing the help files.

One advantage of the content files being in HTML format is that common editors can be used to modify help content. The specifics of editing HTML files are not discussed here since these depend on the editor; however, the following general always apply:

1. Before an HTML content file within a JAR file can be edited, the file must be extracted to a working location using a tool, such as WinZip. The extracted HTML file is a copy of the original file. Make a backup of the original file and place it in a specified archive directory for later retrieval. All editing should be done on the extracted copy.
2. Select an appropriate HTML editor. Note that some HTML editors automatically add embedded XML, HTML and other types of objects to HTML code. Such objects can adversely affect the display of the content within JavaHelp. As a result, editing tools that do not automatically add objects are recommended. Such tools include Macromedia's Dreamweaver and ASCII editors, such as Notepad.
3. Save the modified HTML file to the working location.
4. Add the modified file to the applicable JAR file replacing the original file in the JAR (the original being maintained in the archive directory location). Do not change the file extension.
5. If the name of the HTML file is changed to reflect customization, such as from `f_connection.htm` to `f_connection_custom.htm`, the URL attribute of the `map.jhm` file needs to be updated to reflect the name change. The `.jhm` file can be updated using an ASCII editor.

Change the Display of Content

The format and style of the content displayed in the Helpset Viewer can be modified by altering the values of the style properties in the applicable cascading style sheet (CSS) file. CSS files are defined in the <head>...</head> section of each HTML file used in the ACI online help using <link> tags as follows:

```
<link rel="StyleSheet" href="Templates/forScreen.css" type="text/css"
media="screen">
```

```
<link rel="StyleSheet" href="Templates/forPrint.css" type="text/css"
media="print">
```

CSS files are located in the Templates folder within the applicable helpset JAR (ACI_Help_es.jar, ACI_Help_tss.jar, and ACI_Help_pm.jar).

Note: For ACI Payments Manager, the name of the CSS is document.css for both screen and print media.

To ensure that content displays properly in the Helpset Viewer, always test before releasing the modified CSS files.

Install JavaHelp for Stand-alone Use


JavaHelp can be installed for direct access to helpset (.hs) files without the need to have the ACI desktop open. Note that Java must be already installed. The remainder of this topic discusses installing JavaHelp on a Java enabled Windows-based PC.

1. Download the latest version of JavaHelp from:


<http://java.sun.com/products/javahelp>

Note: JavaHelp is distributed as a zip file such as **Javahelp 2.0_02.zip** (a more current version might be available).

2. Open the zip file and extract all files to an easily accessible location, such as (e.g., C:\jh2.0). Among the files extracted is the **hsvviewer.jar** file that is needed later in this procedure.
3. Find java.exe and create a shortcut to the file. Java.exe must be already installed. Cut and paste the shortcut to an easily accessible location.
4. Right click on the shortcut and select Properties on the drop-down menu:



The properties for the shortcut are available in the Properties window:




5. In the Target field located on the Shortcut tab, enter the path to java.exe, followed by a space, -jar, another space, and then the path to the installed location of hviewer.jar. In the illustration above, the full text of the Target field is partially obscured, but contains:

"C:\Program Files\jdk1.5.0_05\bin\java.exe" -jar "C:\jh2.0\demos\bin\hviewer.jar"

Note: If a blank space is located in a file path (e.g., C:\Program Files\...), enclose the path in quotes, as shown above.

6. Click OK.

7. Test the install by clicking on the shortcut, after which the following Set HelpSet window should display that can be used to browse to a helpset file (.hs extension) that you want to open.



If the above window does not display, a number of problems could exist. For example, either Java, JavaHelp, or both are not installed properly. Also, the target path in the shortcut could be incorrect. Verify that the paths in the shortcut reflect the actual paths for both java.exe and hsvviewer.jar.

A: Window (UI) Information

The term *window* is used in documentation and online help. This term relates to a collection of graphical user interface (GUI) components (i.e., buttons, fields, field names, tabs, buttons, tables, trees, and messages) that provide access to a particular application, function and data source(s).

Each window, which can also be called a UI, is managed by a particular application server on the host. The applications available (therefore, the windows available) depend on the ACI desktop configuration and user security access permissions.

An application (and the corresponding window) is identified by a task ID. Tasks available on a desktop can be viewed in the Task ID selectable field located on the Permissions tab of the User Security Role Configuration window (**Configure > User Security > Role**).

Window information is presented alphabetically by window name. Information is structured as follows:

Task ID:	The unique task ID for the window.
Permissions:	Full access and view access permissions, as applicable.
Help ID:	The unique ID for context sensitive help between the desktop and the online help system.
Data Sources:	A list of data sources possibly updated by the window. The actual data source(s) impacted by a change made at a window can vary by application configuration. Verify impacted data sources using the OLTP Warmboot Management window.
Desktop Access:	How the window is accessed on the ACI desktop.
Messages:	Messages exchanged with the server.

Acquirer Transactions Allowed Profile Configuration Window

Task ID:	AcquirerTransactionsAllowed
Permissions:	FullAcqTransAllowedPermission ViewAcqTransAllowedPermission
Help ID:	w_acquirer_transactions_allowed_profile_configuration
Data Sources:	ACQ_TXN_ALLOWED
Desktop Access:	Configure > Transactions Allowed > Acquirer Transactions Profile
Messages:	ATAPrflListRq ATAPrflInsertRq ATAPrflViewRq ATAPrflUpdateRq ATAPrflDeleteRq ATAPrflGenericDeleteRq

Action Code Profile Configuration Window

Task ID:	ActionCode
Permissions:	FullActionCodePermission FullIFXHostActCdPermission ViewActionCodePermission ViewIFXHostActCdPermission
Help ID:	w_action_code
Data Sources:	ACT_CDE_EXT_INT ACT_CDE_INT_EXT
Desktop Access:	Configure > Action Code Profile
Messages:	ActionCodeIntInsertRq ActionCodeExtInsertRq ActionCodeListRq ActionCodeIntViewRq ActionCodeIntUpdateRq ActionCodeExtViewRq ActionCodeExtUpdateRq ActionCodeIntDeleteRq ActionCodeExtDeleteRq ActionCodeGenericDeleteRq

Active Scripts Statistics and Management Window

Task ID:	ActiveScript
Permissions:	FullActiveScriptPermission ViewActiveScriptPermission
Help ID:	w_active_script_statistics_and_management
Data Sources:	ACTV_SCRIPT_STAT
Desktop Access:	System Operations > Active Script Statistics
Messages:	ActiveScriptListRq ActiveScriptMsgTypeListRq AuthScriptDataRq ActiveScriptViewRq ActiveScriptResetDataRq

Administrative Card Configuration Window

Task ID:	AdministrativeCardManagement
Permissions:	FullAdminCardMgmtPermission ViewAdminCardMgmtPermission
Help ID:	w_administrative_card_configuration
Data Sources:	ADMIN_CARD
Desktop Access:	Configure > Administrative Card
Messages:	AdminCardInsertRq AdminCardViewRq AdminCardUpdateRq AdminCardDeleteRq

Application Configuration Window

Task ID:	IWTApplicationConfig
Permissions:	FullIWTApplCfgPermission ViewIWTApplCfgPermission
Help ID:	w_application_configuration
Data Sources:	APPLCNFG
Desktop Access:	System Operations > Server Management > Application
Messages:	IWTAppCfgInsertRq IWTAppCfgGetPropertyRq IWTAppCfgListRq IWTAppCfgUpdateRq IWTAppCfgDeleteRq

Application Management Comms Handler Window

Task ID:	ApplctnManagementSummary
Permissions:	FullApplctnManagementSummary ViewApplctnManagementSummary
Data Sources:	Not specified.
Help ID:	w_appmanage_comms_handler_summary
Desktop Access:	System Operations > Application Management > Comms Handler Summary
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

Application Management Message Router Summary Window

Task ID:	ApplctnManagementSummary
Permissions:	FullApplctnManagementSummary ViewApplctnManagementSummary
Data Sources:	Not specified.
Help ID:	w_appmanage_message_router_summary
Desktop Access:	System Operations > Application Management > Message Router Summary
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

Application Management Process Summary Window

Task ID:	ApplctnManagementSummary
Permissions:	FullApplctnManagementSummary ViewApplctnManagementSummary
Data Sources:	Not specified.
Help ID:	w_appmanage_process_summary
Desktop Access:	System Operations > Application Management > Process Summary
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

Application Management Queue Manager Summary Window

Task ID:	ApplctnManagementSummary
Permissions:	FullApplctnManagementSummary ViewApplctnManagementSummary
Data Sources:	Not specified.
Help ID:	w_appmanage_queue_manager_summary
Desktop Access:	System Operations > Application Management > Queue Manager Summary
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

Application Management Queue Summary Window

Task ID:	ApplctnManagementSummary
Permissions:	FullApplctnManagementSummary ViewApplctnManagementSummary
Data Sources:	Not specified.
Help ID:	w_appmanage_queue_summary
Desktop Access:	System Operations > Application Management > Queue Summary
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

Application Management Station Summary Window

Task ID:	ApplctnManagementSummary
Permissions:	FullApplctnManagementSummary ViewApplctnManagementSummary
Data Sources:	Not specified.
Help ID:	w_appmanage_station_summary
Desktop Access:	System Operations > Application Management > Station Summary
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

Application Management Window

Task ID:	ApplctnManagement
Permissions:	FullApplctnManagement ViewApplctnManagement
Data Sources:	Not specified.
Help ID:	t_appmanage_detail
Desktop Access:	System Operations > Application Management > Application Management
Messages:	ApMgButtonRq ApMgMbListRq ApMgSummaryRq ApMgUpdateRq ApMgViewRq

ATM BASE24 Compatibility Profile Configuration Window

Task ID:	ATMB24CompatProfile
Permissions:	FullATMB24CompatPrflPermission ViewATMB24CompatPrflPermission
Help ID:	w_atm_base24_compatibility_profile_configuration
Data Sources:	CMPTPRFL
Desktop Access:	Configure > ATM (Java) > ATM BASE24 Compatibility Profile
Messages:	ATM BASE24 Compatibility Profile ATMB24CompatProfileInsertRq ATMB24CompatProfileListRq ATMB24CompatProfileViewRq ATMB24CompatProfileUpdateRq ATMB24CompatProfileViewRq ATMB24CompatProfileDeleteRq

ATM Channel Administration Window

Task ID:	ATMChannelAdministration
Permissions:	FullATMChannelAdminPermission ViewATMChannelAdminPermission
Help ID:	w_atm_channel_administration_java
Data Sources:	ATDCNFG ESATDD1 ESATDS1 HPRPRFL
Desktop Access:	System Operations > ATM (Java) > ATM Channel Administration
Messages:	ATM Channel Administration ATMChannelAdminListRq ATMChannelAdminViewRq ATMChannelAdminUpdateRq ATMChannelAdminSubmitRq

ATM Channel Administration Window

Task ID:	ATMDHChannelAdministration
Permissions:	FullATMDHChannelAdminPerm ViewATMDHChannelAdminPerm
Help ID:	w_atm_channel_administration_cplus
Data Sources:	ATDCNFG ESATDD1 ESATDS1
Data Sources:	HPRPRFL
Desktop Access:	System Operations > ATM > ATM Channel Administration
Messages:	ATMChannelAdminListRq ATMChannelAdminViewRq ATMChannelAdminUpdateRq ATMChannelAdminSubmitRq

ATM Channel Configuration Window

Task ID:	ATMChannel
Permissions:	FullATMChannelPermission FullATMChannelAdminPermission FullATMChannelMgmtPermission FullATMChannelPrflPermission ViewATMChannelPermission ViewATMChannelAdminPermission ViewATMChannelMgmtPermission ViewATMChannelPrflPermission
Help ID:	w_atm_channel_configuration_java
Data Sources:	Not specified.
Desktop Access:	Configure > ATM (Java) > ATM Channel
Messages:	Not specified.

ATM Channel Configuration Window

Task ID:	ATMDHChannel
Permissions:	FullATMDHChannelPermission FullATMDHChannelAdminPerm FullATMDHChannelMgmtPermission FullATMDHChannelPrflPermission ViewATMDHChannelPermission ViewATMDHChannelAdminPerm ViewATMDHChannelMgmtPermission ViewATMDHChannelPrflPermission
Help ID:	w_atm_channel_configuration_cplus
Data Sources:	ATM_DS1
Desktop Access:	Configure > ATM > ATM Channel
Messages:	Not specified.

ATM Channel Management - All Channels Window

Task ID:	ATMChannelManagement
Permissions:	FullATMChannelMgmtPermission ViewATMChannelMgmtPermission
Help ID:	w_atm_channel_management_all_java
Data Sources:	ESATDD1 ESATDS1
Desktop Access:	System Operations > ATM (Java) > ATM Channel Management > All Channels
Messages:	ATMChannelMgmtAllSubmitRq

ATM Channel Management - All Channels Window

Task ID:	ATMDHChannelManagement
Permissions:	FullATMDHChannelMgmtPermission ViewATMDHChannelMgmtPermission
Help ID:	w_atm_channel_management_all_cplus
Data Sources:	ESATDD1 ESATDS1
Desktop Access:	System Operations > ATM > ATM Channel Management > All Channels
Messages:	ATMChannelMgmtAllSubmitRq

ATM Channel Management - Selected Channels Window

Task ID:	ATMDHChanMgmtSelectedChannels
Permissions:	FullATMDHChanMgmtSCPermission ViewATMDHChanMgmtSCPermission
Help ID:	w_atm_channel_management_selected_cplus
Data Sources:	ESATDD1 ESATDS1
Desktop Access:	System Operations > ATM > ATM Channel Management > Selected Channels
Messages:	ATMChannelMgmtViewRq ATMChannelMgmtSubmitRq

ATM Channel Management - Selected Channels Window

Task ID:	ATMChanMgmtSelectedChannels
Permissions:	FullATMChanMgmtSCPermission ViewATMChanMgmtSCPermission
Help ID:	w_atm_channel_management_selected_java
Data Sources:	ESATDD1 ESATDS1
Desktop Access:	System Operations > ATM (Java) > ATM Channel Management > Selected Channels
Messages:	ATMChannelMgmtViewRq ATMChannelMgmtSubmitRq

ATM Channel Profile Configuration Window

Task ID:	ATMChannelProfile
Permissions:	FullATMChannelPrflPermission ViewATMChannelPrflPermission
Help ID:	w_atm_channel_profile_configuration
Data Sources:	ATM_PRFL
Desktop Access:	Configure > ATM (Java) > ATM Channel Profile
Messages:	ATMConfigProfileInsertRq ATMConfigProfileListRq ATMConfigProfileViewRq ATMConfigProfileUpdateRq ATMConfigProfileDeleteRq

ATM Channel Profile Configuration Window

Task ID:	ATMDHChannelProfile
Permissions:	FullATMDHChannelPrflPermission ViewATMDHChannelPrflPermission
Help ID:	w_atm_channel_profile_cplus
Data Sources:	ATM_PRFL
Desktop Access:	Configure > ATM > ATM Channel Profile
Messages:	ATMConfigProfileInsertRq ATMConfigProfileListRq ATMConfigProfileViewRq ATMConfigProfileUpdateRq ATMConfigProfileDeleteRq

ATM Consumer Media Configuration Window

Task ID:	ATMDHConsumerMedia
Permissions:	FullATMDHConsumerMediaPerm ViewATMDHConsumerMediaPerm
Help ID:	w_consumer_media_configuration
Data Sources:	ATM_CONSUMER_MEDIA
Desktop Access:	Configure > ATM > ATM Consumer Media
Messages:	ATMDHConsumerMediaInsertRq ATMDHConsumerMediaListRq ATMDHConsumerMediaViewRq ATMDHConsumerMediaUpdateRq ATMDHConsumerMediaDeleteRq ATMDHConsumerMediaGenericDeleteRq

ATM Depository Bin Profile Configuration Window

Task ID:	ATMDHDepositoryBinProfile
Permissions:	FullATMDHDepBinPrflPermission ViewATMDHDepBinPrflPermission
Help ID:	UnknownHelpID
Data Sources:	ATM_SSB_BIN
Desktop Access:	Configure > ATM > ATM Depository Bin Profile
Messages:	ATMDHDepBinProfileInsertRq ATMDHDepBinProfileListRq ATMDHDepBinProfileViewRq ATMDHDepBinProfileUpdateRq ATMDHDepBinProfileDeleteRq ATMDHDepBinProfileGenericDeleteRq

ATM Device Handler Interface Configuration Window

Task ID:	ATMDHInterfaceConfiguration
Permissions:	FullATMDHIFCfgPermission ViewATMDHIFCfgPermission
Help ID:	w_atm_device_handler_interface_configuration
Data Sources:	Not specified.
Desktop Access:	Configure > Interface > Host > ATM Device Handler
Messages:	Not specified.

ATM Diebold Channel Operator Configuration Window

Task ID:	ATMDHDieboldChannelOperatorID
Permissions:	FullATMDHDbldChanOpIDPerm ViewATMDHDbldChanOpIDPerm
Help ID:	w_atm_diebold_channel_operator_configuration
Data Sources:	ATM_OPER
Desktop Access:	Configure > ATM > ATM Diebold Channel Operator
Messages:	ATMDHOperIdInsertRq ATMDHOperIdListRq ATMDHOperIdViewRq ATMDHOperIdUpdateRq ATMDHOperIdDeleteRq ATMDHOperIdGenericDeleteRq

ATM Diebold Channel Operator ID Configuration Window

Task ID:	ATMDieboldChannelOperatorID
Permissions:	FullATMDbldChanOprIDPermission ViewATMDbldChanOprIDPermission
Help ID:	w_atm_diebold_channel_id_configuration
Data Sources:	ATM_OPER
Desktop Access:	Configure > ATM (Java) > ATM Diebold Channel Operator
Messages:	ATMDHOperIdInsertRq ATMDHOperIdListRq ATMDHOperIdViewRq ATMDHOperIdUpdateRq ATMDHOperIdDeleteRq ATMDHOperIdGenericDeleteRq

ATM EMV Profile Configuration Window

Task ID:	ATMDHEmvProfile
Permissions:	FullATMDHEmvProfilePermission ViewATMDHEmvProfilePermission
Help ID:	w_atm_emv_profile_configuration
Data Sources:	ATM_EMV
Desktop Access:	Configure > ATM > ATM EMV Profile
Messages:	ATMEmvProfileInsertRq ATMEmvProfileListRq ATMEmvProfileViewRq ATMEmvProfileUpdateRq ATMEmvProfileDeleteRq

ATM EMV Profile Configuration Window

Task ID:	ATMEmvProfile
Permissions:	FullATMEMVProfilePermission ViewATMEMVProfilePermission
Help ID:	w_atm_emv_profile_configuration
Data Sources:	ATM_EMV
Desktop Access:	Configure > ATM (Java) > ATM EMV Profile
Messages:	ATMEmvProfileInsertRq ATMEmvProfileListRq ATMEmvProfileViewRq ATMEmvProfileUpdateRq ATMEmvProfileDeleteRq

ATM Fast Cash Profile Configuration Window

Task ID:	ATMDHFastCashProfile
Permissions:	FullATMDHFastCashPrflPerm ViewATMDHFastCashPrflPerm
Help ID:	w_atm_fast_cash_profile_configuration
Data Sources:	ATM_FAST_CASH
Desktop Access:	Configure > ATM > ATM Fast Cash Profile
Messages:	ATMFastCashProfileInsertRq ATMFastCashProfileListRq ATMFastCashProfileViewRq ATMFastCashProfileUpdateRq ATMFastCashProfileDeleteRq

ATM Fast Cash Profile Configuration Window

Task ID:	ATMFastCashProfile
Permissions:	FullATMFastCashPrflPermission ViewATMFastCashPrflPermission
Help ID:	w_atm_fast_cash_profile_configuration
Data Sources:	ATM_FAST_CASH
Desktop Access:	Configure > ATM (Java) > ATM Fast Cash Profile
Messages:	ATMFastCashProfileInsertRq ATMFastCashProfileListRq ATMFastCashProfileViewRq ATMFastCashProfileUpdateRq ATMFastCashProfileDeleteRq

ATM Flow Configuration

Task ID:	ATMDHFlowconfig
Permissions:	FullATMDHFlowConfigPermission ViewATMDHFlowConfigPermission
Help ID:	w_atm_flow_configuration
Data Sources:	ATM_FLOW_CNTL
Desktop Access:	Configure > ATM > ATM Flow > ATM Flow Configuration
Messages:	ATMDHFlowInsertRq ATMDHFlowListRq ATMDHFlowGetControlInfoRq ATMDHFlowViewRq ATMDHFlowUpdateRq ATMDHFlowDeleteRq ATMDHFlowCreateWorkingRq ATMDHFlowCheckInWorkingRq ATMDHFlowSequenceControlListRq ATMDHFlowGenericDeleteRq ATMDHFlowWorkingListRq ATMDHFlowActiveListRq

ATM Flow Management

Task ID:	ATMDHFlowManagement
Permissions:	FullATMDHFlowMgmtPermission ViewATMDHFlowMgmtPermission
Help ID:	w_atm_flow_management
Data Sources:	ATM_FLOW_CNTL
Desktop Access:	Configure > ATM > ATM Flow > ATM Flow Management
Messages:	ATMDHFlowInsertRq ATMDHFlowListRq ATMDHFlowGetControlInfoRq ATMDHFlowViewRq ATMDHFlowUpdateRq ATMDHFlowDeleteRq ATMDHFlowCreateWorkingRq ATMDHFlowCheckInWorkingRq ATMDHFlowSequenceControlListRq ATMDHFlowGenericDeleteRq ATMDHFlowWorkingListRq ATMDHFlowActiveListRq

ATM Flow Perusal

Task ID:	ATMDHFlowPerusal
Permissions:	FullATMDHFlowPerusalPermission ViewATMDHFlowPerusalPermission
Help ID:	w_atm_flow_perusal
Data Sources:	ATM_FLOW_CNTL
Desktop Access:	Configure > ATM > ATM Flow > ATM Flow Perusal
Messages:	ATMDHFlowInsertRq ATMDHFlowListRq ATMDHFlowGetControlInfoRq ATMDHFlowViewRq ATMDHFlowUpdateRq ATMDHFlowDeleteRq ATMDHFlowCreateWorkingRq ATMDHFlowCheckInWorkingRq ATMDHFlowSequenceControlListRq ATMDHFlowGenericDeleteRq ATMDHFlowWorkingListRq ATMDHFlowActiveListRq

ATM Hardware Status Window

Task ID:	ATMHardwareStatus
Permissions:	FullATMHardwareStatPermission ViewATMHardwareStatPermission
Help ID:	w_atm_hardware_status
Data Sources:	ESATDD1
Desktop Access:	System Operations > ATM (Java) > ATM Hardware Status
Messages:	ATMHardwareStatusListRq ATMHardwareStatusViewRq

ATM Hopper Profile Configuration Window

Task ID:	ATMDHHopperProfile
Permissions:	FullATMDHHopperPrflPermission ViewATMDHHopperPrflPermission
Help ID:	w_atm_hopper_profile_configuration_cplus
Data Sources:	ATM_HOPR
Desktop Access:	Configure > ATM > ATM Hopper Profile
Messages:	ATMHopperProfileInsertRq ATMHopperProfileListRq ATMHopperProfileViewRq ATMHopperProfileUpdateRq ATMHopperProfileDeleteRq

ATM Hopper Profile Configuration Window

Task ID:	ATMHopperProfile
Permissions:	FullATMHopperPrflPermission ViewATMHopperPrflPermission
Help ID:	w_atm_hopper_profile_configuration_java
Data Sources:	ATM_HOPR
Desktop Access:	Configure > ATM (Java) > ATM Hopper Profile
Messages:	ATMHopperProfileInsertRq ATMHopperProfileListRq ATMHopperProfileViewRq ATMHopperProfileUpdateRq ATMHopperProfileDeleteRq

ATM Inactivity Alert Profile Configuration Window

Task ID:	ATMDHInactivityProfile
Permissions:	FullATMDHInactiveAlertPrflPerm ViewATMDHInactiveAlertPrflPerm
Help ID:	w_atm_inactivity_alert_profile_configuration
Data Sources:	ATM_INACT
Desktop Access:	Configure > ATM > ATM Inactivity Alert Profile
Messages:	ATMInactProfileInsertRq ATMInactProfileListRq ATMInactProfileViewRq ATMInactProfileUpdateRq ATMInactProfileDeleteRq

ATM Inactivity Alert Profile Configuration Window

Task ID:	ATMInactivityProfile
Permissions:	FullATMInactivePrflPermission ViewATMInactivePrflPermission
Help ID:	w_atm_inactivity_alert_profile_configuration
Data Sources:	ATM_INACT
Desktop Access:	Configure > ATM (Java) > ATM Inactivity Alert Profile
Messages:	ATMInactProfileInsertRq ATMInactProfileListRq ATMInactProfileViewRq ATMInactProfileUpdateRq ATMInactProfileDeleteRq

ATM Load Configuration Administration Window

Task ID:	ATMDHLoadConfigAdmin
Permissions:	FullATMDHLoadCnfgAdminPerm ViewATMDHLoadCnfgAdminPerm
Help ID:	w_atm_load_configuration_administration
Data Sources:	ATM_CONF
Desktop Access:	System Operations > ATM > ATM Load Configuration Administration
Messages:	ATMDHConfUtilSubmitRq

ATM Load Profile Window

Task ID:	ATMDHLoadProfile
Permissions:	FullATMDHLoadPrflPermission ViewATMDHLoadPrflPermission
Help ID:	w_atm_load_profile
Data Sources:	ATMCNFG
Desktop Access:	Configure > ATM > ATM Load Profile
Messages:	ATMLoadProfileDeleteRq ATMLoadProfileListRq ATMLoadProfileViewRq

ATM Load Profile Window

Task ID:	ATMLoadProfile
Permissions:	FullATMLoadProfilePermission ViewATMLoadProfilePermission
Help ID:	w_atm_load_profile
Data Sources:	ATMCNFG
Desktop Access:	Configure > ATM (Java) > ATM Load Profile
Messages:	ATMLoadProfileDeleteRq ATMLoadProfileListRq ATMLoadProfileViewRq

ATM Load Timeout Profile Configuration Window

Task ID:	ATMLdTmtProfile
Permissions:	FullATMLoadTimerPrflPermission ViewATMLoadTimerPrflPermission
Help ID:	w_atm_load_timeout_profile_configuration
Data Sources:	LTMRPRFL
Desktop Access:	Configure > ATM (Java) > ATM Load Timeout Profile
Messages:	ATMLdTmtProfileInsertRq ATMLdTmtProfileListRq ATMLdTmtProfileViewRq ATMLdTmtProfileUpdateRq ATMLdTmtProfileDeleteRq

ATM MAC Profile Configuration Window

Task ID:	ATMDHMacProfile
Permissions:	FullATMDHMacProfilePermission ViewATMDHMacProfilePermission
Help ID:	w_atm_mac_profile_configuration_cplus
Data Sources:	ATM_MAC
Desktop Access:	Configure > ATM > ATM MAC Profile
Messages:	ATMMacProfileInsertRq ATMMacProfileListRq ATMMacProfileViewRq ATMMacProfileUpdateRq ATMMacProfileDeleteRq

ATM MAC Profile Configuration Window

Task ID:	ATMMacProfile
Permissions:	FullATMMACProfilePermission ViewATMMACProfilePermission
Help ID:	w_atm_mac_profile_configuration_java
Data Sources:	ATM_MAC
Desktop Access:	Configure > ATM (Java) > ATM MAC Profile
Messages:	ATMMacProfileInsertRq ATMMacProfileListRq ATMMacProfileViewRq ATMMacProfileUpdateRq ATMMacProfileDeleteRq

ATM Operation Code Configuration Window

Task ID:	ATMDHOpCodeMapping
Permissions:	FullATMDHOpCodeMapPermission ViewATMDHOpCodeMapPermission
Help ID:	w_atm_operation_code_configuration
Data Sources:	ATM_OP_CDE
Desktop Access:	Configure > ATM > ATM Operation Code
Messages:	ATMDHOpCodeInsertRq ATMDHOpCodeListRq ATMDHOpCodeViewRq ATMDHOpCodeUpdateRq ATMDHOpCodeDeleteRq

ATM Optional Receipt Profile Window

Task ID:	ATMOptionalReceiptProfile
Permissions:	FullATMOptnRcptPrflPermission ViewATMOptnRcptPrflPermission
Help ID:	w_atm_optional_receipt_profile
Data Sources:	ATM_OP_CDE
Desktop Access:	Configure > ATM (Java) > ATM Optional Receipt Profile
Messages:	ATMOptnRcptPrflInsertRq ATMOptnRcptPrflListRq ATMOptnRcptPrflViewRq ATMOptnRcptPrflUpdateRq ATMOptnRcptPrflDeleteRq

ATM Receipt Format Profile Configuration Window

Task ID:	ATMDHReceiptFormat
Permissions:	FullATMDHRCptFrmtPrflPerm ViewATMDHRCptFrmtPrflPerm
Help ID:	w_atm_receipt_format_profile_configuration_cplus
Data Sources:	ATM_RECEIPT
Desktop Access:	Configure > ATM > ATM Receipt Format Profile
Messages:	ATMDHReceiptFormatInsertRq ATMDHReceiptFormatListRq ATMDHReceiptFormatViewRq ATMDHReceiptFormatUpdateRq ATMDHReceiptFormatDeleteRq ATMDHReceiptFormatGenericDeleteRq

ATM Receipt Format Profile Configuration Window

Task ID:	ATMReceiptFormat
Permissions:	FullATMReceiptFormatPermission ViewATMReceiptFormatPermission
Help ID:	w_atm_receipt_format_profile_configuration_java
Data Sources:	ATM_RECEIPT
Desktop Access:	Configure > ATM (Java) > ATM Receipt Format
Messages:	ATMDHReceiptFormatInsertRq ATMDHReceiptFormatListRq ATMDHReceiptFormatViewRq ATMDHReceiptFormatUpdateRq ATMDHReceiptFormatDeleteRq ATMDHReceiptFormatGenericDeleteRq

ATM Receipt Required Profile Configuration Window

Task ID:	ATMDHReceiptRequiredType
Permissions:	FullATMDHRCptRqdTypPrflPerm ViewATMDHRCptRqdTypPrflPerm
Help ID:	w_atm_receipt_required_profile_configuration
Data Sources:	ATM_REQ_RCPT
Desktop Access:	Configure > ATM > ATM Receipt Required Profile
Messages:	ATMReceiptReqTypeInsertRq ATMReceiptReqTypeListRq ATMReceiptReqTypeViewRq ATMReceiptReqTypeUpdateRq ATMReceiptReqTypeTableDeleteRq ATMReceiptReqTypeDeleteRq

ATM Receipt Required Profile Configuration Window

Task ID:	ATMReceiptRequiredType
Permissions:	FullATMRcptReqTypePermission ViewATMRcptReqTypePermission
Help ID:	w_atm_receipt_required_profile_configuration
Data Sources:	ATM_REQ_RCPT
Desktop Access:	Configure > ATM (Java) > ATM Receipt Required Profile
Messages:	ATMReceiptReqTypeInsertRq ATMReceiptReqTypeListRq ATMReceiptReqTypeViewRq ATMReceiptReqTypeUpdateRq ATMReceiptReqTypeTableDeleteRq ATMReceiptReqTypeDeleteRq

ATM Reload Map Request Window

Task ID:	ATMReloadMaps
Permissions:	FullATMReloadMapsPermission
Help ID:	w_atm_reload_map_request
Data Sources:	Not specified.
Desktop Access:	System Operations > ATM (Java) > ATM Reload Map
Messages:	ATMReloadMapSubmitRq

ATM State and Screen Configuration Window

Task ID:	CurrencyConvRateConfiguration
Permissions:	FullCrncyConvRateCfgPermission ViewCrncyConvRateCfgPermission
Help ID:	w_atm_state_and_screen_configuration
Data Sources:	ATM_STATE_SCRN
Desktop Access:	Configure > ATM > ATM State and Screen
Messages:	ATMDHStateScreenInsertRq ATMDHStateScreenListRq ATMDHStateScreenViewRq ATMDHStateScreenUpdateRq ATMDHStateScreenGenericDeleteRq

ATM Statement Print Profile Configuration Window

Task ID:	ATMDHStatementPrintProfile
Permissions:	FullATMDHStmntPrntPrflPerm ViewATMDHStmntPrntPrflPerm
Help ID:	w_atm_statement_print_profile_configuration
Data Sources:	ATM_STMNT_PRNT
Desktop Access:	Configure > ATM > ATM Statement Print Profile
Messages:	ATMStmntPrntProfileInsertRq ATMStmntPrntProfileListRq ATMStmntPrntProfileViewRq ATMStmntPrntProfileUpdateRq ATMStmntPrntProfileDeleteRq

ATM Statement Print Profile Configuration Window

Task ID:	ATMStatementPrintProfile
Permissions:	FullATMStmtPrntPrflPermission ViewATMStmtPrntPrflPermission
Help ID:	w_atm_statement_print_profile_configuration
Data Sources:	ATM_STMNT_PRNT
Desktop Access:	Configure > ATM (Java) > ATM Statement Print Profile
Messages:	ATMStmntPrntProfileInsertRq ATMStmntPrntProfileListRq ATMStmntPrntProfileViewRq ATMStmntPrntProfileUpdateRq ATMStmntPrntProfileDeleteRq

ATM Status Query Window

Task ID:	ATMDHStatusQuery
Permissions:	FullATMDHStatusQueryPermission ViewATMDHStatusQueryPermission
Help ID:	w_atm_status_query_cplus
Data Sources:	Not specified.
Desktop Access:	System Operations > ATM > ATM Status Query
Messages:	ATMStatusViewRq

ATM Status Query Window

Task ID:	ATMStatusQuery
Permissions:	FullATMStatusQueryPermission
Help ID:	w_atm_status_query_java
Data Sources:	ESATDD1 ESATDS1
Desktop Access:	System Operations > ATM (Java) > ATM Status Query
Messages:	ATMStatusViewRq

ATM Status Window

Task ID:	ATMHardwareStatus
Permissions:	FullATMHardwareStatPermission ViewATMHardwareStatPermission
Help ID:	w_atm_status
Data Sources:	ATM_DD1
Desktop Access:	System Operations > ATM > ATM Status
Messages:	ATMDHStatusListRq ATMDHStatusViewRq

ATM Surcharge Profile Configuration Window

Task ID:	ATMDHSurchargeProfile
Permissions:	FullATMDHSurchargePrflPerm ViewATMDHSurchargePrflPerm
Help ID:	w_atm_surcharge_profile_configuration_cplus
Data Sources:	ATM_SUR
Desktop Access:	Configure > ATM > ATM Surcharge Profile
Messages:	ATMSurchargeProfileInsertRq ATMSurchargeProfileListRq ATMSurchargeProfileViewRq ATMSurchargeProfileUpdateRq ATMSurchargeProfileDeleteRq

ATM Surcharge Profile Configuration Window

Task ID:	ATMSurchargeProfile
Permissions:	FullATMSurchPrflPermission ViewATMSurchPrflPermission
Help ID:	w_atm_surcharge_profile_configuration_java
Data Sources:	ATM_SUR
Desktop Access:	Configure > ATM (Java) > ATM Surcharge Profile
Messages:	ATMSurchargeProfileInsertRq ATMSurchargeProfileListRq ATMSurchargeProfileViewRq ATMSurchargeProfileUpdateRq ATMSurchargeProfileDeleteRq

ATM Totals Window

Task ID:	ATMDHTotals
Permissions:	FullATMDHTotalsPermission ViewATMDHTotalsPermission
Help ID:	w_atm_totals
Data Sources:	ATM_DD1 ATM_DS1 ATM_HOPR ATM_PREV_TTL ATM_PRFL
Desktop Access:	System Operations > ATM > ATM Totals
Messages:	ATMDHTotalsCurViewRq ATMDHTotalsPrvViewRq

Audit Store and Forward (SAF) Configuration Window

Task ID:	AuditSAFConfig
Permissions:	FullAuditSAFConfigPermission ViewAuditSAFConfigPermission
Help ID:	w_audit_store_and_forward_configuration
Data Sources:	AUDIT_SAF_CONFIG
Desktop Access:	System Operations > Audit SAF
Messages:	AuditSAFViewRq AuditSAFUpdateRq

Authentication Profile Configuration Window

Task ID:	AuthenticationConfiguration
Permissions:	FullAuthentConfigPermission ViewAuthentConfigPermission
Help ID:	UnknownHelpID
Data Sources:	CARD_VRFCTN DIEBOLD_NUM_TBL DYN_CARD_VRFCTN EMV_SECURITY IBM_DES IDENTIKEY NCR_PIN_VRFY VISA_PVV
Desktop Access:	Configure > Transaction Security > Authentication Profile
Messages:	AuthentCnfgCardProfilesRq AuthentCnfgIdentikeyProfilesRq AuthentCnfgPinProfilesRq AuthentCnfgInsertDNTRq AuthentCnfgSummaryViewRq AuthentCnfgViewDNTRq AuthentCnfgUpdateDNTRq AuthentCnfgViewDNTRq AuthentCnfgDeleteRq AuthentCnfgProfileDeleteRq AuthentCnfgInsertNCRRq AuthentCnfgNCRProfilesRq AuthentCnfgViewNCRRq AuthentCnfgUpdateNCRRq AuthentCnfgInsertEMVRq AuthentCnfgEMVProfilesRq AuthentCnfgViewEMVRq AuthentCnfgUpdateEMVRq AuthentCnfgInsertIdentikeyRq AuthentCnfgViewIdentikeyRq AuthentCnfgUpdateIdentikeyRq AuthentCnfgInsertRq AuthentCnfgViewRq AuthentCnfgUpdateRq

Authorization Script Configuration Window

Task ID:	AuthScript
Permissions:	FullAuthScriptPermission ViewAuthScriptPermission
Help ID:	w_authorization_script_configuration
Data Sources:	AUTH_SCRIPT
Desktop Access:	Configure > Script > Authorization Script
Messages:	AuthScriptListRq AuthScriptInsertRq AuthScriptViewRq AuthScriptUpdateRq AuthScriptDeleteRq AuthScriptGenericDeleteRq

Banknet Acquirers Configuration Window

Task ID:	BanknetInterface
Permissions:	FullBanknetInterfacePermission ViewBanknetInterfacePermission
Help ID:	Not specified.
Data Sources:	BANKNET_INST_ID
Desktop Access:	Configure > Interface > Network > BankNet > Banknet Acquirers
Messages:	Not specified.

BankNet ISO Interface Configuration Window

Task ID:	BanknetInterface
Permissions:	FullBanknetInterfacePermission ViewBanknetInterfacePermission
Help ID:	w_banknet_iso_interface_configuration
Data Sources:	BANKNET_CONFIG BANKNET_INST_ID BANKNET_MRCH_PGM INTERFACE INTERFACE_SAF INTERFACE_STA
Desktop Access:	Configure > Interface > Network > BankNet ISO
Messages:	BanknetMerchantProgramInsertRq BanknetMerchantProgramViewRq BanknetMerchantProgramUpdateRq BanknetMerchantProgramDeleteRq

BASE24 ISO8583 Host Interface Configuration Window

Task ID:	B24HISOInterfaceConfig
Permissions:	FullB24HISOIFConfigPermission ViewB24HISOIFConfigPermission
Help ID:	w_base24_iso8583_host_interface_configuration
Data Sources:	HISO87_INTERFACE INTERFACE INTERFACE_SAF INTERFACE_STA
Desktop Access:	Configure > Interface > Host > BASE24 ISO8583 Host > BASE24 ISO8583 Host
Messages:	HISO87InsertRq HISO87ViewRq HISO87UpdateRq HISO87DeleteRq

BASE24 KEYF Configuration Window

Task ID:	B24KEYFSecurity
Permissions:	FullB24KEYFSecuritPermission ViewB24KEYFSecuritPermission
Help ID:	w_base24_keyf_configuration
Data Sources:	Not specified.
Desktop Access:	Configure > BASE24 > KEYF
Messages:	B24KEYFGetFIIDListRq B24KEYFInsertRq B24KEYFGetSymbolicNameListRq

BASE24-atm Transaction Mapping Profile Configuration Window

Task ID:	B24AtmTranMapping
Permissions:	FullB24ATMTranMapPermission ViewB24ATMTranMapPermission
Help ID:	w_base24atm_transaction_mapping_profile
Data Sources:	ATM_TC_PROC_CODE PROC_CODE_ATM_TC
Desktop Access:	Configure > BASE24 > Transaction Mapping > ATM
Messages:	B24AtmTranMappingListRq B24AtmTranMappingInbInsertRq B24AtmTranMappingOutInsertRq B24AtmTranMappingInbViewRq B24AtmTranMappingInbUpdateRq B24AtmTranMappingOutViewRq B24AtmTranMappingOutUpdateRq B24AtmTranMappingInbDeleteRq B24AtmTranMappingOutDeleteRq B24AtmTranMappingGenericDeleteRq

BASE24-pos Transaction Mapping Profile Configuration Window

Task ID:	B24PosTranMapping
Permissions:	FullB24POSTranMapPermission ViewB24POSTranMapPermission
Help ID:	w_base24pos_transaction_mapping_profile
Data Sources:	POS_TC_PROC_CODE PROC_CODE_POS_TC
Desktop Access:	Configure > BASE24 > Transaction Mapping > POS
Messages:	B24PosTranMappingListRq B24PosTranMappingInbInsertRq B24PosTranMappingOutInsertRq B24PosTranMappingInbViewRq B24PosTranMappingInbUpdateRq B24PosTranMappingOutViewRq B24PosTranMappingOutUpdateRq B24PosTranMappingInbDeleteRq B24PosTranMappingOutDeleteRq B24PosTranMappingGenericDeleteRq

BNTng Key Header Configuration Window

Task ID:	BNTngHeaderConfig
Permissions:	FullBNTngHdrCnfgPermission ViewBNTngHdrCnfgPermission
Help ID:	w_bntng_key_header_configuration
Data Sources:	BNTNG_HEADER
Desktop Access:	Configure > Transaction Security > BNTng Header
Messages:	BNTngHeaderInsertRq BNTngHeaderListRq BNTngHeaderViewRq BNTngHeaderUpdateRq BNTngHeaderDeleteRq

Cache Administration Window

Task ID:	IWTCacheAdministration
Permissions:	FullIWTCacheAdminPermission ViewIWTCacheAdminstratioin
Help ID:	w_cache_administration
Data Sources:	Not specified.
Desktop Access:	System Operations > Server Management > Server Administration > Cache Administration
Messages:	IWTFCacheAdminListRq IWTFCacheAdminResetRq

Card Management Window

Task ID:	CardConfiguration
Permissions:	FullCardConfigPermission ViewCardConfigPermission
Help ID:	w_card_management
Data Sources:	CARD CARD_ACCOUNT ENVIRONMENT
Desktop Access:	Customer Management > Card
Messages:	CardEnvParamRq CardInsertRq CardPANListRq CardAcctInsertRq CardViewRq CardUpdateRq CardAcctViewRq CardAcctUpdateRq CardAcctDeleteRq CardDeleteRq

Certificate Management Window

Task ID:	Certificate
Permissions:	FullCertificatePermission ViewCertificatePermission
Help ID:	w_certificate_management
Data Sources:	Not specified.
Desktop Access:	Configure > Transaction Security > Automated Key Distribution > Certificate Management
Messages:	CertGenMesgDigestRq CertGetPublicKeyDataRq CertValidateRq

Channel Public Key Perusal Window

Task ID:	ChannelPKPerusal
Permissions:	FullChannelPKPerusalPermission ViewChannelPKPerusalPermission
Help ID:	w_channel_public_key_perusal
Data Sources:	CHAN_PKEY_SEC
Desktop Access:	View > Automated Key Distribution > Channel Public Key Perusal
Messages:	ChannelPubKeyListRq

Channel Security Configuration Window

Task ID:	ChannelSecurity
Permissions:	FullChannelSecurityPermission ViewChannelSecurityPermission
Help ID:	w_channel_security_configuration
Data Sources:	CHANNEL_SECURITY
Desktop Access:	Configure > Transaction Security > Channel
Messages:	ChannelIDSecurListGetRq ChannelListGetRq

Configuration Properties Window

Task ID:	IWTConfigurationAdministration
Permissions:	FullIWTConfigAdminPermission ViewIWTConfigurationAdmin
Help ID:	w_configuration_properties
Data Sources:	Not specified.
Desktop Access:	System Operations > Server Management > Server Administration > Configuration Properties
Messages:	IWTFCfgPropertiesListRq IWTFCfgPropertiesReloadRq

Context Profile Configuration Window

Task ID:	ContextConfiguration
Permissions:	FullContextConfigPermission ViewContextConfigPermission
Help ID:	w_context_profile_configuration
Data Sources:	CONTEXT_CONFIG
Desktop Access:	Configure > Interface > Context Profile
Messages:	ContextConfigInsertRq ContextConfigListRq ContextConfigViewRq ContextConfigUpdateRq ContextConfigDeleteRq

Contingency Interface Configuration Window

Task ID:	ContingencyInterface
Permissions:	FullContingencyInterface
Help ID:	w_contingency_interface_configuration
Data Sources:	Not specified.
Desktop Access:	Configure > Interface > Host > Contingency
Messages:	Not specified.

Contingency Store and Forward (SAF) Configuration Window

Task ID:	ContingencySAF
Permissions:	FullContingencySAFPermission ViewContingencySAFPermission
Help ID:	w_contingency_store_and_forward
Data Sources:	CNTGICY_INTERFACE
Desktop Access:	System Operations > Contingency SAF
Messages:	ContingencySAFCnfgViewRq ContingencySAFCnfgUpdateRq

CSC Interface Configuration Window

Task ID:	CSC
Permissions:	FullCSCPermission ViewCSCPermission
Help ID:	w_iso_93_host_interface_configuration
Data Sources:	HISO93_INTERFACE INTERFACE INTERFACE_SAF INTERFACE_STA
Desktop Access:	Configure > Interface > Host > CSC Interface
Messages:	Not specified.

Currency Conversion Rate Configuration Window

Task ID:	CurrencyConvRateConfiguration
Permissions:	FullCrncyConvRateCfgPermission ViewCurrencyConvRateConfig
Help ID:	w_currency_conversion_rate_configuration
Data Sources:	CRNCY_CONV_RATE
Desktop Access:	Configure > Currency Conversion > Currency Conversion Rate
Messages:	CurrConvRateInsertRq CurrConvRateListRq CurrConvRateUpdateRq CurrConvRateDeleteRq CurrConvRateGenericDeleteRq

Database Administration Window

Task ID:	IWTDatabaseAdministration
Permissions:	FullIWTDatabaseAdminPermission ViewIWTDatabaseAdministration
Help ID:	w_database_administration
Data Sources:	Not specified.
Desktop Access:	System Operations > Server Management > Server Administration > Database Administration
Messages:	IWTFDBConnectionAdminViewRq

Destination Routing Profile Configuration Window

Task ID:	IssuerProfileConfig
Permissions:	FullIssProfConfigPermission ViewIssuerProfileConfig
Help ID:	w_destination_routing_profile_configuration
Desktop Access:	Configure > Routing > Profile Description > Destination Routing Profile
Messages:	Not specified.

Disable KEYGEN Window

Task ID:	KEYGENLockdown
Permissions:	FullKEYGENLockdownPermission ViewKEYGENLockdownPermission
Help ID:	w_disable_keygen
Data Sources:	HOST_PKEY_PRI
Desktop Access:	Configure > Transaction Security > Automated Key Distribution > Disable KEYGEN
Messages:	DisableKeyGenViewRq DisableKeyGenUpdateRq

DUKPT Derivation Key Profile Configuration Window

Task ID:	B24SPDHDUKPTDerivationKey
Permissions:	FullB24SPDHDUKPTDKeyPermission ViewB24SPDHDUKPTDKeyPermission
Help ID:	w_dukpt_derivation_key_profile_configuration
Data Sources:	DERIVATION_KEY
Desktop Access:	Configure > Transaction Security > DUKPT Derivation Key Profile
Messages:	DrvKeyInsertRq DrvKeyProfileListRq DrvKeyViewRq DrvKeyUpdateRq DrvKeyDeleteRq

Environment Configuration Window

Task ID:	EnvironmentManagement
Permissions:	FullEnvironmentMgmtPermission ViewEnvironmentMgmtPermission
Help ID:	w_environment_configuration
Data Sources:	ENVIRONMENT
Desktop Access:	System Operations > Environment
Messages:	EnvironmentInsertRq EnvironmentViewRq EnvironmentUpdateRq EnvironmentDeleteRq

EPP Serial Number Configuration Window

Task ID:	EPPSerialNumberConfig
Permissions:	FullEPPSerialNumCfgPermission ViewEPPSerialNumCfgPermission
Help ID:	w_epp_serial_number_configuration
Data Sources:	EPP_SERIAL_NUM
Desktop Access:	Configure > Transaction Security > Automated Key Distribution > EPP Serial Number
Messages:	EPPSerNumInsertRq EPPSerNumViewRq EPPSerNumUpdateRq EPPSerNumDeleteRq

EPS-Net Institution Configuration Window

Task ID:	EPSNetInstitution
Permissions:	FullEPSNetInstPermission ViewEPSNetInstPermission
Help ID:	w_epsnet_institution_configuration
Data Sources:	EPSNET_INST
Desktop Access:	Configure > Interface > Network > EPS-Net > EPS-Net Institution
Messages:	EPSNetInstitutionInsertRq EPSNetInstitutionListRq EPSNetInstitutionViewRq EPSNetInstitutionUpdateRq EPSNetInstitutionDeleteRq

EPS-Net ISO Interface Configuration Window

Task ID:	EPSNetInterfaceConfiguration
Permissions:	FullEPSNetInterfacePermission ViewEPSNetInterfacePermission
Help ID:	w_epsnet_iso_interface_configuration
Data Sources:	EPSNET_INTERFACE INTERFACE INTERFACE_SAF INTERFACE_STA
Desktop Access:	Configure > Interface > Network > EPS-Net > EPS-Net ISO
Messages:	EPSNetInsertRq EPSNetViewRq EPSNetUpdateRq EPSNetDeleteRq

Euro Opted Currency Configuration Window

Task ID:	EuroOptedCurrencyConfiguration
Permissions:	FullEuroOptedCurrCfgPermission ViewEuroOptedCurrencyConfig
Help ID:	w_euro_opted_currency_configuration
Data Sources:	EURO_OPTED_CRNCY
Desktop Access:	Configure > Currency Conversion > Euro Opted Currency
Messages:	EuroOptCurrInsertRq EuroOptCurrListRq EuroOptCurrUpdateRq EuroOptCurrDeleteRq

Event Configuration and Management Window

Task ID:	EventConfiguration
Permissions:	FullEventConfigPermission ViewEventConfiguration
Help ID:	w_integrated_server_event_configuration
Data Sources:	Not specified.
Desktop Access:	System Operations > Event > Event Management
Messages:	Not specified.

Event Perusal Window

Task ID:	EventPerusal
Permissions:	FullEventPerusalPermission ViewEventPerusalPermission
Help ID:	w_event_perusal
Data Sources:	EVNTLOG
Desktop Access:	System Operations > Event > Event Perusal
Messages:	EventPerusalViewRq

Event Subsystem ID Configuration Window

Task ID:	EventSubsystemConfiguration
Permissions:	FullEventSubConfigPermission ViewEventSubsystemConfig
Help ID:	w_event_subsystem_id_configuration
Data Sources:	Not specified.
Desktop Access:	System Operations > Event > Subsystem ID
Messages:	Not specified.

Exported Operators Configuration Window

Task ID:	ExportedOperator
Permissions:	FullExportedOperatorPermission ViewExportedOperatorPermission
Help ID:	w_exported_operators_configuration
Data Sources:	EXPORTD_OPER_DOC
Desktop Access:	Configure > Script > Exported Operators
Messages:	ExpOperListRq ExpOperInsertRq ExpOperViewRq ExpOperUpdateRq ExpOperDeleteRq

External Connection Configuration Window

Task ID:	IWTConnectionConfig
Permissions:	FullIWTConnectionCfgPermission ViewIWTConnectionCfgPermission
Help ID:	w_external_connection_configuration
Data Sources:	EXTRCNCT
Desktop Access:	System Operations > Server Management > External Connection
Messages:	IWTFCConnectionListRq IWTFCConnectionInsertRq IWTFCConnectionViewRq IWTFCConnectionUpdateRq IWTFCConnectionDeleteRq

File Partition Configuration Window

Task ID:	FilePartition
Permissions:	FullFilePartitionPermission ViewFilePartitionPermission
Help ID:	w_file_partition_configuration
Data Sources:	FILE_PART_FIELDS FILE_PART_LIST
Desktop Access:	System Operations > Database Management > File Partition
Messages:	FilePartAssgnFieldsListRq FilePartAssgnListRq FilePartCatalogInsertRq FilePartCatalogUpdateRq FilePartCatalogViewRq FilePartGenericDeleteRq

File Update Router Configuration Window

Task ID:	FileUpdateRouterConfig
Permissions:	FullFileUpdateRouterConfigPerm ViewFileUpdateRouterConfigPerm
Help ID:	w_file_update_router_configuration
Data Sources:	FILE_UPDATE_ROUTE
Desktop Access:	Configure > Routing > File Update Router
Messages:	FilUpdRtrInsertRq FilUpdRtrListRq FilUpdRtrViewRq FilUpdRtrDeleteRq FilUpdRtrGenericDeleteRq

Host Public Key Perusal Window

Task ID:	HostPKPerusal
Permissions:	FullHostPKPerusalPermission ViewHostPKPerusalPermission
Help ID:	w_host_public_key_perusal
Data Sources:	HOST_PKEY_PRI HOST_PKEY_SCND
Desktop Access:	View > Automated Key Distribution > Host Public Key Perusal
Messages:	HostPubKeyListRq

IFX Host Action Code Profile Configuration Window

Task ID:	IFXHostActionCode
Permissions:	FullIFXHostActCdPermission ViewIFXHostActCdPermission
Help ID:	w_ifx_host_action_code_profile_configuration
Data Sources:	IFX_HOST_ACT_CDE
Desktop Access:	Configure > Interface > Host > IFX Host >
Messages:	IFX Host Action Code Profile IFXHostActionCodeListRq IFXHostActionCodeInsertRq IFXHostActionCodeViewRq IFXHostActionCodeUpdateRq IFXHostActionCodeDeleteRq IFXHostActionCodeGenericDeleteRq

IFX Host Interface Configuration Window

Task ID:	IFXHostInterface
Permissions:	FullIFXHostIntfPermission ViewIFXHostIntfPermission
Help ID:	w_ifx_host_interface_configuration
Data Sources:	IFX_HOST_INTF INTERFACE INTERFACE_SAF INTERFACE_STA
Desktop Access:	Configure > Interface > Host > IFX Host > IFX Host Interface
Messages:	IFXHostInterfaceInsertRq IFXHostInterfaceViewRq IFXHostInterfaceUpdateRq IFXHostInterfaceDeleteRq

IMT Interface Configuration Window

Task ID:	IMTInterface
Permissions:	FullIMTInterfacePermission ViewIMTInterfacePermission
Help ID:	w_imt_interface_configuration
Data Sources:	IMT_INTERFACE INTERFACE INTERFACE_SAF INTERFACE_STA
Desktop Access:	Configure > BASE24 > IMT (Internal Message Translator)
Messages:	IMTInsertRequest IMTViewRequest IMTUpdateRequest IMTDeleteRequest

Institution Configuration Window

Task ID:	InstitutionConfiguration
Permissions:	FullInstConfigPermission ViewInstConfigPermission
Help ID:	w_institution_configuration
Data Sources:	INSTITUTION
Desktop Access:	Configure > Institution
Messages:	InstConfigGetIDListRq InstConfigGetIDListFilteredRq InstConfigInsertRq InstConfigViewRq InstConfigUpdateRq InstConfigDeleteRq

Instrument Status Mapping Profile Configuration Window

Task ID:	InstrStatusMappingProfile
Permissions:	FullInstStatMapPrflPermission ViewInstStatMapPrflPermission
Help ID:	w_instrument_status_mapping_profile_configuration
Data Sources:	Not specified.
Desktop Access:	Configure > Interface > Instrument Status Mapping Profile
Messages:	InstrumentStatusMappingInsertRq InstrumentStatusMappingListRq InstrumentStatusMappingViewRq InstrumentStatusMappingUpdateRq InstrumentStatusMappingDeleteRq InstrumentStatusMappingGenericDeleteRq

Instrument Type/Interchange Relationship Configuration Window

Task ID:	InstrumentTypeIchgRelation
Permissions:	FullInstTypIchgRelPermission ViewInstTypIchgRelPermission
Help ID:	w_instrument_type_interchange_relationship_configuration
Data Sources:	Not specified.
Desktop Access:	Configure > Interface > Instrument Type/Interchange Relationship
Messages:	Not specified.

Interchange Prefix Configuration Window

Task ID:	InterchangePrefixConfiguration
Permissions:	FullIchgPrefixConfigPermission ViewIchgPrefixConfigPermission
Help ID:	w_interchange_prefix_configuration
Data Sources:	Not specified.
Desktop Access:	Configure > Prefix > Not-On-Us > Interchange Prefix
Messages:	InterchangePrefixInsertRq InterchangePrefixGetFileRq InterchangePrefixViewRq InterchangePrefixUpdateRq InterchangePrefixDeleteRq

Interface Security Configuration Window

Task ID:	InterfaceSecurityConfiguration
Permissions:	FullIFSecurityConfigPermission ViewIFSecurityConfigPermission
Help ID:	Not specified.
Data Sources:	ICHG_SECURITY
Desktop Access:	Configure > Transaction Security > Interface
Messages:	InterfaceSafInsertRq InterfaceSafViewRq InterfaceListRequest InterfaceInsertRequest InterfaceStationInsertRq InterfaceSecInsertRq InterfaceViewRequest InterfaceUpdateRequest InterfaceStationListRq InterfaceStationUpdateRq InterfaceSecViewRq InterfaceSecUpdateRq InterfaceSecDeleteRq InterfaceStationDeleteRq InterfaceDeleteRequest

Interface Status Window

Task ID:	InterfaceStatus
Permissions:	FullInterfaceStatusPermission ViewInterfaceStatusPermission
Help ID:	w_interface_configuration
Data Sources:	Not specified.
Desktop Access:	System Operations > Interface Status
Messages:	Not specified.

Interface Terminal Configuration Window

Task ID:	InterfaceTerm
Permissions:	FullInterfaceTermPermission ViewInterfaceTermPermission
Help ID:	w_interface_terminal_configuration
Data Sources:	INTERFACE_TERM
Desktop Access:	Configure > Interface > Network > STAR > Interface Terminal
Messages:	InterfaceTerminalInsertRq InterfaceTerminalListRq InterfaceTerminalFindListRq InterfaceTerminalViewRq InterfaceTerminalUpdateRq InterfaceTerminalDeleteRq

Interpay BIM Interface Configuration Window

Task ID:	InterpayInterface
Permissions:	FullInterpayIntfPermission ViewInterpayIntfPermission
Help ID:	w_interpay_bim_interface_configuration
Data Sources:	INTERFACE INTERFACE_SAF INTERFACE_STA IPAY_INTERFACE
Desktop Access:	Configure > Interface > Network > Interpay BIM
Messages:	InterPayInsertRq InterPayViewRq InterPayUpdateRq InterPayDeleteRq

ISO 93 Host Interface Configuration Window

Task ID:	B24HISO93InterfaceConfig
Permissions:	FullB24HISO93IFCnfgPermission ViewB24HISO93IFCnfgPermission
Help ID:	w_iso_93_host_interface_configuration
Data Sources:	HISO93_INTERFACE INTERFACE INTERFACE_SAF INTERFACE_STA
Desktop Access:	Configure > Interface > Host > ISO 93 Host
Messages:	HISO93InsertRq HISO93ViewRq HISO93UpdateRq HISO93DeleteRq

ISO Message Profile Configuration Window

Task ID:	ISOFrameworkConfiguration
Permissions:	FullISOFrameworkCfgPermission ViewISOFrameworkCfgPermission
Help ID:	w_iso_message_profile_configuration
Data Sources:	ISO_FIELD ISO_MESSAGE
Desktop Access:	Configure > ISO > Message Profile
Messages:	ISOMsgPrflListRq ISOFldInsertRq ISOMsgInsertRq ISOFldViewRq ISOFldUpdateRq ISOMsgDataListRq ISOMsgUpdateRq ISOMsgDeleteRq ISOFldDeleteRq

ISO Transaction Mapping Profile Configuration Window

Task ID:	ISOTranMapping
Permissions:	FullISOTranMapPermission ViewISOTranMapPermission
Help ID:	w_iso_transaction_mapping_profile_configuration
Data Sources:	ISO_PROC_CODE PROC_CODE_ISO
Desktop Access:	Configure > ISO > Transaction Mapping
Messages:	IsoTranMappingListRq IsoTranMappingInbInsertRq IsoTranMappingOutInsertRq IsoTranMappingInbViewRq IsoTranMappingInbUpdateRq IsoTranMappingOutViewRq IsoTranMappingOutUpdateRq IsoTranMappingInbDeleteRq IsoTranMappingOutDeleteRq IsoTranMappingGenericDeleteRq

Issuer Transactions Allowed Profile Configuration Window

Task ID:	IssuerTransactionsAllowed
Permissions:	FullIssTransAllowedPermission ViewIssTransAllowedPermission
Help ID:	w_issuer_transactions_allowed_profile_configuration
Data Sources:	ISS_TXN_ALLOWED
Desktop Access:	Configure > Transactions Allowed > Issuer Transaction Profile
Messages:	IssuerTransAllowedInsertRq IssuerTransAllowedListRq IssuerTransAllowedViewRq IssuerTransAllowedUpdateRq IssuerTransAllowedDeleteRq IssuerTransAllowedGenericDeleteRq

Journal Issuer Profile Relationship Configuration Window

Task ID:	JournalConfigurationMapping
Permissions:	FullJrnlCfgMappingPermission ViewJrnlCfgMappingPermission
Help ID:	w_journal_issuer_profile_relationship_configuration
Data Sources:	Not specified.
Desktop Access:	Configure > Journal > Issuer Profile Relationship
Messages:	Not specified.

Journal Profile Configuration Window

Task ID:	JournalProfileConfiguration
Permissions:	FullJrnlProfileCfgPermission ViewJrnlProfileCfgPermission
Help ID:	w_journal_profile_configuration
Data Sources:	Not specified.
Desktop Access:	Configure > Journal > Journal Profile
Messages:	Not specified.

Journal Perusal Window

Task ID:	LogFilePerusal
Permissions:	FullLogFilePerusalPermission ViewLogFilePerusalPermission
Help ID:	w_journal_perusal
Data Sources:	Not specified.
Desktop Access:	View > Journal Perusal
Messages:	Not specified.

Journal Query Configuration Window

Task ID:	JournalQueryConfiguration
Permissions:	FullJrnlQueryConfigPermission ViewJournalQueryConfiguration
Help ID:	w_journal_query_configuration
Data Sources:	Not specified.
Desktop Access:	Configure > Journal > Journal Query
Messages:	JournalQueryListRq JournalQueryInsertRq JournalQueryPositionViewRq JournalQueryViewRq JournalQueryUpdateRq JournalQueryDeleteRq

Journal TDE Suppression Configuration Window

Task ID:	JournalTDESuppression
Permissions:	FullJrnlTDESuppressPermission ViewJrnlTDESuppressPermission
Help ID:	w_journal_tde_suppression
Data Sources:	JRNL_DATA_SUPPRS
Desktop Access:	Configure > Journal > Journal TDE Suppression
Messages:	JrnlTdeSpInsertRq JrnlTdeSpListRq JrnlTdeSpViewRq JrnlTdeSpUpdateRq JrnlTdeSpDeleteRq JrnlTdeSpGenericDeleteRq

Limit Profile Management Window

Task ID:	PaymentLimitConfig
Permissions:	FullPmtLimitConfigPermission ViewPmtLimitConfigPermission
Help ID:	w_limit_profile_configuration
Data Sources:	LIMITS
Desktop Access:	Customer Management > Limit Profile
Messages:	LimitListRq LimitInsertRq LimitDetailRq LimitUpdateRq LimitDeleteRq LimitDeletePrflRq

LINK ISO Interface (LIS5) Configuration Window

Task ID:	LIS5Interface
Permissions:	FullLIS5InterfacePermission ViewLIS5InterfacePermission
Help ID:	w_link_lis5_interface_configuration
Data Sources:	INTERFACE INTERFACE_SAF INTERFACE_STA LIS5_INTERFACE
Desktop Access:	Configure > Interface > Network > LINK ISO
Messages:	Lis5InsertRq Lis5ViewRq Lis5UpdateRq Lis5DeleteRq

Linked Currency Configuration

Task ID:	LinkedCurrencyConfiguration
Permissions:	FullLinkedCurrCfgPermission ViewLinkedCurrencyConfig
Help ID:	w_linked_currency_configuration
Data Sources:	LINKED_CURRENCY
Desktop Access:	Configure > Currency Conversion > Linked Currency
Messages:	LinkedCurrencyInsertRq LinkedCurrencyListRq LinkedCurrencyDeleteRq

Listener Configuration Window

Task ID:	IWTListenerConfig
Permissions:	FullIWTListenerCfgPermission ViewIWTListenerCfgPermission
Help ID:	w_listener_configuration
Data Sources:	LISTENER
Desktop Access:	System Operations > Server Management > Listener
Messages:	IWTFLListenerInsertRq IWTFLListenerListRq IWTFLListenerViewRq IWTFLListenerUpdateRq IWTFLListenerDeleteRq

Master File Key Conversion Window

Task ID:	MFKConverter
Permissions:	FullMFKConverterPermission ViewMFKConverterPermission
Help ID:	w_master_file_key_conversion
Data Sources:	Not specified.
Desktop Access:	Configure > Transaction Security > Master File Key Conversion
Messages:	MFKConv_ConvertKeysRq

MasterCard Debit Switch (MDS) Interface Configuration Window

Task ID:	MaestroDebitSwitch
Permissions:	FullMaestroPermission ViewMaestroPermission
Help ID:	w_mastercard_debit_switch_configuration
Data Sources:	BANKNET_MRCH_PGM INTERFACE INTERFACE_SAF INTERFACE_STA MDS_INTERFACE
Desktop Access:	Configure > Interface > Network > MasterCard Debit Switch (MDS)
Messages:	MdsInsertRequest MdsViewRequest MdsUpdateRequest MdsDeleteRequest

Merchant Channel Configuration and Statistics Window

Task ID:	MerchantChannel
Permissions:	FullMerchantChannelPermission FullMerchantChnlPrflPermission ViewMerchantChannelPermission ViewMerchantChnlPrflPermission
Help ID:	w_merchant_channel_configuration_and_statistics
Data Sources:	MRCH_DLVR_CHAN
Desktop Access:	Configure > Merchant Processing > Merchant Channel
Messages:	Not specified.

Merchant Channel Profile Window

Task ID:	MerchantChannelProfile
Permissions:	FullMerchantChnlPrflPermission ViewMerchantChnlPrflPermission
Help ID:	w_merchant_channel_profile_configuration
Data Sources:	APACS_CONFIG CHAN_PIM_TYP_RLN MRCH_DLVR_CHAN_P
Desktop Access:	Configure > Merchant Processing > Merchant Channel Profile
Messages:	Not specified.

Merchant Configuration and Statistics Window

Task ID:	MerchantConfiguration
Permissions:	FullMerchantConfigPermission ViewMerchantConfigPermission
Help ID:	w_merchant_configuration_and_statistics
Data Sources:	MERCHANT MRCH_IM_TYP_RLN
Desktop Access:	Configure > Merchant Processing > Merchant
Messages:	MerchantInstrmTypeInsertRq MerchantInstrmTypeViewRq MerchantInstrmTypeUpdateRq MerchantInstrmTypeDeleteRq

OLTP Warmboot Management Window

Task ID:	OltpWarmbootManagement
Permissions:	FullOLTPWarmbootMgmtPermission ViewOLTPWarmbootMgmtPermission
Help ID:	w_oltp_warmboot_management
Data Sources:	OLTP_WARMBOOT
Desktop Access:	System Operations > OLTP Warmboot Management
Messages:	OltpWarmbootMngmntViewRq OltpWarmbootMngmntUpdateRq OltpWarmbootMngmntDeleteRq

On-Us Prefix Configuration Window

Task ID:	PrefixConfiguration
Permissions:	FullIchgPrefixConfigPermission FullPrefixConfigPermission ViewIchgPrefixConfigPermission ViewPrefixConfigPermission
Help ID:	w_prefix_configuration
Data Sources:	PREFIX
Desktop Access:	Configure > Prefix > On-Us
Messages:	PrefixListRq PrefixConfigInsertRq PrefixConfigViewRq PrefixConfigUpdateRq PrefixConfigDeleteRq

Perusal Profile Configuration Window

Task ID:	PerusalConfiguration
Permissions:	FullPerusalConfigPermission ViewPerusalConfiguration
Help ID:	w_perusal_profile_configuration
Data Sources:	PERUSAL_SCRIPT
Desktop Access:	Configure > Journal > Perusal > Perusal Profile
Messages:	PerusalPrflListRq PerusalPrflInsertRq PerusalPrflViewRq PerusalPrflUpdateRq PerusalPrflDeleteRq PerusalPrflGenericDeleteRq PerusalUserIDListRq

Positive Balance Management Window

Task ID:	PositiveBalance
Permissions:	FullPositiveBalancePermission ViewPositiveBalancePermission
Help ID:	w_positive_balance_management
Data Sources:	INSTITUTION POSITIVE_BALANCE
Desktop Access:	Customer Management > Positive Balance
Messages:	PositiveBalanceAcctListRq PositiveBalanceInsertRq PositiveBalanceViewRq PositiveBalanceUpdateRq PositiveBalanceDeleteRq

Preauthorization Hold Management Window

Task ID:	PreAuthHold
Permissions:	FullPreAuthHoldPermission ViewPreAuthHoldPermission
Help ID:	w_preauthorization_hold_management
Data Sources:	PRE_AUTH_HOLD
Desktop Access:	Customer Management > Preauthorization Hold
Messages:	PreAuthHoldUITblInsertRq PreAuthHoldUITblListRq PreAuthHoldUITblViewRq PreAuthHoldUITblUpdateRq PreAuthHoldUITblDeleteRq PreAuthHoldUIDeleteRq

PRM Interface Configuration Window

Task ID:	PRMInterface
Permissions:	FullPRMInterfacePermission ViewPRMInterfacePermission
Help ID:	w_prm_interface_configuration
Data Sources:	INTERFACE INTERFACE_SAF INTERFACE_STA PRM_INTERFACE
Desktop Access:	Configure > Interface > Network > PRM
Messages:	Not specified.

Process Configuration Window

Task ID:	IWTProcessConfig
Permissions:	FullIWTProcessCfgPermission ViewIWTProcessCfgPermission
Help ID:	w_process_configuration
Data Sources:	PROCESS
Desktop Access:	System Operations > Server Management > Process
Messages:	IWTFProcessListRq IWTFProcessInsertRq IWTFProcessViewRq IWTFProcessUpdateRq IWTFProcessDeleteRq

Process Control Window

Task ID:	ProcessControl
Permissions:	FullProcessControl ViewProcessControl
Help ID:	w_process_control
Data Sources:	Not specified.
Desktop Access:	System Operations > Process Control
Messages:	ProcessControlRq

Query Execute Window

Task ID:	JournalQueryExecution
Permissions:	FullJrnlQueryExecutePermission ViewJrnlQueryExecutePermission
Help ID:	w_query_execute
Data Sources:	Not specified.
Desktop Access:	System Operations > Query Execution
Messages:	Not specified.

Real Time Feed Interface Configuration Window

Task ID:	RealTimeFeedInterface
Permissions:	FullRealTimeFeedIFPermission ViewRealTimeFeedIFPermission
Help ID:	w_realtimefeed_interface_configuration
Data Sources:	INTERFACE INTERFACE_SAF INTERFACE_STA REAL_TIME_FEED_CONFIG
Desktop Access:	Configure > Interface > Network > Real Time Feed
Messages:	RealTimeFeedInsertRq RealTimeFeedViewRq RealTimeFeedUpdateRq RealTimeFeedDeleteRq

Routing Configuration - Destination Window

Task ID:	RoutingConfiguration
Permissions:	FullRoutingConfigPermission ViewRoutingConfiguration
Help ID:	w_routing_configuration_destination
Data Sources:	ACQ_RTE_PROFILE ISS_RTE_PROFILE ROUTE ACQUIRER_ISSUER_RELATION
Desktop Access:	Configure > Routing > Destinations
Messages:	Not specified.

Routing Configuration - Destination/Source Relationship Window

Task ID:	AcquirerIssuerRelationConfig
Permissions:	FullAcqIssRelatnCfgPermission ViewRoutingConfiguration
Help ID:	w_destination_source_relationship
Data Sources:	ACQ_RTE_PROFILE ISS_RTE_PROFILE ROUTE ACQUIRER_ISSUER_RELATION
Desktop Access:	Configure > Routing > Destination/Source
Messages:	Not specified.

Script Editor Window

Task ID:	ScriptEditor
Permissions:	FullScriptEditorPermission
Help ID:	w_script_editor
Data Sources:	SCRIPT SCRIPT_CNFG SCRIPT_SOURCE
Desktop Access:	Configure > Script > Editor
Messages:	ScriptListRetrvRq ScriptInsertRq ScriptSourceRetrvRq ScriptUpdateRq ScriptCompileRq ScriptDeleteRq

Script Repository Window

Task ID:	ScriptRepository
Permissions:	FullScriptRepository ViewScriptRepository
Help ID:	w_script_repository
Data Sources:	SCRIPT SCRIPT_CNFG SCRIPT_SOURCE
Desktop Access:	Configure > Script > Repository
Messages:	ScriptListRetrvRq ScriptInsertRq ScriptSourceRetrvRq ScriptUpdateRq ScriptCompileRq ScriptDeleteRq

Security Device Configuration Window

Task ID:	SecurityDeviceConfiguration
Permissions:	FullSecurityDevCfgPermission ViewSecurityDevCfgPermission
Help ID:	w_security_device_configuration
Data Sources:	SEC_DEV_CONFIG
Desktop Access:	Configure > Transaction Security > Security Device
Messages:	SDC_DevListRq SDC_InsertRq SDC_DetailRq SDC_UpdateRq SDC_DeleteRq

Socket Administration Window

Task ID:	IWTSocketAdministration
Permissions:	FullIWTSocketAdminPermission ViewIWTSocketAdministration
Help ID:	w_socket_administration
Data Sources:	Not specified.
Desktop Access:	System Operations > Server Management > Server Administration > Socket Administration
Messages:	IWTFSocketAdminViewRq IWTFSocketInClientListRq IWTFSocketInClientUpdateRq IWTFSocketInServerListRq IWTFSocketInServerUpdateRq IWTFSocketOutClientListRq IWTFSocketOutClientUpdateRq IWTFSocketOutServerListRq IWTFSocketOutServerUpdateRq

Source Routing Profile Configuration Window

Task ID:	AcquirerProfileConfiguration
Permissions:	FullAcqProfileConfigPermission ViewAcquirerProfileConfig
Help ID:	w_source_routing_profile_configuration
Data Sources:	ACQ_RTE_PROFILE ISS_RTE_PROFILE ROUTE ACQUIRER_ISSUER_RELATION
Desktop Access:	Configure > Routing > Profile Description > Source Routing Profile
Messages:	AcquirerProfileListRq AcquirerProfileInsertRq AcquirerProfileViewRq AcquirerProfileUpdateRq AcquirerProfileDeleteRq

SPDH Device Profile Configuration Window

Task ID:	SPDHDeviceConfig
Permissions:	FullSPDHDeviceConfigPermission ViewSPDHDeviceConfigPermission
Help ID:	w_spdh_device_profile_configuration
Data Sources:	SPDH_ACT_CDE_DSC SPDH_MESSAGE SPDH_OPT_DATA SPDH_TXN_CDE_DSC
Desktop Access:	Configure > Merchant Processing > SPDH Device Profile
Messages:	SPDHActCodesDescrsInsertAllRq SPDHActCodesDescrsGetAllRq SPDHActCodesDescrsUpdateAllRq SPDHActCodesDescrsDeleteAllRq SPDHActionCodesInsertAllRq SPDHActionCodesGetAllRq SPDHActionCodesUpdateAllRq SPDHActionCodesDeleteAllRq SPDHMessagesInsertAllRq SPDHMessagesGetAllRq SPDHMessagesUpdateAllRq SPDHMessagesDeleteAllRq SPDHTranCodesDescrsInsertAllRq SPDHTranCodesDescrsGetAllRq SPDHTranCodesDescrsUpdateAllRq SPDHTranCodesDescrsDeleteAllRq

STAR Institution Configuration Window

Task ID:	StarInstitution
Permissions:	FullStarInstitutionPermission ViewStarInstitutionPermission
Help ID:	w_star_institution_configuration
Data Sources:	STAR_INSTITUTION
Desktop Access:	Configure > Interface > Network > STAR > STAR Institution
Messages:	StarInstitutionInsertRq StarInstitutionListRq StarInstitutionViewRq StarInstitutionUpdateRq StarInstitutionDeleteRq

STAR ISO Interface Configuration Window

Task ID:	StarInterface
Permissions:	FullStarInterfacePermission ViewStarInterfacePermission
Help ID:	w_star_iso_interface_configuration
Data Sources:	INTERFACE INTERFACE_SAF INTERFACE_STA STAR_INTERFACE
Desktop Access:	Configure > Interface > Network > STAR > STAR ISO
Messages:	StarInsertRequest StarViewRequest StarUpdateRequest StarDeleteRequest

STAR Network Identifier/Instrument Type Relationship Configuration Window

Task ID:	StarNetworkIdRelationship
Permissions:	FullStarNtwkIdRelationPerm ViewStarNtwkIdRelationPerm
Help ID:	w_star_network_identifier_instrument_type_relationship_configuration
Data Sources:	Not specified.
Desktop Access:	Configure > Interface > Network > STAR > STAR Network Identifier/Instrument Type Relationship
Messages:	Not specified.

Surcharge Profile Configuration Window

Task ID:	ATMSurcharge
Permissions:	FullATMSurchargePermission FullATMSurchPrflPermission ViewATMSurchargePermission ViewATMSurchPrflPermission
Help ID:	w_surcharge_profile_configuration
Data Sources:	SURCHARGE
Desktop Access:	Configure > Surcharge Profile
Messages:	SrchgPrflInsRq SrchgPrflListRq SrchgPrflViewTypeRq SrchgPrflUpdRq SrchgPrflDelRq SrchgPrflGenericDeleteRq

System Algorithm Configuration Window

Task ID:	SystemAlgorithm
Permissions:	FullSystemAlgorithmPermission ViewSystemAlgorithm
Help ID:	w_system_algorithm
Data Sources:	SYS_ALGO_CONFIG
Desktop Access:	Configure > Prefix > Not-On-Us > System Algorithm
Messages:	SysAlgoInsertRq SysAlgoListRq SysAlgoViewRq SysAlgoUpdateRq SysAlgoDeleteRq SysAlgoGenericDeleteRq

System Monitor Window

Task ID:	IWTSystemMonitor
Permissions:	FullIWTSystemMonitorPermission ViewIWTSystemMonitor
Help ID:	w_system_monitor
Data Sources:	Not specified.
Desktop Access:	System Operations > Server Management > Server Administration > System Monitor
Messages:	Not specified.

System Prefix Configuration Window

Task ID:	SystemPrefix
Permissions:	FullSystemPrefixPermission ViewSystemPrefix
Help ID:	w_system_prefix_configuration
Data Sources:	SYSTEM_PREFIX
Desktop Access:	Configure > Prefix > Not-On-Us > System Prefix
Messages:	SysPrfxInsertRq SysPrfxPrflListRq SysPrfxDetailListRq SysPrfxUpdateRq SysPrfxDeleteRq SysPrfxDeletePrflRq

System Properties Window

Task ID:	IWTSystemProperties
Permissions:	FullIWTSysPropertiesPermission ViewIWTSystemProperities
Help ID:	w_system_properties
Data Sources:	Not specified.
Desktop Access:	System Operations > Server Management > Server Administration > System Properties
Messages:	Not specified.

Terminal Logical Network FIID Mapping Configuration Window

Task ID:	TermLnFiidMap
Permissions:	FulltermLnFiidMapPermission ViewtermLnFiidMapPermission
Help ID:	w_terminal_logical_network_fiid_mapping
Data Sources:	Not specified.
Desktop Access:	Configure > Interface > Host > BASE24 ISO8583 Host > Terminal Logical Network/FIID Mapping
Messages:	Not specified.

Token Profile Configuration Window

Task ID:	TokenProfile
Permissions:	FullTokenProfilePermission ViewTokenProfilePermission
Help ID:	w_token_profile_configuration
Data Sources:	TOKEN_CONFIG TOKEN_ID_LIST
Desktop Access:	Configure > BASE24 > Token Profile
Messages:	TokenDescListRq TokenProfileInsertRq TokenProfileListRq TokenProfileViewRq TokenProfileUpdateRq TokenProfileDeleteRq

Trace Configuration Window

Task ID:	TraceConfiguration
Permissions:	FullTraceConfigPermission ViewTraceConfigPermission
Help ID:	w_trace_configuration
Data Sources:	TRACE_CONFIG
Desktop Access:	System Operations > Trace > Trace Configuration
Messages:	TraceConfigInsertRq TraceConfigListRq TraceConfigViewRq TraceConfigUpdateRq TraceConfigDeleteRq

Trace Filter Profile Configuration Window

Task ID:	TraceFilterConfiguration
Permissions:	FullTraceFilterCfgPermission ViewTraceFilterCfgPermission
Help ID:	w_trace_filter_profile_configuration
Data Sources:	TRACE_FILTER
Desktop Access:	System Operations > Trace > Trace Filter Profile
Messages:	TraceFilterInsertRq TraceFilterListRq TraceFilterViewRq TraceFilterUpdateRq TraceFilterDeleteRq TraceFilterGenericDeleteRq

Usages Management Window

Task ID:	Usages
Permissions:	FullUsagesPermission ViewUsagesPermission
Help ID:	w_usages_management
Data Sources:	USAGE
Desktop Access:	Customer Management > Usages
Messages:	UsagesUIListRq UsagesUITblViewRq

User Audit

Task ID:	UserAuditReport
Permissions:	FullUserAuditRptPermission
Help ID:	w_audit_report_wizard
Data Sources:	Not specified.
Desktop Access:	View > User Audit
Messages:	Not specified.

User Permissions

Task ID:	UserSecurityProfile
Permissions:	ViewUSPPermission
Help ID:	w_user_permissions
Data Sources:	Not specified.
Desktop Access:	View > User Permissions
Messages:	Not specified.

User Profile Relationship Window

Task ID:	UserProfileRelation
Permissions:	FullUserProfRelationPermission ViewUserProfileRelation
Help ID:	w_user_profile_relationship
Data Sources:	Not specified.
Desktop Access:	Configure > Journal > Perusal > User Profile Relationship
Messages:	UserRelationshipInsertRq UserRelationshipViewRq UserRelationshipUpdateRq UserRelationshipDeleteRq

User Security Control Management Window

Task ID:	UserSecurityControl
Permissions:	FullUSCtlPermission
Help ID:	w_user_security_control_management
Data Sources:	Users
Desktop Access:	Configure > User Security > Control
Messages:	Not specified.

User Security Group Configuration Window

Task ID:	UserSecurityGroupConfig
Permissions:	FullUSGCfgPermission ViewUSGCfgPermission
Help ID:	w_user_security_group_configuration
Data Sources:	SecGrp
Desktop Access:	Configure > User Security > Group
Messages:	Not specified.

User Security Profile Configuration Window

Task ID:	UserSecurityProfile
Permissions:	FullUSPPermission ViewUSPPermission
Help ID:	w_user_security_profile_configuration
Data Sources:	Users
Desktop Access:	Configure > User Security > Profile
Messages:	Not specified.

User Security Role Configuration Window

Task ID:	UserSecurityRoleConfig
Permissions:	FullUSRCfgPermission ViewUSRCfgPermission
Help ID:	w_user_security_role_configuration
Data Sources:	UsrXRole
Desktop Access:	Configure > User Security > Role
Messages:	Not specified.

User Status

Task ID:	UserAuditReport
Permissions:	FullUserAuditRptPermission
Help ID:	w_user_status
Data Sources:	UsrStat
Desktop Access:	View > User Status
Messages:	Not specified.

Visa Acquirers Configuration Window

Task ID:	VisaAcquirers
Permissions:	FullVisaAcquirersPermission ViewVisaAcquirersPermission
Help ID:	w_visa_acquirers_configuration
Data Sources:	VISA_INST
Desktop Access:	Configure > Interface > Network > VisaNet > Visa Acquirers
Messages:	Not specified.

Visa Brand Instrument Type Relationship Configuration Window

Task ID:	VisaIpf
Permissions:	FullVisaIpfPermission ViewVisaIpfPermission
Help ID:	w_visa_brand_instrument_type_relationship_configuration
Data Sources:	Not specified.
Desktop Access:	Configure > Interface > Network > VisaNet > Visa Brand/ Instrument Type Relationship
Messages:	Not specified.

Visa DPS Acquirers Configuration Window

Task ID:	VisaDPSAcquirers
Permissions:	FullVisaDPSAcquirersPermission ViewVisaDPSAcquirersPermission
Help ID:	w_visa_dps_acquirers_configuration
Data Sources:	VISA_DPS_INSTITUTION
Desktop Access:	Configure > Interface > Network > Visa DPS > Visa DPS Acquirers
Messages:	VisaDPSInstitutionInsertRq VisaDPSInstitutionListRq VisaDPSInstitutionViewRq VisaDPSInstitutionUpdateRq VisaDPSInstitutionDeleteRq

Visa DPS Interface Configuration Window

Task ID:	VisaDPSInterface
Permissions:	FullVisaDPSInterfacePermission ViewVisaDPSInterfacePermission
Help ID:	w_visa_dps_interface_configuration
Data Sources:	INTERFACE INTERFACE_SAF INTERFACE_STA VISA_DPS_INTERFACE
Desktop Access:	Configure > Interface > Network > Visa DPS > Visa DPS Interface
Messages:	VisaDPSInsertRq VisaDPSViewRq VisaDPSUpdateRq VisaDPSDeleteRq

VisaNet ISO Interface Configuration Window

Task ID:	VisanetInterfaceConfig
Permissions:	FullVisanetIFConfigPermission ViewVisanetIFConfigPermission
Help ID:	w_visanet_iso_interface_configuration
Data Sources:	INTERFACE INTERFACE_SAF INTERFACE_STA VISA_INTERFACE
Desktop Access:	Configure > Interface > Network > VisaNet > VisaNet ISO
Messages:	VisaInsertRequest VisaViewRequest VisaUpdateRequest VisaDeleteRequest

Index

A

Access user security windows, [3-2](#)
Active sessions (maximum allowed), [3-6](#)
Active user sessions, [4-3](#)
Application Area, [1-1](#)
Audit report XML format, [5-2](#)
Audit_Store_and_Forward data source, [5-1](#)
Automatic file updating, [6-2](#)

C

Cascading Style Sheets (CSS), JavaHelp, [7-3](#)
Complex password requirements, [3-4](#)
Concurrent active sessions, [2-3](#)
Confirm deletes check box, [2-7](#)
Confirm updates check box, [2-7](#)
Content files, JavaHelp, [7-3](#)
Context sensitive help, [7-5](#)
Currency format locale, [2-7](#)
Custom online help, [7-7](#)

D

Desktop layout (areas), [1-1](#)
DeskTop.log file, [2-11](#)
Distributed Security Administration (DSA), [3-7](#)
DSA (Distributed Security Administration), [3-7](#)

F

Filter settings, [3-15](#)
Frame open indicator, [2-7](#)

G

Get Info function, [3-19](#)

H

Help IDs, [7-5](#)
Helpset file, JavaHelp, [7-3](#)
Helpset Viewer, [7-1](#)
hsvviewer.jar, [7-10](#)

I

Images, JavaHelp, [7-3](#)

J

JAR files for JavaHelp, [7-3](#)
JAR versions, [2-12](#)
JavaHelp, [7-1](#)
JavaHelp configuration files, [7-3](#)
JavaHelp viewer, [7-1](#)

L

local.cfg, [1-2](#)

M

Map file, JavaHelp, [7-3](#)
Map IDs, [7-5](#)
Maximum number of allowed active sessions, [3-6](#)
Menu Bar, [1-1](#)
Mirror the repository, [6-2](#)

N

Navigation tree, [1-1](#)
Navigation tree check box, [2-7](#)

O

Online help viewer (JavaHelp), [7-1](#)
OwnerIDSupport property, [3-7](#)

P

Packaging of online help, [7-3](#)
Password group, [3-4](#)
Passwords, [3-4](#)

- change by a user, [2-5](#)
- change by an administrator, [4-5](#)
- restrictions, [3-4](#)

Permission groups, [3-3](#)
Permissions, [3-3](#)
Pre-show frame indicator, [2-8](#)

P Continued

Print Screen Orientation, 2-8

Procedures

- Access online help from the desktop, 7-2
- Access user security windows, 3-2
- Assign a security group, 3-21
- Assign a system administration role filter, 3-12
- Assign roles to a user, 3-23
- Change a password (by a user), 2-5
- Change a user password (by admin), 4-5
- Change the display of JavaHelp content, 7-9
- Configure a password group, 3-9
- Configure a security group, 3-10
- Configure a user role, 3-13
- Configure field filters, 3-14
- Configure permission groups, 3-19
- Configure permissions, 3-17
- Connect to a web server, 2-4
- Create custom JavaHelp content HTML files, 7-8
- Create custom online help, 7-7
- Display the user interface framework version, 2-12
- Display user password history, 4-5
- Expire a user password, 4-5
- Hide or show the navigation tree, 2-7
- Install JavaHelp, 7-10
- Log off (out), 2-5
- Log off a user, 4-4
- Mirror the repository, 6-2
- Search the helpset, 7-6
- Send a snapshot, 2-11
- Set a user status, 4-2
- Set Error Notification settings, 2-9
- Set sound preferences, 2-10
- Set user preferences, 2-6
- Terminate an active user session, 4-4
- View active user sessions (refreshing, updating), 4-4
- View password change history, 4-5

R

- report.userauditlog.loc environment attribute, 5-3
- report.userdetail.xxx properties, 4-7
- report.userpermissions.xxx properties, 4-10
- Roles, 3-3
- RunDesktop.bat, 2-1, 6-1

S

- Search the helpset, 7-6
- Secure Sockets Layer (SSL) protocol, 1-3
- Security domains, 3-7
- Security error alert message, 2-2
- Security groups (users), 3-5
- Security warning alert message, 2-3
- Session timeout, 3-6, 3-11
- Sessions (active), 4-3
- Snapshots, 2-11

sound.cfg, 2-10

Status Pane, 1-1

Status pane, 2-8

SysAdmin Profile, 3-12

System Administration Profile, 3-12

T

Table of contents, JavaHelp, 7-3

Timeouts

session, 3-11

UI, 3-11

Title Bar, 1-1

Toolbar, 1-1, 2-8

Tooltip text (display errors in tooltip text), 2-9

U

UI timeout, 3-6, 3-11

User authentication, 1-4

User authorization, 1-4

User interface framework, 1-2

User interface framework version, 2-12

User Permissions window

Error Notification tab, 2-9

Sound tab, 2-10

User roles, 3-3

User Securit Group Configuration window

Password Group tab, 3-9

User Security Control Management window

Active Sessions tab, 4-3, 4-4

Password Maintenance tab, 4-5

User Security Group Configuration window

Security Group tab, 3-10

User Security Profile Configuration window

Active Sessions tab, 4-3, 4-4

General tab, 3-20, 4-2

User Security Profile window

Password tab, 4-5

Roles tab, 3-23

User Security Role Configuration window

Permission Groups tab, 3-19

Permissions tab, 3-17

Roles tab, 3-13

User security server

overview, 1-4

User sessions, 4-3

User status, 4-2

User Status window, 4-6

USRAULOG data source, 5-1

V

VC quiet mode, [6-2](#)

Version Checker, [6-1](#)

Version Checker Client window, [6-2](#)

Versions, [2-12](#)

W

Web servers

 selecting, [2-4](#)

 user interface framework, [1-2](#)

X

XML audit message format, [5-2](#)

XML index file, JavaHelp, [7-3](#)

ACI Worldwide Inc.