

BASE24 External Message Data Elements

Data field:	P-1
Type:	b 16
Usage:	Bitmap
Description:	● The secondary bit map in BASE24 shows whether data elements 65 to 128 are included in the message, similar to how the primary bit map handles elements 1 to 64. ● It is only used if any data elements from 65 to 128 are present. ● The primary bit map's first bit indicates if the secondary bit map is included. ● If the secondary bit map is missing, elements 65 to 128 cannot be included.
Data field:	P-2
Type:	n..19
Usage:	Primary account number (PAN)
Description:	● The Primary Account Number (PAN) identifies the cardholder account involved in a transaction or update request. ● If the PAN is present but Track 2 Data (P-35) is missing, BASE24 sets the Track 2 start sentinel to "M" in the internal message. BASE24-atm: ● PAN is not required in external messages since PAN from Track 2 (P-35) or Track 1 (P-45) is used. ● If both Track 2 and Track 1 data are missing, the PAN from this data element is used (if available). ● For outgoing messages, the PAN is derived from the Track data in the internal message. BASE24-pos: ● Same handling as BASE24-atm — PAN is not required but can be included if Track 2 data is missing. ● On incoming messages, PAN from Track 2 or Track 1 is used if available; otherwise, the PAN from this element is used. ● For outgoing messages, PAN is derived from the Track data in the internal message.
Data field:	P-3
Type:	n 6
Usage:	Processing Code
Description:	● The Processing Code describes how a transaction affects the customer's account and other linked accounts. ● It is mandatory for all messages except network management messages. ● BASE24 translates internal transaction codes to/from external transaction codes through the ISO Host Interface. BASE24-atm:

	● On incoming messages – Processing code is translated and placed in TRAN-CDE, FROM-ACCT-TYP, and TO-ACCT-TYP fields of the STM. ● On outgoing messages – Processing code is translated from these fields and placed in this element. BASE24-pos: ● Non-Reconciliation Control Messages: ■ On incoming messages – Processing code is translated and placed in TRAN.TRAN-CDE.TC, TRAN.TRAN-CDE.T, and TRAN.TRAN-CDE.AA fields of the PSTM. ■ On outgoing messages – These fields are translated and placed in the processing code element. ● Reconciliation Control Messages: ■ On outgoing reconciliation messages – The processing code is set based on the SETL-TYP field in the 0500-series message: ◆ 0 – Batch record → 900000 ◆ 1 – Shift record → 910000 ◆ 2 – Daily record → 920000 ◆ 3 – Network record → 930000 ◆ 9 – Service record → 99XYZZ (X = message number, Y = total messages, ZZ = number of service totals) ● Incoming reconciliation control messages are not supported.
Data field:	P-4
Type:	n 12
Usage:	Amount Transaction
Description:	● The Transaction Amount represents the amount of funds requested (for debit or credit) in the source currency of the transaction. ● Decimalization is based on the Transaction Currency Code (P-49). ■ Example: 000000001000 = \$10.00 (if currency is USD) or 1000 lire (if currency is lire). BASE24-atm: ● Mandatory for all financial and reversal messages (zero-filled if not applicable). ● Incoming messages: Amount is placed in RQST.AMT-1 field of the STM. ● Outgoing messages: Amount is taken from RQST.AMT-1 and placed in this data element. ● Surcharges: Value in RQST.AMT-1 includes the value from ORIG-FEE (Surcharge Data token). ● Adjustment Transactions: ■ For deposit adjustments: ◆ Adjustment = RQST.AMT-2 – RQST.AMT-1 ◆ Negative result → Processing Code (P-3) starts with 02 (debit adjustment). ◆ Positive result → Processing Code (P-3) starts with 22 (credit

	- adjustment). ◆ Transaction amount = Absolute value of result. ■ For withdrawal adjustments: ◆ Adjustment = RQST.AMT-1 – RQST.AMT-2 ◆ Negative result → Processing Code (P-3) starts with 02 (debit adjustment). ◆ Positive result → Processing Code (P-3) starts with 22 (credit adjustment). ◆ Transaction amount = Absolute value of result. ● Hosts must handle balance inquiries, PIN changes, and PIN unblock transactions with positive amounts (due to access fees). BASE24-pos: ● Mandatory for all authorization, financial, and reversal messages. ● Incoming messages: Amount is placed in TRAN.AMT-1 field in the PSTM. ● Outgoing messages: Amount is taken from TRAN.AMT-1 and placed in this element. ● Negative values: First byte contains a minus sign (–) for balance inquiries. ● Purchase with cash back: ■ Contains the total amount (purchase + cash back). ■ Cash back amount → Data element P-54. ■ Adjusted cash back → Data element S-95. ● Partially approved transactions (P-39 = 10): ■ This element contains the authorized amount in the response (may differ from the requested amount).
Data field:	P-7
Type:	n 10
Usage:	Transmission date & time
Description:	● Contains the Greenwich Mean Time (GMT) when the message is initiated by the sender. ● Mandatory for all message types. BASE24-atm: ● Incoming messages: Information is dropped. ● Outgoing messages: Current GMT is placed in this element. BASE24-pos: ● Incoming messages: Information is dropped. ● Outgoing messages: Current GMT is placed in this element.
Data field:	P-11
Type:	n 6
Usage:	System trace audit number (STAN)
Description:	● A unique number set by the message sender and echoed by the receiver to match responses with original messages. ● It does not remain constant throughout a transaction's life (e.g., reversal may have a different number).

	● Mandatory for all BASE24 messages (except telebanking, where it exists in both internal and external messages). Network Management: ● Used to match network management requests and responses: ■ Generated in 0800 messages and expected in 0810 responses. ■ In 0810 responses, the number from the corresponding 0800 request is echoed. BASE24-from Host Maintenance: ● For file update messages: ■ If the host generates the value in 0300 messages, the ISO Host Interface process returns it in the corresponding 0310 messages.
Data field:	P-12
Type:	n 6
Usage:	Local transaction time (hhmmss)
Description:	● Contains the local time (in HHMMSS format) when the transaction started at the card acceptor location. ● Time zone offsets for terminals are maintained by BASE24 to adjust the system date and time to local transaction time. ● Internally stored as HHMMSShh (includes hundredths of seconds), but hundredths are set to zeros in incoming messages and truncated in outgoing messages. BASE24-atm: ● Mandatory for: 0200, 0205, 0210, 0215, 0220, 0221, 0420, and 0421 messages. ● Incoming messages: Time is placed in TRAN-TIM field in the STM. ● Outgoing messages: Time is taken from TRAN-TIM field in the STM. ● Terminal time offsets are maintained in the Terminal Data File. BASE24-pos: ● Mandatory for: 0100, 0110, 0120, 0121, 0200, 0210, 0220, 0221, 0402, 0420, 0421, and outbound 430 messages to an e-commerce host. ● Incoming messages: Time is placed in TRAN-TIM field in the PSTM. ● Outgoing messages: Time is taken from TRAN-TIM field in the PSTM. ● Terminal time offsets are maintained in the Terminal Data Files.
Data field:	P-15
Type:	n 4
Usage:	Settlement date
Description:	● Holds the interchange settlement date (the date a transaction is settled by the interchange). ● If an interchange is involved, this element holds the settlement date on the interchange system, while Capture Date (P-17) holds the settlement date on the BASE24 system. ● Format: ■ External format: MMDD

	■ Internal format: YYMMDD (year added internally and truncated in outgoing messages). ● Required only if an interchange is involved (considered conditional). BASE24-atm: ● Conditional for: 0200 (outgoing), 0210, 0220, 0221, 0420, and 0421 messages. BASE24-pos: ● Conditional for: 0100, 0110, 0120, 0121, 0200, 0210, 0220, 0221, 0402, 0420, and 0421 messages.
Data field:	P-18
Type:	n 4
Usage:	Merchant type, or merchant category code
Description:	● Contains the Standard Industrial Classification (SIC) code of the retailer involved in the transaction. BASE24-pos: ● Incoming messages: Code is placed in RETL-SIC-CDE field in the PSTM. ● Outgoing messages: Code is taken from RETL-SIC-CDE field in the PSTM.
Data field:	P-22
Type:	n 3
Usage:	Point of service entry mode
Description:	● Contains two codes: ■ First code (2 digits) → Method of entering Track data or PAN. ■ Second code (1 digit) → Entry capabilities at the point of service. ● Value 01 → Track data entered manually; PIN entry capabilities unknown. BASE24-atm: ● Conditional for 0200 request messages from a host. ● Required if Track 2 data is manually entered. ● Incoming messages: ■ If value = 010, sets M in the first byte of RQST.TRACK2 field (indicating incomplete Track 2 data). ● Outgoing messages: Not used. BASE24-pos: ● Mandatory for 0100 messages; conditional for other authorization, financial, and reversal messages. ● Incoming messages: ■ Value placed in PT-SRV-ENTRY-MDE field in PSTM. ■ If first code = 01, sets M in the start sentinel of Track data (P-35). ● Outgoing messages: Value taken from PT-SRV-ENTRY-MDE field in PSTM.
Data field:	P-23
Type:	n 3
Usage:	Application PAN sequence number

Description:	● Contains the BASE24 member number to differentiate multiple cards with the same card number. ● Must be right-justified and zero-filled or contain three zeros. BASE24-atm: ● Default: Not included in the message. ● Incoming messages: Value placed in RQST.MBR-NUM field in the STM. ● Outgoing messages: Value from RQST.MBR-NUM field is placed in this element. BASE24-pos: ● Conditional for 0500, 0520, and 0521 messages. ● Incoming messages: Value placed in TRAN.MBR-NUM field in the PSTM. ● Outgoing messages: ■ For 0500 or 0520 → Value from SETL.HEAD.CRD.CARD.MBR-NUM (settlement message). ■ For others → Value from TRAN.MBR-NUM field in the PSTM.
Data field:	P-25
Type:	n 2
Usage:	Point of service condition code
Description:	● Identifies the condition under which the transaction is occurring at the point of service. ● Conditional for: 0200, 0210, 0220, 0230, 0420, and 0430 messages. ● Incoming messages: ■ If present → Value placed in PT-SRV-COND-CDE field in the PSTM. ■ If absent → PT-SRV-COND-CDE is set to 00. ● Outgoing messages: ■ Value taken from PT-SRV-COND-CDE field in the PSTM
Data field:	P-32
Type:	n ..11
Usage:	Acquiring institution identification code
Description:	● Identifies the acquiring institution or its agent. ● In the U.S., usually represents a Federal Reserve routing number BASE24-atm: ● Mandatory for all financial and reversal messages. ● Incoming messages: Value placed in RQST.ACQ-INST-ID-NUM field in the STM. ● Outgoing messages: Value taken from RQST.ACQ-INST-ID-NUM field in the STM. ● If terminal is directly connected, value is set from INST-ID-NUM field in the Terminal Data File. BASE24-pos: ● Mandatory for all authorization, financial, and reversal messages. ● Incoming messages: Value placed in ACQ-INST-ID-NUM field in the PSTM. ● Outgoing messages: Value taken from ACQ-INST-ID-NUM field in the

	PSTM. ● If terminal is directly connected, value is set from RTTN field in the POS Terminal Data File.
Data field:	P-33
Type:	n ..11
Usage:	Forwarding institution identification code
Description:	● Identifies the BASE24 service provider. BASE24-atm: ● Incoming messages: Value placed in FRWD-INST-ID-NUM field in the STM. ● Outgoing messages: Value taken from FRWD-INST-ID-NUM field in the STM. ● Initially obtained from ATM-FORWARD-INST-ID parameter in LCONF. BASE24-pos: ● Incoming messages: Value placed in FRWD-INST-ID-NUM field in the PSTM. ● Outgoing messages: Value taken from FRWD-INST-ID-NUM field in the PSTM. ● Initially obtained from POS-FORWARD-INST-ID parameter in LCONF.
Data field:	P-37
Type:	AN 12
Usage:	Retrieval Reference Number
Description:	● Uniquely identifies a transaction throughout its lifecycle. ● If initiated from BASE24 → Number is generated by BASE24. ● If initiated from an acquirer host → Number comes from the original 0200 message. BASE24-atm: ● Mandatory for financial, reversal, and statement print messages. ● Incoming messages: Value placed in SEQ-NUM field in the STM. ● Outgoing messages: Value taken from SEQ-NUM field in the STM. ● If from a directly connected terminal → Generated by ATM or BASE24-atm Device Handler. BASE24-pos: ● Mandatory for authorization, financial, reversal, and reconciliation control messages. ● Incoming messages: Value placed in SEQ-NUM field in the PSTM. ● Outgoing messages: Value taken from SEQ-NUM field in the PSTM. ● If from a directly connected terminal → Generated by POS device or BASE24-pos Device Handler.
Data field:	P-38
Type:	AN 6
Usage:	Authorization Identification Response

Description:	● Contains a response ID assigned by the authorizing institution. ● Generated internally by BASE24-pos and BASE24-telebanking or by an interchange/host. ● Mandatory unless specified otherwise in the EMF (External Message Format). BASE24-atm: ● Mandatory for 0210, 0220, 0221, 0420, and 0421 messages. ● BASE24-atm does not generate these IDs but accepts them from an interchange or host. ● Incoming messages: Value placed in AUTH-ID-RESP field in the STM. ● Outgoing messages: Value taken from AUTH-ID-RESP field in the STM. BASE24-pos: ● Mandatory for 0110, 0120, 0121, 0210, 0220, 0221, 0420, and 0421 messages. ● Incoming messages: Value placed in TRAN.APPRV-CDE field in the PSTM. ● Outgoing messages: Value taken from TRAN.APPRV-CDE field in the PSTM (last two bytes are dropped).						
Data field:	P-39						
Type:	AN 2						
Usage:	Response Code						
Description:	● Contains a code that indicates the outcome or status of a transaction. ● Used to communicate approval, denial, or errors in transaction processing. Network Management: ● Mandatory in 0810 messages. ● Common response codes: 00 = Approved 05 = Denied 12 = Bad check digits 91 = DPC down BASE24-atm: ● Mandatory for all BASE24-atm financial transactions, statement prints, and reversals (except 0200 messages). ● The ISO Host Interface translates internal response codes to/from ISO codes. <table border="1"> <thead> <tr> <th>Message Type</th><th>Details</th></tr> </thead> <tbody> <tr> <td>0210/0215</td><td>Indicates request approval or denial; translated and placed in RQST.RESP field of STM.</td></tr> <tr> <td>0220/0221</td><td>Indicates transaction completion status; on outgoing 0220 (adjustment) messages, translated from RQST.RVSL-CDE.</td></tr> </tbody> </table>	Message Type	Details	0210/0215	Indicates request approval or denial; translated and placed in RQST.RESP field of STM.	0220/0221	Indicates transaction completion status; on outgoing 0220 (adjustment) messages, translated from RQST.RVSL-CDE.
Message Type	Details						
0210/0215	Indicates request approval or denial; translated and placed in RQST.RESP field of STM.						
0220/0221	Indicates transaction completion status; on outgoing 0220 (adjustment) messages, translated from RQST.RVSL-CDE.						

		0230	Set to 00.														
		0420/0421	Indicates reason for reversal; translated and placed in RQST.RVSL-CDE field of STM.														
		0430	Set to 00.														
	BASE24-pos:																
	● Mandatory for all BASE24-pos authorization, financial transactions, and reversals (except 0100 and 0200 messages). ● The ISO Host Interface translates internal response codes to/from ISO codes.																
		<table><tr><th>Message Type</th><th>Details</th></tr><tr><td>0210</td><td>On incoming messages, translated and placed in TRAN.RESP-CDE field in PSTM; on outgoing, value taken from TRAN.RESP-CDE.</td></tr><tr><td>0200/0220 (Adjustments)</td><td>If first two digits of P-3 (Processing Code) = 02, 14, 19, or 22, value moved to TRAN.RVSL-CDE field in PSTM.</td></tr><tr><td>0220 (Adjustments)</td><td>If TRAN-CDE in PSTM = 21, 22, 23, or 24, value taken from TRAN.RVSL-CDE or TRAN.RESP-CDE (based on ADJ-ADVICE-RC setting).</td></tr><tr><td>0230</td><td>Set to 00.</td></tr><tr><td>0402/0420</td><td>Translated and placed in TRAN.RVSL-CDE field in PSTM; on outgoing, value taken from TRAN.RVSL-CDE.</td></tr><tr><td>0430</td><td>Set to 00.</td></tr></table>	Message Type	Details	0210	On incoming messages, translated and placed in TRAN.RESP-CDE field in PSTM; on outgoing, value taken from TRAN.RESP-CDE.	0200/0220 (Adjustments)	If first two digits of P-3 (Processing Code) = 02, 14, 19, or 22, value moved to TRAN.RVSL-CDE field in PSTM.	0220 (Adjustments)	If TRAN-CDE in PSTM = 21, 22, 23, or 24, value taken from TRAN.RVSL-CDE or TRAN.RESP-CDE (based on ADJ-ADVICE-RC setting).	0230	Set to 00.	0402/0420	Translated and placed in TRAN.RVSL-CDE field in PSTM; on outgoing, value taken from TRAN.RVSL-CDE.	0430	Set to 00.	
	Message Type	Details															
	0210	On incoming messages, translated and placed in TRAN.RESP-CDE field in PSTM; on outgoing, value taken from TRAN.RESP-CDE.															
	0200/0220 (Adjustments)	If first two digits of P-3 (Processing Code) = 02, 14, 19, or 22, value moved to TRAN.RVSL-CDE field in PSTM.															
	0220 (Adjustments)	If TRAN-CDE in PSTM = 21, 22, 23, or 24, value taken from TRAN.RVSL-CDE or TRAN.RESP-CDE (based on ADJ-ADVICE-RC setting).															
0230	Set to 00.																
0402/0420	Translated and placed in TRAN.RVSL-CDE field in PSTM; on outgoing, value taken from TRAN.RVSL-CDE.																
0430	Set to 00.																

	BASE24-pos: ● Mandatory in all authorization, financial transaction, and reversal messages. ● Incoming Messages: ■ Code from this data element is placed in the TERM-ID field in the PSTM. ● Outgoing Messages: ■ Code for this data element is taken from the TERM-ID field in the PSTM. ● Directly Connected Terminals: ■ Code is taken from the TERM-ID field in the POS Terminal Data File record for the terminal.
Data field:	P-42
Type:	ANS 15
Usage:	Card Acceptor Identification Code
Description:	● Contains a code used to identify the card acceptor in a transaction if the card acceptor is different from the acquiring institution. ● First 11 bytes are used; any remaining bytes are truncated to the right. BASE24-atm: ● Conditional for the following messages: ● 0200, 0210, 0220, 0221, 0420, and 0421 ● Incoming Messages: ● First 11 bytes of the code are placed in the CRD-ACCPT-ID-NUM field in the STM. ● Remaining bytes are truncated. ● Outgoing Messages: ● Value from the CRD-ACCPT-ID-NUM field in the STM is placed in the first 11 bytes of this data element. ● Remaining positions are set to blanks. BASE24-pos: ● Conditional for all authorization, financial transaction, and reversal messages, except: ■ 0130, 0230, 0412, and 0430 messages. ● Incoming Messages: ■ First 11 bytes of the code are placed in the CRD-ACCPT-ID-NUM field in the PSTM. ■ Remaining bytes are truncated. ● Outgoing Messages: ■ If the CRD-ACCPT-ID-NUM field in the PSTM is not set to blanks or zeros, the value is placed in the first 11 bytes of this data element. ■ Remaining positions are set to blanks.
Data field:	P-43
Type:	ANS 40

Usage:	Card Acceptor Name/Location
Description:	● Contains the name and location of the card acceptor, defining the point of service in both local and interchange environments. ● Mandatory for most transaction types, including financial, authorization, and reversal messages. BASE24-atm: ● Mandatory for the following messages: ■ 0200, 0220, 0221, 0420, and 0421 ● Reversal Handling: ■ If a reversal (0420) is due to a late or unsolicited approval response, the following text is inserted instead of the regular data: ** REVERSAL FOR LATE/UNSOL RESPONSE ** ● In other reversal cases, the value is copied from the original request. BASE24-pos: ● Mandatory for the following messages: ■ 0100, 0120, 0121, 0200, 0220, 0221, 0402, 0420, and 0421 ● Reversal Handling: ■ If a reversal (0420) is due to a late or unsolicited approval response, the following text is inserted instead of the regular data: ** REVERSAL FOR LATE/UNSOL RESPONSE ** ● In other reversal cases, the value is copied from the original request.
Data field:	P-48
Type:	ANS 47 (includes a 3-position field length indicator)
Usage:	BASE24-atm Additional Data
Description:	● The Additional Data element in BASE24-atm carries sharing information used to determine if not-on-us transactions are allowed. ■ Not-on-us transaction – A transaction where the card issuer and card acceptor are different entities. BASE24-atm: ● Mandatory for incoming 0200 messages. ● BASE24-atm Authorization Process checks the sharing parameters from this element before sending a 0200 message to the host. ● Not required in outgoing 0200 messages since the sharing check is already performed at the authorization stage.
Data field:	P-48
Type:	ANS 30 (includes a 3-position field length indicator)
Usage:	BASE24-pos Retailer Data
Description:	● The Retailer Data element in BASE24-pos contains information used to identify the retailer involved in the transaction. BASE24-pos: ● Mandatory for all: ■ Authorization messages ■ Financial transaction messages

	■ Reversal messages ■ Reconciliation control messages ● Not required for the following message types: ■ 0130 – Account Verification ■ 0230 – Financial Advice Response ■ 0412 – Batch Upload ■ 0430 – Reversal Response
Data field:	P-49
Type:	N 3
Usage:	Transaction Currency Code
Description:	● The Transaction Currency Code data element contains a code that defines the currency of the source location of the transaction. ● BASE24 products use numeric currency codes only BASE24-atm: ● The code in the Transaction Currency Code identifies the currency that applies to: ■ Transaction Amount (P-4) ■ Transaction Fee Amount (P-28) ● Mandatory for all: ■ Financial transaction messages ■ Reversal messages ● Incoming Messages: ■ The code from this data element is placed in the RQST.ORIG-CRNCY-CDE field in the STM. ● Outgoing Messages: ■ The value for this data element is taken from the RQST.ORIG-CRNCY-CDE field in the STM. ● Initialization: ■ Direct Terminal Connection: Initially set from the Terminal Data File (in the HOPPERx.CRNCY-CDE field). ● Interchange: Initially set from the CRNCY-CDE field in the Base segment of the ICF or ICFE. BASE24-pos: ● The code in the Transaction Currency Code identifies the currency that applies to: ■ Transaction Amount (P-4) ● Mandatory for all: ■ Authorization messages ■ Financial transaction messages ■ Reversal messages ■ Reconciliation control messages ● Incoming Messages: ■ The code from this data element is placed in the ORIG-CRNCY-CDE

	field in the PSTM. ● Outgoing Messages: ■ The value for this data element is taken from the CRNCY-CDE field in the PSTM. ● Initialization: ■ Initially set from the ORIG-CRNCY-CDE field in the POS Terminal Data File.
Data field:	P-52
Type:	AN 16
Usage:	Personal Identification Number (PIN) Data
Description:	● The PIN Data element contains a number assigned to a customer that uniquely identifies them at the point of service. ■ This data element can contain the PIN itself or a derivative of the PIN. ■ The Key File (KEYF) or Key 6 File (KEY6) controls whether the PIN is encrypted or in the clear. ● BASE24-atm: ● Mandatory for incoming 0200 messages ● Conditional for outgoing 0200 messages ● Incoming Messages: ■ The value from this data element is placed in the RQST.PIN field in the STM. ■ If the PIN is absent or filled with the pad character (specified by the PRE-VERIFIED-PIN-PAD-CHAR param in the LCONF, e.g., FFFFFFFFFFFFFFFF), BASE24-atm treats the PIN as pre-verified. ● Outgoing Messages: ■ The value from the RQST.PIN field in the STM is placed in this data element. ● BASE24 omits this data element from outgoing messages if: ■ RQST.PIN-SIZE = 0 ■ RQST.PIN-TRIES = Z (indicating that the PIN has already been verified) ● BASE24-pos: ● Conditional for 0100 and 0200 messages ● Incoming Messages: ■ Required for transactions involving a PIN. ■ If the message contains a PIN: ◆ The value is placed in the PIN field in the PSTM. ■ If the transaction does not include a PIN: ◆ The data element is omitted or set to spaces (in this case, the PIN field in the PSTM is not set). ■ If the PIN is pre-verified: ◆ The data element should be filled with the pad character (FFFFFFFFFFFFFFFF). ◆ The PIN-TRIES field in the PSTM is set to Z. ● Outgoing Messages:

	■ The PIN is taken from the PIN field in the PSTM. ■ BASE24 sends this data element if: ◆ PINs have been pre-verified ◆ PINs are to be verified by the host ■ If the PIN-SIZE field in the PSTM is 0 and the PIN-TRIES field is Z: ◆ BASE24 sends this data element filled with the pad character (FFFFFFFFFFFFFFFF). ■ If the transaction does not include a PIN: ◆ BASE24 omits this data element.
Data field:	P-55
Type:	ANS ..999
Usage:	P-55 Through P-56 ISO Reserved
Description:	Not used by BASE24
Data field:	P-61
Type:	ANS 16 (includes a 3-position field length indicator)
Usage:	Card Issuer and Authorizer Data
Description:	● The Card Issuer and Authorizer Data element uniquely identifies a financial institution within a BASE24 system. It also helps in identifying the transaction category and carrying additional response code data. ● BASE24-atm: ● Mandatory in the following message types: ■ 0200 (outgoing) ■ 0210 ■ 0220 ■ 0221 ■ 0420 ■ 0421 ● Purpose: ■ Identifies the financial institution involved in the transaction. ■ BASE24-atm uses this element to ensure the transaction is routed to the correct financial institution. ● BASE24-pos: ● Mandatory for: ■ Authorization messages ■ Financial transaction messages ■ Reversal messages ● Purpose: ■ Carries: ◆ FIID (Financial Institution Identifier) ◆ Logical Network of the card issuer ◆ Transaction category ◆ Additional response code data ■ Ensures proper routing and processing of transactions based on the card issuer's network and category.

Data field:	P-63
Type:	ANS 19 (includes a 3-position field length indicator)
Usage:	BASE24-atm PIN Offset
Description:	● The PIN Offset data element is used to carry the PIN offset value, which allows ATM customers to select and update their own PINs. This data element helps synchronize the host's PIN database with the BASE24-atm database when a customer changes their PIN at an ATM. BASE24-atm: ● Conditional for the following message types: ■ 0200 (outgoing) – Transaction Request ■ 0210 – Transaction Response ■ 0220 – Financial Advice Request ■ 0221 – Financial Advice Response ■ 0420 – Reversal Request ● Purpose: ■ Supports PIN change functionality at ATMs. ■ If a PIN change is initiated, the new PIN Offset is transmitted to the host. ■ The value is taken from the RQST.PIN-OFST field in the STM. ● Processing Behavior: ■ Outgoing messages: ◆ If RQST.PIN-OFST in the STM is non-blank, the PIN Offset value is included in the outbound message. ■ Failed PIN change transaction: ◆ If an outgoing 0210 message (PIN Change) fails: ◆ If PIN Offset is present → Stored in RQST.PIN-OFST field in the STM. ◆ If PIN Offset is absent → RQST.PIN-OFST field is set to ZZZZZZZZZZZZZZZZZZ. ◆ ZZZZZZZZZZZZZZZZZZ indicates that the Authorization Process should not update the PIN-OFST field in the CAF (Customer Account File).
Data field:	S-90
Type:	N 42
Usage:	Original Data Elements
Description:	● The Original Data Elements data element (P-90) contains a group of five sub-elements that identify the original transaction being reversed or adjusted. It is used primarily in reversal and adjustment messages to link back to the original transaction. ● Used to identify the original transaction in cases of: ■ Reversal – When a transaction is cancelled or rolled back. ■ Adjustment – When the financial details of a transaction need to be corrected.
Data field:	P-100
Type:	N ..11

Usage:	Receiving Institution Identification Code
Description:	- Identifies the institution receiving a request message, essential for routing transactions accurately. BASE24-atm Handling: - Mandatory in 0200 (outgoing), 0210, 0220, 0221, 0420, and 0421 messages. - On 0420 messages, value is copied from the 0210 message. - Stored in RCV-INST-ID-NUM field in the STM (incoming and outgoing). - If authorized locally, value from INST-ID-NUM is used; if routed to host, host value is used. BASE24-pos Handling: - Mandatory in 0100, 0110, 0120, 0121, 0200, 0210, 0220, 0221, 0402, 0420, and 0421 messages. - Stored in RCV-INST-ID-NUM field in the PSTM (incoming and outgoing).
Data field:	P-102
Type:	ANS ..28
Usage:	Account Identification 1
Description:	- Identifies a customer account, typically linked to a primary or card account. Left-justified and blank-filled to the right. BASE24-atm Handling: - Mandatory for statement print messages. - Conditional for financial and reversal messages (included if known to host). - Stored in RQST.FROM-ACCT field in STM (incoming and outgoing). BASE24-pos Handling: - Mandatory for 0402 and 0412 messages. - Conditional for authorization (except 0100), reversal, and financial (except 0200) messages. - Stored in TRAN.ACCT field in PSTM (incoming and outgoing).
Data field:	P-103
Type:	ANS ..28
Usage:	Account Identification 2
Description:	- Identifies a customer account, typically linked to a primary or card account. Left-justified and blank-filled to the right. BASE24-atm Handling: - Used for the to account in a transaction (e.g., credited account in a transfer). - Conditional for all financial and reversal messages (except 0200). - Stored in RQST.TO-ACCT field in STM (incoming and outgoing).