

User Security Manual

BASE24®



© 2009 by ACI Worldwide, Inc. All rights reserved.

All information contained in this documentation, as well as the software described in it, is confidential and proprietary to ACI Worldwide, Inc., or one of its subsidiaries, is subject to a license agreement, and may be used or copied only in accordance with the terms of such license. Except as permitted by such license, no part of this documentation may be reproduced, stored in a retrieval system, or transmitted in any form or by electronic, mechanical, recording, or any other means, without the prior written permission of ACI Worldwide, Inc., or one of its subsidiaries.

ACI, ACI Worldwide, and the ACI product names used in this documentation are trademarks or registered trademarks of ACI Worldwide, Inc., or one of its subsidiaries.

Other companies' trademarks, service marks, or registered trademarks and service marks are trademarks, service marks, or registered trademarks and service marks of their respective companies.

Contents

Conventions Used in This Manual	vii
Preface	xi
1: Introduction	1-1
BASE24 User Access	1-2
BASE24 Menu Structure	1-4
BASE24 Logon Screen	1-6
BASE24 Virtual Menu	1-6
BASE24 Product Menus	1-6
BASE24 Screens	1-6
Moving to a New Screen	1-8
Moving to a Specific Screen Within a File, Table, or Function	1-8
Moving to a New File, Table, or Function	1-9
Moving to a New Logical Network	1-11
FILE DESTINATION Field Entries	1-12
2: Screens and Terminal Functions	2-1
BASE24 Screen Organization	2-2
Base Layer	2-4
Overlay Layer	2-5
BASE24 Screen Types	2-6
File and Table Maintenance Screens	2-7
Operator Command Screens	2-8
BASE24 Screen Documentation	2-9
Field Length	2-12
Required Field	2-12
Default Value	2-12
Data Name	2-13
Column Name	2-13

Screens and Terminal Functions *continued*

Help Screens	2-14
Menu Help Screens	2-14
File and Table Help Screens	2-15
Screen Messages	2-16
Function Keys	2-17
 3: Logging On to the BASE24 User Access System	 3-1
BASE24 Logon Screen Fields	3-2
Using the BASE24 Logon Screen	3-7
Logging On to the BASE24 User Access System for the First Time	3-7
Logging On to the BASE24 User Access System	3-8
Configuring Passwords	3-8
Changing Your Password	3-10
Moving Directly to a File, Table, or Function	3-10
 4: Accessing BASE24 Menus and Screens	 4-1
BASE24 Menu Structure	4-2
BASE24 Virtual Menu	4-5
Product Menus	4-10
ATM Product Menu	4-11
Base Product Menu	4-14
Billpay Product Menu	4-22
Card Management Product Menu	4-27
Check Authorization User Menu	4-29
Check Disbursements User Menu	4-31
Core Product Menu	4-34
Customer Service	4-39
Frequent Shopper User Menu	4-41
Kernel/IEP Product Menu	4-44
Mail Product Menu	4-50
Operator Product Menu	4-52
POS Product Menu	4-54

Accessing BASE24 Menus and Screens *continued*

Refunds User Menu	4-61
Retail Configuration Menu	4-64
Teller Product Menu	4-68
5: Setting Up BASE24 User Access Security	5-1
BASE24 User Access Security	5-2
Restricting Access to the BASE24 System.	5-3
Logical Network	5-5
Financial Institution	5-6
Region and Branch	5-8
XPNET Node	5-8
Time of Day	5-8
Terminal	5-8
Screen	5-9
Access Codes	5-9
Network Control Commands	5-10
Assigning Access	5-13
SUPER/SUPER	5-13
PROD/SUPER	5-13
Group Leaders.	5-15
Users	5-15
Rules for Assigning Access	5-15
Using Security Screens to Assign Access.	5-16
Other Security Features	5-17
Inactivity Timers.	5-17
Passwords	5-17
Logon Attempt Limitations	5-18
Security Screen 1	5-19
Function Keys.	5-26
Security Screen 2	5-29
Function Keys.	5-30
Security Screen 3	5-32
Function Keys.	5-35

Setting Up BASE24 User Access Security *continued*

Security Screen 4	5-37
Function Keys	5-46
Network Control Security Profile File	5-49
Function Keys	5-52
Procedures for Assigning Access	5-55
Adding an NCSP Record	5-55
Updating an Existing NCSP Record	5-57
Copying an NCSP Record	5-58
Adding a Security Record	5-58
Adding a Security Record Identical to Your Security Record	5-61
Updating a Security Record	5-62
Reinstating Access for a Locked Out User	5-64
Deleting All Security Records for a Specified User	5-65
 6: Audit Reports	 6-1
Security Audit Reports	6-2
Generic Runfiles	6-3
Report Generation	6-6
Error Messages	6-6
Report Samples and Field Descriptions	6-6
OMF Audit Reports	6-19
OMF Description Table	6-21
Configuration	6-22
Generic Runfiles	6-23
Report Generation	6-28
Error Messages	6-28
Report Samples and Field Descriptions	6-30
 Index	 Index-1

Conventions Used in This Manual

This section explains the different terminology used to describe the screens used to maintain Enscribe files and Structured Query Language (SQL) tables and how field descriptions are documented in this manual.

Enscribe Files and SQL Tables

Throughout this manual, specific terminology is used when discussing screens that access Enscribe files or SQL tables. For Enscribe files, the terms field, record, and file are used. For SQL tables, the analogous terms of column, row, and table are used, respectively.

Field Descriptions

Each field appearing on the BASE24 Logon screen or a security file maintenance screen is listed by name and then described. Field descriptions in this manual briefly summarize the contents, purpose, and permissible values, as shown in the following example taken from the BASE24 Logon screen.

Example

USER NAME — The name that uniquely identifies you to the BASE24 system. This name must match your alias in the Security File (SEC) or access to BASE24 is denied.

Normally, your supervisor gives you your user name. You must have security clearance under an identical user name for all logical networks you want to access without logging on again.

Field Length:	1–16 alphanumeric characters
Required Field:	Yes
Default Value:	None

Explanation

Each field description is completed by one or more of the following items of information:

Item	Description
Example	Illustrates a possible entry for the field to further clarify the value or values that can be entered.
Field Length	Specifies the size of the field and the type of characters that can be entered. This length refers to the field and valid values for the file maintenance screen, not the field in the DDLs. Possible values are alphabetic, alphanumeric, hexadecimal, and numeric. The term <i>alphanumeric</i> includes all alphabetic, numeric, and special characters that can be entered from a keyboard without using a control sequence. The term <i>hexadecimal</i> includes all numbers and the letters A through F. When a field value cannot be modified by the operator, the field length is <i>System Protected</i>.
Occurs	Indicates the number of times the field can be displayed on the screen. This information is provided only when the field can be displayed multiple times.
Required Field	Specifies whether a value has to be entered in the field. Possible values are Yes and No. Some fields are required only under certain conditions. In this case, the entry is Yes, followed by the conditions that determine when the field is required.
Default Value	Specifies the value that is automatically placed in the field when the screen is first displayed or when the F8 key is pressed to clear the screen.
Data Name	Provides the DDL name associated with the field appearing on the screen. Data names are included in the documentation to assist in communicating screen and field issues to your technical staff. Note that screen data is not always stored in the BASE24 database as it appears on the screen or as it is described in the field description. If you need information on how screen data is actually stored, consult the DDLs.

Item	Description
Column Name	Provides the SQL column name associated with the field appearing on the screen. Column names are included in the documentation to assist in communicating screen and field issues to your technical staff. Note that screen data is not always stored in the BASE24 database as it appears on the screen or as it is described in the field description. If you need information on how screen data is actually stored, consult the DDLs or SQL table creation source file.

ACI Worldwide, Inc.

Preface

The BASE24 user access system enables you, the BASE24 user, to interact with the BASE24 transaction processing software. The BASE24 user access system is an organized structure of menus, screens, and functions that allow you to monitor and control BASE24 processing. This manual is an introduction to using the BASE24 user access system. All other BASE24 operator documentation is written based on the assumption that you understand the material in this manual.

Audience

This manual is intended for the BASE24 operational staff who monitor and control BASE24 processing. Anyone who is required to access the BASE24 system should be familiar with the information in this manual.

Additional Documentation

The BASE24 documentation set is arranged so that each BASE24 manual presents a topic or group of related topics in detail. When one BASE24 manual presents a topic that has already been covered in detail in another BASE24 manual, the topic is summarized and the reader is directed to the other manual for additional information. Information has been arranged in this manner to be more efficient for readers who do not need the additional detail and at the same time provide the source for readers who require the additional information. This manual contains references to the following BASE24 publications:

- The ***BASE24 Base Files Maintenance Manual*** contains file maintenance information for the files used by more than one BASE24 product. In addition, this manual contains information on interchange file maintenance functions.
- The ***BASE24 Core Files and Tables Maintenance Manual*** contains file and table maintenance information for all core files and tables.
- The ***BASE24 Device Control Manual*** contains information on screens that are accessed from the Device Control Terminal (DCT).

- The ***BASE24 Refresh and Extract Operators Manual*** contains file maintenance information on the Extract and Refresh screens.
- The ***BASE24-atm Files Maintenance Manual*** contains additional information on file maintenance functions for the BASE24-atm screens.
- The ***BASE24-atm Settlement and Reporting Manual*** contains information on file maintenance functions for the Report File (RPT) screen.
- The ***BASE24-atm Diebold 1000-Series Device Support Manual*** contains additional information on file maintenance functions for the Operator Identification File (OIF).
- The device-specific BASE24-atm self service banking (SSB) manuals contain additional information on file maintenance functions for the SSB screens.
- The ***BASE24-billpay Billing Application Manual*** contains information on the BASE24-billpay billing application screens.
- The ***BASE24-billpay Tables Maintenance Manual*** contains information on the BASE24-billpay tables maintenance screens.
- The ***BASE24-card Reference Manual*** contains information about the screens available from the Card Management Product Menu.
- The ***BASE24-check auth SQL Tables Maintenance Manual*** contains table maintenance and function information for the screens accessed from the Check Authorization Product Menu.
- The ***BASE24-check auth SQL Database Manual*** contains SQL table descriptions and initial values for parameters configured in the Application Configuration Table (ACT).
- The ***BASE24 Remote Banking Customer Service Support Manual*** describes all of the customer service representative screens available from the CSRC entry on the Core Menu.
- The ***BASE24 Remote Banking Transaction Processing Manual*** describes the valid BASE24-telebanking and BASE24-billpay action codes.
- The ***BASE24-pos CRT Authorization and CRT Administration Manual*** contains file maintenance and function information for the BASE24-pos CRT Authorization and CRT Administration add-on products.
- The ***BASE24-pos Standard POS Device Support Manual*** contains information on file maintenance functions for the BASE24-pos Standard POS Device Handler process.
- The ***BASE24-pos Stored Value Support Manual*** contains file maintenance and function information for the BASE24-pos Stored Value add-on product.

- The ***BASE24-pos Hypercom Device Support Manual*** contains information on file maintenance functions for the Hypercom Device Handler process.
- The ***BASE24-pos Files Maintenance Manual*** contains information on file maintenance functions for the BASE24-pos screens.
- The ***BASE24-pos Settlement and Reporting Manual*** contains information on file maintenance functions for the POS Report Generator screen.
- The ***BASE24-pos Merchant Host Interface Manual*** contains information on file maintenance functions for the Merchant Host Interface process.
- The ***BASE24-pos VISA II Device Support Manual*** contains information on file maintenance functions for the VISA II Device Handler process.
- The ***BASE24-teller Files Maintenance Manual*** contains file maintenance information for the BASE24-teller screens.
- The ***BASE24-teller Settlement and Reporting Manual*** contains file maintenance information for the Teller Report Generator screen.
- The ***BASE24 Log Message Reference Manual*** contains information on the Log Message Configuration File (LMCF).
- The ***BASE24 IEP Configuration Manual*** contains information on the Destination File (DEST).
- The ***BASE24 ITS Kernel Files Maintenance Manual*** contains information on the files and functions found on the Kernel Product Menu.
- The interchange-specific documentation contains file maintenance information on interchange files.

This manual also contains references to the following NET24-XPNET publication:

- The ***NET24-XPNET Network Control Operations Guide*** contains file maintenance information on the NCS and XNI.

Software

This manual documents standard processing for all BASE24 release 6.0 compatible products and later releases. These products run under NET24-XPNET release 3.1.

Custom software modifications (that is, CSMs) may result in processing that differs from the material presented in this manual. The customer is responsible for identifying and noting these changes.

Manual Summary

The following is a summary of the contents of this manual.

“Conventions Used in This Manual” follows this preface and describes notation and documentation conventions necessary to understand the information in the manual.

Section 1, “Introduction,” provides a brief overview of the BASE24 menu structure and shows you how to move within the BASE24 user access system.

Section 2, “User Screens and Terminal Functions,” describes the organization and composition of the screens that give you access to BASE24 files, tables, and functions. It also defines the standard functions assigned to BASE24 function keys.

Section 3, “Logging On to the BASE24 User Access System,” shows you how to log on to the BASE24 system and how to use the BASE24 Logon screen.

Section 4, “Accessing BASE24 Menus and Screens,” describes the current product menu entries available from the BASE24 Virtual Menu and the file, table, and function screens accessible from the product menus.

Section 5, “Setting Up BASE24 User Access Security,” describes how to set up BASE24 security.

Section 6, “Audit Reports,” describes the reports used to track user authentication and user access and shows you how to initiate those reports.

Publication Identification


Three entries appearing at the bottom of each page uniquely identify this BASE24 publication. The publication date (for example, Dec-2009 for December, 2009) indicates the issue of the manual. The software release information (for example, R6.0v10 for release 6.0, version 10) specifies the software that the manual describes. The publication number (for example, BA-AE000-02 for the ***BASE24 User Security Manual***) appears on every page to assist readers in identifying the manual from which a page of information was printed. This information matches the document information on the copyright page of the manual.

1: Introduction

This section provides an introduction to the BASE24 user access system. It describes the two layers of menus by which you can access BASE24 screens and functions and shows you how to move within the BASE24 system using these menus. This section also provides you with a quicker alternate method for moving between BASE24 screens.

BASE24 User Access

The BASE24 user access system, shown schematically below, is an organized structure of menus, screens, and functions that allows you to monitor and control BASE24 processing.



Using these screens and functions, you can:

- Start and stop a BASE24 network and carry out other critical network operations.
- Perform refresh and extract functions.
- Change the text, severity, or routing information for log messages.
- Load configuration data to ATM, POS, and teller terminals and execute other device control commands.
- Perform network control operations, which include inquiring into and updating system configuration information.
- Read and update application files and tables.


- Peruse BASE24-atm reports.
- Generate BASE24-pos and BASE24-teller reports. (Reports for all other BASE24 products are generated from a TACL prompt or an OBEY file.)

To perform a function, you enter information on the applicable screen and press a function key. The information is then processed by BASE24 software on the HP NonStop computer.

The user access system provides user-defined security and logon requirements, which keep access to the BASE24 user access system secure. User access security is described in section 5.

BASE24 Menu Structure

The screens that allow you to monitor and control BASE24 processing are organized in multiple layers of menus that you can access from the BASE24 Logon screen. A menu is a list of screen options that you can select for display. This logical system of access is designed to help you locate the screen you want quickly and easily. The organization of BASE24 menus is shown on the next page and described on the pages following.



BASE24 Logon Screen

In order to access the BASE24 system, you must first log on to the system. Logon is accomplished using the BASE24 Logon screen. You must have security file records that give you access to the BASE24 system in order to log on to the system. Procedures for using the BASE24 Logon screen are provided in section 3.

BASE24 Virtual Menu

Once you have logged on to the BASE24 user access system, the first screen you normally see is the BASE24 Virtual Menu. The Virtual Menu displays all BASE24 products purchased by your organization to which you have been given access in your security records. Products are displayed in the order in which they have been added to your security records. Selecting an item on the Virtual Menu gives you access to one of the BASE24 product menus or direct access to a particular BASE24 screen or function if no product menu exists for the screen or function. Instructions on how to select Virtual Menu items are provided in section 4.

BASE24 Product Menus

BASE24 product menus display the files, tables, and functions required to maintain a BASE24 product. As with all BASE24 menus, only those files, tables, or functions to which you have been given access in your security records are displayed. Files, tables, and functions are displayed in the order in which they have been added to your security records. Detailed descriptions of each product menu and instructions for accessing files, tables, and functions from it are provided in section 4.

BASE24 Screens

Like BASE24 menus, BASE24 screens are organized logically to help you move easily within the BASE24 user access system. Each product menu entry gives you access to a screen or group of screens that you can use to interact with the selected file, table, or function. When you select a product menu item, the first screen to which you have access and which is associated with that file, table, or function is displayed. Other screens accessing the file, table, or function are numbered consecutively (though gaps have been left to facilitate future expansion) to allow

you to keep track of your location. Further information on screen organization and layout is contained in section 2. Brief descriptions of all screens accessible from BASE24 product menus are provided in section 4.

Moving to a New Screen

BASE24 menus are designed to allow you easy access to BASE24 screens. You move the cursor, using the **Tab** key, to the selected menu item and press the **F1** key. The first screen of the selected menu item that the user has access to is then displayed.


You can move within the BASE24 user access system more quickly by using the NEW PAGE, FILE DESTINATION, and NEW LOGICAL NETWORK ID fields located at the bottom of all BASE24 screens. Entering a destination identifier in one or more of these fields and pressing the appropriate function key allows you to move directly to a new screen within a file, table, or function; to a new file, table, or function; or to a new logical network. Remember, however, that you can move only to those screens, files, tables, and logical networks to which you have been granted access in your security records. Also, moving to a new logical network is not supported from screens that access SQL tables.

Step-by-step procedures for using the NEW PAGE, FILE DESTINATION, and NEW LOGICAL NETWORK ID fields are provided below and on the following pages. The location of these fields on BASE24 screens and the function keys used in conjunction with each field are shown in the illustrations accompanying these procedures.

Moving to a Specific Screen Within a File, Table, or Function

The NEW PAGE field allows you to move directly to a new screen within the file, table, or function you are currently accessing. Moving to a new screen can also be accomplished by paging forward or backward one screen at a time using the **F9** or **F11** keys (see section 2). However, the NEW PAGE field allows you to move as many screens forward or backward as you want within the current file, table, or function with just a few keystrokes.

The location of the NEW PAGE field on BASE24 screens and the function key used in conjunction with the field are depicted in the following illustration.




To move to a new screen, perform the following:

1. Tab to the NEW PAGE field.
2. Enter the number of the screen you want to access within the currently displayed file, table, or function.
3. Press the **F7** key. The screen you indicated is displayed.

Moving to a New File, Table, or Function

The FILE DESTINATION field allows you to move directly to a BASE24 file, table, or function without accessing a menu. Using the BASE24 menu structure, you normally move to a file, table, or function from the Virtual Menu, the appropriate product menu, or both. The FILE DESTINATION field provides a shortcut.

The location of the FILE DESTINATION field on BASE24 screens and the function keys used in conjunction with the field are depicted in the following illustration.



To access a new file, table, or function, perform the following:

1. Tab to the FILE DESTINATION field.
2. Enter the acronym of the file, table, or function you want to access. Valid acronyms and the file, table, or screen names they represent are listed under the topic “FILE DESTINATION Field Entries” later in this section.
3. Press the **F1** key if you are currently on the Logon screen, Virtual Menu, or a product menu.

OR

Press the **F16** key if you are currently on another BASE24 screen.

The first screen you have access to in the selected file, table, or function is displayed.


If you want to move simultaneously to a new logical network when you move to the new file, table, or function, enter a valid logical network ID in the NEW LOGICAL NETWORK ID field before pressing the **F16** key. See “Moving to a New Logical Network” on the following page.

Note: Currently, moving to a new logical network is not supported from screens that access Structured Query Language (SQL) tables.

Moving to a New Logical Network

The NEW LOGICAL NETWORK ID field allows you to move directly to a new logical network without returning to the Logon screen. This enables you to access a different database from the one in which you are currently working.

The location of the NEW LOGICAL NETWORK ID field on BASE24 screens and the function keys used in conjunction with the field are depicted in the following illustration.



To change logical networks, perform the following:

1. Tab to the NEW LOGICAL NETWORK ID field.
2. Enter the name of the logical network (for example, PRO1) you want to access.
3. Press the **F13** or **F16** key. You are moved to the selected logical network.

If you want to move simultaneously to a new file, table, or function within the new logical network, enter a valid file, table, or function acronym in the FILE DESTINATION field before pressing the **F13** or **F16** key in step 3. Valid acronyms and the file names they represent are listed under the topic “FILE DESTINATION Field Entries” later in this section.

Note: Currently, moving to a new logical network is not supported from screens that access Structured Query Language (SQL) tables.

Your institution can set up security records in two ways. Two or more logical networks can share security records, allowing you the same access privileges and restrictions within each logical network; or each logical network can maintain its own security records, allowing your institution to establish different access privileges and restrictions for you within each logical network.

If your security record is shared by two or more logical networks, you are able to move to a new logical network as described above. If you have a separate security record for each logical network, you must have the same alias and password in each of your security records to move to a new logical network as described above. Otherwise, you must return to the BASE24 Logon screen to change logical networks.

FILE DESTINATION Field Entries

The acronyms you can enter in the FILE DESTINATION field and the file, table, or screen names they represent are shown in the following table. The BASE24 product menu or BASE24 Virtual Menu on which the file, table, or function appears is also shown. The table is arranged alphabetically by acronym.

Acronym	File, Table, or Screen Name	Menu
ACNF	ACI Standard Device Configuration File	POS
ACT	Application Configuration Table	Retail Configuration
ACTA	Refund Activity by Address screen	Refunds User
ACTF	Refund Activity by Refund screen	Refunds User
ACTI	Refund Activity by ID screen	Refunds User
ACTP	Refund Activity by Purchase screen	Refunds User
ADMN	Administrative Card File	POS
AORF	Assign/Object Relationship File	Kernel/IEP
APCF	Acquirer Processing Code File	Base
APRF	Assign/Process Type Relationship File	Kernel/IEP
ARF	Account Routing File	Base
ARSP	ACI Standard Device Response File	POS
ASGN	Assign File	Kernel/IEP
AST	Authorization Selection Table File	POS

Acronym	File, Table, or Screen Name	Menu
ART	Authorization Routing screen	Retail Configuration
ATD	BASE24-atm Terminal Data files	ATM
ATT	Account Type Table File	Base
AWB	Assign Warmboot screen	Kernel/IEP
BKAV	Bank Transaction Advice Table	Billpay
BKBR	Bank Branch Table	Billpay
BKNT	Bank Notice Table	Billpay
BLG	Billing Group Table	Billpay
BLRT	Billing Rate Table	Billpay
BLTY	Billing Type Table	Billpay
BSF	Bin Sort File	ATM
CAF	Cardholder Authorization File	Base
CAPF	Card Authorization Parameters File	POS
CART	Check Authorization Routing Table File	POS
CATT	Customer Allowed Transaction Table	Core
CBPT	Customer Billpay Table	Billpay
CCF	Corporate Check File	ATM
CCIF	Customer/Cardholder Information File	Customer Service
CCS	Configuration Control screen	Kernel/IEP
CHF	Card History File	POS
CIS	Customer Information screens	Customer Service
CLPT	Cleanup Configuration Table	Billpay

Acronym	File, Table, or Screen Name	Menu
CLST	Cardholder List Function	Card
CMF	Card Management Function	Card
CMTS	Comments screen	Refunds User
COF	Card Operator Function	Card
CPF	Card Prefix File	Base
CRAT	Customer Retailer Activity screen	Frequent Shopper User
CRED	Credibility History screen	POS
CRTA	CRT Administration Maintenance screens	POS
CRUF	CRT Authorization Retailer Usage File	POS
CSEC	CRT Authorization Security File	POS
CSF	Check Status File	ATM
CSRC	Customer Service Representative screens	Core
CSTP	Customer Service Transaction Perusal	Customer Service
CSTT	Customer Table	Core
CUST	Customer Information screens	Check Authorization User
CVND	Customer Vendor Table	Billpay
DADR	Refund Check Address Update screen	Check Disbursements User
DAID	Refund Check Activity by ID screen	Check Disbursements User

Acronym	File, Table, or Screen Name	Menu
DANM	Refund Check Activity by Name screen	Check Disbursements User
DARC	Check Activity by Refund Check Info screen	Check Disbursements User
DARI	Check Activity by Refund Info screen	Check Disbursements User
DASI	Refund Check Activity by Store Info screen	Check Disbursements User
DBG	Debug screen	Kernel/IEP
DCCD	Dynamic Currency Conversion Data File	Base
DCT	DCT Menu	Operator
DEMO	Demographics Maintenance screen	Frequent Shopper User
DEST	Destination File	Kernel/IEP
DGLE	General Ledger Event screen	Check Disbursements User
DMCK	Manual Check Maintenance screen	Check Disbursements User
DPND	Dependents Maintenance screen	Frequent Shopper User
EACT	External Authorization Configuration screen	Retail Configuration
ECF	Extract Configuration File	Base
EMF	External Message File	Base

Acronym	File, Table, or Screen Name	Menu
EMT	Extended Memory Table File	Kernel/IEP
EORF	EMT/Object Relationship File	Kernel/IEP
EPRF	EMT/Process Type Relationship File	Kernel/IEP
ERF	Exchange Rate File	Base
ESF	Event Suppression File	Kernel/IEP
EWB	EMT Warmboot screen	Kernel/IEP
EXTR	Extract screens	Operator
FCF	File Control File	Core
FSCS	Funding Scheme Configuration screen	Retail Configuration
HCF	Host Configuration File	Base
HIST	Billpay History Table	Billpay
HMBF	Host Mail Box File	Mail
HPCF	Hypercom Configuration File	POS
HPTC	Hypercom T7 Configuration File	POS
ICF	Interchange Configuration File	Base
ICFE	Enhanced Interchange Configuration File	Base
IDF	Institution Definition File	Base
IDST	ID Status/Maintenance screen	Frequent Shopper User
IDTD	ID Type Configuration screen	Retail Configuration
IMTF	Internal Message Translation File	Core
IPCF	Issuer Processing Code File	Base
IRCF	Institution Routing Configuration File	Core

Acronym	File, Table, or Screen Name	Menu
ISF	Interface Security File	Core
ITLF	ITS Transaction Log File	Core
JID	Joined ID Status/Maintenance screen	Frequent Shopper User
KEYA	Key Authorization File	Base
KEYD	Derivation Key File	Base
KEYF	Key File	Base
KEYI	EMV ICC Key File	Base
KEY6	KEY 6 File	Base
LCF	Log Configuration File	Core
LCT	Check Authorization Limits Configuration screens	Retail Configuration
LMCF	Log Message Configuration File	Operator
LNCF	Logical Network Configuration File (LCONF)	Base
LPF	Log Permission Process Partition File	Kernel/IEP
LWB	LCONF Warmboot screen	Kernel/IEP
MBAF	Mail Box Address File	Mail
MBF	Mail Box File	Mail
MCNF	Merchant Terminal Configuration File	POS
MERC	Merchant Interface Configuration screen	Retail Configuration
MHCF	Merchant Host Configuration File	POS
MHIS	Move ID History Maintenance screen	Frequent Shopper User
MREG	MHI Regulation E File	POS

Acronym	File, Table, or Screen Name	Menu
MRF	Multiple Referrals screen	POS
MRSP	Merchant Terminal Response Display File	POS
MSG	Error Message Configuration screens	Retail Configuration
MTCF	Merchant Totals Configuration File	POS
NAMS	Frequent Shopper Name Search screen	Frequent Shopper User
NBF	No Book File	Teller
NCS	Network Control Supervisor screen	Operator
NCSP	Network Control Supervisor Profile File	Base
NEG	Negative Card File	Base
NNF	National Negative Card File	POS
NSEA	Refunds Name Search screen	Refunds User
OBJ	Object File	Kernel/IEP
OIF	Operator Identification File	ATM
OLT	Online Transaction screen	POS
ORF	Override Response File	Teller
PBF	Positive Balance File	Base
PCDF	Processing Code Definition File	Core
PCDU	Postal Code Update screen	Retail Configuration
PDF	Processing Code Description File	Base
PHIS	Purchase History screen	Frequent Shopper User
PIT	Personal Information Table	Core

Acronym	File, Table, or Screen Name	Menu
PORF	Process/Object Relationship File	Kernel/IEP
PRDF	POS Retailer Definition File	POS
PRE	Prefix File Build Utility screen	Base
PRF	POS Referral File	POS
PRG	POS Report Generator screen	POS
PRO	Process File	Kernel/IEP
PTD	BASE24-pos Terminal Data files	POS
PTF	Process Type File	Kernel/IEP
PTLF	POS Transaction Log File	POS
PWB	Param Warmboot screen	Kernel/IEP
RATD	Rating Configuration screens	Retail Configuration
RATE	Rate Table	Billpay
RATG	Rate Group Table	Billpay
RCPT	Receipt File	ATM
REFR	Refresh screens	Operator
RETL	Retailer Configuration screens	Retail Configuration
RLCT	Refund Limits Configuration screen	Retail Configuration
RPT	ATM Report screens	ATM
RTBL	Routing Table File	POS
RTRY	Retry Table	Billpay
RTXT	Response Text Table	Billpay
SCM	Source Class Map File	Kernel/IEP

Acronym	File, Table, or Screen Name	Menu
SCS	Server Control screen	Kernel/IEP
SCT	Server Class Type File	Kernel/IEP
SDT	Summarized Detail Perusal screens	Check Authorization User
SEC	Security File	Base
SMA	Send Mail Terminal screen	Mail
SPAS	Address Swap screen	Refunds User
SPF	Stop Payment File	Base
SPRF	Server Class Type/Process Relationship File	Kernel/IEP
STAT	Status screen	Kernel/IEP
STF	Switch Terminal File	Base
STOR	Store Configuration screens	Retail Configuration
STPD	State/Province Configuration screen	Retail Configuration
SURF	Surcharge File	Base
SVHF	Stored Value History File	POS
SVPT	Service Provider Table	Billpay
TCF	Transaction Code File	Base
TDT	Transaction Perusal Detail screen	Check Authorization User
THCF	Transaction History Configuration File	Core
TKN	Token File	Base
TLF	Transaction Log File	ATM

Acronym	File, Table, or Screen Name	Menu
TRC	Trace Control screen	Kernel/IEP
TRF	Terminal Receipt File	ATM
TRPT	Teller Report Generator screen	Teller
TTDF	Teller Terminal Data File	Teller
TTF	Teller Transaction File	Teller
TTLF	Teller Transaction Log File	Teller
TTSC	Transaction Type By Source Code Table	Core
UAF	Usage Accumulation File	Base
VADJ	Value Adjustment screen	Frequent Shopper User
VBUD	Vendor Budget Category Table	Billpay
VCD	VRU Configuration Data	Core
VELO	Velocity by ID screens	Check Authorization User
VNDB	Vendor Branch Table	Billpay
VNDM	Vendor Mask Table	Billpay
VNDR	Vendor Table	Billpay
VREF	Mail Refund Transactions screen	Refunds User
VSAL	View Sales History screen	Refunds User
VVT	VISA II Terminal and Configuration Maintenance File	POS
WHFF	Warning/Hold/Float File	Teller
XNI	X.25 Network Inquiry screen	Operator


ACI Worldwide, Inc.

2: Screens and Terminal Functions

This section describes the user access screens and terminal functions through which you can monitor and control BASE24 processing. It covers user screen organization, BASE24 screen types, help screens, and screen messages. This section also defines the standard function keys for BASE24 screens.

BASE24 Screen Organization

All BASE24 screens are constructed in two layers: a base layer and an overlay layer. The base layer contains heading and functional information. The information on the base layer generally remains the same for all screens within a file, table, or function. The overlay layer contains fields unique to that particular screen. This layered construction is illustrated on the following page, using Institution Definition File (IDF) screen 1 as an example.



Base Layer

The base layer of a BASE24 screen displays the following information (from left to right, top to bottom of the screen):

- The name of the system, which is BASE24.
- The name of the product menu on which the screen is listed, in this case BASE (the Logon screen and most menus have ADMN in this position).
- The name, often abbreviated, of the file, table, or function being accessed, in this case INSTITUTION FILE (for Institution Definition File).
- The logical network, represented here as LNET.
- The date (YY/MM/DD) and time (HH:MM).
- The number of the screen in relation to the total number of screens in the file, table, or function, in this case 01 OF 42.
- The key fields (for example, FIID and FI-NAME).
- The information line, identifying the operator who last changed the record or row, the action taken, and the date and time the action occurred.

The RECORD LAST CHANGED field displays the date and time, in YY/MM/DD HH:MM format, an action was last taken on this record or row.

The BY USER field displays the group number and user number of the operator who last changed the record or row. If the record or row was last added or changed from a remote banking device, the group number and user number will display all zeros. For more information on group and user numbers, refer to section 5.

The action that occurred (that is, an addition or change) is displayed to the right of the BY USER field value.

- The NEW PAGE, FILE DESTINATION, and NEW LOGICAL NETWORK ID fields.
- A summary of function definitions for important function keys, in this case F12-HELP.

The base layer of the screen generally remains the same for all screens within a file, table, or function.

The NEW PAGE, FILE DESTINATION, and NEW LOGICAL NETWORK ID fields are used in combination with several function keys to move directly from one screen, file, or table to another and to change logical networks. This feature allows you to move more quickly and directly through the BASE24 user access system than is possible when selecting items from menus. Use of these fields is explained in detail in section 1.

Overlay Layer

The overlay layer of a BASE24 screen displays the fields unique to that particular screen. Four types of fields can be displayed in the overlay:

- System-protected, display fields display information for you to view but do not allow you to enter data. These fields generally appear dimmer on the screen than those fields in which you can enter data.
- Entry, no-default fields display information for you to view and also allow you to enter data. The number and type of characters you can enter is restricted for each field. The FI-NAME field on IDF screen 1 is of this type.
- Entry, default-displayed fields are identical to entry, no-default fields but contain information, called a default value, when they are first displayed on the screen. You can enter data over the default value, in which case the system processes the entered data. If you blank out the default value using the space bar, blanks (if the field is alphanumeric) or zeros (if the field is numeric) are entered into the system. If you do not make an entry, the system uses the default value. The INSTITUTION ID NUMBER field on IDF screen 1, which contains the default value 00000000000, is of this type.
- Cursor fields indicate where the cursor must be positioned in order to execute specified commands. This type of field may display a default value and allow data entry to specify more exactly the command option desired.

BASE24 Screen Types

There are two types of screens that can be accessed from BASE24 product menus: those used to maintain and peruse files or tables and those used to execute commands.

File and Table Maintenance Screens

File and table maintenance screens display and allow you to update information maintained in the files and tables required for BASE24 processing. Files and tables contain the parameters and customer information required for the system to operate. This type of screen is composed almost exclusively of data entry and display fields. (Transaction log file screens contain only display fields.)

Institution Definition File (IDF) screen 1 (shown below), for example, displays and allows you to update information about each customer-servicing, card-issuing, and terminal-owning financial institution or service provider in the logical network. The fields on this screen display the financial institution identifier (FIID); the state, county, and country in which the institution is located; the institution's phone number; and the fully-qualified HP NonStop file names (for example, \$DATA.PRO1DATA.NEG) of the files in which the institution maintains authorization data (for example, NEG, UAF, etc.). Data can be entered in all fields on this screen.

```

BASE24-BASE  INSTITUTION FILE          LLLL          YY/MM/DD  HH:MM  01 OF 45

                FIID:                FI-NAME:

STATE:    0   COUNTY:    0   COUNTRY:  840   PHONE:
INSTITUTION ID NUMBER:  000000000000   REFRESH GROUP:

                FILE NAMES:

                NEG:
                UAF:
                CAF:
                SPF:
                PBF1:
                PBF2:
                PBF3:

***** BASE24 *****
NEW PAGE:          FILE DESTINATION:          NEW LOGICAL NETWORK ID:
                  F12-HELP

```

Operator Command Screens

Operator command screens are designed for the execution of commands rather than for the display and entry of data. They are composed predominantly of cursor fields, though they also contain a few data entry fields for specifying the file, table, process, or device on which the command is to be executed. Command screens allow you to perform a variety of network functions, including starting and stopping the network, inquiring into the status of various processes, altering log messages, generating reports, and down loading configuration and key information to terminal devices.

DCT screen 4, shown below, is an example of an operator command screen.

```
BASE24-PCT      PROCESS CONTROL COMMANDS LLLL      YY/MM/DD  HH:MM  04 OF 46

                REINITIALIZATION COMMANDS

                TYPE: 9501
PRODUCT INDICATOR:
                _ ALL
                LOGO:
                _ FI-ID
PROCESS NAME:
                _ PROCESS

***** BASE24 *****
NEW PAGE:          FILE DESTINATION:          NEW LOGICAL NETWORK ID:
PLACE CURSOR IN FRONT OF DESIRED FUNCTION AND DEPRESS F1      F12-HELP
```


BASE24 Screen Documentation


Specific information about each field displayed on BASE24 screens is provided in the appropriate BASE24 or NET24 manual. These include the following:

- *BASE24 Device Control Manual*
- *BASE24 Refresh and Extract Operators Manual*
- BASE24 Logical Network Configuration File Manual
- BASE24 product-specific files and tables maintenance manuals
- BASE24 device support manuals
- BASE24 add-on product manuals
- *NET24-XPNET Network Control Operations Guide*

The illustrations on the following two pages show the relationship between Virtual Menu items and the manuals that document the items.

Field descriptions contained in these and other BASE24 manuals provide information on how the field is used in BASE24 processing and instructions on how to correctly enter data in the field. In addition, for files or tables maintenance and some operator command screens, standard captions follow each description: Field Length, Required Field, Default Value, and Data Name or Column Name. These captions are explained following the illustrations.





Field Length

This caption specifies the number and type of characters you can enter in the field. When an entry consisting of the maximum number of allowed characters is entered in a field, the cursor automatically tabs to the first position of the next field. When an entry consisting of less than the maximum number of allowed characters is entered in a field, the operator must press the **Tab** key to move the cursor to the first position in the next field.

There are three character types: alphanumeric, numeric, and alphabetic. Alphanumeric characters include all the letters, numbers, and symbols on the terminal keyboard. Numeric characters are all the numbers on the keyboard. Alphabetic characters are the letters of the alphabet.

This caption also indicates when a field is system-protected, in which case the number and type of characters are omitted.

Required Field

This caption indicates whether you must enter a value in the field in order for the BASE24 user access system to read a record or row, or validate a record or row prior to record or row addition, deletion, or updating. Required fields consist of all key fields and those fields highlighted by the VALIDATE function (performed by pressing the **F1** key) when you fail to enter data in them.

Default Value

This caption specifies the default value displayed in the field when you first access the screen. The default value is entered into the BASE24 user access system if you do not enter data in the field. If there is no default value, the phrase “No default value” appears after this caption.

Data Name

This caption specifies the Enscribe Data Definition Language (DDL) name of the field displayed on the screen. This Enscribe DDL name is how the field is defined and referenced by the BASE24 transaction processing software. Systems programmers in your institution may require the Enscribe DDL name of a field in case of processing errors or customer-specific code changes (RPQs). If a screen field has multiple corresponding Enscribe DDL names, each one is listed after this caption. If a screen field does not have a corresponding Enscribe DDL field name, “Not applicable” appears after this caption.

Column Name

The caption specifies the Structured Query Language (SQL) column name of the field displayed on the screen. This SQL column name is how the field is defined and referenced by the BASE24 transaction processing software. Systems programmers in your institution may require the SQL column name of a field in case of processing errors, customer-specific code changes (RPQs), or for creating user-defined SQL reports or queries. If a screen field has multiple corresponding SQL column names, each one is listed after this caption. If a screen field does not have a corresponding SQL column name, “Not applicable” appears after this caption.

Help Screens

The BASE24 user access system provides help screens to assist you in performing system functions. There are two types of help screens: menu help screens; and file, table, or function help screens.

Menu Help Screens

Menu help screens, which can be accessed from most BASE24 menus, display a brief description of each menu item. These screens help you identify what files, tables, or functions can be accessed from that menu. When a help screen is displayed, it replaces the overlay of the screen from which it is accessed.

A sample menu help screen is shown below. The sample defines the menu items on the Base Product Menu.

```

BASE24-ADNM  MENU                                LLLL          YY/MM/DD  HH:MM  01 OF 01

  ARF  ACCOUNT ROUTING FILE                      ATT  ACCOUNT TYPE TABLE SCREEN
  CAF  CARDHOLDER ACCOUNT FILE                  CPF  CARD PREFIX FILE
  ECF  EXTRACT CONFIG FILE                       EMF  EXTERNAL MESSAGE FILE
  HCF  HOST CONFIGURATION FILE                   ICF  INTERCHANGE CONFIGURATION
  IDF  INSTITUTION DATA FILE                    KEYA KEY AUTHORIZATION FILE
  KEYF  KEY FILE                                 NCSP NCS SECURITY PROFILE FILE
  NEG  NEGATIVE CARD FILE                       PBF  POSITIVE BALANCE FILE
  PRE  PREFIX FILE BUILD UTILITY                 SEC  SECURITY FILE
  SPF  STOP PAYMENT FILE                        STF  SWITCH TERMINAL FILE
  SURF  SURCHARGE FILE                          TKN  TOKEN FILE
  TSCF  TERM SUPPORT CONFIG FILE                 UAF  USAGE ACCUMULATION FILE
  APCF  ACQ PROCESSING CODE FILE                 ERF  EXCHANGE RATE FILE
  ICFE  ENHANCED INTERCHANGE CONFIG              IPCF ISSUER PROCESSING CODE FILE
  KEYI  EMV KEY FILE                             LNCF LOGICAL NET CONFIG FILE
  PDF  PROCESSING CODE DESCR FILE                TCF  TRANSACTION CODE FILE

***** BASE24 *****
                                FILE DESTINATION:
  ANY FUNCTION KEY EXCEPT SF9-SF16, F10, OR F16 RETURNS. F10 PRINTS AND RETURNS

```

File and Table Help Screens

File and table help screens, which can be accessed from most BASE24 file, table, or function screens, display the functions assigned to the function keys for the screen from which they are accessed. Abbreviated lists of function key definitions are displayed in the base layer at the bottom of all BASE24 screens.

When a help screen is displayed, it replaces the overlay of the screen from which it is accessed. The help screen is headed, STANDARD FILE MAINTENANCE FUNCTION FOR KEYS 6520/6530 (3270). Beneath this heading is a list of the function keys and their assigned functions for the particular screen. The function keys not encompassed by parentheses are for 6520/6530 terminals. The function keys encompassed by parentheses are for IBM 3270 terminals.

The help screen accessible from most BASE24 screens is shown below. The screen is shown as it is displayed when accessed from Institution Definition File (IDF) screen 1. The function assignments on this screen are standard throughout the BASE24 user access system, though a few screens use slightly different functions and, as a result, display help screens that differ from the one shown below. Nonstandard function key assignments are noted in the BASE24 or NET24 manuals documenting the applicable screens. Complete descriptions of standard BASE24 function key assignments are provided under the topic “Function Keys” later in this section.

```
BASE24-BASE  INSTITUTION FILE          LLLL          YY/MM/DD  HH:MM  01 OF 45
```

```

          FIID:          FI-NAME:
STANDARD FILE MAINTENANCE FUNCTION FOR KEYS 6520/6530 (3270)
          F1 (ENTER) - VALIDATE DATA
          F2 (PF2)  - READ RECORD
          F3 (PF3)  - ADD RECORD
          F4 (PF4)  - DELETE RECORD
          F5 (PF5)  - UPDATE RECORD
          F6 (PF6)  - READ NEXT RECORD
          F7 (PF7)  - GOTO NEW PAGE
          F8 (PF8)  - CLEAR SCREEN
          F9 (PF9)  - NEXT SCREEN
          F10 (PF10) - PRINT SCREEN
          F11 (PF11) - PREVIOUS SCREEN
          F12 (PF12) - DISPLAY HELP SCREEN
          F13 (PF13) - CHANGE CURRENT LOGICAL NET
          F16 (PF16) - EXIT OR GOTO FILE
          SF16 (PA2) - LOGOFF

```

```

***** BASE24 *****
NEW PAGE:          FILE DESTINATION:          NEW LOGICAL NETWORK ID:
ANY FUNCTION KEY EXCEPT SF9-SF16, F10, OR F16 RETURNS. F10 PRINTS AND RETURNS

```

Screen Messages

Additional help in interacting with the BASE24 user access system is provided by screen messages. These messages are displayed at the bottom of BASE24 screens, as shown in the illustration below. Messages alert you to errors in data entry or commands, indicate special screen requirements, and provide additional information about a screen or screen entry. Each message provides a short explanation of the condition that caused it and, if applicable, a remedy.

BASE24-BASE	INSTITUTION FILE	LNET	YY/MM/DD	HH:MM	01 OF 42
FIID:		FI-NAME:			
STATE: 0	COUNTY: 0	COUNTRY: 840	PHONE:		
INSTITUTION ID NUMBER: 0000000000		REFRESH GROUP:			
FILE NAMES:					
NEG:					
UAF:					
CAF:					
SPF:					
PBF1:					
PBF2:					
PBF3:					
*****BASE24*****					
NEW PAGE:	FILE DESTINATION:	NEW LOGICAL NETWORK ID:			
	F12-HELP				

Screen message
display area

Function Keys

In order to display screens or enter data in fields, you must press various keyboard keys on the terminal. Function keys allow you to perform various functions, such as reading a record or row, adding or deleting a record or row, and updating a record or row.

The first column of a function key table shows the name of the BASE24 or NET24 key. The second column describes the function that the key performs.

The function keys described on the following pages are used with many BASE24 screens. However, a number of screens do not allow use of some of these function keys, and on other screens many of these keys are assigned different functions. Exceptions to the standard definitions that follow are discussed in the section of the appropriate BASE24 or NET24 manual dealing with the specific screen in question. If no exceptions are noted, you can assume that these standard definitions apply.

Key	Description
F1	VALIDATE DATA — Functions differently depending on the type of screen. For file and table maintenance screens, this key checks the data currently displayed on the screen for errors. If the data is error-free, you can use it to read records or rows, or perform adds, deletes, and updates. If an entry is invalid or missing, the field is highlighted and an error message is displayed indicating the information that needs to be changed or added. <i>Continued on the following page</i>

Key	Description
F1 <i>continued</i>	On the BASE24 Logon screen, Virtual Menu, and product menus (except the DCT Menus), this key moves you to the file or table specified in the FILE DESTINATION field. If a file or table is not specified in the FILE DESTINATION field, this key moves you to the next menu or to the file or table at which the cursor is positioned on the screen. On the BASE24 Logon screen, this key also moves you to the logical network specified in the LOGICAL NET field. On the Refund User Menu and the Frequent Shopper User Menu, this key moves you to the function screen specified in the Command field. For operator command screens, this key executes the specified command. For these screens, this key is defined as ENTER DATA.
F2	READ RECORD — Reads a record from a file or a row from a table. The record or row displayed is the one you specify in the key field(s).
F3	ADD RECORD — Adds a record to a file or a row to a table. The record or row added consists of the values displayed on the current screen page in addition to those on any other screen pages for that file record or table row. You cannot add a record or row that already exists.
	On the Refund User Menu, this key displays the previous screen or menu.
F4	DELETE RECORD — Deletes a record from a file or a row from a table. The record or row deleted consists of the values displayed on the current screen page in addition to those on any other screen pages for that file record or table row. You must read the record or row before you can delete it. You cannot delete a record or row that does not already exist.
F5	UPDATE RECORD — Changes a record that already exists in a file or a row that already exists in a table. You must read the record or row before updating it. The data to be changed must be entered on the screen. You cannot update a record or row that does not already exist.

Key	Description
F6	READ NEXT RECORD — Reads the next record from a file or the next row from a table. You can perform this function even when data has not been entered on the screen. When using this function with customer files (Cardholder Authorization File, Negative Card File, Positive Balance File, Stop Payment File, and Usage Accumulation File), you must specify the FIID of the financial institution whose records you want to access. For all of the above files (except the Positive Balance File), this function reads the next record until 50 attempts have been made without an FIID match. At this point, a message is displayed, prompting you to continue reading the next record or to select a new function. For the Positive Balance File, this function reads the next record until the last record in the file is reached. When using this function with customer tables (Customer Table and Customer Allowed Transaction Table), you can read only rows to which you have FIID security access. For the Customer Table, this function reads the next row until 10 consecutive attempts have been made without an FIID match. At this point, an informational message is displayed indicating that you do not have security access to the rows you have been attempting to read and you are prompted to read the next row. For the Customer Allowed Transaction Table, an error message is displayed each time you attempt to read a row without an FIID match.
F7	GOTO NEW PAGE — Moves you to another screen in the current file record or table row. You must identify the screen you want to display in the NEW PAGE field. You must also have security access to the new screen. On the DCT Menu, this key moves you to the function screen identified by the number displayed in the NEW PAGE field.

Key	Description
F8	CLEAR SCREEN — Clears all fields in which you have entered data on the current screen, replacing them with spaces or default values. This function also clears all fields on other screens in the current file or table. Note: If you perform an addition or update after executing this function, the record or row is added or updated. Be sure not to inadvertently delete data by performing an addition or update after clearing a screen.
F9	NEXT SCREEN — Displays the next screen of the current file or table. If you are on the last screen of the file or table, this function displays the first screen. On most product menus, this function key displays the next page of product selections, if more than one page of entries exist. Most product menus can have up to three pages of selection entries. This key is not used on the Frequent Shopper Product Menu or the Refund Product Menu.
F10	PRINT SCREEN — Sends the screen currently displayed for printing to the spooler location indicated on the Logon screen.
F11	PREVIOUS SCREEN — Displays the previous screen of the current file or table. If you are on the first screen of the file or table, this key displays the last screen. On most product menus, this function key displays the previous page of product selections, if more than one page of entries exist. Most product menus can have up to three pages of selection entries. This key is not used on the Frequent Shopper Product Menu or the Refund Product Menu.
F12	DISPLAY HELP SCREEN — Displays the help screen for the current screen. The help screens for file maintenance, table maintenance, and function screens list the functions performed by the function keys on that particular screen. On product menus, the help screen provides the full descriptive name for each file, table, or function acronym selection displayed on the menu.

Key	Description
F13	CHANGE CURRENT LOGICAL NET — Changes the logical network to the one specified in the NEW LOGICAL NETWORK ID field. If a file, table, or function is also specified in the FILE DESTINATION field, this function moves you to the specified file, table, or function in the specified logical network. Note: This function is not currently supported on screens that access Structured Query Language (SQL) tables.
F16	EXIT OR GOTO FILE — Displays the previous screen or menu. If you are working in a file, table, or function when you perform this function and you accessed this file, table, or function from the product menu, the applicable product menu is displayed. If you are working in a file, table, or function and you accessed this file, table, or function directly from the Logon screen or if you are using a product menu, the Virtual Menu is displayed. If you are using the Virtual Menu, the Logon screen is displayed. If you perform this function from the Logon screen, the Logon screen is displayed again. This function can also be used to move you to a new logical network[*], or to a new file, table, or function. To move to a new logical network, enter the network name in the NEW LOGICAL NETWORK ID field. To move to a new file, table, or function, enter the appropriate file, table, or function acronym in the FILE DESTINATION field. See section 1 for more information on using these fields. [*]Moving to a new logical network is not supported if you are currently accessing an SQL table maintenance screen.

Key	Description
Shift-F16	LOGOFF — Logs you off the BASE24 user access system. If you are currently accessing a screen, this function returns you to a blank Logon screen. If you are currently accessing a BASE24 menu or the Logon screen, this function either redisplay the Logon screen or returns you to the TACL prompt, depending on how the terminal is configured. Note: A hyphen connecting two keys indicates the keys are pressed simultaneously (for example, Shift-F16 indicates the Shift and F16 keys are pressed simultaneously).

3: Logging On to the BASE24 User Access System

In order to access BASE24 menus and screens, you must log on to the BASE24 user access system. Logon is accomplished using the BASE24 Logon screen. The BASE24 Logon screen limits BASE24 user access system access to users who have proper security clearance, which is established in the BASE24 security files. See section 5 for a detailed explanation of BASE24 security.

On many terminals, the BASE24 Logon screen is displayed whenever the terminal is not in use. On other terminals, however, the TACL prompt is displayed. To call up the BASE24 Logon screen from the TACL prompt, move to the subvolume containing the GOAFT obey file (the control subvolume), type O GOAFT at the TACL prompt, and press the **Return** key. This executes a standard BASE24 obey file that brings up the user access system.

This section shows you how to log on to the BASE24 system using the BASE24 Logon screen. It shows you an illustration of the BASE24 Logon screen, describes all fields displayed on the BASE24 Logon screen, and provides detailed instructions on how to use the BASE24 Logon screen.

BASE24 Logon Screen Fields

The BASE24 Logon screen is shown below, followed by descriptions of its fields. You must enter data in at least three of these fields—USER NAME, PASSWORD, and LOGICAL NET—in order to gain access to the BASE24 system.

```

BASE24-ADMN  LOGON                                YY/MM/DD  HH:MM  01 OF 01

                P L E A S E   L O G   O N

USER NAME:                PASSWORD:                LOGICAL NET:

      BBBBBBBB      AAAA      SSSSSS      EEEEEEEE      22222222      4444
      BB      BB      AA      AA      SS      EE      22      44      44
      BB      BB      AA      AA      SS      EE      22      44      44
      BBBBBBBB      AAAAAAAAAA      SSSSSS      EEEEEEEE      22222222      44444444
      BB      BB      AA      AA      SS      EE      22      44
      BB      BBB      AA      AA      SS      EE      22      44
      BBBBBBBB      AA      AA      SSSSSS      EEEEEEEE      22222222      44

      SCREEN PRINTER: $S.#HOLD
      CHANGE PASSWORD (Y/N): N
      NEW PASSWORD:                (TAKES EFFECT ON NEXT LOGON)

***** BASE24 *****
      FILE DESTINATION:
F1-ENTER DATA      F10-PRINT                F16-EXIT      SF16-LOGOFF

```

USER NAME — The name that uniquely identifies you to the BASE24 system. This name must match your alias in the Security File (SEC) or access to BASE24 system is denied.

Normally, your supervisor gives you your user name. You must have security clearance under an identical user name for all logical networks you want to access, if you want to access a different logical network without logging on again.

Field Length:	1–16 alphanumeric characters
Required Field:	Yes
Default Value:	None
Data Name:	Not applicable

PASSWORD — Your password. The BASE24 system requires each user to select a confidential password to ensure that user names are not employed by unauthorized individuals.

As you enter each character of this field, the cursor moves one position to the right; however, as a security precaution, the characters you enter are not displayed on the screen.

If an attempt to log on to the BASE24 system fails because you entered your password incorrectly, enter your password again; you do not need to space over the incorrect password because the BASE24 system clears this field with every logon attempt.

The first time you try to log on with a new user name, you must enter the initial password provided by your supervisor. You must then enter a new password via the CHANGE PASSWORD (Y/N) and NEW PASSWORD fields.

If you forget your password, contact your supervisor. The supervisor will change your password to a temporary value which will be provided to you. Enter this value in the PASSWORD field.

If your institution has implemented complex passwords since the last time that you logged on and your current password does not meet the new requirements, you will receive the message “PASSWORD REQUIRES CHANGE, COMPLEXITY REQUIREMENTS NOT MET” when you attempt to log on. Follow the procedure described under the topic “Changing Your Password” in this section for entering a password that meets the new complexity requirements. Be sure to re-enter your existing password in the PASSWORD field.

Note: An institution can set a maximum number of consecutive failed logon attempts allowed via the MAX-LOGON-ATTEMPTS param in the LCONF. If a user attempts to log on to the BASE24 system the number of times specified in this param and fails with each consecutive attempt, the system locks out the user. See section 5 for information on how to reinstate a locked out user.

Field Length:	1–8 alphanumeric characters
Required Field:	Yes
Default Value:	None
Data Name:	Not applicable

LOGICAL NET — The logical network you want to access. Your entry in this field (for example, PRO1) determines the database and processes accessible to you after you have logged on. If you are not sure which database to access, contact your supervisor.

You can change the logical network after logon has been completed as long as you have an identical user name and password in the other network and you are not currently accessing an SQL table maintenance screen.

Field Length: 1–4 alphanumeric characters
Required Field: Yes
Default Value: None
Data Name: Not applicable

SCREEN PRINTER — The location to which screen images are sent for printing when you perform the PRINT SCREEN function (using the **F10** key). You can change the printer location by entering a new name over the letters HOLD in the default value \$S.#HOLD. The new name can be up to 12 characters long.

The first character in this field must be \$ or \.

Field Length: 1–16 alphanumeric characters
Required Field: No
Default Value: \$S.#HOLD
Data Name: Not applicable

CHANGE PASSWORD (Y/N) — An indicator of whether you want to change your password. If you want to change your password or set your password for the first time, enter the value Y in this field and the new password in the NEW PASSWORD field. The new password takes effect the next time you try to log on.

If you do not want to change your password, let this field default to the value N. When the value N is left in this field, the BASE24 user access system does not check the NEW PASSWORD field.

Field Length: 1 alphanumeric character
Required Field: No
Default Value: N
Data Name: Not applicable

NEW PASSWORD — The new password that takes effect on the next logon. The BASE24 user access system prompts you to change your password at the time interval your institution has specified in the PASSWORD-CHNG-INTERVAL param in the LCONF. You can change your password at any time.

As you enter each character in the NEW PASSWORD field, the cursor moves one position to the right; however, as a security precaution, the characters you enter are not displayed on the screen. The BASE24 user access system requires you to enter your new password twice. After entering your new password the first time, a screen message asks you to verify the new password by entering it again.

The password must contain at least one unique character; it cannot consist of a single character repeated several times. For example, if your institution requires that passwords be at least three characters long, the passwords “ab” and “aaa” would not be valid; the password “ab” does not meet the minimum length requirement, while the password “aaa” consists of a single repeated character.

A password must meet the minimum length requirement established by your institution in the PASSWORD-LENGTH-MIN param in the LCONF. You cannot reenter your old password as your new password.

If you want to access a different logical network without logging on again, you must have an identical user name and password in each logical network.

If your institution has configured complex passwords, a password must be a mix of alpha, numeric, upper and lower case and special characters. Configuring passwords is described under the topic “Configuring Passwords” in this section.

Field Length:	1–8 alphanumeric characters
Required Field:	Yes, when you have entered the value Y in the CHANGE PASSWORD field.
Default Value:	None
Data Name:	Not applicable

FILE DESTINATION — The acronym of a file, table, or function you want to access without going through the BASE24 menu structure. In order to move to the specified file, table, or function, you must be authorized to access the file, table, or function.

Use of this field is explained in section 1. Valid values are also provided in section 1.

Field Length:	3–4 alphanumeric characters
Required Field	No
Default Value:	None
Data Name:	Not applicable

Using the BASE24 Logon Screen

Instructions for using the BASE24 Logon screen are provided below. These instructions show you how to perform the following:

- Log on to the BASE24 system for the first time
- Log on to the BASE24 system
- Change your password
- Move directly to a specified file, table, or function

These instructions assume that the BASE24 Logon screen is displayed at your terminal. To call up the BASE24 Logon screen from the TACL prompt, move to the subvolume containing the GOAFT obey file (the control subvolume), type O GOAFT at the TACL prompt, and press the **Return** key. This executes a standard BASE24 obey file that brings up the user access system.

Logging On to the BASE24 User Access System for the First Time

To log on to the BASE24 user access system for the first time, perform the following steps:

1. Enter your user name in the USER NAME field.
2. Enter your initial password, which must be provided by your supervisor in the PASSWORD field.
3. Enter the logical network you want to access in the LOGICAL NET field.
4. Enter a spooler location where you want screen images sent for printing in the SCREEN PRINTER field, if desired.
5. Enter the value Y (Yes) in the CHANGE PASSWORD field.
6. Enter the password you want to use in the NEW PASSWORD field. The password must meet the minimum length requirement established by your institution in the PASSWORD-LENGTH-MIN param in the LCONF.

The password must contain at least one unique character, and it cannot consist of a single character repeated several times.

If your institution has configured complex passwords, a password must be a mix of alpha, numeric, upper and lower case and special characters. Configuring complex passwords is described under the topic “Configuring Passwords” in this section.

7. Press the F1 key. The message VERIFY NEW PASSWORD BY RE-ENTERING VALUE is displayed and the cursor is positioned at the NEW PASSWORD field.
8. Reenter the password you want to use in the NEW PASSWORD field. This password takes effect on your next logon attempt.
9. Press the **F1** key. The BASE24 Virtual Menu is displayed.

Logging On to the BASE24 User Access System

To log on to the BASE24 user access system, perform the following steps:

1. Enter your user name in the USER NAME field.
2. Enter your password in the PASSWORD field.
3. Enter the logical network you want to access in the LOGICAL NET field.
4. Enter a spooler location where you want screen images sent for printing in the SCREEN PRINTER field, if desired.
5. Press the **F1** key. The BASE24 Virtual Menu is displayed.

Configuring Passwords

When configuring passwords, the following two options are available:

- Standard password configuration
- Complex password configuration

Standard password configuration requires that passwords be 2–8 characters in length and contain more than one character. They can contain alpha, numeric or special characters but it is not required. Passwords are not case sensitive. When resetting the password, the previous password cannot be used. Each user name and password combination must be unique within the BASE24 system.

The following parameters in the Logical Network Configuration File (LCONF) are used to configure standard passwords.

- The PASSWORD-CHG-INTERVAL parameter determines how often a password must be changed.
- The PASSWORD-LENGTH-MIN parameter determines how long a password must be (2–8 characters).
- The MAX-LOGON-ATTEMPTS parameter determines the number of unsuccessful logon attempts that are allowed before locking out a user.
- The LOGOFF-INTERVAL parameter determines how long a terminal can be idle before requiring a user to log in again.

If your institution chooses to use complex passwords, passwords must contain a mix of alpha, numeric, upper and lower case and special characters. It also enables your institution to store up to ten old passwords. To implement complex password requirements, the following options are available through LCONF parameters. These parameters are in addition to the LCONF parameters described above to configure standard passwords.

- The PASSWORD-COMPLEX parameter determines whether an institution uses complex passwords. It makes passwords case sensitive, and must be set to a value of Y for the following parameters to be effective.
- The PASSWORD-MAX-CHNG-PER-DAY parameter sets the maximum number of password changes a day.
- The PASSWORD-NUM-ALPHA parameter sets the minimum number of alpha characters required in a new password.
- The PASSWORD-NUM-NUMERIC parameter sets the minimum number of numeric characters required in a new password.
- The PASSWORD-NUM-SPCL parameter sets the minimum number of special characters required in a new password.
- The PASSWORD-MAX-STORE parameter determines the number of old passwords to be stored.

Caution: Once you set the PASSWORD-COMPLEX parameter to a value of Y, it is not intended to be reset to a value of N at a later time. Changes are made to the password fields in the Security File (SEC) to indicate that the network is using complex passwords, and these changes cannot be undone. In order to turn on complex passwords for a time and then turn them off (e.g., in a test system), you should make a backup of the SEC before you set the PASSWORD-COMPLEX parameter to a value of Y.

The ***BASE24 Logical Network Configuration File (LCONF) Manual*** contains complete descriptions of LCONF parameters used in configuring passwords.

Changing Your Password

To change your password, perform the following steps:

1. Enter your user name in the USER NAME field.
2. Enter your existing password in the PASSWORD field.
3. Enter the logical network you want to access in the LOGICAL NET field.
4. Enter the value Y (Yes) in the CHANGE PASSWORD field.
5. Enter the new password you want to use in the NEW PASSWORD field. The password must meet the minimum length requirement established by your institution in the PASSWORD-LENGTH-MIN param in the LCONF. The password must contain at least one unique character, and it cannot consist of a single character repeated several times.

If your institution has configured complex passwords, a password must be a mix of alpha, numeric, upper and lower case and special characters. Complex passwords requires that you store up to ten old passwords. Configuring passwords is described under the topic “Configuring Passwords” in this section.

6. Press the **F1** key. The message VERIFY NEW PASSWORD BY RE-ENTERING VALUE is displayed and the cursor is positioned at the NEW PASSWORD field.
7. Reenter the password you want to use in the NEW PASSWORD field. This password takes effect on your next logon attempt.
8. Press the **F1** key. The BASE24 Virtual Menu is displayed.

Note: If you want to access a different logical network without logging on again, you must have an identical user name and password in each logical network.

Moving Directly to a File, Table, or Function

To move directly from the BASE24 Logon screen to a specified BASE24 file, table, or function, perform the following steps:

1. Enter your user name in the USER NAME field.
2. Enter your password in the PASSWORD field.
3. Enter the logical network you want to access in the LOGICAL NET field.

4. Enter the acronym of the file, table, or function you want to access in the FILE DESTINATION field. See section 1 for a list of valid acronyms.
5. Press the **F1** key. The first screen to which you have access in the file, table, or function you selected is displayed.

ACI Worldwide, Inc.


4: Accessing BASE24 Menus and Screens


This section provides the information required to access BASE24 menus and screens after you have logged on to the BASE24 user access system. It provides you with an overview of the BASE24 menus through which you can access BASE24 files, tables, and functions, including illustrations of the BASE24 Virtual Menu and all product menus and brief descriptions of each menu item.

BASE24 Menu Structure

BASE24 menus display lists of screen options that you can select to access BASE24 files, tables, and functions. The menus provide a logical organization for these files, tables, and functions.

The BASE24 user access system provides multiple layers of menus, shown in the following diagrams, to help you move quickly and logically through the system. The first layer consists of the BASE24 Virtual Menu, which lists BASE24 products and several function groupings. The second layer consists of BASE24 product menus, which list the files, tables, and functions specific to that product or function grouping.





BASE24 Virtual Menu

Normally, the BASE24 Virtual Menu is the first screen displayed when you have successfully logged on to the BASE24 user access system. The BASE24 Virtual Menu lists all BASE24 products purchased by your institution to which you have been given access in your security records. It also lists several function groupings that are available with all BASE24 products. Items are displayed in the order in which they were added to your security records.

There are three cases in which the BASE24 Virtual Menu is not displayed upon successful logon:

1. If you have access to only one file, table, or function, the first screen that you have access to for that file, table, or function is displayed after a successful logon.
2. If you have access to only one product or function grouping, the product menu for that group, rather than the BASE24 Virtual Menu, is displayed after a successful logon.
3. If you enter a valid file, table, or function acronym in the FILE DESTINATION field at the bottom of the Logon screen, the first screen to which you have access for that file, table, or function is displayed upon successful logon.

The BASE24 Virtual Menu, shown on the following page, lists all products and function groupings currently available. Brief descriptions of each product or function grouping in alphabetical order are also provided on the following pages.

All the function keys available on the BASE24 Virtual Menu are listed at the bottom of the screen. Function keys are described in section 2 of this manual.

To access a BASE24 Virtual Menu item, place the cursor next to a selection and press the **F1** key.

```
BASE24-ADMN  VIRTUAL MENU                LLLL      YY/MM/DD  HH:MM  01 OF 01
              V I R T U A L  M E N U
```

BASE	ATM
POS	TELLER
CORE	BILLPAY
KERNEL/IEP	MAIL
CARD MANAGEMENT	RETAIL CONFIGURATION
CUSTOMER SERVICE	CHECK DISBURSEMENTS
OPERATOR FUNCTIONS	CHECK AUTHORIZATION
FREQUENT SHOPPER	REFUNDS

```
***** BASE24 *****
              FILE DESTINATION:
F1-ENTER DATA  F10-PRINT                F16-EXIT  SF16-LOGOFF
```

BASE24 Virtual Menu Items

The following paragraphs describe the items available on the Virtual Menu. If you do not have security access to an item, it will not be displayed.

ATM — Accesses the ATM Product Menu, from which you can select files and functions used exclusively by the BASE24-atm product and its add-on products. An example of a BASE24-atm file is the BASE24-atm Terminal Data files (ATD), which contains one record for each Automated Teller Machine (ATM) in the logical network.

BASE — Accesses the Base Product Menu, from which you can select files used by one or more BASE24 products. An example of a Base file is the Institution Definition File (IDF), which is used by BASE24 products to retrieve information about financial institutions.

BILLPAY — Accesses the Billpay Product Menu, from which you can select tables and functions used exclusively by the BASE24-billpay product. An example of a BASE24-billpay table is the Customer Vendor Table (CVND), which contains one row for each customer and vendor relationship in the logical network.

CARD MANAGEMENT — Accesses the BASE24-card User Menu, from which you can select functions used by the BASE24-card product. An example of a BASE24-card function is the Card Operator Function (COF). This screen is used to generate account numbers.

CHECK AUTHORIZATION — Accesses the Check Authorization User Menu, from which you can select user function screens used by the BASE24-check auth product. An example of a BASE24-check auth user screen is the Customer Information (CUST) screen. This screen is used to view and maintain customer information based on a customer's primary or alternate ID.

CHECK DISBURSEMENTS — Accesses the Check Disbursements User Menu, from which you can select functions used exclusively by the check disbursements enhancement to the BASE24-refunds product. An example of a check disbursements screen is the Refund Check Activity by ID (DAID) screen. This screen allows you to view all refund check activity associated with a particular customer ID.

CORE — Accesses the Core Product Menu, from which you can select files, tables, and functions used exclusively by object-oriented Integrated Authorization Server processes. An example of a core table is the Customer Table (CSTT), which contains one row for each customer ID in the logical network.

CUSTOMER SERVICE — Accesses the Customer Service Product Menu, from which you can select files and functions used exclusively by the BASE24-atm and BASE24-pos products to provide customer service processing. An example of a customer service function is the Customer Service Transaction Perusal screen, which allows you to peruse cardholder transaction activity from one central set of screens.

FREQUENT SHOPPER — Accesses the Frequent Shopper User Menu used exclusively by the BASE24-frequent shopper product. The Frequent Shopper User Menu allows you to execute user functions for the BASE24-frequent shopper product. An example of a frequent shopper screen is the Customer Retailer Activity (CRAT) screen. This screen allows you to view a summarized display of all retail activity by customer ID.

KERNEL/IEP — Accesses the Kernel/Integrated Endpoint Product Menu, from which you can select files and functions used exclusively to configure and control the object-oriented integrated transaction server (ITS) environment on behalf of core and IEP applications. An example of a kernel file is the Object File (OBJ), which contains one record for each object used in the logical network.

The Integrated Endpoint process is an object-oriented process running in the integrated transaction services (ITS) environment. The IEP accesses the Destination File (DEST). The DEST is used by Integrated Endpoint processes to route messages to destinations based on the source class and message class associated with the given message.

For more information on the DEST, refer to the ***BASE24 IEP Configuration Manual***.

MAIL — Accesses the Mail Product Menu, from which you can select files and functions used exclusively by the BASE24-mail product. An example of a BASE24-mail file is the Host Mail Box File (HMBF), which contains one record for each mail message to a host that is being stored for later delivery.

OPERATOR FUNCTIONS — Accesses the Operator Product Menu, from which you can select BASE24 operator functions, including network control, refresh and extract control, device and process control, and log message control.

POS — Accesses the POS Product Menu, from which you can select files and functions used exclusively by the BASE24-pos product (including its CRT Authorization and CRT Administration add-on products). An example of a BASE24-pos file is the POS Terminal Data File (PTDF), which contains one record for each point-of-sale (POS) terminal in the logical network.

REFUNDS — Accesses the Refunds User Menu used exclusively by the BASE24-refunds product. The Refunds User Menu allows you to execute user functions for the BASE24-refunds product. An example of a refunds user screen is the Refund Activity by Address (ACTA) screen. This screen allows you to view all refund activity based on an address.

RETAIL CONFIGURATION — Accesses the retail product configuration screens, from which you can configure the retail products. An example of a retail configuration screen is the Application Configuration screen. This screen is used to maintain the Application Configuration Table (ACT) which contains one row for each parameter used by specific Check Authorization, Refunds or Frequent Shopper modules and procedures.

TELLER — Accesses the Teller Product Menu, from which you can select files and functions used exclusively by the BASE24-teller product. An example of a BASE24-teller file is the Teller Terminal Data File (TTDF), which contains one record for each teller terminal in the logical network.

Product Menus

Product menus list the files, tables, and functions included within a BASE24 Virtual Menu item grouping. Product menus are displayed when you select one of the items on the BASE24 Virtual Menu or when you enter the file name in the FILE DESTINATION field on any screen.

As on the BASE24 Virtual Menu, only the items to which you have access are displayed on the product menu. The order in which these items are displayed depends on the order in which they were added to your security records. The product menus shown on the following pages are the menus that are displayed for users with access to all files, tables, and functions. If a user has access to only one file, table, or function, the first screen for that file, table, or function, rather than the product menu, is displayed.

All the function keys available on product menus are listed at the bottom of the product menu screen, except for the **F16** and **Shift-F16** keys. Function key descriptions are provided in section 2 of this manual.

Help screens for product menus provide the full descriptive names of each file, table, or function acronym entry displayed on the menu.

To access a product menu item, place the cursor next to the item and press the **F1** key. The first screen to which you have access in that file, table, or function is displayed.

ATM Product Menu

The ATM Product Menu is displayed when you select the ATM item from the BASE24 Virtual Menu. The ATM Product Menu, shown on the following page, gives you access to the following files and functions, assuming you have the proper security:

ATD = Terminal Data files
BSF = Bin Sort File
CCF = Corporate Check File
CSF = Check Status File
OIF = Operator Identification File
RCPT = Receipt File
RPT = ATM Report screen
TLF = Transaction Log File
TRF = Terminal Receipt File

These files and functions are described briefly on the following pages. Refer to the following manuals for additional information on these files and functions.

- The device-specific BASE24-atm self-service banking (SSB) manuals contain additional information on file maintenance functions for the BSF, CCF, and CSF.
- The *BASE24-atm Files Maintenance Manual* contains additional information on file maintenance functions for the ATD, RCPT, RPT, TLF, and TRF.
- The *BASE24-atm Settlement and Reporting Manual* contains information on file maintenance functions for the RPT.
- The *BASE24-atm Diebold 1000-Series Device Support Manual* contains additional information on file maintenance functions for the OIF.

```
BASE24-ADMN  MENU                      LLLL      YY/MM/DD  HH:MM  01 OF 01
      A T M      P R O D U C T M E N U

      ATD          BSF          CCF          CSF
      OIF          RCPT         RPT          TLF
      TRF
```

```
***** BASE24 *****
FILE DESTINATION:
F1-ENTER DATA  F9-NEXT PAGE      F11-PREVIOUS PAGE  F10-PRINT  F12-HELP
```

ATM Product Menu Items

The following paragraphs describe the items available on the ATM Product Menu. If you do not have security access to an item, it will not be displayed.

ATD — Accesses the BASE24-atm Terminal Data files (ATD). The Terminal Data files define the characteristics of the terminal, including the transaction security parameters, sharing parameters, transaction totals, terminal owner, and device-dependent data. They are also used to preserve transaction context.

Data entered on ATD screens is stored in different files, depending on the type of terminal being defined. For Diebold 10XX/478X and NCR 5XXX terminals, dynamic and static data is stored in the ATM Terminal Data Dynamic File—general data (ATDD1) and ATM Terminal Data Static File—general data (ATDS1), respectively. For all other types of ATM terminals, data is stored in the ATM Terminal Data File (TDF).

BSF — Accesses the Bin Sort File (BSF), which is used with the BASE24-atm self service (SSB) banking product. The BSF defines the terminal check sorting mechanism based on the check issuer and the check amount.

CCF — Accesses the Corporate Check File (CCF), which is used with the BASE24-atm self service banking (SSB) product. The CCF defines check authorization parameters based on the institution that owns the accounts.

CSF — Accesses the Check Status File (CSF), which is used with the BASE24-atm self service banking (SSB) product. The CSF defines the current status of specific checking accounts used in check-related transaction authorizations.

OIF — Accesses the Operator Identification File (OIF). The OIF contains one record for each operator that services Diebold 10XX/478X ATMs with the optional host-controlled, solenoid-activated lock feature. OIF records specify whether the operator has access to the ATM chest door.

RCPT — Accesses the Receipt File (RCPT). The RCPT contains configuration information for ATM receipt formats that are unique to an institution. One RCPT screen is used to configure one receipt template for each receipt type and language indicator.

RPT — Accesses the ATM Report (RPT) screens. The RPT screens are used to peruse BASE24 settlement and statistical reports, which contain information from the Transaction Log File (TLF) for each terminal and institution in the logical network. The TLF is described below.

TLF — Accesses the Transaction Log File (TLF). The TLF contains one record for each transaction occurring at an ATM in the logical network and each transaction processed by the BASE24 transaction processing system during a business day. TLF records are maintained for both cardholder transactions and terminal balancing transactions. One TLF is maintained for each business day, and each TLF can be saved for the number of days specified in the Logical Network Configuration File (LCONF). The TLF provides an audit trail of ATM activity.

TRF — Accesses the Terminal Receipt File (TRF). The TRF defines the receipt options for approved and denied transactions that occur at devices with the specified terminal receipt profile defined in the BASE24-atm Terminal Data File (ATD). The TRF contains one record for each terminal receipt profile, message category, and processing code combination in the system.

Base Product Menu

The Base Product Menu is displayed when you select the BASE item from the BASE24 Virtual Menu. The Base Product Menu, shown on the following page, gives you access to the following files and functions, assuming you have the proper security:

APCF	=	Acquirer Processing Code File
ARF	=	Account Routing File
ATT	=	Account Type Table File
CAF	=	Cardholder Authorization File
CPF	=	Card Prefix File
DCCD	=	Dynamic Currency Conversion Data File
ECF	=	Extract Configuration File
EMF	=	External Message File
ERF	=	Exchange Rate File
HCF	=	Host Configuration File
ICF	=	Interchange Configuration File
ICFE	=	Enhanced Interchange Configuration File
IDF	=	Institution Definition File
IPCF	=	Issuer Processing Code File
KEYA	=	Key Authorization File
KEYD	=	Derivation Key File
KEYF	=	Key File
KEYI	=	EMV ICC Key File
KEY6	=	KEY 6 File
LNCF	=	Logical Network Configuration File
NCSP	=	Network Control Security Profile File
NEG	=	Negative Card File
PBF	=	Positive Balance File
PDF	=	Processing Code Description File
PRE	=	Prefix File Build Utility screen
SEC	=	Security screens
SPF	=	Stop Payment File
STF	=	Switch Terminal File
SURF	=	Surcharge File
TCF	=	Transaction Code File
TKN	=	Token File
UAF	=	Usage Accumulation File

These files and functions are described briefly on the following pages. For additional information on the SEC and NCSP, refer to section 5. For additional information on the remaining Base files maintenance functions, refer to the ***BASE24 Base Files Maintenance Manual***. For more information on the LNCF function, refer to the ***BASE24 Logical Network Configuration File Manual***.

```

BASE24-ADMN  MENU                      LLLL      YY/MM/DD  HH:MM  01 OF 01
      B A S E  P R O D U C T  M E N U

      ACPF          ARF          ATT          CAF
      CPF          DCCD        ECF          EMF
      ERF          HCF          ICF          ICFE
      IDF          IPCF        KEYA          KEYD
      KEYF          KEYI        KEY6          LNCF
      NCSP          NEG          PBF          PDF
      PRE          SEC          SPF          STF
      SURF          TCF          TKN          UAF

***** BASE24 *****
      FILE DESTINATION:
F1-ENTER DATA  F9-NEXT PAGE      F11-PREVIOUS PAGE  F10-PRINT  F12-HELP

```

Base Product Menu Items

The following paragraphs describe the items available on the Base Product Menu. If you do not have security access to an item, it will not be displayed.

APCF — Accesses the Acquirer Processing Code File (APCF). The APCF defines the ISO processing codes allowed by various transaction acquirers. The APCF contains one record for each combination of acquirer transaction profile, message category, and ISO processing code that is supported by a BASE24-atm or BASE24-pos acquirer endpoint in the system.

ARF — Accesses the Account Routing File (ARF). The ARF provides routing information to supplement the account information entered at a teller terminal or ATM so that the account can be located on the BASE24 database. The ARF is used in interbank routing for the BASE24-teller product and in self-service banking (SSB) for the BASE24-atm product.

ATT — Accesses the Account Type Table File (ATT). The ATT contains one record for each valid account type in the BASE24 network. Each ATT record contains an ISO code and a corresponding description.

CAF — Accesses the Cardholder Authorization File (CAF). The CAF contains one record for each cardholder whose card-issuing institution uses the Positive Authorization or Positive Balance Authorization method. Each record contains authorization parameters and usage accumulation information. The CAF is used in authorizing transaction requests.

CPF — Accesses the Card Prefix File (CPF). The CPF contains one record for each card prefix used in a BASE24 logical network. CPF records define the characteristics of each prefix and contain prefix-specific parameters that can be used to control aspects of authorization processing at the prefix level. The CPF also allows institutions to establish authorization parameters for selected prefix groups.

DCCD — Accesses the Dynamic Currency Conversion Data File (DCCD). The DCCD contains the data the DCCD add-on product needs to process dynamic currency conversion transactions. This file contains the BIN currency record and the currency data record. The dynamic currency conversion feature provides the option of locking in a foreign currency conversion rate and having the conversion performed by the acquirer before being sent to a network for authorization.

ECF — Accesses the Extract Configuration File (ECF). The ECF contains one record for each type of extract an institution wants to perform in a particular logical network. ECF records are used to set extract processing parameters, including the name of the file or files to be extracted and the tape or disk location to which the extract is to be performed. ECF records can also specify that an extract is to be performed automatically at a set time each day.

EMF — Accesses the External Message File (EMF). The EMF can contain up to one record for each BASE24 external message type available to each data processing center (DPC), BASE24 process, and BASE24 product combination. The BASE24 process can be an ISO Host Interface, BIC ISO Interchange Interface, From Host Maintenance, BASE24 Remote Banking Standard Interface,

or BASE24-pos NCR NDP Device Handler process. EMF records specify the data elements that should be included in the BASE24 External Message. The EMF is used by the ISO Host Interface process, BIC ISO Interchange Interface process, From Host Maintenance process, BASE24 Remote Banking Standard Interface process, and BASE24-pos NCR NDP Device Handler process to determine how to create the external messages they send and interpret the external messages they receive.

ERF — Accesses the Exchange Rate File (ERF). The ERF is used with the BASE24 Multiple Currency add-on product. It contains one record for each currency used by BASE24 except the Base currency. All exchange rates in the ERF are used in the relationship of the Base currency to a specific currency rate. Information in the ERF is used by the currency conversion utilities to convert amount fields within BASE24 from one currency to another.

HCF — Accesses the Host Configuration File (HCF). The HCF contains one record for each unique data processing center (DPC) and Host Interface process pair in the logical network. Each record contains pertinent information about host message formats, timer limits, and request/response sequences. The HCF is used to establish BASE24-to-host communication links for transaction message traffic routed to a host authorization system.

ICF — Accesses the Interchange Configuration File (ICF). The ICF contains parameters relevant to interchange transaction processing. It is used by the institution to define institution and terminal interchange sharing, holidays, transaction handling in offline and online situations, and settlement handling. There is one ICF record for each Interchange Interface process that uses the ICF.

ICFE — Accesses the Enhanced Interchange Configuration File (ICFE). Like the Interchange Configuration File (ICF), the ICFE is used by the institution to define institution and terminal interchange sharing, holidays, transaction handling in offline and online situations, and settlement handling. However, the ICFE uses transaction profiles instead of the hard-coded tables used in the ICF to define the transactions allowed.

IDF — Accesses the Institution Definition File (IDF). The IDF contains one record for each institution participating in the logical network. Each record establishes how processing is handled for that institution and includes routing tables for transaction routing within BASE24 products and parameters for cards, dates, processing control, and sharing.

IPCF — Accesses the Issuer Processing Code File (IPCF). The IPCF contains one record for each combination of issuer transaction profile, message category, and ISO processing code that is supported by a BASE24-atm or BASE24-pos card issuer in the BASE24 system. Each issuer transaction profile defines a set of cardholder transactions supported for an institution, card prefix, or individual cardholder account. For interchanges, each BASE24-atm or BASE24-pos issuer transaction profile defines a set of transactions allowed to be sent (outbound) to the issuer interchange.

KEYA — Accesses the Key Authorization File (KEYA). The KEYA contains one record for each financial institution or data processing center (DPC) associated with a BASE24 transaction processing system. KEYA records contain specific key processing information for each of these entities, including parameters for the PIN verification that BASE24 authorization processes must perform.

KEYD — Accesses the Derivation Key File (KEYD). The KEYD contains derivation keys required for SPDH-driven terminals that support the encryption type of derived unique key per transaction (DUKPT). The KEYD contains the 32-byte derivation key from the terminals encrypted under a double-length Master File Key (MFK) for Atalla security device or a double-length Local Master Key (LMK) pair variant of 28-29 for Thales e-Security (Racal) security devices.

KEYF—Accesses the Key File (KEYF). The KEYF contains one record for each Host Interface process or Interchange Interface process associated with a BASE24 transaction processing system. KEYF records contain specific key processing information for both of these entities, including parameters for PIN encryption and decryption and key management throughout the BASE24 transaction processing system.

KEYI — Accesses the EMV ICC Key File (KEYI). This file is used with the BASE24 EMV add-on product. The file contains multiple authentication keys used for Authorization Request Cryptogram (ARQC) verification and Authorization Response Cryptogram (ARPC) generation. The file also contains a double length DES key used for Secure Messaging for Message Integrity, (i.e., the generation of the Issuer Script message authorization code (MAC)).

KEY6 — Accesses the KEY 6 File (KEY6). The KEY6 contains the information and parameters required by release 6.0 BASE24 Host Interface and Interchange Interface processes running in release 5.x or 6.0 networks for PIN encryption, PIN translation, message authentication, and dynamic key management. The KEY6 allows for double-length encryption keys, which are required when translating

PINs from encryption under a double length key using the Triple Data Encryption algorithm (3DEA) to encryption under a single length key using the Data Encryption algorithm (DEA) and vice versa.

LNCF — Accesses the Logical Network Configuration File (LCONF). The LCONF is the central location of file information and processing information. One LCONF exists for each logical network. Records in the LCONF are classified as either assigns or params, depending on their function. Assigns link the physical names of objects in the logical network to names used in BASE24 code. Params set processing values at the logical network level. The LNCF is used to modify assigns and params.

NCSP — Accesses the Network Control Supervisor Profile File. The NCSP allows you to set up network control command profile records. The command profile records indicate whether each network command can be executed and whether the command is audited when it is executed. After you have created a command profile and stored it in the NCSP, you can associate it with the security record for one or more users.

NEG — Accesses the Negative Card File (NEG). The NEG contains one record for each special-status card whose card issuer uses a negative authorization method. The NEG is used to flag cards that require special processing, such as restricted cards (lost or stolen), VIP cards, administrative cards, and deposit-only cards. The Authorization process checks this file to determine whether a transaction request should be approved and, if not, what action should be taken with the card.

PBF — Accesses the Positive Balance File (PBF). The PBF contains one record for each application account whose issuer uses the Positive Balance Authorization method, Parametric Authorization method, or Positive Customer with Balances/History Authorization method. Each PBF record contains available and ledger balances for the account. The PBF is used to authorize transaction requests without having to forward them to a back-end host authorization system.

Institutions can maintain up to three different PBFs: one for checking accounts (DDAs), one for savings (SAV) accounts, and one for credit (CCD) accounts.

PDF — Accesses the Processing Code Description File (PDF). The PDF is an optional file that contains the descriptions of each processing code description tag used in the Acquirer Processing Code File (APCF) or Issuer Processing Code File (IPCF).

Each description tag record in the PDF defines a long description and an optional short description. These descriptions are displayed on various screens whenever a record with the corresponding description tag is read.

PRE — Accesses the Prefix File Build Utility (PRE) screen. The PRE screen is used to create and maintain Interchange Prefix Files (IPFs) when prefix tapes are not provided by an interchange. The prefixes maintained in the IPF are used for routing with the logical network (LGNT) routing method.

SEC — Accesses the four screens used to maintain BASE24 security. These screens allow you to change security records in the Security File (SEC), User/FIID Relation File (UFIR), User/Product File Relation File (UPFR), and Network Control Security Specification File (NCSS). The SEC, UFIR, UPFR, and NCSS contain one record for each authorized BASE24 user. Security records restrict BASE24 user access by user name, time of day, terminal, XPNET node, financial institution identifier, region, branch, and screen. Screen use is further restricted to read, add, delete, or update privileges or a combination of these. In addition, security records restrict access to text commands initiated via any network control facility. See section 5 of this manual for more information on BASE24 security.

SPF — Accesses the Stop Payment File (SPF). The SPF contains one record for each institution- or customer-initiated stop payment request that has been issued in the logical network. SPF records are used to stop payment of bad checks, which is a feature of the BASE24-atm self-service banking (SSB) add-on product and the BASE24-teller product.

STF — Accesses the Switch Terminal File (STF). The STF contains one record for each terminal that is required by any interchange to transmit an interchange-assigned identification rather than the BASE24 terminal identification. One screen is used to access records in the STF.

SURF — Accesses the Surcharge File (SURF). The SURF contains information about whether transactions are charged an additional surcharge fee for the use of your terminal. The SURF determines when and how much the surcharge is applied to a transaction. Surcharges can either be calculated as a flat amount per transaction or a percentage of the transaction amount requested.

TCF — Accesses the Transaction Code File (TCF). The TCF contains the text description of each ISO transaction code used in the Acquirer Processing Code File (APCF), Issuer Processing Code File (IPCF), or Terminal Receipt File (TRF).

TKN — Accesses the Token File (TKN). The TKN contains records that indicate which of the data tokens carried in the internal messages will be logged to the various log files, extracted by the Super Extract process, or sent in external messages created by the ISO Host Interface and BASE24 Interchange (BIC) Interface processes. The information in the TKN also determines the order of data tokens being logged, extracted, or sent.

UAF — Accesses the Usage Accumulation File (UAF). The UAF, which is used for usage accumulation with the Negative Authorization with Usage Accumulation method, contains one record for each cardholder who has had a transaction authorized by the BASE24-atm or BASE24-pos products during the current usage accumulation period. Cardholder usage is tracked, or accumulated, based on the institution's business day, which is the time period from one usage period to the next. UAF records contain such information as withdrawal amounts and bad PIN tries. This information enables BASE24 products to determine when a cardholder has reached the institution's usage limits for a given period.

Billpay Product Menu

The Billpay Product Menu is displayed when you select the BILLPAY item from the BASE24 Virtual Menu. The Billpay Product Menu, shown on the following page, gives you access to the following tables, assuming you have the proper security:

BKAV	=	Bank Transaction Advice Table
BKBR	=	Bank Branch Table
BKNT	=	Bank Notice Table
BLG	=	Billing Group Table
BLRT	=	Billing Rate Table
BLTY	=	Billing Type Table
CBPT	=	Customer Billpay Table
CLPT	=	Cleanup Configuration Table
CVND	=	Customer Vendor Table
HIST	=	History Table
RATE	=	Rate Table
RATG	=	Rate Group Table
RTRY	=	Retry Table
RTXT	=	Response Code Text Table
SVPT	=	Service Provider Table
VBUD	=	Vendor Budget Category Table
VNDB	=	Vendor Branch Table
VNDM	=	Vendor Mask Table
VNDR	=	Vendor Table

These tables are described briefly on the following pages. Refer to the manuals listed below for additional information on these tables.

- The ***BASE24-billpay Tables Maintenance Manual*** contains table maintenance information for the BKAV, BKBR, BKNT, CBPT, CLPT, CVND, HIST, RTRY, RTXT, SVPT, VBUD, VNDB, VNDM, and VNDR.
- The ***BASE24-billpay Billing Application Manual*** contains table maintenance information for the BLG, BLRT, BLTY, RATE, and RATG.

```

BASE24-ADMN  MENU                      LLLL      YY/MM/DD  HH:MM  01 OF 01
                                B P      P R O D U C T  M E N U

      B K A V      B K B R      B K N T      B L G
      B L R T      B L T Y      C B P T      C L P T
      C V N D      H I S T      R A T E      R A T G
      R T R Y      R T X T      S V P T      V B U D
      V N D B      V N D M      V N D R

***** BASE24 *****
FILE DESTINATION:
F1-ENTER DATA  F9-NEXT PAGE      F11-PREVIOUS PAGE  F10-PRINT  F12-HELP

```

Billpay Product Menu Items

The following paragraphs describe the items available on the Billpay Product Menu. If you do not have security access to an item, it will not be displayed.

BKAV — Accesses the Bank Transaction Advice Table (BKAV). The BKAV defines the FIID, transaction source (that is, remote banking endpoint device or customer service terminal), and transaction type combinations for which transaction data is logged to the ITS Transaction Log File by the Billpay Server process. Transactions can be logged only when they are approved, only when they are denied, or when they are approved or denied.

BKBR — Accesses the Bank Branch Table (BKBR). The BKBR defines contact information for specific branches of customer financial institutions. The table may optionally contain information for each branch or just the main branch. Each row contains contact information for the branch that is primarily used by inbound customer service representatives (CSRs) to refer customers for additional information on their billpay service.

BKNT — Accesses the Bank Notice Table (BKNT). The BKNT defines the FIID and transaction action code combinations for which a customer notice is to be generated. This table is used by the Scheduled Transaction Initiator process to determine whether a notice needs to be generated for a particular error condition. Generated customer notices are placed in the Report Action Table for later processing. Financial institutions must be defined to the Bank Table before they can be used in this table. Valid BASE24-billpay transaction action codes are described in the *BASE24 Remote Banking Transaction Processing Manual*.

BLG — Accesses the Billing Group Table (BLG). The BLG defines all billing groups used by a financial institution. Each table row indicates whether the group is used for bank or customer billing, and defines the effective billing statement cycle begin and end dates for the billing month.

BLRT — Accesses the Billing Rate Table (BLRT). The BLRT defines the billing type and rate name for each billing statement cycle used by a financial institution.

BLTY — Accesses the Billing Type Table (BLTY). The BLTY defines the billing types used by a financial institution. Each table row contains the billing type, a flag indicating whether the row is used for bank billing or customer billing, the number of billing statement cycles for which the type applies, and the next billing type.

CBPT — Accesses the Customer Billpay Table (CBPT). The CBPT provides the current billing and vendor information maintained by the BASE24-billpay product on behalf of a billpay customer. The CBPT allows you to view up-to-date information for a particular customer, including the following: current and original billing type, billing group, remaining number of cycles, last cycle end date, last customer vendor number, and the next customer reference number.

CLPT — Accesses the Cleanup Configuration Table (CLPT). The CLPT contains configuration information used by the Archive and Cleanup programs. Data can be retained for a configurable number of days before it is deleted or archived.

CVND — Accesses the Customer Vendor Table (CVND). The CVND contains one row for each vendor a specific customer wants to pay. Each row contains information specific to the customer's relationship with the vendor such as the customer's ID, customer vendor number, verification flag, effective date range, the customer's account number with the vendor, and a budget category code. If a customer has multiple accounts with the same vendor, a separate row must be configured for each account relationship.

HIST — Accesses the History Table (HIST). The HIST contains one row for each transaction processed by the Billpay Server or Scheduled Transaction Initiator process. The Remittance Generator and ACHclear processes also update the HIST during end-of-period processing. The HIST screens allow you to peruse transactions based on the customer ID, customer reference number, and the business date when the transaction was performed. Each HIST row includes such information as the transaction type, transaction amount, *to* and *from* accounts, transaction source, transaction status flags and codes, and vendor remittance information.

RATE — Accesses the Rate Table (RATE). The RATE allows you to set up different usage rates for BASE24-billpay service, depending on the source of transactions, the type of transactions processed, and the action code indicating the outcome of transaction processing. The RATE also allows you to indicate a specific group of rates defined in a row in the Rate Group Table.

RATG — Accesses the Rate Group Table (RATG). The RATG defines the rates charged in online billing or customer billing for specified rate groups. Each rate group defines the range (that is, number of transactions processed), the cost for each range, the number of ranges that apply, and whether a cumulative or flat rate is used for each range. Using these fields, you can define service costs based on usage. Rate groups are related to specific transaction types and sources in the Rate Table (RATE).

RTRY — Accesses the Retry Table (RTRY). The RTRY defines the action codes for which a transaction will be retried on behalf of a financial institution and how retry transactions are performed. Valid action codes for the BASE24-billpay product are described in the ***BASE24 Remote Banking Transaction Processing Manual***.

RTXT — Accesses the Response Text Table (RTXT). The RTXT contains any internally or externally displayed text associated with a specific action code or reversal reason code. Internally displayed text appears on customer service representative (CSR) terminal screens and table maintenance screens and externally displayed text normally appears only on reports. Valid action codes and reversal reason codes for the BASE24-billpay product are described in the ***BASE24 Remote Banking Transaction Processing Manual***.

SVPT — Accesses the Service Provider Table (SVPT). The SVPT contains one row on behalf of the service provider. This row is used to set the initial last customer ID used for automatically generating customer IDs for financial institutions that do not use preloaded customer data. The last customer ID is used as a starting point by the system for generating customer IDs.

VBUD — Accesses the Vendor Budget Category Table (VBUD). The VBUD contains one row for each vendor budget category tracked by the system. Budget categories are defined by customers and are used for reporting purposes only to indicate how much money a customer paid to vendors in a specified budget category for a specified period of time. For example, a budget category of UTIL could be used to track all payments made to vendors for gas, electricity, and water utility service.

VNDB — Accesses the Vendor Branch Table (VNDB). The VNDB contains information regarding the branches for a vendor. It may optionally contain information for each vendor branch or just the main vendor branch. Each row contains information specific to a particular vendor branch such as the branch name, address, and contact information. An account mask group can be defined if a vendor mask is used to perform edit checks of customer account numbers with the vendor. Vendor masks are defined in the Vendor Mask Table (VNDM).

VNDM — Accesses the Vendor Mask Table (VNDM). The VNDM provides a means for performing edit checks of customer vendor account numbers when they are first entered into the system as verified accounts using customer service representative (CSR) terminal screens or the Customer Vendor Table maintenance screen. Edit mask checks can include minimum and maximum account number lengths, account number matching, and user-defined account number analysis algorithms.

VNDR — Accesses the Vendor Table (VNDR). The VNDR contains the master list of vendors, with one row for each vendor used in the logical network. A vendor is any recipient of payment transactions from a BASE24-billpay customer. BASE24-billpay customers can access only the vendors that have been defined in this table. Each row maintains information pertinent to the vendor such as the vendor name, the vendor number, the vendor type, vendor audio token, main vendor branch, vendor government ID, vendor institution ID, vendor remittance information, verification flag, effective date range, vendor mask group, and default budget category.

Card Management Product Menu

The Card Management Product Menu is displayed when you select the CARD MANAGEMENT item from the BASE24 Virtual Menu. The Card Management Product Menu, shown below, gives you access to the following terminal functions, assuming you have the proper security:

CLST = Cardholder List Functions
 CMF = Card Management Functions
 COF = Card Operator Functions

These functions are described briefly on the following pages. Refer to the *BASE24-card Reference Manual* for additional information on these functions.

```

BASE24-ADMN  MENU                      LLLL      YY/MM/DD  HH:MM  01 OF 01
                                C M S      P R O D U C T  M E N U

                                CLST          CMF          COF

*****
***** BASE24 *****
FILE DESTINATION:
F1-ENTER DATA  F9-NEXT PAGE  F11-PREVIOUS PAGE  F10-PRINT  F12-HELP
  
```

Card Management Product Menu Items

The following paragraphs describe the items available on the Card Management Product Menu. If you do not have security access to an item, it will not be displayed.

CLST — Accesses the Cardholder List Functions terminal (CLST). The CLST is used to locate a cardholder's account number by entering their name. The CLST gives an operator access to the Cardholder Authorization File (CAF) records using only a name. It is designed for situations where an operator is not in possession of an account number but has at least an approximate spelling of a cardholder's name.

COF — Accesses the Card Operator Function terminal (COF). The COF is used to initiate the generation of account numbers. The Account Number Generation function is initiated using a function key from a COF terminal work screen. The number generation function is used to generate a list of possible card account numbers for a particular prefix.

CMF — Accesses the Card Management Functions terminal (CMF). The CMF enables an operator to perform the following: generation of the Issue Projection Project Report, issue maintenance, and plastic card generation force/mass issue.

The Issue Projection Project Report can be used to forecast supply needs for card production as well as to evaluate the institution's current card reissue schedule. The issue maintenance function examines individual card accounts against issue/reissue criteria to determine whether or not a card should be issued and whether or not PIN mailers and card carriers should be generated. The force issue function enables plastic cards to be individually produced in emergency situations such as loss, theft, or damage. The mass issue function enables an institution to reissue cards for its entire card base or for certain card prefixes.

Check Authorization User Menu

The Check Authorization User Menu is displayed when you select the CHECK AUTHORIZATION item from the BASE24 Virtual Menu. The Check Authorization User Menu, shown below, gives you access to the following user screens and functions, assuming you have the proper security:

CUST = Customer Information
 SDT = Summarized Detail Perusal
 TDT = Transaction Detail Perusal
 VELO = Velocity by ID (activity accumulation)

These screens are described briefly on the following pages. Refer to the *BASE24-check auth SQL Tables Maintenance Manual* for additional information on these screens.

```

BASE24-ADMN  MENU                LLLL      YY/MM/DD  HH:MM  01 OF 01
                                C H K A   U S E R   M E N U

                                CUST          SDT          TDT          VELO

***** BASE24 *****
                                FILE DESTINATION:
F1-ENTER DATA  F10-PRINT  F12-HELP  F16-EXIT  SF16-LOGOFF
  
```

Check Authorization User Menu Items

The following paragraphs describe the items available on the Check Authorization User Menu. If you do not have security access to an item, it will not be displayed.

CUST — Accesses the Customer Information screens (CUST). The CUST is composed of three related screens—the Customer Information and Associations screen, the Customer Information Negative Source screen, and the Customer Information Associated Names screen. You can use these screens to maintain the following features of primary and alternate IDs: statuses, ratings, joined IDs, negative information, and name information. An ID provides a means of identifying a check-writing customer to the system.

SDT — Accesses the Summarized Detail Perusal screen (SDT). This screen allows you to view summarized transaction detail by retailer; by retailer and date; by retailer and store; and by retailer, store, and date.

TDT — Accesses the Transaction Perusal Detail screen. This screen allows you to view transaction detail recorded in the Transaction Detail Table (TDT) by primary, alternate, or terminal ID for a retailer, store, and date, with the most current activity first.

VELO — Accesses the Velocity by ID screens (VELO). The VELO is composed of two screens—the Velocity Amounts and Counts screen and the Velocity Associated IDs screen—that allow you to view the activity accumulation, also known as velocity, of a primary or alternate ID. You can view activity accumulation of an ID by retailer, store, payment type, rating, and period. Activity accumulation data is obtained from the Transaction Detail Table (TDT).

Check Disbursements User Menu

The Check Disbursements User Menu is displayed when you select the CHECK DISBURSEMENTS item from the BASE24 Virtual Menu. The Check Disbursements User Menu, shown below, gives you the access to the following user screens and functions, assuming you have the proper security.

DADR = Refund Check Address Update
 DAID = Refund Check Activity by ID
 DANM = Refund Check Activity by Name
 DARC = Check Activity by Refund Check Info
 DARI = Check Activity by Refund Info
 DASI = Refund Check Activity by Store Info
 DGLE = General Ledger Event
 DMCK = Manual Check

These files and functions are described briefly on the following pages.

```

BASE24-ADMN  MENU                      LLLL      YY/MM/DD  HH:MM  01 OF 01
                                C H K D  U S E R  M E N U

                                DADR      DAID      DANM      DARC
                                DARI      DASI      DGLE      DMCK
  
```

```

***** BASE24 *****
FILE DESTINATION:
F1-ENTER DATA  F10-PRINT  F12-HELP  F16-EXIT  SF16-LOGOFF
  
```

Check Disbursements User Menu Items

The following paragraphs describe the items available on the Check Disbursements Menu. If you do not have security access to an item, it will not be displayed.

DADR — Accesses the Refund Check Address Update screen (DADR). This screen allows you to view the current address associated with a specified refund and up to four additional addresses associated with the customer ID for the refund. From this screen, you can change the address associated with the refund.

DAID — Accesses the Refund Check Activity by ID screen (DAID). This screen allows you to view all refund check activity associated with a particular customer ID in reverse chronological order, beginning with the most recent action. From this screen, you can also select to view detailed information for a particular refund.

DANM — Accesses the Refund Check Activity by Name screen (DANM). This screen allows you to view all refund check activity associated with a particular customer name, customer name and state of ID, or customer name, state of ID, along with additional filters of store and specified time period. Check activity is listed in reverse chronological order, beginning with the most recent action. From this screen, you can also select to view detailed information for a particular refund action.

DARC — Accesses the Check Activity by Refund Check Info screen (DARC). This screen allows you to view all check activity associated with a particular refund check. All activity for the check is listed in reverse chronological order, beginning with the most recent action. From this screen, you can also change the check status for the most recent action associated with the check and display detailed check status information for a particular action.

DARI — Accesses the Check Activity by Refund Info screen (DARI). This screen allows you to view all check activity associated with a particular refund. All check activity associated with the refund is listed in reverse chronological order, beginning with the most recent action. From this screen, you can also change the check status for the most recent action associated with the refund and display detailed check status information for a particular action.

DASI — Accesses the Refund Check Activity by Store Info screen (DASI). This screen allows you to view all refund check activity associated with a particular store for a specified time period. Activity is listed in reverse chronological order, beginning with the most recent action. From this screen, you can also select to view detailed information for a particular refund.

DGLE — Accesses the General Ledger Event screen (DGLE). This screen allows you to view all the general ledger events associated with a particular refund. Ledger events are listed in reverse chronological order, beginning with the most

recent event. From this screen, you can also add a general ledger event for an existing refund. A general ledger event describes a particular action taken for a refund such as issuing a refund check, re-issuing a refund check, or *earmarking* a refund check.

DMCK — Accesses the Manual Check Reference Maintenance screen (DMCK). This screen allows you to add refund and check information for manually disbursed refund checks.

Core Product Menu

The Core Product Menu is displayed when you select the CORE item from the BASE24 Virtual Menu. The Core Product Menu, shown on the following page, gives you access to the following files, tables, and functions, assuming you have the proper security:

CATT = Customer Allowed Transaction Table
CSRC = Customer Service Representative screens
CSTT = Customer Table
FCF = File Control File
IMTF = Internal Message Translation File
IRCF = Institution Routing Configuration File
ISF = Interface Security File
ITLF = ITS Transaction Log File
LCF = Log Configuration File
PCDF = Processing Code Definition File
PIT = Personal Information Table
THCF = Transaction History Configuration File
TTSC = Transaction Type by Source Code Table
VCD = VRU Configuration Data

These files, tables, and functions are described briefly on the following pages. Refer to the manuals listed below for additional information on these files, tables and functions.

- The ***BASE24 Core Files and Tables Maintenance Manual*** contains file and table maintenance information for all core files and tables.
- The ***BASE24 Remote Banking Customer Service Support Manual*** describes all of the customer service representative screens available from the CSRC entry.


```

BASE24-ADMN  MENU                LLLL      YY/MM/DD  HH:MM  01 OF 01
                C O R E  P R O D U C T  M E N U

                CATT              CSRC              CSTT              FCF
                IMTF              IRCF              ISF              ITLF
                LCF              PCDF              PIT              THCF
                TTSC              VCD

```

```

***** BASE24 *****
FILE DESTINATION:
F1-ENTER DATA  F9-NEXT PAGE      F11-PREVIOUS PAGE  F10-PRINT  F12-HELP

```

Core Product Menu Items

The following paragraphs describe the items available on the Core Product Menu. If you do not have security access to an item, it will not be displayed.

CATT — Accesses the Customer Allowed Transaction Table (CATT). The CATT contains one row for each supported combination of FIID, customer profile, and processing code. The CATT defines the remote banking transactions that can be performed for each customer ID. The Processing Code Definition File (PCDF) defines the remote banking transactions that can be performed at the institution level. A transaction must be defined in both the CATT and PCDF before it can be performed by a customer.

CSRC — Accesses the remote banking (BASE24-telebanking and BASE24-billpay) customer service representative (CSR) screens. These screens allow customer service representatives to execute BASE24-telebanking and BASE24-billpay transactions and inquire on previous transaction activity on behalf of a calling customer.

The BASE24-telebanking CSR screens allow customer service representatives to verify the authenticity of the calling customer, obtain account balances, perform immediate transfers, and inquire on previous transaction activity.

The BASE24-billpay CSR screens allow customer service representatives to sign up new customers for the BASE24-billpay service, provide customer account and vendor information, execute payment, transfer, and balance inquiry transactions, schedule payment and transfer transactions, enter customer loan applications, inquire on currently scheduled payments and transfers, and inquire on previous transaction activity.

CSTT — Accesses the Customer Table screens. These screens access the Customer Table (CSTT), Customer/Account Relation Table (CACT), and the Customer/Personal ID Relation Table (CPIT). The CSTT contains one row for each customer, which can be a business or an individual. Each CSTT row defines the authorization parameters and usage accumulation information for the customer. The CACT maintains the application accounts for each customer, and the CPIT relates personal information for each individual associated with the customer's ID.

FCF — Accesses the File Control File (FCF). The FCF contains version records for several core files and tables that are audited by the HP NonStop Transaction Monitoring Facility (TMF), and, therefore, cannot be renamed. When refreshing these files or tables, the Enscribe Refresh process or SQL Refresh process develops a new name for each file or table it builds instead of renaming the old file or table. The Enscribe Refresh process or SQL Refresh process then updates the FCF with the version indicator of the new file or table.

IMTF — Accesses the Internal Message Translation File (IMTF). The IMTF is used by the Internal Message Translation Interface object to map authorization destinations to symbolic process names and DPC numbers. The IMTF is used any time the Integrated Authorization Server process needs to communicate with an external authorizer (for example, the Pathway- or XPNET-based Billpay Server processes) or interface process (for example, ISO Host Interface process) that is not object-oriented.

IRCF — Accesses the Institution Routing Configuration File (IRCF). The IRCF contains one record for each possible combination of product ID, route profile, route code, and account type in the system. Through configuration of IRCF records, institutions define the routing and authorization parameters for their remote banking transactions.

ISF — Accesses the Interface Security File (ISF). The ISF contains the information and parameters required by integrated transaction services (ITS) interfaces for PIN encryption, PIN translation, message authentication, and dynamic key management.

ITLF — Accesses the ITS Transaction Log File (ITLF). The ITLF contains one record for each remote banking transaction processed by a BASE24 integrated transaction services (ITS) application during the business day. The ITLF records are extracted daily to provide detailed transaction data to participating institutions for processing at their host computer systems. The ITLF provides an audit trail of remote banking transaction activity that the operator can peruse from the beginning or end of the file.

LCF — Accesses the Log Configuration File (LCF). The LCF controls the logging destination for each ITS object that logs information to the ITS Transaction Log File (ITLF). The LCF contains one record for each group of ITS objects that logs information to the ITLF.

PCDF — Accesses the Processing Code Definition File (PCDF). The PCDF contains one record for each combination of product ID, route profile, and processing code that is supported by an institution. PCDF records control the following at the institution level for each remote banking transaction: whether the transaction is supported, the type of account or accounts that are affected by the transaction, the routing code for the transaction, and whether an advice is required for the transaction. Subsets of the transactions defined in the PCDF can be established at the customer level in the Customer Allowed Transaction Table (CATT).

The transaction descriptions defined in default PCDF records are displayed on BASE24-telebanking customer service representative (CSR) screens and BASE24-telebanking issuer reports.

PIT — Accesses the Personal Information Table (PIT). The PIT contains one row for each person associated with a row in the Customer Table (CSTT). The PIT is required if BASE24-billpay is installed and is optional if only BASE24-telebanking is installed. Each PIT row contains personal information used to uniquely identify the person such as name, address, phone number, government ID, and date of birth. This information can be used to authenticate calling customers by customer service representatives and is also used in billing and remittance processing. PIT screens are also used to maintain the customer IDs associated with individuals in the Customer/Personal ID Relation Table (CPIT).

THCF — Accesses the Transaction History Configuration File (THCF). The THCF is used by the BASE24-telebanking product to determine which Transaction History File (THF) contains the information needed to authorize a transaction history inquiry, since multiple THFs can be maintained.

TTSC — Accesses the Transaction Type By Source Code Table (TTSC). The TTSC contains one row for each unique combination of source code and BASE24-telebanking or BASE24-billpay transaction type allowed at a customer service representative (CSR) terminal. Currently, the TTSC is used only to restrict the transactions that can be performed at a CSR terminal.

VCD — Accesses the VRU Configuration Data (VCD) screens. The VCD screens are used to configure the Remote Banking Standard Interface and the Customer Service Interface. These interfaces are responsible for communicating with remote banking endpoint devices and customer service representative (CSR) terminals, respectively.

Customer Service

The Customer Service Product Menu is displayed when you select the CUSTOMER SERVICE item from the BASE24 Virtual Menu. The Customer Service Product Menu, shown below, gives you access to the following files and functions, assuming you have the proper security:

CCIF = Customer/Cardholder Information File
CIS = Customer Information screens
CSTP = Customer Service Transaction Perusal

These files and functions are described briefly on the following pages.

```
BASE24-ADMN  MENU                LLLL      YY/MM/DD  HH:MM  01 OF 01
                   C S    P R O D U C T  M E N U
                   CCIF          CIS          CSTP
```

```
***** BASE24 *****
FILE DESTINATION:
F1-ENTER DATA  F9-NEXT PAGE      F11-PREVIOUS PAGE  F10-PRINT  F12-HELP
```

Customer Service Product Menu Items

The following paragraphs describe the items available on the Customer Service Product Menu. If you do not have security access to an item, it will not be displayed.

CCIF — Accesses the Customer/Cardholder Information File (CCIF). The CCIF contains information about the primary cardholder (and optionally the secondary cardholder) that is not found elsewhere in BASE24, such as the cardholder's address and telephone number.

CIS — Accesses the Customer Information (CIS) screens. The CIS screens allow you to view data from the Cardholder Authorization File (CAF), Customer/Cardholder Information File (CCIF), Positive Balance File (PBF), and Customer/Cardholder Memo File (CCMF) from one set of screens. Customer service personnel can also add, update, and delete memo information and update the card status from the CIS, or add, delete, and update a CCMF record.

CSTP — Accesses the Customer Service Transaction Perusal (CSTP) screens. The CSTP screens allow you to peruse cardholder transaction activity from one central set of screens, regardless of the BASE24 product that originally processed the transaction. Transactions from the BASE24-atm Transaction Log File (TLF) and the BASE24-pos Transaction Log File (PTLF) are sorted and displayed based on transaction time. Detail information about a transaction is available.

Frequent Shopper User Menu

The Frequent Shopper User Menu is displayed when you select the FREQUENT SHOPPER item from the BASE24 Virtual Menu. The Frequent Shopper User Menu, shown below, gives you access to the following user screens and functions, assuming you have the proper security.

CRAT = Customer Retailer Activity
 DEMO = Demographics Maintenance
 DPND = Dependents Maintenance
 IDST = ID Status/Maintenance
 JID = Joined ID Stat/Maintenance
 MHIS = Move ID History Maintenance
 NAMS = Name Search
 PHIS = Purchase History
 VADJ = Value Adjustment

These user screens and functions are described on the following pages.

```

BASE24-ADMN  MENU                LLLL      YY/MM/DD  HH:MM  01 OF 01
                                F S      U S E R   M E N U

      CRAT      DEMO      DPND      IDST
      JID      MHIS      NAMS      PHIS
      VADJ

***** BASE24 *****
                        FILE DESTINATION:
F1-ENTER DATA  F10-PRINT  F12-HELP  F16-EXIT  SF16-LOGOFF
  
```

Frequent Shopper User Menu Items

The following paragraphs describe the items available on the Frequent Shopper User Menu. If you do not have security access to an item, it will not be displayed.

CRAT — Accesses the Customer Retailer Activity screen (CRAT). The CRAT allows you to view a summarized display of all retail activity recorded in the Customer Retailer Activity Table for a customer ID in descending start date order.

DEMO — Accesses the Demographics Maintenance screen (DEMO). The DEMO allows you to enter product codes (for example, a Universal Product Code, a European Article Number, or any other code specific to the retailer) that represent the buying habits, hobbies, and interests of the customer.

DPND — Accesses the Dependents Maintenance screen (DPND). The DPND allows you to define a customer's dependents. From this screen, you can indicate whether a dependent is a coapplicant, the gender of the dependent, and the dependent's date of birth.

IDST — Accesses the ID Status/Maintenance screen (IDST). The IDST allows you to view and maintain the status and personal/corporate information about a BASE24-frequent shopper customer. You access the information for a customer by entering the customer's primary or alternate ID. From this screen, you can also obtain the current balance for the customer.

JID — Accesses the Joined ID Status/Maintenance screen (JID). The JID allows you to view a summary of all the customer IDs joined to a primary ID as well as all alternative IDs associated to the primary ID. Joining IDs allows you to use the available points for redemption from the ID to which the ID used in a transaction is joined. From this screen, you can also join or disjoin IDs as well as associate or disassociate alternate IDs with a primary ID.

MHIS — Accesses the Move ID History Maintenance screen (MHIS). The MHIS allows you to move the ID history from one ID to another. This is required anytime the customer's ID is lost, stolen, or damaged.

NAMS — Accesses the Name Search screen (NAMS). The NAMS allows you to search for a customer either by customer name or by an alternate ID. When searching by a customer name, you can use wildcard characters if you do not know the full customer name or the exact spelling of the name. When searching by alternate ID, you must provide the ID. In any search, you must provide the type of ID, the state or province identifier (if applicable for the type of ID), the retailer/program indicator, and the retailer/program ID.

PHIS — Accesses the Purchase History screen (PHIS). The PHIS allows you to view a summarized display of all purchase transactions for a customer. From this screen, you can also view detailed information for an individual purchase transaction.

VADJ — Accesses the Value Adjustment screen (VADJ). The VADJ allows you to adjust the purchase, redemption, and earned values for a customer. The screen displays various balances before and after the value adjustment is made.

Kernel/IEP Product Menu

The Kernel/IEP Product Menu is displayed when you select the KERNEL/IEP item from the BASE24 Virtual Menu. The Kernel/IEP Product Menu, shown on the following page, gives you access to the following files and functions, assuming you have the proper security:

AORF = Assign/Object Relationship File
APRF = Assign/Process Type Relationship File
ASGN = Assign File
AWB = Assign Warmboot screens
CCS = Configuration Control screens
DBG = Debug screen
DEST = Destination File
EMT = Extended Memory Table File
EORF = EMT/Object Relationship File
EPRF = EMT/Process Type Relationship File
ESF = Event Suppression File
EWB = EMT Warmboot screens
LPF = Log Permission Process Partition File
LWB = LCONF Warmboot screen
OBJ = Object File
PORF = Process/Object Relationship File
PRO = Process File
PTF = Process Type File
PWB = Param Warmboot screen
SCM = Source Class Map File
SCS = Server Control screens
SCT = Server Class Type File
SPRF = Server Class Type/Process Relationship File
STAT = Status screens
TRC = Trace Control screens

These files and functions are described briefly on the following pages. Refer to the ***BASE24 ITS Kernel Files Maintenance Manual*** for additional information on these files and functions. Refer to the ***BASE24 IEP Configuration Manual*** for more information on the DEST.

```

BASE24-ADMN  MENU                LLLL      YY/MM/DD  HH:MM  01 OF 01
                        K N L  P R O D U C T  M E N U

      AORF                APRF                ASGN                AWB

      CCS                DBG                DEST                EMT

      EORF                EPRF                ESF                EWB

      LPF                LWB                OBJ                PORF

      PRO                PTF                PWB                SCM

      SCS                SCT                SPRF                STAT

      TRC

***** BASE24 *****
                        FILE DESTINATION:
F1-ENTER DATA  F9-NEXT PAGE      F11-PREVIOUS PAGE  F10-PRINT  F12-HELP

```

Kernel/IEP Product Menu Items

The following paragraphs describe the items available on the Kernel/IEP Product Menu. If you do not have security access to an item, it will not be displayed.

AORF — Accesses the Assign/Object Relationship File (AORF). The AORF establishes relationships between Logical Network Configuration File (LCONF) assigns and ITS objects and is used by the ASSIGN WARMBOOT command. The assign/object relationship indicates that the object uses the assign and that the object can be warmbooted to reread the specific assign.

APRF — Accesses the Assign/Process Type Relationship File (APRF). The APRF establishes relationships between Logical Network Configuration File (LCONF) assigns and process types. The relationship indicates that the process type uses the assign and that processes of that type may be warmbooted to reread the specific assign. The records in this file are used to validate the process type during assign warmboot processing.

ASGN — Accesses the Assign File (ASGN). The ASGN identifies the assigns that should be listed on the Assign Warmboot (AWB) screen. Only assigns for which a specific assign warmboot is to be provided need to be defined in this file. If an assign is not supported by the Assign Warmboot command, it does not need to be defined in this file.

AWB — Accesses the Assign Warmboot (AWB) screens. The AWB screens allows you to select specific LCONF assigns to be reread. An assign warmboot should be done any time a change is made to an assign and the assign can be reread.

CCS — Accesses the Configuration Control (CCS) screens. The CCS screens provide a mechanism to build or rebuild extended memory tables as needed. When an extended memory table is selected to be rebuilt from these screens, the Configuration Control server process starts the Extended Memory Table Build utility. The Extended Memory Table Build utility then rebuilds the specified extended memory table.

DBG — Accesses the Debug (DBG) screen. The DBG screen allows you to run a particular ITS environment process or Queue process under control of the HP NonStop debugging tool, INSPECT, for debugging purposes.

DEST — Accesses the Destination File (DEST). The DEST is used by Integrated Endpoint processes to route messages to destinations based on the source class and message class associated with the given message. The Integrated Endpoint process is an object-oriented process running in the integrated transaction services (ITS) environment.

EMT — Accesses the Extended Memory Table File (EMT). The EMT defines all extended memory tables used in the ITS environment that can be warmbooted to the process control subsystem. The EMT contains one record for each extended memory table in the ITS environment that can be warmbooted.

EORF — Accesses the EMT/Object Relationship File (EORF). The EORF defines relationships between all objects and extended memory tables that can be reread in the ITS environment. Only extended memory tables for which a specific extended memory table warmboot command is to be provided need to be defined in this file. The file contains one record for each object and extended memory table combination.

EPRF — Accesses the EMT/Process Type Relationship File (EPRF). The EPRF defines relationships between extended memory tables and all process types that access these tables. The records in this file are used to validate the process type for processes to receive an extended memory table warmboot. There is one EPRF record for each extended memory table that can be reread and each process type that uses the extended memory table.

ESF — Accesses the Event Suppression File (ESF). The ESF defines events that are to be suppressed at either the process or network level. The file contains one record for each event that is to be suppressed in some way. Event suppression is used to reduce the number of times a log message is generated, and is needed in an environment where multiple processes report the same error condition or when an error is continually reported by the same process.

EWB — Accesses the EMT Warmboot (EWB) screens. The EWB screens allow you to select extended memory tables for which the processes that access those extended memory tables are to be warmbooted. An EMT warmboot should be done any time a change is made to the extended memory table data stored on disk. The rebuilt extended memory table is not used until all the processes that access the table are warmbooted.

LPF — Accesses the Log Permission Process Partition File (LPF). The file maps ranges of subsystem identifiers (SSIDs) to specific Log Permission processes (LPPs) responsible for arbitration when determining whether an event is to be logged. This allows log permission requests to be spread across multiple Log Permission processes, effectively distributing the workload of network-level event suppression processing.

LWB — Accesses the LCONF Warmboot (LWB) screen. The LWB screen allows you to select objects to be warmbooted with all applicable Logical Network Configuration File (LCONF) assigns and params. Using this screen, you can warmboot a single object, a few objects, or all objects in the ITS environment.

OBJ — Accesses the Object File (OBJ). The OBJ defines all objects used in the ITS environment and their process control capabilities. All kernel, integrated endpoint (IEP), and core objects used in your ITS environment must be defined to the OBJ. Each record defines the object and its processing parameters.

PORF — Accesses the Process/Object Relationship File (PORF). The PORF defines relationships between processes and objects. An entry in this file must exist for each occurrence of an object in an ITS process. This file is accessed

during assign warmboot, param warmboot, LCONF warmboot, EMT warmboot, and status command processing to automatically determine the processes associated with the objects to which the warmboot or status command is directed.

PRO — Accesses the Process File (PRO). The PRO defines all processes used in the ITS environment, including both ACI- and customer-defined processes as well as Queue processes, that can receive process control commands. Each entry in the Process File defines the HP NonStop Process Pair Directory (PPD) name assigned to the process, the type of process (from the Process Type File), and indicates whether the process functions as a Queue process.

PTF — Accesses the Process Type (PTF). The PTF defines all process types used in the ITS environment, including both ACI-defined and customer-defined process types, to the process control subsystem. The process type is typically a category for a particular type of process and is used by the process control subsystem in determining which processes should receive particular commands.

PWB — Accesses the Param Warmboot (PWB) screen. The PWB screen allows you to select objects to be warmbooted with Logical Network Configuration File (LCONF) parameters. Using this screen, you can warmboot a single object, a few objects, or all objects in the ITS environment.

SCM — Accesses the Source Class Map File (SCM) screen. The SCM is used to relate source class values (for example, class element values) defined in the NEFS with objects in the ITS environment. A source class is a user-defined grouping of processes or stations, or of endpoints, from which the system can receive messages. A source class provides a mechanism for ensuring that messages from a particular source are processed by a particular object in the ITS environment.

SCS — Accesses the Server Control (SCS) screens. The SCS screens allow you to send general server control commands such as logon or key exchange commands to processes in the ITS environment. These commands cannot be entered through the XPNET network operator control facilities.

SCT — Accesses the Server Class Type File (SCT). The SCT defines all server class types used in the ITS environment to the process control subsystem, including both ACI-defined and any customer-defined server class types. Each server class type accesses a different Integrated Server Control File (ISCF). Each record describes the server class type and provides the LCONF assign for the control file associated with the server class type.

SPRF — Accesses the Server Class Type/Process Relationship File (SPRF). The SPRF defines all the relationships between server class types and processes in the ITS environment. Processes that are identical in nature and object composition are related to the same server class. Each process can be related to only one server class. All processes of the same server class type look at the same Integrated Server Control File (ISCF) for commands entered by the process control subsystem.

STAT — Accesses the Status (STAT) screens. The STAT screens allow you to send a status command to ITS objects within a process. The information generated by the status command can vary with each object to which the command is sent. All response data to the status command is generated using HP NonStop Event Management System (EMS) events.

TRC — Accesses the Trace Control (TRC) screens. The TRC screens allow you to start, stop, and inquire about traces executed on ITS environment objects within a process. Traces are used as a tool in debugging and to verify that transaction processing is proceeding as anticipated. Trace response data can be displayed on a terminal or written to a trace file.

Mail Product Menu

The Mail Product Menu is displayed when you select the MAIL item from the BASE24 Virtual Menu. The Mail Product Menu, shown below, gives you access to the following files and functions, assuming you have the proper security:

HMBF = Host Mail Box File
MBAF = Mail Box Address File
MBF = Mail Box File
SMA = Send Mail Terminal screen

These files and functions are described briefly on the following page.

```
BASE24-ADMN  MENU                      LLLL      YY/MM/DD  HH:MM  01 OF 01
                                M A I L  P R O D U C T  M E N U
                                HMBF          MBAF          MBF          SMA
```

```
***** BASE24 *****
FILE DESTINATION:
F1-ENTER DATA  F9-NEXT PAGE      F11-PREVIOUS PAGE  F10-PRINT  F12-HELP
```


MAIL Product Menu Items

The following paragraphs describe the items available on the Mail Product Menu. If you do not have security access to an item, it will not be displayed.

HMBF — Accesses the Host Mail Box File (HMBF). The HMBF contains one record for each mail message to a host that is being stored for later delivery.

MBAF — Accesses the Mail Box Address File (MBAF). The MBAF contains one record for each terminal that is part of a broadcast list. This file is used in routing mail messages to multiple terminals.

MBF — Accesses the Mail Box File (MBF). The MBF contains one record for each mail message to be sent to a terminal.

SMA — Accesses the Send Mail Terminal (SMA) screen. The SMA screen allows you to add records to the MBF. Functions allowed on the SMA screen include sending a message directly to a terminal, storing a message for a terminal in the MBF, and sending a message to several terminals using a broadcast list.

Operator Product Menu

The Operator Product Menu is displayed when you select the OPERATOR FUNCTIONS item from the BASE24 Virtual Menu. The Operator Product Menu, shown below, gives you access to the following files and functions, assuming you have the proper security:

DCT = Device Control Terminal
 EXTR = Extract screens
 LMCF = Log Message Configuration File
 NCS = Network Control Supervisor screen
 REFR = Refresh screens
 XNI = X.25 Network Inquiry screen

These files and functions are described briefly on the following pages. For additional information on the DCT screens, refer to the ***BASE24 Device Control Manual***. For additional information on the EXTR and REFR screens, refer to the ***BASE24 Refresh and Extract Operators Manual***. For additional information on the LMCF, refer to the ***BASE24 Log Message Reference Manual***. For additional information on the NCS and XNI screens, refer to the ***NET24-XPNET Network Control Operations***.

```

BASE24-ADMN  MENU                      LLLL      YY/MM/DD  HH:MM  01 OF 01
              O P R      P R O D U C T  M E N U

              DCT          EXTR          LMCF          NCS

              REFR          XNI
  
```

```

***** BASE24 *****
FILE DESTINATION:
F1-ENTER DATA  F9-NEXT PAGE      F11-PREVIOUS PAGE  F10-PRINT  F12-HELP
  
```

Operator Product Menu Items

The following paragraphs describe the items available on the Operator Product Menu. If you do not have security access to an item, it will not be displayed.

DCT — Accesses the Device Control (DCT) screens. The device control functions allow you to operate and maintain terminals in the BASE24 product family, including ATMs, POS terminals, and attended teller terminals. DCT screens also cover the process control function which allows you to reinitialize or warmboot selected processes.

EXTR — Accesses the Extract (EXTR) screens, which allow you to extract selected BASE24 product files to tape or disk for processing or analysis by a host computer.

LMCF — Accesses the Log Message Configuration File (LMCF). This screen allows you to modify the text or severity of standard-format log messages in the LMCF.

NCS — Accesses the Network Control Supervisor (NCS) screen, which allows you to perform network control facility functions, such as starting, stopping, and modifying lines, stations, and processes; changing the Network Environment File (NEF); and terminating a BASE24 transaction processing system.

REFR — Accesses the Refresh screens, which allow you to initiate full- and partial-file refreshes of selected BASE24 files. Refresh tapes are generated by a host after it has completed batch processing for a reporting day.

XNI — Accesses the X.25 Network Inquiry screen, which allows you to send supervisory inquiries into data networks via the DATAPAC RAPID service in Canada and send RAPID READ messages through selected User Circuits.

POS Product Menu

The POS Product Menu is displayed when you select the POS item from the BASE24 Virtual Menu. The POS Product Menu, shown on the following page, gives you access to the following files and functions, assuming you have the proper security:

ACNF	=	ACI Standard Device Configuration File
ADMN	=	Administrative Card File
ARSP	=	ACI Standard Device Response File
AST	=	Authorization Selection Table
CAPF	=	Card Authorization Parameters File
CART	=	Check Authorization Routing Table File
CHF	=	Card History File
CRED	=	Credibility History screen
CRTA	=	CRT Administration Maintenance screens
CRUF	=	CRT Authorization Retailer Usage File
CSEC	=	CRT Authorization Security File
HPCF	=	Hypercom Configuration File
HPTC	=	Hypercom T7 Configuration File
MCNF	=	Merchant Terminal Configuration File
MHCF	=	Merchant Host Configuration File
MREG	=	Merchant Regulation E File
MRF	=	Multiple Referrals screen
MRSP	=	Merchant Terminal Response Display File
MTCF	=	Merchant Totals Configuration File
NNF	=	National Negative Card File
OLT	=	Online Transaction screen
PRDF	=	POS Retailer Definition File
PRF	=	POS Referral File
PRG	=	POS Report Generator screen
PTD	=	POS Terminal Data files
PTLF	=	POS Transaction Log File screen
RTBL	=	Routing Table File
SVHF	=	Stored Value History File
VVT	=	VISA II Terminal and Configuration Maintenance File

These files and functions are described briefly on the following pages. Refer to the following manuals for additional information on these files and functions.

- The ***BASE24-pos Standard POS Device Support Manual*** contains information on file maintenance functions for the ACNF and ARSP.

- The ***BASE24-pos Hypercom Device Support Manual*** contains information on file maintenance functions for the HPCF and HPTC.
- The ***BASE24-pos Files Maintenance Manual*** contains information on file maintenance functions for the ADMN, AST, CAPF, CART, NNF, PRDF, PTD, PTLF, and RTBL.
- The ***BASE24-pos Settlement and Reporting Manual*** contains information on file maintenance functions for the PRG.
- The ***BASE24-pos Stored Value Support Manual*** contains information on file maintenance functions for the SVHF.
- The ***BASE24-pos Merchant Host Interface Manual*** contains information on file maintenance functions for the MCNF, MHCF, MREG, MRSP, and MTCF.
- The ***BASE24-pos VISA II Device Support Manual*** contains information on file maintenance functions for the VVT.
- The ***BASE24-pos CRT Authorization and CRT Administration Manual*** contains file maintenance and function information for the CHF, CRED, CRTA, CRUF, CSEC, MRF, OLT, and PRF.

```

BASE24-ADMN  MENU                LLLL      YY/MM/DD  HH:MM  01 OF 01
                P O S      P R O D U C T  M E N U
                ACNF      ADMN      ARSP      AST
                CAPF      CART      CHF      CRED
                CRTA      CRUF      CSEC      HPCF
                HPTC      MCNF      MHCF      MREG
                MRF      MRSP      MTCF      NNF
                OLT      PRDF      PRF      PRG
                PTD      PTLF      RTBL      SVHF
                VVT

```

```

***** BASE24 *****

```

POS Product Menu Items

The following paragraphs describe the items available on the POS Product Menu. If you do not have security access to an item, it will not be displayed.

ACNF — Accesses the ACI Standard Device Configuration File (ACNF). The ACNF contains records used in the configuration of the BASE24 Standard POS Device Handler (SPDH). The ACNF contains processing parameters, the fields to be included in requests and responses for each transaction type, the fields within messages to be encrypted using message authentication codes (MACs), and information to be downline loaded to the POS terminal.

ADMN — Accesses the Administrative Card File (ADMN). The ADMN contains one record for each administrative card or employee ID in the logical network. Each record contains transaction codes that specify administrative transactions the user is permitted to perform.

ARSP — Accesses the ACI Standard Device Response File (ARSP). The ARSP contains a table of terminal responses in up to three different languages. The BASE24 Standard POS Device Handler (SPDH) uses this file to display a response on the terminal.

AST — Accesses the Authorization Selection Table File (AST). The AST contains records for retailer sponsors or terminal owners in the logical network. Each record defines authorization routing parameters for a given transaction, including the primary authorizer, up to two secondary authorizers, and a default action for each card service supported by the retailer. AST records also contain special parameters such as floor limits and specify whether the card issuer is on-us or not-on-us.

CAPF — Accesses the Card Authorization Parameters File (CAPF). The CAPF contains one record for each card type supported by institutions that use the Parametric Authorization method. Each record contains authorization criteria beyond those defined in the Cardholder Authorization File (CAF) and Positive Balance File (PBF), including checks for account delinquency, credit overlimit, single purchase, and single cash advance. The CAPF is used to authorize requests that exceed the cardholder's limits, including authorization requests on accounts that are delinquent.

CART — Accesses the Check Authorization Routing Table File (CART). The CART contains information that defines how check authorization transactions are routed to the host. The CART contains one record for each routing group that processes check authorization transactions. If check authorization transactions are not supported, the CART does not exist.

CHF — Accesses the Card History File (CHF). The CHF contains one record for each cardholder who has been issued a credit or debit card by the participating institution. Each record contains the credit card history for the previous twelve months and the debit card history for the previous six months for each account owned by an institution using the BASE24-pos CRT Authorization add-on product. Personal information pertaining to the primary and secondary cardholders, such as name, address, home and work telephone numbers, and social security numbers, is also contained in each record. The CHF is used by the BASE24-pos CRT Authorization add-on product to perform referral processing. The CHF is created and maintained by the Enscribe Refresh process via the full-file refresh function, and can also be updated using a terminal screen.

CRED — Accesses the Credibility History (CRED) screen. The CRED screen contains credit and debit history information taken from the Cardholder Authorization File (CAF), the Positive Balance File (PBF), and the Card History File (CHF). The CRED screen allows you to analyze a cardholder account and determine whether a referral request should be approved or declined. This screen makes it possible for you to take other cardholder credit and debit history factors into consideration besides those displayed on the POS Referral File (PRF) screen. The CRED screen is used with the BASE24-pos CRT Authorization add-on product.

CRTA — Accesses the two CRT Administration Maintenance (CRTA) screens. The CRTA screens allow you to enter and reverse sales draft transactions and to enter chargeback and representation transactions. The selected transaction is sent to the appropriate authorizing entity for approval or denial. The CRTA screens are used with the BASE24-pos CRT Administration add-on product.

CRUF — Accesses the CRT Authorization Retailer Usage File (CRUF). The CRUF contains limits and accumulators for transactions processed via the BASE24-pos CRT Authorization add-on product. These transactions include merchandise returns, adjustments to merchandise returns, reversals on merchandise returns, and reversals on merchandise return adjustments.

CSEC — Accesses the CRT Authorization Security File (CSEC). The CSEC allows institutions to restrict CRT authorization operators from performing certain transactions and functions on the Online Transaction (OLT) screen and the POS Referral File (PRF) screen. The CSEC is used with the BASE24-pos CRT Authorization add-on product.

HPCF — Accesses the Hypercom Configuration File (HPCF), which is used for Hypercom T4, T5, and T6 terminals. The HPCF contains records used in the configuration of the Hypercom Device Handler (HPDH) process. The HPCF contains processing parameters, message authentication code (MAC) information, and information to be down loaded to the POS terminal.

HPTC — Accesses the Hypercom T7 Configuration File (HPTC), which is used for Hypercom T7 terminals. The HPTC contains records used in the configuration of the Hypercom Device Handler (HPDH) process. The HPTC contains processing parameters, message authentication code (MAC) information, and information to be down loaded to the POS terminal.

MCNF — Accesses the Merchant Terminal Configuration File (MCNF). The MCNF contains one record for each terminal group controlled by a Merchant Host Interface (MHI) process. Each record contains processing information, request and response matrixes for transaction use, and down load data.

MHCF — Accesses the Merchant Host Configuration File (MHCF). The MHCF contains one record for each data processing center (DPC) that communicates with a Merchant Host Interface (MHI) process. Each record contains processing information specific to that DPC, including processing flags and station tables. MHCF records also contain host message formats, timer limits, and request/response sequences.

MREG — Accesses the Merchant Regulation E File (MREG). The MREG contains Regulation E data for specified terminals. Data in the MREG must be in compliance with Regulation E requirements, and this data overrides the corresponding data in the POS Terminal Data files (PTD) when a particular set of conditions are set.

MRF — Accesses the Multiple Referrals (MRF) screen. The MRF screen allows you to view pending referrals for a specified retailer ID and select referrals for further processing. Referrals selected for further processing are displayed on the POS Referral File (PRF) screen. The MRF screen is used with the BASE24-pos CRT Authorization add-on product.

MRSP — Accesses the Merchant Terminal Response Display File (MRSP). The MRSP contains a table of merchant terminal responses in up to three different languages. MRSP records are used by the Merchant Host Interface (MHI) process to format terminal response text for the merchant host.

MTCF — Accesses the Merchant Totals Configuration File (MTCF). The MTCF contains one record for each terminal included in a totaling group. The Merchant Host Interface (MHI) process uses totaling groups to obtain group totals for a retailer (group) subtotals request.

NNF — Accesses the National Negative Card File (NNF). The NNF contains one record for each restricted credit card. The NNF is used to add restricted cards manually to the national negative files (for example, INEG, BNEG, ANEG), which are normally updated by the Enscribe Refresh process.

OLT — Accesses the Online Transaction (OLT) screen. The OLT screen allows you to enter transaction requests made by a retailer, modify existing transactions displayed on the screen, or display a transaction for viewing. The OLT screen also allows you to access the POS Referral File (PRF) screen for a selected transaction. The OLT screen is used with the BASE24-pos CRT Authorization add-on product.

PRDF — Accesses the POS Retailer Definition File (PRDF). The PRDF contains one record for each retailer in the logical network. Each PRDF record defines the characteristics of the POS retailer, including POS transaction authorization, routing, and settlement reporting parameters. The PRDF is used to validate POS transactions.

PRF — Accesses the POS Referral File (PRF). The PRF allows you to override authorization responses online for referrals, based on cardholder information contained on the screen. The PRF is used with the BASE24-pos CRT Authorization add-on product.

PRG — Accesses the POS Report Generator (PRG) screen. The PRG screen allows you to generate periodic reports from information maintained in the POS Institution Reporting File (PIRF) and the POS Retailer Reporting File (PRRF). These reports display debits, credits, and adjustments for POS terminals, retailers, and institutions in the logical network for a specified period of time.

PTD — Accesses the POS Terminal Data files (PTD). The PTD files define the characteristics of the POS terminal, including the transaction security methods, terminal owner, logging and transaction data, floor limits, card type, and the POS retail transaction set. They are also used to accumulate transaction and settlement counts and amounts and preserve transaction context.

Data entered on PTD screens is actually stored in different files, depending on the type of terminal being defined. For Merchant Host Interface, Hypercom, and Standard POS Device Handler (SPDH) terminals, dynamic and static data is stored in the POS Terminal Data Dynamic File—general data (PTDD1) and POS Terminal Data Static File—general data (PTDS1), respectively. For all other types of POS terminals, data from the PTD screens is stored in the POS Terminal Data File (PTDF).

PTLF — Accesses the BASE24-pos Transaction Log File (PTLF) Key screen. Using the PTLF Key screen, users can access specific transaction records in the PTLF. The PTLF contains one record for each transaction occurring at a POS terminal in the logical network during a business day and one record for each transaction occurring at POS terminals in the logical network during a business day for a particular retailer. The PTLF contains records for both cardholder transactions and terminal balancing transactions. One PTLF is maintained for each business day, and each PTLF can be saved for the number of days specified in the Logical Network Configuration File (LCONF). The PTLF provides an audit trail of POS cardholder activity, which the operator can peruse from the beginning or the end of the file.

RTBL — Accesses the Routing Table File (RTBL). The RTBL identifies allowable authorization destination processes and their associated codes for routing point-of-sale transactions. Any authorization destination code entered in the AST must have a matching code and symbolic process name specified in the RTBL.

SVHF — Accesses the Stored Value History File (SVHF). The SVHF gets written to whenever a record is added to the POS Transaction Log file (PTLF) for every Stored Value transaction. It is configurable to not log to the SVHF if the database of record is not on BASE24.

VVT — Accesses the VISA II Terminal and Configuration Maintenance File (VVT). The VVT contains configuration and terminal information for VISA II terminals.

Refunds User Menu

The Refunds User Menu is displayed when you select the REFUNDS item from the BASE24 Virtual Menu. The Refunds User Menu, shown below, gives you access to the following user screens and functions, assuming you have the proper security

ACTA = Refund Activity by Address
ACTF = Refund Activity by Refund
ACTI = Refund Activity by ID
ACTP = Refund Activity by Purchase
CMTS = Comments
NSEA = Name Search
SPAS = Address Swap
VREF = Mail Refund Transactions
VSAL = View Sales History

These user screens and functions are described briefly on the following pages.

```
BASE24-ADMN  MENU                LLLL      YY/MM/DD  HH:MM  01 OF 01
                                R F N D   U S E R   M E N U
                                ACTA      ACTF      ACTI      ACTP
                                CMTS      NSEA      SPAS      VREF
                                VSAL
```

```
***** BASE24 *****
FILE DESTINATION:
F1-ENTER DATA  F10-PRINT  F12-HELP  F16-EXIT  SF16-LOGOFF
```

Refunds User Menu Items

The following paragraphs describe the items available on the Refunds User Menu. If you do not have security access to an item, it will not be displayed.

ACTA — Accesses the Refund Activity by Address screen (ACTA). This screen allows you to view all refund activity based on an address. From this screen, you can update the status of the address. For a specified refund, you can update the refund status, the ID related to the refund, the ID status, the privileged attribute, and the letter type.

ACTF — Accesses the Refund Activity by Refund Info screen (ACTF). This screen allows you to view refund activity by date and store, along with additional filters of terminal, transaction sequence number, reason code, and refund status. For a specified refund, you can update the refund status, the ID related to the refund, the ID status, the privileged attribute, and the letter type.

ACTI — Accesses the Refund Activity by ID screen (ACTI). This screen allows you to view refund activity based on the customer's ID. From this screen, you can update a customer's name, ID status, privileged attribute, address, and address status. For a specified refund, you can update the refund status, the ID related to the refund, the ID status, the privileged attribute, and the letter type.

ACTP — Accesses the Refund Activity by Orig Purchase screen (ACTP). This screen allows you to view refund activity by date, store, terminal, and transaction sequence number to examine refund activity against a particular sales receipt. For a specified refund, you can update the refund status, the ID related to the refund, the ID status, the privileged attribute, and the letter type.

CMTS — Accesses the Comments and Add Comments screens (CMTS). These screens allow you to view and add comments related to a particular customer ID, customer address, original purchase receipt, refund request, or check status.

NSEA — Accesses the Name Search screen (NSEA). This screen allows you to search for a customer name and ID by entering the customer's ID type and state or province along with a full or partial customer name. You can use wildcard characters if you do not know the full customer name or the exact spelling of the name. From this screen, you can also delete customer names and IDs.

SPAS — Accesses the Secondary to Primary Address Swap screen (SPAS). This screen allows you to view the primary address along with up to six secondary addresses at one time for the customer ID corresponding to the refund. From this screen, you can select a secondary address to become the primary address for the customer ID.

VREF — Accesses the Mail Refund Transactions screen (VREF). This screen allows you to view all the refund transactions being mailed as a check for a store for a specified date range. From this screen, you can also update or enter address and name information to complete a refund request when this information could not be entered at the point-of-sale (POS) terminal.

VSAL — Accesses the View Original Sales History screen (VSAL). This screen allows you to view the original sales history for a refund by date and store, along with additional filters of terminal and transaction sequence number.

Retail Configuration Menu

The Retail Configuration Menu is displayed when you select the RETAIL CONFIGURATION item from the BASE24 Virtual Menu. The Retail Configuration Menu, shown below, gives you access to the following configuration screens and functions, assuming you have the proper security.

ACT = Application Configuration
 ART = Authorization Routing
 EACT = External Auth Configuration
 FSCS = Fund Scheme Configuration
 IDTD = ID Type Configuration
 LCT = Check Authorization Limits Configuration
 MERC = Merchant I/F Configuration
 MSG = Error Message Configuration
 PCDU = Postal Code Update
 RATD = Rating Configuration
 RETL = Retailer Configuration
 RLCT = Refund Limits Configuration
 STOR = Store Configuration
 STPD = State/Prov Configuration

The configuration screens and functions are described briefly on the following pages.

```

BBASE24-ADMN  MENU                      LLLL      YY/MM/DD  HH:MM  01 OF 01
                R E T L    C O N F I G U R A T I O N    M E N U

                ACT          ART          EACT          FSCS
                IDTD         LCT          MERC          MSG
                PCDU         RATD         RETL          RLCT
                STOR         STPD
  
```

```

***** BASE24 *****
                FILE DESTINATION:
F1-ENTER DATA  F10-PRINT  F12-HELP  F16-EXIT  SF16-LOGOFF
  
```

Retail Configuration Menu Items

The following paragraphs describe the items available on the Retail Configuration Menu. If you do not have security access to an item, it will not be displayed.

ACT — Accesses the Application Configuration screen. This screen is used to maintain the Application Configuration Table (ACT), which contains one row for each parameter used system-wide by specific retail product modules and procedures.

ART — Accesses the Authorization Routing screen. This screen is used to maintain the Authorization Routing Table (ART), which configures the processes used to route messages between Merchant Interface/Authorization processes that reside under different XPNET networks on different physical HP NonStop nodes. You do not need to configure or maintain the ART if you are using only one XPNET network or multiple XPNET networks on one physical HP NonStop node.

EACT — Accesses the External Authorization Configuration screen. This screen is used to maintain the External Authorization Configuration Table (EACT), which identifies the third-party authorizer interface process defined within the system. The data within the EACT is used to configure the processing of transactions to be sent to a third-party authorizer (for example, TeleCheck). If your system does not use a third-party authorizer, you do not need to configure or maintain the EACT.

FSCS — Accesses the Funding Scheme Configuration screen (FSCS). This screen allows you to maintain the funding scheme and rate tier configuration for a retailer and maintains the Funding Scheme Table (FST) and Funding Rate Tier Table (FRTT).

This configuration screen is specific to the BASE24-frequent shopper product. If this product is not installed, this item will not be displayed.

IDTD — Accesses the ID Type Configuration screen. This screen is used to maintain the ID Type Description Table (IDTD), which allows you to view, add, delete, and update ID Types. You can maintain the following information on this screen: numeric and alphabetic codes for the type of ID, check digit algorithm used for the ID, description of the ID Type, and retention periods for the ID Types.

LCT — Accesses the Check Authorization Limits Configuration screens (LCT). The LCT is comprised of two screens—the Period Limits screen and the Transaction Limits screen—that allow you to set period and per-transaction limits for the following levels: retailer, region, district, store, payment type, and rating.

This screen is specific to the BASE24-check auth product. If this product is not installed, this item will not be displayed.

MERC — Accesses the Merchant Interface Configuration screen (MERC). The MERC defines processing parameters for the Merchant Interface/Authorization processes defined within the system on the Merchant Interface Configuration Table (MICT).

MSG — Accesses the Error Message Configuration screens (MSG). The MSG allows you to modify the text for screen messages that can appear on the retail configuration or user screens. The MSG accesses the Message Table (MSGT).

PCDU — Accesses the Postal Code Update screen. This screen allows you to view and update information related to a postal code such as the city name within the postal code, the state or province in which the postal code is located, and the country in which the postal code is located. From this screen, you can also delete postal codes.

RATD — Accesses the Rating Configuration screens (RATD). The RATD screens is composed of two screens—the Rating Description screen and the System Ratings Definitions screen—used to configure all of the ratings used in the system. These ratings apply to all check writers and must be the same for all retailers in your system. The RATD screens maintain the Application Configuration Table (ACT) and the Rating Description Table (RATD)

This screen is specific to the BASE24-check auth product. If this product is not installed, this item will not be displayed.

RETL — Accesses the Retailer Configuration screens (RETL). The RETL screens is composed of up to eleven active screens—three retail base screens, three Check Authorization-specific screens, four Refunds-specific screens and one Check Disbursements screen—that allow you to configure retailer attributes. These screens maintain the following tables: Partial Line Item Table (PLIT) Payment Configuration Table (PMNT), Retailer Configuration Table (RCT), Retailer Negative Source Table (RNST), Sales History Configuration Table (SHCT), and Status Retention Period Table (SRPT).

RLCT — Accesses the Refund Limits Configuration screen (RLCT). The RLCT allows you to set up various limits by retailer ID, region, district, store, and period. The RLCT maintains the Refund Period Limits Configuration Table (RLCT) and the Refund Transaction Limits Configuration Table (RTLTL).

This screen is specific to the BASE24-refunds product. If this product is not installed, this item will not be displayed.

STOR — Accesses the Store Configuration screens (STOR). These screens allow you to configure the following information for an individual store: store ID and name, address and telephone number, check digit validation, and various retail product-specific parameters. The STOR screens are composed of up to three active screens—one retail base screen, one BASE24-check auth screen, and one BASE24-refunds screen. The STOR maintains the Store Configuration Table (SCT).

STPD — Accesses the State/Province Configuration screen (STPD). This screen allows you to view valid state and province codes and to define edit masks for each state. This screen maintains the Application Configuration Table (ACT) and the State/Province Description Table (STPD).

Teller Product Menu

The Teller Product Menu is displayed when you select the TELLER item from the BASE24 Virtual Menu. The Teller Product Menu, shown below, gives you access to the following files and functions, assuming you have the proper security:

NBF = No Book File
 ORF = Override Response File
 TRPT = Teller Report Generator
 TTDF = Teller Terminal Data File
 TTF = Teller Transaction File
 TTLF = Teller Transaction Log File
 WHFF = Warning/Hold/Float File

These files and functions are described briefly on the following pages. Refer to the manuals listed below for additional information on these files and functions.

- The *BASE24-teller Files Maintenance Manual* contains file maintenance information for the NBF, ORF, TTDF, TTF, TTLF, and WHFF.
- The *BASE24-teller Settlement and Reporting Manual* contains file maintenance information for the TRPT.

```

BASE24-ADMN  MENU                      LLLL      YY/MM/DD  HH:MM  01 OF 01
              T L R    P R O D U C T  M E N U

              NBF      ORF      TRPT      TTDF
              TTF      TTLF      WHFF
  
```

```

***** BASE24 *****
              FILE DESTINATION:
F1-ENTER DATA  F9-NEXT PAGE    F11-PREVIOUS PAGE  F10-PRINT  F12-HELP
  
```

Teller Product Menu Items

The following paragraphs describe the items available on the Teller Product Menu. If you do not have security access to an item, it will not be displayed.

NBF — Accesses the No Book File (NBF). The NBF contains one record for each transaction processed on a passbook account. NBF records are arranged in chronological order. This file stores passbook account transactions until they can be posted to the customer's passbook. When a transaction is posted, the NBF record is flagged. The flagged record is deleted from the NBF when the Enscribe Refresh process performs file refresh.

ORF — Accesses the Override Response File (ORF). The ORF contains one record for each response code supported by the BASE24-teller product. Each teller transaction receives a response code, which indicates whether the transaction is approved or denied. Using the ORF, an institution can also establish an override level enabling a denial response to a transaction request to be overridden, thereby allowing the transaction to be approved at the appropriate override level.

TRPT — Accesses the Teller Report Generator (TPRT) screen. The TRPT screen allows you to generate daily audit and periodic statistical reports. The Reports program uses the TTLF as input on daily audit reports. For periodic reports, the Reports program uses the Report Transaction by Time Block File (RTTB) and Report Transaction by Type File (RTTF). From this screen, you can also generate a network settlement summary report.

TTDF — Accesses the Teller Terminal Data File (TTDF). The TTDF contains one record for each teller terminal in the logical network. TTDF records define the characteristics of the teller terminal, including the terminal owner and device-dependent data. This file is also used to preserve transaction context.

TTF — Accesses the Teller Transaction File (TTF). The TTF contains one record for each type of transaction that can be processed for an institution. TTF records determine whether a transaction is supported, the type of account or accounts that are affected by the transaction, the operator level required to perform the transaction, and the process responsible for authorizing the transaction.

TTLF — Accesses the Teller Transaction Log File (TTLF). The TTLF contains one record for each transaction originating at a teller terminal processed by the BASE24-teller product during a business day. TTLF records are extracted daily to provide detailed transaction data to participating institutions for processing at their host computer systems. Transaction data includes logon and logoff transactions, financial transactions, and inquiries and updates to the Cardholder Authorization File (CAF), Positive Balance File (PBF), No Book File (NBF), Stop Payment File (SPF), and Warning/Hold/Float File (WHFF).

WHFF — Accesses the Warning/Hold/Float File (WHFF). The WHFF contains one record for each institution- or customer-initiated warning. It can also contain one record for each institution- or customer-initiated hold or deposit float request that has been issued in the logical network. Hold and deposit float request records are placed in the WHFF based on the TLR-WRITE-HLDS-DEP-FLOATS param in the Logical Network Configuration File (LCONF).

WHFF records are used to make institutions and tellers aware that there may be problems with the transaction requests associated with certain accounts or cards.

5: Setting Up BASE24 User Access Security

This section shows you how to establish security for operators using the BASE24 user access system. It explains how BASE24 user access security works, shows you the screens on which you can set up security restrictions, describes all the fields in which you can enter data on these screens, and defines functions specific to the screens. This section also contains procedures you can follow to add, update, and delete security records for operators using the BASE24 system.

BASE24 User Access Security

The BASE24 user access system enables institutions to establish individual user access restrictions for each employee via security records. Security records define what system entities an employee can access, when an employee can access the system, which files and tables the employee can access, which terminals the employee can use, and what functions the employee can perform.

In addition to file and tables restrictions, time restrictions, and institution restrictions, employees can also be restricted from database maintenance functions such as reading, adding, updating, and deleting file records or table rows. For example, your institution can allow customer service personnel to read and update file records or table rows, while restricting them from adding or deleting file records or table rows.

When logging on to the BASE24 user access system, employees identify themselves to the system via a user name and their own unique password. The BASE24 system then reads that employee's security record to identify the restrictions that employee is operating under.

Access to BASE24 operational security is flexible and is designed hierarchically. For example, some employees can have access to many security records, while other employees have access to very few records or none at all. Your institution can also grant managers the ability to set up or modify security records for their individual employees. These managers can also modify their own security records, but cannot grant themselves more access to the system than they already have.

Security records can be set up for groups of employees or for individuals. Note that employees cannot grant other employees greater access to the system than they have themselves. Initially, only one logon, SUPER/SUPER, has access to all files, tables, functions, and terminals. This logon can also be used to set up and modify all security records. ACI recommends that a second logon, PROD/SUPER, be established that has access to all files, tables, functions, and terminals. This second logon should be used to provide dual control over the system.

Restricting Access to the BASE24 System

The BASE24 user access security system allows you to restrict BASE24 user access to authorized users and to specify the files, tables, and functions each user can access. It uses the following files to store each user's security information:

Security File (SEC) — Maintains the names of all users authorized to access the BASE24 user access system.

User/FIID Relation File (UFIR) — Specifies the financial institutions (FIIDs), regions, and branches each user can access.

User/Product File Relation File (UPFR) — Contains security information for each operator. The purpose of the UPFR is to build the BASE24 Virtual Menu, according to the files, tables, and functions to which the operator has been given access. The UPFR is also used to build each user's product menus.

Network Control Security Profile File (NCSP) — Contains network control command profiles. These profiles specify whether a network control command can be performed and whether the command is audited.

Network Control Security Specification File (NCSS) — Associates a network control command profile with a specified user, thus determining the network control commands to which the user has access.

Functionally, the SEC, UFIR, UPFR, and NCSS are accessed using a single set of security screens. In order to access BASE24 products via the BASE24 user access system, a user must have at least one record in the SEC, UFIR, and UPFR. A record in the NCSS is also recommended for each user. The NCSP can be accessed from SEC screen 4, or it can be accessed separately from the Base Product Menu.

The security files work together to restrict access to the BASE24 user access system. Access is restricted by the following:

- Logical network
- Financial institution
- Region
- Branch
- XPNET node
- Time of day
- Terminal
- Screen
- Access code
- Network control command

These restrictions are explained in more detail on the following pages.


Note: The FIID AUTH FILE SEGMENT INDICATORS fields on screens 5 and 6 of the Institution Definition File (IDF) indicate which products a specific institution supports. However, if these fields indicate that a product is not supported, the screens for that product are still displayed unless the institution's security records are set up to not allow access to those screens. If data is entered on screens of a product the institution does not support, that data is not written to disk or used by the BASE24 product in any way.

Logical Network


The logical network is the highest-level security element in the system. To perform any files maintenance, tables maintenance, or function, you must have access to the logical network affected. If you do not have access to a particular logical network, you cannot access any file, table, or function for that logical network.

A complete set of security files consists of the SEC, UFIR, UPFR, NCSS and NCSP. The records in these files determine your access to the files, tables, and functions in each network. Two or more logical networks can share a set of security files; or each logical network can maintain its own set of security files.

If logical networks share a set of security files, as illustrated below, you have the same access privileges and restrictions for all logical networks sharing your security record.



If each logical network maintains its own set of security files, as shown in the following illustration, you must have a record with the same alias and password in each set of security files in each network. Because each network has its own set of files, you could have different access privileges and restrictions for each logical network.



Specifying logical network access gives you the ability to limit access to specific databases. For example, in a system with several logical networks operating on remote HP NonStop nodes, operators at each site could be given access to the logical network operating on the local node only. This would allow the operators to perform work on their local nodes, but not on the remote nodes. A system administrator might be given access to all nodes.

Financial Institution

A BASE24 user access system can be used by multiple financial institutions. Specifying the financial institutions that each user can access allows access to each financial institution's data to be limited to personnel within the financial institution or authorized personnel at the service provider. In this way, personnel at one

financial institution cannot make changes to the configuration, cardholder, or customer information for another financial institution. The financial institutions each user can access are restricted on SEC screen 2.

Region and Branch

Regions, as defined in the BASE24 user access system, are subdivisions of financial institutions. Branches are subdivisions of regions. The region and branch access parameters are checked only when users attempt to access device-controlling files and processes. When you restrict BASE24 user access by region and branch, you are, in effect, determining the devices to which the user has access. The regions and branches each user can access are restricted on SEC screen 2.

XPNET Node

The XPNET nodes to which authorized users can send commands from a network control facility and Device Control Terminal (DCT) screens can be restricted. The XPNET nodes for which authorized users can perform functions using the EXTR, REFR, XNI, PCT, and ICF files and functions can also be restricted. These XPNET nodes are specified on SEC screen 1.

Time of Day

The time of day during which each user is authorized to access the BASE24 user access system can be restricted by specifying a start and end time on SEC screen 1. These times are used to deny BASE24 system access to the specified user before the start time and after the end time. When the end time has expired, a user accessing the BASE24 system is logged off the system. However, to prevent work being lost, the system waits until the user attempts to change screens or return to a menu before logging him or her off.

Terminal

The terminals from which each user can access the BASE24 user access system can be restricted on SEC screen 1.

Screen

Each screen in the BASE24 user access system must be secured individually. You can grant access to individual screens on SEC screen 3 by specifying at least one access code for each screen to which you want to grant access. Screens are identified on SEC screen 3 by acronym, page number, product indicator, and description.

In general, when giving a user access to some of the screens for a specific file, table, or function, you should give a user access to screen 1 in addition to any subsequent screen. Screen 1 contains key fields that are used to access a file or table. If a user does not have access to screen 1, the user can clear a subsequent screen to which he or she has access by pressing the **F8** key. The system then places the cursor on the key fields of that screen, allowing the user to enter data in the key fields. The user can then perform read, add, delete, and update functions as the user's security record allows.

Access Codes

Access levels for each screen can be restricted. The possible access levels are:

- READ = Allows the user to read file records or table rows from the specified screen. On utility or operation function screens, this access level grants execution access.
- ADD = Allows the user to add file records or table rows from the specified screen.
- DELETE = Allows the user to delete file records or table rows from the specified screen.
- UPDATE = Allows the user to update file records or table rows from the specified screen.

You can specify screen access restrictions in the ACCESS field on SEC screen 3 by entering R (for read), A (for add), D (for delete), or U (for update). At least one of these access levels must be specified, or the screen cannot be accessed. Also, whenever update or delete access is granted, the system ensures that read access is also granted. This is because a file record or table row cannot be updated or deleted unless the record or row already exists. For example, if a user is granted only update access to a screen, the system automatically adds read access for that user.

Network Control Commands

Network control command security is configurable. At its most basic level, access to network control commands is determined by access to a network control facility. If a user has access to a network control facility, he or she can execute any network control command. Two additional network control command security measures can be taken, either separately or in conjunction with each other. These measures are to limit network control command access by command and to audit network control commands.

Command access limitations allow you to specify for each user whether the user has access to each network control command. When command access limitations are enabled, each user is assigned a security profile in his or her security record. The security profile indicates, for each network control command, whether the user has access to the network control command. More than one NCSS record can exist for each user. This would enable independent command access profiles for individual XPNET nodes.

Command auditing creates an audit trail of network control command activity. When auditing is enabled by itself (without command access limitations), an event message is generated each time a network control command is executed. The event message identifies the user who issued the command, the XPNET node affected, the terminal the command was issued from, and the command that was performed.

When command auditing and command access are used together, the security profile can be used to control not only whether the user can perform the command, but also whether execution of the command is audited. In this way, system administrators can audit selected commands or users. For example, new network control operators could be assigned a special security profile that gives audited access to some or all commands. Or, security profiles could be created that allow users to execute inquiries without being audited, while commands that change the system configuration are audited.

Enabling Command Access Limitations

Command access limitation is enabled using the ENABLE-SECURITY parameter in the definition for the NCPI Server process in the PATHCONF. The following values are valid for the ENABLE-SECURITY parameter. The default is ON.

ON	= Security is enabled.
OFF	= Security is disabled.
DETAIL	= Security is enabled, and invalid logon attempts are logged to EMS.

If the value of this parameter is set to **DETAIL**, the NCPI Server process generates an event message when a **SET USER** command fails because an invalid user name or password was entered or the password has expired.

If security is enabled, an additional parameter can be configured to govern whether security violation messages are returned for commands that reference objects on an XPNET node to which the user does not have command access. This parameter is the **XN-LOCK** parameter. Valid values are as follows. The default is **ON**.

- ON** = Security violation messages are not returned for objects on the node to which the user does not have access.
- OFF** = Security violation messages are returned for each object on the node to which the user does not have access.

If a user attempts to issue a command referencing multiple XPNET nodes and the user does not have command access to one or more of the nodes, this parameter specifies if invalid security messages are generated for each object. If the **XN-LOCK** parameter is set to **OFF**, a security violation message is generated for each object referenced by the command. If the **XN-LOCK** parameter is set to **ON**, no security violation message is generated. In essence, setting the **XN-LOCK** parameter to **ON** prevents the user from learning the names of objects on nodes to which he or she does not have command access.

In addition, two files are required to limit network control command access. These files are the Network Control Security Profile File (NCSP) and the Network Control Security Specification File (NCSS). Command access limitations (Y for access, N for no access, and A for audit access) are specified on the NCSP screen. SEC screen 4 (which accesses the NCSS) allows you to specify the network control security profile to be associated with a user's security record.

Enabling Command Auditing

Command auditing is enabled using the ENABLE-AUDIT parameter in the definition for the NCPI Server process in the PATHCONF. The following values are valid for the ENABLE-AUDIT parameter. The default is OFF. By itself, command auditing does not require any setup in the security files.

- ON = Enables command auditing by generating one event message for each command issued.
- OFF = Disables command auditing.
- DETAIL = Enables command auditing by generating one event message for each object involved in a multiple-object command. Detail auditing applies only to object management commands.

Assigning Access

ACI recommends that BASE24 user access system security be established in a hierarchical manner, as explained below. If possible, responsibility for assigning access should be delegated by SUPER/SUPER to PROD/SUPER, and by PROD/SUPER to group leaders, who assign access to the remaining system users.

This hierarchical method of assigning access is described below and illustrated on the following page. SUPER/SUPER gives access to PROD/SUPER, and PROD/SUPER delegates the authority to assign access to group leaders. The group leaders create security records for individual users.

SUPER/SUPER


Overall responsibility for system security should be vested in a security control officer, with a user name, or alias, of SUPER/SUPER. SUPER/SUPER has unlimited access to the user access system. SUPER/SUPER can be one person or several people.

When a BASE24 system is first started, SUPER/SUPER is the only user name that has a security record. As a result, SUPER/SUPER is the only USER NAME entry on the BASE24 Logon screen that results in a successful logon. The required password for SUPER/SUPER on first logon is eight zeros, but this must be changed immediately to a confidential password.

SUPER/SUPER has access to all products and functions operating in the BASE24 system, including update access to the security files. SUPER/SUPER belongs to group number 255 with a user number of 255. Each unique user name is associated with a group number and user number. Only users in group 255 can assign access privileges to users belonging to other group numbers.

PROD/SUPER

Once SUPER/SUPER has successfully logged on, ACI recommends that he or she delegate a backup security officer, with a user name like PROD/SUPER, to be responsible for assigning security access to all BASE24 users. PROD/SUPER should enter the initial password provided by the SUPER/SUPER user in the PASSWORD field at first logon but immediately select a unique password. Like SUPER/SUPER, PROD/SUPER should have access to all BASE24 products and functions and be assigned to group number 255. Belonging to group 255 allows



PROD/SUPER to assign access privileges to users with other group numbers.
PROD/SUPER can be assigned any user number other than 255, which is reserved
for SUPER/SUPER.

Once PROD/SUPER has complete access to the BASE24 system, he or she can assign access to all system users. This can be done in two ways. PROD/SUPER can assign access privileges to each user individually, or he or she can delegate this authority to other individuals via the assignment of different group numbers.

Group Leaders

Delegation of authority for assigning access might work as follows: PROD/SUPER divides BASE24 users into groups based on the functions they perform (for example, files and tables maintenance, network control, etc.). PROD/SUPER assigns each group a leader, who is responsible for assigning access to users in that group.

Each group leader is given a different alias and group number and granted only those access privileges pertaining to the system functions of his or her group. No group leader is assigned to group number 255, so no group leader can assign access to another group. In fact, group leaders do not have read access to the security records of users outside their group (that is, users with different group numbers).

Users

Group leaders, in turn, assign access to all users in their group. Each user in a group is given the same group number but assigned a unique user number and alias. Users are granted access to only those files, tables, and functions essential to the duties they perform. The same person may be a group leader or user in two or more different groups, but that individual must have a unique alias in each group.

Rules for Assigning Access

The following rules govern the assigning of system access:

- Users responsible for assigning access (SUPER/SUPER, PROD/SUPER, or group leaders) must have read, add, update, and delete access to all four security screens to enable them to grant various levels of access to other system users.
- Users cannot give themselves additional access privileges.

- Users cannot give other users access to a file, table, or function to which they themselves do not have access.
- Users with a group number other than 255 cannot build security records for users with a group number different from theirs.

Using Security Screens to Assign Access

Access is assigned and updated on four security screens. Security records must be updated beginning on SEC screen 1, which contains the key data fields. SEC screen 2 contains fields for specifying the financial institutions, regions, and branches to which each user has access. SEC screen 3 contains fields for specifying each screen the user has access to and the level of user access for each screen. SEC screen 4 contains a field to associate a network control command profile with the user's security record. In addition, the contents of the specified profile can be viewed from screen 4, but the access defined in the profile cannot be changed from the security screens. To change the network control command access defined in the profile, the profile record in the NCSP must be changed.

SEC screens 2, 3, and 4 have multiple pages. SEC screen 2 has as many pages as it takes to list the financial institutions, regions, and branches to which the user has access. SEC screen 3 has as many pages as it takes to list the screens to which the user has access. SEC screen 4 has as many pages as it takes to list all network control commands. The commands are separated by type, so there are multiple pages of system commands, line commands, process commands, station commands, and device commands.

Descriptions of the fields and functions available on these screens are presented later in this section. After the field and function descriptions, instructions for adding, updating, and deleting security records on these screens are presented.

Other Security Features

The BASE24 user access security system also provides inactivity timers, password features, and the ability to limit unsuccessful logon attempts by users. These features provide additional security for the BASE24 system and are explained below.

Inactivity Timers

Once you have logged on to the BASE24 user access system, you can perform tasks and access screens, files, and tables according to your security record. ACI recommends that when you must leave the terminal for a period of time, you log off the BASE24 system. This prevents other individuals from accessing the system with your security records.

However, it is not always possible to log off the system. In these situations, the BASE24 user access security system automatically logs users off after a configurable period of time in which the user has not initiated any activity on the system. When a user is automatically logged off, the BASE24 Logon screen is displayed.

Passwords

As you enter your password on the BASE24 Logon screen, it is not displayed. This protects your password from being seen as you log on to the system. Although your password never appears on screen, ACI recommends that you change your password periodically. Your institution may also require you to change your password at specified time intervals. If your institution is using complex passwords (i.e., a mix of alpha, numeric, upper and lower case and special characters), passwords are stored in the user security database in encrypted form using a Secure Hash Algorithm (SHA 1) that is not reversible, ensuring that passwords cannot be extracted in clear form from the database. If your institution is not using complex passwords, passwords are encrypted using the DES algorithm. For more information on configuring standard or complex passwords, see the “Configuring Passwords” subsection in section 3.

Logon Attempt Limitations

Your institution can limit the number of consecutive unsuccessful logon attempts users can initiate before they are locked out of the BASE24 user access system. Unsuccessful logon attempts can be limited for all users by configuring a param in the Logical Network Configuration File (LCONF). Your institution can also establish individual limitations in the security records of specific users.

For example, all users may be allowed three consecutive logon attempts using the LCONF param. However, user A may be allowed five unsuccessful logon attempts using his or her own security record. The limit in an individual's security record always overrides the limit set in the LCONF.

When a user is locked out of the BASE24 system, the user's manager must reinstate the user by accessing the user's security record and setting the logon attempt counter to zero. Refer to the procedures later in this section for more information on reinstating a locked out user.

Security Screen 1

SEC screen 1 allows you to read and update base security records. Base records are the records contained in the Security File (SEC). This screen also gives you access, via the other three Security screens, to records in the other security files—the User/FIID Relation File (UFIR), User/Product File Relation File (UPFR), and the Network Control Security Specification File (NCSS). The key to these records, the user's alias, is entered on this screen. The alias is the entry that the user must make in the USER NAME field on the BASE24 Logon screen in order to access the BASE24 system.

This screen also allows you to assign a group number and user number to the specified user. Like the alias, the combination of the group number and the user number must uniquely identify the user. That is, two users with the same group number cannot have the same user number.

When an operator reads, adds or updates any file record or table row in the BASE24 system, the group number and user number of the operator are stored in the record or row, together with the action taken and the time. This information is displayed on the information line whenever the record or row is read. The group number and user number are also stored in the Online Maintenance File (OMF) records. The OMF contains detailed records of each record or row read, added, updated, or deleted in the logical network. For reads, an OMF record is written only if the record being read contains sensitive cardholder data, e.g., a PAN. For more information on the OMF, refer to the DDLs located on the BA_{xx}DDL (_{xx} = current release number) subvolume. For information on the OMF audit reports, refer to Section 6 in this manual.

The group number and user number give auditors the ability to trace which operator made a change in the system, without having the operator's alias directly associated with a file record or table row.

SEC screen 1 also allows you to restrict the user's access to the BASE24 system by logical network, XPNET node, time of day, terminal, length of inactivity, and number of unsuccessful logon attempts.

Unless logical networks are sharing the SEC, the user is restricted to the logical network you are logged on to when you assign user access. If you want to give the user access to additional logical networks, you must change networks. You can do this by returning to the BASE24 Logon screen and logging on to another network or by entering a different network in the NEW LOGICAL NETWORK ID field and pressing the **F13** or **F16** key.

Note: Currently, you cannot change logical networks when accessing an SQL table maintenance screen.

SEC screen 1 is shown below, followed by descriptions of its fields and function keys.

```

BASE24-BASE SECURITY FILE          LLLL          YY/MM/DD HH:MM 01 OF 04
ALIAS:                            GROUP NUMBER:    USER NUMBER:      0

      GROUP NAME:                  USER NAME:

START TIME (HHMM): 00:00          END TIME (HHMM): 00:00
MAX LOGON ATTEMPTS:                LOGOFF INTERVAL: 00000 (SECS)
CUR LOGON ATTEMPTS: 00            MASKING FLAG (Y/N):
      PASSWORD:                  VERIFY:

      LIST THE RESOURCE NODES THIS USER CAN ACCESS:

_____|_____|_____|_____|
_____|_____|_____|_____|
_____|_____|_____|_____|

      LIST THE TERMINALS THIS USER CAN LOGON WITH:

_____|_____|_____|
_____|_____|_____|
_____|_____|_____|

***** BASE24 *****
NEW PAGE:          FILE DESTINATION:          NEW LOGICAL NETWORK ID:
F12-HELP  F14-FIID/REGN/BRCH  F15-FILE ACCESS  SF7-NCS ACCESS  SF15-ADD LIKE

```

ALIAS — A name that uniquely identifies a BASE24 user. This is the name that must be entered in the USER NAME field on the BASE24 Logon screen. The only restriction on the alias entry is that it cannot be SUPER/SUPER unless the user has logged on as SUPER/SUPER.

Field Length: 1–16 alphanumeric characters
 Required Field: Yes
 Default Value: No default value
 Data Name: SEC.PRIKEY.ALIAS

GROUP NUMBER — The group number identifying the group to which the user name entered in the ALIAS field is assigned. The group number field is intended to identify a particular group of BASE24 users. For example, one group number could identify files and tables maintenance operators and another group number could identify network operators. Valid entries range from 0 through 9999.

The **GROUP NUMBER** and **USER NUMBER** fields form an alternate key to the SEC.

Field Length: 1–4 numeric characters
Required Field: Yes
Default Value: The group number of the user currently accessing SEC screen 1.
Data Name: SEC.ALTKEY.USER-GRP

USER NUMBER — A number identifying a specific user within the group identified in the **GROUP NUMBER** field. Valid entries range from 0 through 99999999.

Field Length: 1–8 numeric characters
Required Field: Yes
Default Value: 0
Data Name: SEC.ALTKEY.USER-NUM

GROUP NAME — A name identifying the group number of the specified alias. This optional field is informational only.

Field Length: 1–20 alphanumeric characters
Required Field: No
Default Value: No default value
Data Name: SEC.GRP-DESC

USER NAME — A name identifying the user number of the specified alias. This optional field is informational only.

Field Length: 1–20 alphanumeric characters
Required Field: No
Default Value: No default value
Data Name: SEC.USER-DESC

START TIME — The time the user with the specified alias can begin accessing the BASE24 user access system. Valid entries range from 0000, which represents midnight, to 2359, which represents 11:59 p.m. The value you enter can either

contain the colon (that is, 23:59) or can be placed in the first four positions of the field (that is, 2359). If you do not enter a colon, the system automatically displays your entry with a colon when you add or update this field.

Field Length: 3–5 numeric characters
Required Field: No
Default Value: 00:00
Data Name: SEC.STRT-TIM

END TIME — The time after which the user with the specified alias cannot access the BASE24 system. Valid values range from 0000, which represents midnight, to 2359, which represents 11:59 p.m. The value you enter can either contain the colon (that is, 23:59) or can be placed in the first four positions of the field (that is, 2359). If you do not enter a colon, the system automatically displays your entry with a colon when you add or update this field.

If you enter the default value of 00:00 for both this and the START TIME field, the specified user cannot log on to the BASE24 system. To give the specified user 24-hour access to the BASE24 system, enter 0000 or 00:00 in the START TIME field and 2359 or 23:59 in this field.

Field Length: 3–5 numeric characters
Required Field: No
Default Value: 00:00
Data Name: SEC.END-TIM

MAX LOGON ATTEMPTS — The maximum number of consecutive failed logon attempts allowed before this particular user is locked out of the BASE24 system. Valid values are 00 through 99. If zeros are entered in this field, the user cannot be locked out of the BASE24 system.

A maximum number of failed logon attempts allowed can also be established for all users via the MAX-LOGON-ATTEMPTS param in the LCONF. The value in this field overrides the LCONF param. If a value is not entered in this field, the MAX-LOGON-ATTEMPTS param is used.

Note: The SUPER/SUPER logon is also controlled by this field; therefore, a user logging on as SUPER/SUPER can be locked out of the BASE24 system the same as any other user. To enable a SUPER/SUPER user to log on once they have been

locked out, another user who has access to the Security File (SEC) must reset the CUR LOGON ATTEMPTS field on this screen to zero for the SUPER/SUPER security record.

Field Length: 2 numeric characters
Required Field: No
Default Value: No default value
Data Name: SEC.SEC-DATA.MAX-LOGON-ATTEMPTS

LOGOFF INTERVAL — The number of seconds this particular user can remain inactive in the BASE24 system before being automatically logged off. A logoff interval can also be established for all users via the LOGOFF-INTERVAL param in the LCONF. The value in the LOGOFF INTERVAL field overrides the LCONF param.

Valid values for the LOGOFF INTERVAL field are 00000 through 32767. A value of 00000 in the LOGOFF INTERVAL field indicates that the value in the LOGOFF-INTERVAL param in the LCONF should be used as the logoff interval. If the LOGOFF INTERVAL field contains the value 00000 and the LOGOFF-INTERVAL param is not configured, users are logged off after an interval of 1024 seconds.

Field Length: 5 numeric characters
Required Field: No
Default Value: 00000
Data Name: SEC.SEC-DATA.LOGOFF-INTERVAL

CUR LOGON ATTEMPTS — The number of consecutive failed logon attempts since the last successful logon to the BASE24 system for this user. This field is incremented by one at every unsuccessful logon attempt and is set to zero at every successful logon. The user is locked out of the BASE24 system when the value in this field equals the maximum number of logon attempts allowed. In that case, the user's supervisor must manually reset this field to zero.

Field Length: 2 numeric characters
Required Field: No
Default Value: 00
Data Name: SEC.SEC-DATA.CUR-LOGON-ATTEMPTS

MASKING FLAG — A flag indicating whether the user can view sensitive data in the clear. If this field contains a value of Y, then sensitive cardholder data, e.g., PANs, on all screens accessed by the user are masked when displayed. The extent of the masking is defined by the AFT-PAN-DIGITS parameter in the Logical Network Configuration File (LCONF). Valid values are as follows:

Y = Mask sensitive data
N = Do not mask sensitive data

Field Length: 1 alphanumeric character
Required Field: No
Default Value: Y
Data Name: SEC.SEC-BASE-INFO.MASKING-FLG

PASSWORD — The password that uniquely identifies a BASE24 user. Initial passwords must be set to unique values for every user and must be changed immediately after the first use.

When adding a new user, the supervisor is required to enter an initial password. This password must follow the complexity requirements specified by the institution, if complex passwords are enabled. The supervisor is required to enter the password twice to avoid the chance of typographical errors.

The new user is required to change the password when logging on to the BASE24 system for the first time. The new password must also meet the institution's complexity requirements.

To change a user's password, the supervisor must update the password on SEC screen 1 according to the institution's complexity requirements. The user must then change the password when logging on to the BASE24 system.

Field Length: 8 alphanumeric characters
Required Field: Yes
Default Value: None
Data Name: SEC.PASSWORD if complex passwords are not enabled.
SEC.PSWD-HIST.PSWD(1) if complex passwords are enabled.

VERIFY — The password that the user entered in the PASSWORD field. The supervisor is required to verify the value entered in the PASSWORD field by re-entering the password in this field.

Field Length: 8 alphanumeric characters
Required Field: Yes
Default Value: None
Data Name: Not applicable

LIST THE RESOURCE NODES THIS USER CAN ACCESS — The names of the XPNET nodes to which the user can send commands from the Network Control Supervisor (NCS), and Device Control Terminal (DCT) screens or perform tasks using the EXTR, REFR, XNI, and ICF files and functions. If the user should have access to all BASE24 XPNET nodes, fill the first RESOURCE NODES field with asterisks (*).

Note: This field was used with XPNET release 2.1, but is not applicable to XPNET releases 3.0 and later.

Field Length: 12 fields of 16 alphanumeric characters each
Required Field: No, data must be entered only if the user must have access to screens that require XPNET node access.
Default Value: No default value
Data Name: SEC.RESOURCE-NODE

LIST THE TERMINALS THIS USER CAN LOGON WITH — The names of the terminals through which the user can access BASE24 user functions. The terminal name should be the HP NonStop SYSGEN name of the terminal, which may include the controller address. If multiple HP NonStop nodes exist, then the system name should also be specified (for example, \SYS1.\$TERM01.#I36Z0). The first position of the terminal name cannot contain a blank or a numeric character.

If you want to give the user access to all terminals connected to the system, fill the first TERMINALS field with asterisks (*).

Field Length: 9 fields of 24 alphanumeric characters each
Required Field: Yes, data must be entered in at least one field.
Default Value: No default value
Data Name: SEC.STA

Function Keys

The function keys used on SEC screen 1 are shown in the following table. The first column shows the BASE24 keys. The second column describes the functions that can be accomplished with these keys on SEC screen 1.

Key	Description
F1	VALIDATE DATA — Checks the data currently displayed on the screen for errors.
F2	READ BASE RECORD — Reads a base record for the specified user. Base records are those records contained in the SEC (as opposed to the records contained in the UFIR, UPFR, or NCSS). The record displayed depends on the key fields you entered on the screen. You can read only records for users with the same group number as yours, unless you are a group number 255 user.
F3	ADD BASE RECORD — Adds a base record for the specified user. Base records are those records contained in the SEC (as opposed to the records contained in the UFIR, UPFR, and NCSS). The record added consists of the values displayed on the screen. You cannot add a record that already exists.
F4	DELETE ALL SECURITY RECORD(S) — Deletes all security records, including records in the SEC, UFIR, UPFR, and NCSS for the specified user. The record deleted consists of the values displayed on all four security screens for the specified user. You cannot delete a record that does not already exist.
F5	UPDATE BASE RECORD — Changes a base record. Base records are those records contained in the SEC (as opposed to the records contained in the UFIR, UPFR, and NCSS). You must enter, overwrite, or blank out the data to be changed on the screen. You cannot update a record that does not already exist.
F6	READ NEXT RECORD — Reads the next record from a file.

Key	Description
F7	GOTO NEW PAGE — Moves you to another screen in the current file. You must identify the screen you want to display in the NEW PAGE field. You must also have access to the new screen.
F8	CLEAR SCREEN — Clears all fields in which you have entered data, replacing them with spaces or default values.
F10	PRINT SCREEN — Sends the currently-displayed screen for printing to the spooler location indicated on the Logon screen.
F12	DISPLAY HELP SCREEN — Displays the help screen for the current screen or file.
F13	CHANGE CURRENT LOGICAL NET — Changes the logical network to the one specified in the NEW LOGICAL NETWORK ID field.
F14	GOTO FIRST PAGE OF FIID/REGN/BRCH INFO — Displays SEC screen 2 if you have read access to screen 2. Otherwise, an error message is displayed. If a record was read from SEC screen 1, this function key reads the UFIR record for the user.
F15	GOTO FIRST PAGE OF SCREEN ACCESS INFO — Displays SEC screen 3 if you have read access to screen 3. Otherwise, an error message is displayed. If a record was read from SEC screen 1, this function key reads the SEC record for file and table access information for the user.
F16	EXIT OR GOTO FILE — Displays the previous screen or menu, or moves you to a new logical network, file, table, or function.

Key	Description
Shift-F7	GOTO FIRST PAGE OF NCS ACCESS INFO — Displays SEC screen 4 if you have read access to screen 4. Otherwise, an error message is displayed. If a record was read from SEC screen 1, these function keys read the NCSS record for the user. The NCSS requires XPNET Release 2.0 or higher. Note: A hyphen connecting two keys indicates the keys are pressed simultaneously (for example, Shift-F7 indicates the Shift and F7 keys are pressed simultaneously).
Shift-F15	ADD SECURITY RECORDS LIKE CURRENT USER — Adds security records identical to those of the current user, unless the user who is logged on is SUPER/ SUPER. These records consist of all records for that user in the SEC, UFIR, UPFR, and NCSS. The ALIAS and USER NUMBER fields must be changed in order to add the new record. The system checks the entered alias against existing records to make sure it is not a duplicate.
Shift-F16	LOGOFF — Logs you off the BASE24 system.

ENTER ALL FIID/REGION/BRANCH RELATIONS THIS USER HAS

ACCESS TO — The identifiers specifying the financial institutions (FIIDs), regions, and branches to which the specified user has access. The FIID is entered in the first four positions of this three-part field. The region identifier is entered in the middle four positions. The branch identifier is entered in the last four positions.

If you want to give the user access to all financial institutions in the logical network, enter asterisks (*) in the first four positions of this field. If you want to give the user access to all regions for a specified FIID or FIIDs, enter asterisks (*) in the middle four positions. If you want to give the user access to all branches within a specified region or regions, enter asterisks (*) in the last four positions.

Field Length: 52 fields of 12 alphanumeric characters each, with each field composed of three 1–4 character entries

Required Field: No

Data Names: UFIR.PRIKEY.FI-INFO.FIID
UFIR.PRIKEY.FI-INFO.REGN
UFIR.PRIKEY.FI-INFO.BRCH

Function Keys

The function keys used on SEC screen 2 are shown in the following table. The first column shows the BASE24 keys. The second column describes the functions that can be accomplished with these keys on SEC screen 2.

Key	Description
F1	VALIDATE DATA — Checks the data currently displayed on the screen for errors.
F5	ADD/DELETE/UPDATE FIID/REGN/BRCH INFO — Enters the data currently displayed on the screen. If the data is new, this function adds it. If the data has been entered over previous data, this function updates the existing data with the new data. If blanks are entered over previous data, this function deletes the existing data.
F7	GOTO NEW PAGE — Moves you to another screen in the current file. You must identify the screen you want to display in the NEW PAGE field. You must also have access to the new screen.

Key	Description
F8	CLEAR SCREEN — Clears all fields in which you have entered data, replacing them with spaces or default values.
F9	READ NEXT PAGE OF FIID/REGN/BRCH INFO — Displays the next page of SEC screen 2.
F10	PRINT SCREEN — Sends the currently-displayed screen for printing to the spooler location indicated on the BASE24 Logon screen.
F11	RETURN TO BASE SECURITY INFO (PAGE 1) — Returns you to SEC screen 1.
F12	DISPLAY HELP SCREEN — Displays the help screen for the current screen or file.
F13	CHANGE CURRENT LOGICAL NET — Changes the logical network to the one specified in the NEW LOGICAL NETWORK ID field.
F14	GOTO FIRST PAGE OF FIID/REGN/BRCH INFO — Returns you to the first page of SEC screen 2.
F15	GOTO FIRST PAGE OF SCREEN ACCESS INFO — Displays SEC screen 3 if you have read access to screen 3. Otherwise, an error message is displayed.
F16	EXIT OR GOTO FILE — Displays the previous screen or menu.
Shift-F7	GOTO FIRST PAGE OF NCS ACCESS INFO — Displays SEC screen 4 if you have read access to screen 4. Otherwise, an error message is displayed. If a record was read from SEC screen 1, the NCSS record is read for the specified user. The NCSS requires either XPNET Release 2.0 or higher. Note: A hyphen connecting two keys indicates the keys are pressed simultaneously (for example, Shift-F7 indicates the Shift and F7 keys are pressed simultaneously).
Shift-F16	LOGOFF — Logs you off the BASE24 system.

Security Screen 3

SEC screen 3 allows you to establish the individual screens that the specified user can access. These screen access records are contained in the Security File (SEC). A user cannot access a BASE24 screen unless he or she has been given access to that screen on SEC screen 3.

Users are considered to have access to a screen when they are able to read, add, update, or delete information on the screen. The read function, designated by the value R, allows users to read records that already exist in a file or rows that already exist in a table. The value R is also used to denote execution access on screens from which functions are performed. The add function, designated by the value A, allows users to add records to the file or rows to the table. The delete function, designated by the value D, allows users to delete records from a file or rows from a table. The update function, designated by the value U, allows users to change existing file records or table rows. Screen access can be given in any combination. If delete or update access is given without read access, the system automatically grants the user read access.

When you access SEC screen 3, only those screens to which you have access are listed. As a result, you can only give another user access to the screens to which you have access. This limitation also applies to the level of access. You can only give another user the same levels of access that you have. For example, if you have only read and update access, you can grant another user read and update access but not read, update, and delete access.

When assigning access, you can enter data in the ACCESS field only. The FILE, PAGE, PRODUCT, and DESCRIPTION OF PAGE fields are system-protected.

To update access, you should either enter new access codes over existing access codes or blank out existing access codes. If you blank out existing codes, user access to that screen is removed. In addition, you must press the **F5** (ADD/DELETE/UPDATE SCREEN ACCESS INFO) key on each SEC screen 3 page containing information you want to update. The **F5** key updates only information entered on the screen 3 page from which it is executed.

The information entered on this screen is used in determining what items should be displayed on the Virtual Menu and product menus for all users except SUPER/SUPER. The items displayed on SUPER/SUPER's menus are all the functions, files, and tables associated with all of the products purchased by SUPER/SUPER's location.

SEC screen 3 is shown below as it would appear to SUPER/SUPER when he or she is giving screen access to PROD/SUPER. Note that so far access has only been assigned to ACNF screens 1, 2, and 3. On these four screens, PROD/SUPER has been given read, add, delete, and update access. Screen 3 fields and functions are described following the screen.

```

BASE24-BASE SECURITY FILE          LLLL          YY/MM/DD HH:MM 03 OF 04
ALIAS:  PROD/SUPER                GROUP NUMBER: 255    USER NUMBER: 254
                                FILE POSITION:
ENTER ACCESS CODES (R,A,D,U) FOR EACH PAGE OF EACH FILE SHOWN BELOW:

FILE      PAGE    PRODUCT      DESCRIPTION OF PAGE      ACCESS
ACNF      1      POS          DIRECTIONS              RADU
ACNF      2      POS          1ST PAGE DATA ALL 3 RECS RADU
ACNF      3      POS          2ND PAGE DATA REC T F & D RADU
ACNF      4      POS          TRANS FIELD MAP
ACNF      5      POS          PAGE 4 OF REC F
ACNF      6      POS          PAGE 5 OF REC F
ACNF      7      POS          PAGE 6 OF REC F
ADMN      1      BASE PS      ADMINISTRATIVE CARD INFO
AORF      1      KERNEL      ASSIGN/OBJECT RELATION
APRF      1      KERNEL      ASSIGN/PROCESS RELATION
ARF       1      BASE INFO    ACCOUNT ROUTING FILE MENU
ARSP      1      POS          DIRECTIONS

RECORD LAST CHANGED: YY/MM/DD HH:MM BY USER: 0255 , 00000255 ADD
***** BASE24 *****
NEW PAGE:          FILE DESTINATION:          NEW LOGICAL NETWORK ID:
F12-HELP F14-FIID/REGN/BRCH F15-FILE ACCESS SF7-NCS ACCESS SF15-ADD LIKE

```

FILE POSITION — The screen entry at which to position the cursor. Valid values include any alphabetic character or characters. You can enter a valid file, table, or function screen acronym such as you would enter in the FILE DESCRIPTION field or you can enter any alphabetic character and the system will move you to the file, table, or function screen acronym that occurs next alphabetically. For example, if you enter ADMN, the cursor will be positioned at the ADMN screen entry. If you enter JJJJ, the cursor will be positioned at the KEYA screen entry. A list of valid acronyms is included in section 1.

This field allows you to easily access the screen access information for a particular file, table, or function. To position the screen display at the screen access information for a particular file, table, or function, enter the file, table, or function screen acronym in this field and press the **F9** key.

Field Length: 1–4 alphabetic characters
 Required Field: No
 Data Name: Not applicable

FILE — The acronym of each file, table, or function screen to which you have access. Refer to the list of valid file destinations provided in section 1.

Note: Even though the Bank Table for the BASE24-billpay product does not have a valid file destination, an acronym of BANK is used to define security access for the table.

Field Length: System-protected
Data Name: UPFR.FILES-LIST.FILE-ID

PAGE — The number of each screen within the specified file, table, or screen function to which you have access.

Field Length: System-protected
Data Name: Not applicable

PRODUCT — The name of the product to which each specified screen belongs.

Field Length: System-protected
Data Name: SEC.SCRN-ACCESS-LIT.SCRN-PROD

DESCRIPTION OF PAGE — A description of the function of each specified screen.

Field Length: System-protected
Data Name: Not applicable

ACCESS — The codes identifying the type of access for each displayed screen you want to give the user identified in the ALIAS field. You can enter only the characters R, A, D, and U in this field, but you can enter them in any order. If you enter U or D, the system automatically enters R. If you do not make an entry, user access to that particular screen is denied. Valid values are as follows:

A = Add. Allows the user to add records to a file or rows to a table.
D = Delete. Allows the user to delete records from a file or rows from a table.
R = Read. Allows the user to read records from a file or rows from a table. For utility or operation function screens, this value denotes execution access.
U = Update. Allows the user to update records from a file or rows from a table.

Field Length:	A variable number of fields, depending on the number of screens displayed, of 1–4 alphabetic characters each (R, A, D, or U)
Required Field:	No
Data Names:	SEC.SCRN-ACCESS-LIST.SCRN-ACCESS.R-ACCESS SEC.SCRN-ACCESS-LIST.SCRN-ACCESS.A-ACCESS SEC.SCRN-ACCESS-LIST.SCRN-ACCESS.D-ACCESS SEC.SCRN-ACCESS-LIST.SCRN-ACCESS.U-ACCESS

Function Keys

The function keys used on SEC screen 3 are shown in the following table. The first column shows the BASE24 keys. The second column describes the functions that can be accomplished with these keys on SEC screen 3.

Key	Description
F1	VALIDATE OVERLAY DATA — Checks the data currently displayed on the screen for errors.
F5	ADD/DELETE/UPDATE SCREEN ACCESS INFO — Enters the data currently displayed on the screen. If the data is new, this function adds it. If the data has been entered over previous data, this function updates the existing data. If blanks are entered over previous data, this function deletes the existing data.
F7	GO TO NEW PAGE — Moves you to the screen number specified in the NEW PAGE field. The new page requested must be within the current file.
F8	CLEAR SCREEN — Clears all fields in which you have entered data, replacing them with spaces or default values.
F9	READ NEXT PAGE OF SCREEN ACCESS INFO — Displays the next page of SEC screen 3 or the page identified in the FILE POSITION field.
F10	PRINT SCREEN — Sends the currently-displayed screen for printing to the spooler location indicated on the BASE24 Logon screen.

Key	Description
F11	RETURN TO BASE SECURITY INFO (PAGE 1) — Returns you to SEC screen 1.
F12	DISPLAY HELP SCREEN — Displays the help screen for the current screen or file.
F13	CHANGE CURRENT LOGICAL NET — Changes the logical network to the one specified in the NEW LOGICAL NETWORK ID field.
F14	GOTO FIRST PAGE OF FIID/REGN/BRCH INFO — Displays the first page of SEC screen 2 if you have read access to screen 2. Otherwise, an error message is displayed.
F15	GOTO FIRST PAGE OF SCREEN ACCESS INFO — Returns you to the first page of SEC screen 3.
F16	EXIT OR GOTO FILE — Displays the previous screen or menu.
Shift-F7	GOTO FIRST PAGE OF NCS ACCESS INFO — Displays SEC screen 4 if you have read access to screen 4. Otherwise, an error message is displayed. If a record was read from SEC screen 1, the NCSS record is read for the specified user. The NCSS requires either XPNET Release 2.0 or higher. Note: A hyphen connecting two keys indicates the keys are pressed simultaneously (for example, Shift-F7 indicates the Shift and F7 keys are pressed simultaneously).
Shift-F16	LOGOFF — Logs you off the BASE24 system.

Security Screen 4

SEC screen 4 allows you to specify the network control command profile to be associated with a user's security record. The command profile controls the access to and auditing of network control commands. The user's security records containing user alias, node name, command profile name, and password are stored in the Network Control Security Specification File (NCSS). The command profiles themselves are stored in the Network Control Security Profile File (NCSP). This allows the same command profile to be assigned to multiple users. The command profile must be added to the NCSP before a profile can be assigned to a user.

Access to network control commands depends on how your system is configured. SEC screen 4 is used only when the ENABLE-SECURITY parameter is included in the declaration for the NCPI Server process in the PATHCONF.

When you add or read a command profile by specifying a profile in the PROFILE NAME field on the Network Control Security Profile File (NCSP) screen and pressing the appropriate function key, the first page of command profile information for that profile is displayed on SEC screen 4. However, command access information cannot be changed from SEC screen 4. Command access information can only be changed from the NCSP screen, which can be accessed from the Base Product Menu or by pressing the **Shift-F7** keys from SEC screen 4.

A user can have multiple security records, each associated with unique command profiles for individual XPNET nodes. For example, a new network operator could be assigned one security record associated with a command profile that allowed audited command access to a test network and another security record associated with a command profile that did not allow command access in a production network.

In this instance, the new network operator would have one security record that associated a command profile that allowed audited access to some or all commands for each object type within the XPNET node that was part of the test network. This new network operator would have another security record that associated a different command profile that allowed the user to execute inquiries only within the XPNET node that was part of the production network.

If there is no need to create command profiles for individual XPNET nodes, it is possible to create a default command profile. A security record with the value of up to 16 asterisks (*) for the NODE field acts as a default command profile for XPNET nodes when a command profile for a specific XPNET node does not exist.

SEC screen 4 is shown below as it would appear to give SUPER/SUPER access to all commands. SUPER/SUPER does not require an NCSS record, but one can be added for SUPER/SUPER. By default, SUPER/SUPER can execute all network control commands. If network control command auditing is enabled and SUPER/SUPER does not have an NCSS record, all commands executed by SUPER/SUPER are audited on the network log. SEC screen 4 fields and functions are described following the illustration.

Note: The XPNET product does not require that every user have an NCSS record. However, if the user has the ability to add security records for other users, it is recommended that the user have an NCSS record. A user who does not have an NCSS record cannot use the add like function.

```

NET24-ONCF   NETWORK CONTROL SECURITY PRO1           YY/MM/DD  HH:MM  04 OF 04
  ALIAS:
    NODE: *****

NEW PASSWORD:                                COMMANDS PROFILE: AACCESS

***** USAGE RESTRICTIONS *****
          START TIME (HH:MM): 00:00   DAYS: MO: N TU: N WE: N TH: N
          END TIME (HH:MM): 00:00   FR: N SA: N SU: N
INACTIVITY LIMIT FOR AUTO LOGOFF:      0 (MIN)
INACTIVITY LIMIT FOR AUTO LOCKOUT:     0 (DAYS)   LOCKED OUT: N
          LAST ACCOUNT ACTIVITY: 040308 (YYMMDD)
          ACCOUNT EXPIRATION: 000000 (YYMMDD)

***** PASSWORD REQUIREMENTS *****
MIN LENGTH:  0   MIN ALPHA CHARS:  0   MIN DAYS BEFORE CHANGE:  0
MAX LENGTH:  0   MIN NUMERIC CHARS:  0   MAX DAYS BEFORE CHANGE:  0
PASSWORD HISTORY:  0   MAX INVALID COUNT:  0   CURRENT INVALID COUNT:  0

RECORD LAST CHANGED: YY/MM/DD HH:MM   BY USER: 0000 , 00000000   CHANGE
*****
NEW PAGE:          FILE DESTINATION:          NEW LOGICAL NETWORK ID:
F12-HELP  F14-FIID/REGN/BRCH  F15-FILE ACCESS  SF7-NCS PROFILE  SF15-ADD LIKE

```

ALIAS — A name that is associated with a uniquely identified user. This is the name that must be entered in the USER field on the NCS screen and in the SET USER or SET LOGON command when using NCPCOM.

Field Length: 1–16 alphabetic characters
 Required Field: Yes
 Default Value: No default value

NODE — The name of the XPNET node to which this security profile applies. This field can contain one of the following three values:

- The symbolic name of an XPNET node (for example, P1A^NODE).
- The keyword EXTERNAL (for securing access to EXTERNAL entities).
- 16 asterisks (*) which act as the default profile for XPNET nodes when a profile for a specific XPNET node cannot be found.

Field Length: 1–16 alphabetic characters

Required Field: Yes

Default Value: No default value

NEW PASSWORD — A field that allows the entry of a new password for the identified user. The password cannot include spaces or commas and cannot consist of a single repeated character unless set to all spaces. New passwords entered on the NCSS screen do not follow the limitations set by the password requirements fields configured on the same NCSS screen. A password set to all spaces is considered to be valid for issuing network control commands only if security is not enabled. Passwords are case sensitive.

If security is enabled and a new NCSS record is added for a user with the password requirements field MAX DAYS BEFORE CHANGE having a nonzero value, the user is required to change their password with a SET PASSWORD command before being allowed to perform any commands from NCS or NCPCOM.

If a record is updated with a new password when the current value in the MAX INVALID COUNT field is nonzero or at the same time that you change the MAX INVALID COUNT field to a nonzero value, the new password is applied to all records for this user name. If you change the password and the current value in the MAX INVALID COUNT field is zero, the new password is applied only to the current record.

Field Length: 1–16 alphanumeric characters

Required Field: No

Default Value: Password from an existing security record for the identified user, or spaces if a security record does not already exist.

COMMANDS PROFILE — The name of a network control security profile that is defined in the NCSP.

Field Length: 1–16 alphanumeric characters
Required Field: Yes
Default Value: No default value

USAGE RESTRICTIONS

START TIME — The time the user with the specified alias can begin accessing the XPNET Online Network Control Facility (ONCF). Valid values range from 0000, which represents midnight, to 2359, which represents 11:59 p.m. The value can contain the colon (that is, 23:59) or can be placed in the first four positions of the field (that is, 2359). If a colon is not used, the system automatically displays the time with a colon when the field is added or updated.

Field Length: 3–5 numeric characters with embedded colon (:)
Required Field: Yes
Default Value: 00:00

DAYS: MO, TU, WE, TH, FR, SA, SU — These fields represent the days of the week for allowing or restricting user access to the XPNET Online Network Control Facility (ONCF).

MO = Monday
TU = Tuesday
WE = Wednesday
TH = Thursday
FR = Friday
SA = Saturday
SU = Sunday

Valid values are as follows:

Y = Yes, allow the user access to perform ONCF commands on that day of the week.
N = No, do not allow the user access to perform ONCF commands on that day of the week.

Field Length: 1 alphabetic character
Required Field: Yes
Default Value: N

END TIME — The time after which the user with the specified alias cannot access the XPNET Online Network Control Facility (ONCF). Valid entries range from 0000, which represents midnight, to 2359, which represents 11:59 p.m. The value can either contain the colon (that is, 23:59) or can be placed in the first four positions of the field (that is, 2359). If a colon is not used, the system automatically displays the entry with a colon when this field is added or updated.

If the default value of 00:00 is entered in both this and the START TIME field, the specified user cannot log on to the BASE24 system. To give the specified user 24-hour access to the BASE24 system, enter 0000 or 00:00 in the START TIME field and 2359 or 23:59 in this field.

Field Length: 3–5 numeric characters with embedded colon (:)
Required Field: Yes
Default Value: 00:00

INACTIVITY LIMIT FOR AUTO LOGOFF — The number of minutes of NCS or NCPCOM inactivity that is allowed before the user is automatically logged off. A user who is logged off because of this timer must perform a valid SET USER or SET LOGON command from NCPCOM or re-enter their password on the NCS screen to reinstate the ONCF session.

The range of valid values is 0–999 minutes. A value of 0 specifies that the user is not automatically logged off for inactivity.

Field Length: 1–3 numeric characters
Required Field: No
Default Value: 0

INACTIVITY LIMIT FOR AUTO LOCKOUT — The number of days of ONCF user inactivity that is allowed before the user is automatically locked out of the ONCF system. If the user is locked out because of this timer, the NCSS LOCKED OUT field is set to the value Y (yes) and ONCF access is not be granted until the NCSS record is updated with a value of N (no) in the LOCKED OUT field. Updating the LOCKED OUT field to the value N resets the LAST ACCOUNT ACTIVITY field with the current day's date.

The range of valid values is 0–999 days. A value of 0 specifies that the user will not be automatically locked out for inactivity.

Field Length: 1–3 numeric characters
Required Field: No
Default Value: 0

LOCKED OUT — Indicates whether a user is locked out of the ONCF system. Valid values are as follows:

Y = Yes, the user is locked out of the ONCF system and cannot enter any commands.
N = No, the user is not locked out of the ONCF system.

This field is automatically updated to the value Y when a nonzero value is configured in the INACTIVITY LIMIT FOR AUTO LOCKOUT field, the inactivity limit is exceeded by the user, or the user subsequently attempts to perform an ONCF command. In order to restore the user's access privileges, the NCSS record must be read and updated with a value of N in the LOCKED OUT field.

The LOCKED OUT field can be updated from the NCSS at any time in order to lock out a user or restore user access privileges.

Field Length: 1 alphabetic character
Required Field: Yes
Default Value: N

LAST ACCOUNT ACTIVITY — The date of the most recent ONCF command activity performed by the user.

When an NCSS record is added, this field is set to the current date. It is also reset to the current date when the LOCKED OUT field is updated with a value of N.

This date is in the format YYMMDD and cannot be directly modified on the NCSS AFT screen.

Field Length: System-protected

ACCOUNT EXPIRATION — The last date the user is allowed access to the ONCF system. If a valid date is configured in this field, the user is not allowed to perform any ONCF commands after the date indicated.

This date must be entered in YYMMDD format. A value of zeroes indicates that the user's account does not expire.

Field Length: 6 numeric characters
Required Field: No
Default Value: 000000

PASSWORD REQUIREMENTS

MIN LENGTH — The minimum number of characters required for a new password entered by a user in a SET PASSWORD command. This requirement does not affect passwords updated directly on the NCSS screen.

The range of valid values is 0–16. This value cannot be greater than the value for MAX LENGTH. A value of 0 specifies that a minimum length requirement is not to be applied to new passwords entered in SET PASSWORD commands.

Field Length: 1–2 numeric characters
Required Field: No
Default Value: 0

MIN ALPHA CHARS — The minimum number of alphabetic characters (A–Z, a–z) required for a new password entered by a user in a SET PASSWORD command. This requirement does not affect passwords updated directly on the NCSS screen.

The range of valid values is 0–16. The MIN ALPHA CHARS and MIN NUMERIC CHARS field values together cannot exceed 16. A value of 0 specifies that a minimum number of alphabetic characters will not be required in new passwords entered in SET PASSWORD commands.

Field Length: 1–2 numeric characters
Required Field: No
Default Value: 0

MIN DAYS BEFORE CHANGE — The minimum number of days which must pass before the SET PASSWORD command can be reissued by the user to change their password.

The range of valid values is 0–364. If a nonzero value is entered, it must be less than the value entered in the MAX DAYS BEFORE CHANGE field. A value of 0 specifies that the user is not restricted for how frequently the SET PASSWORD command can be performed and the password reset.

Field Length: 1–3 numeric characters
Required Field: No
Default Value: 0

MAX LENGTH — The maximum number of characters allowed for a new password entered by a user in a SET PASSWORD command. This requirement does not affect passwords updated directly on the NCSS screen.

The range of valid values is 0–16. This value cannot be less than the value for MIN LENGTH. A value of 0 specifies that a maximum length requirement is not applied to new passwords entered in SET PASSWORD commands.

Field Length: 1–2 numeric characters
Required Field: No
Default Value: 0

MIN NUMERIC CHARS — The minimum number of numeric characters (0–9) required for a new password entered by a user in a SET PASSWORD command. This requirement does not affect passwords updated directly on the NCSS screen.

The range of valid values is 0–16. The MIN ALPHA CHARS and MIN NUMERIC CHARS field values together cannot exceed 16. A value of 0 specifies that a minimum number of numeric characters is not required in new passwords entered in SET PASSWORD commands.

Field Length: 1–2 numeric characters
Required Field: No
Default Value: 0

MAX DAYS BEFORE CHANGE — The number of days until the password expires. The range of valid values is 0–365. If a nonzero value is entered, it must be greater than the value entered in the MIN DAYS BEFORE CHANGE field. A value of 0 specifies that the password does not expire.

Field Length: 1–3 numeric characters
Required Field: NO
Default Value: 30

PASSWORD HISTORY — The number of previous passwords that are remembered by the ONCF security system for the user. The user cannot perform a SET PASSWORD command using any of the previous passwords retained in the system.

The range of valid values is 0–9 passwords. A value of 0 specifies that previous passwords are not remembered by the ONCF security system.

Field Length: 1 numeric character
Required Field: No
Default Value: 0

MAX INVALID COUNT — The maximum number of consecutive invalid password attempts allowed. The range of valid values is 0–9. If this field contains the value zero, no commands are denied because of the number of invalid password attempts.

If a record is added when this field is set to a value greater than zero, all records for the user name must have the same password and the same value for this field. If either field is inconsistent among the records with the same user name, an error message is displayed.

If you update this field to a nonzero value, the changed value is applied to all records for the user name. If this field is changed to the value zero, the MAX INVALID COUNT field (and a new password, if entered at the same time) is updated in all records for the user name without checking the consistency of the NEW PASSWORD and MAX INVALID COUNT fields.

Field Length: 1 numeric character
Required Field: No
Default Value: 0

CURRENT INVALID COUNT — The current number of invalid password attempts since the last successful password entry.

From the NCPCOM utility, the SET USER command and any other command entered with an invalid password increases the value of this field by one. From the NCS screen, any command entered with an invalid password increases the value of this field by one.

When the value of the CURRENT INVALID COUNT field is increased but is less than the value of the MAX INVALID COUNT field, an event message is displayed indicating that the user name or password is invalid. If the value of the CURRENT INVALID COUNT field is equal to or greater than the value of the MAX INVALID COUNT field, the NCPI Server process displays an event message, does not attempt to verify the password, and automatically denies all commands. These event messages are logged only when the ENABLE-SECURITY parameter in the NCPI Server process definition is set to DETAIL. A successful password entry resets this field to zero.

Field Length: 1 numeric character
Required Field: No
Default Value: 0

Function Keys

The function keys used on SEC screen 4 are shown in the following table. The first column shows the function keys. The second column describes the functions that can be accomplished with these keys on SEC screen 4.

Key	Description
F1	VALIDATE DATA — Checks the data that has been entered on the screen for errors.
F2	READ RECORD — Reads a record from the file in which the user is working.
F3	ADD RECORD — Adds a record to the file in which the user is working. The record added must be unique within the file.
F4	DELETE RECORD — Deletes a record from the file in which the user is working.

Key	Description
F5	UPDATE NCSS RECORD — Enters the data currently displayed on the screen. If the data has been entered over previous data, this function changes the old data to the new data.
F6	READ NEXT RECORD — Reads the next record in the file in which the user is working.
F7	GOTO NEW PAGE — Displays a different screen in the same record in which the user is working. The screen to be displayed must be identified in the NEW PAGE field at the bottom of the screen.
F10	PRINT SCREEN — Sends the screen currently being displayed to the spooler location indicated on the Logon screen.
F11	RETURN TO BASE (PAGE 1) — Returns you to SEC screen 1.
F12	DISPLAY HELP — Displays the Help screen. The Help screen displayed depends on the screen currently being viewed. The Help screen contains information about XPNET function keys or menu options.
F13	CHANGE CURRENT LNET — Changes the current logical network while in a file.
F14	GO TO FIID/REGN/BRCH INFO — Displays the first page of SEC screen 2 if you have read access to screen 2. Otherwise, an error message is displayed.
F15	GO TO SCREEN ACCESS INFO — Displays the first page of SEC screen 3 if you have read access to screen 3. Otherwise, an error message is displayed.
F16	EXIT OR GOTO FILE — Displays the previous level menu or screen. This key has several purposes. It is used to exit XPNET or the file currently being accessed.
Shift-F7	GOTO NCS PROFILE SCREEN — Displays the NCSP screen, if you have read access to the NCSP. Otherwise, an error message is displayed. If the PROFILE NAME field contains a profile name, the record for that profile is read.

Key	Description
Shift-F15	ADD SECURITY RECORDS LIKE CURRENT USER — Adds security records identical to those of the current user, unless the user who is logged on is SUPER/ SUPER. These records consist of all records for that user in the SEC and NCSS. The ALIAS and USER NUMBER fields must be changed in order to add the new record. The system checks the entered alias against existing records to make sure it is not a duplicate.
Shift-F16	LOGOFF — Logs you off the BASE24 system.

Network Control Security Profile File

The Network Control Security Profile File (NCSP) allows you to set up network control command profile records. The command profile records indicate whether each network control command can be executed and whether the command is audited when it is executed. After a command profile is created and stored in the NCSP, it can be associated, via SEC screen 4, with the security record for one or more users.

Access to network control commands depends on how your system is configured. The NCSP file is used only when the parameter ENABLE-SECURITY is included in the declaration for the NCPI Server process in the PATHCONF. Including the ENABLE-SECURITY parameter in the PATHCONF allows you to specify whether the user has access to the command (N = no access, Y = access). If the additional parameter ENABLE-AUDIT is included in the PATHCONF, a third audited access code is available (A = audited access). Possible command responses are as follows:

- If the user has access to the command, he or she can execute the command.
- If the user has no access to a command, he or she cannot execute the command.
 - If the ENABLE-AUDIT parameter is specified in the PATHCONF, each time the command is attempted, an event message is generated identifying the XPNET node, command, user name, and the terminal from which the command was attempted.
 - If the ENABLE-AUDIT parameter is not specified in the PATHCONF, an event message is not generated when the command is attempted.
- If the user has audit access to the command, he or she can execute the command.
 - If the ENABLE-AUDIT parameter is specified in the PATHCONF, an event message is generated identifying the user and the command that was executed.
 - If the ENABLE-AUDIT parameter is not specified in the PATHCONF, an event message is not generated when the command is executed.

Note: Any changes made to an NCSP command profile affect all users with that command profile named in their security records. For example, if there are five users with the NCSP profile NET OPERATOR specified in their security records and you increase the number of commands accessible to the NET OPERATOR profile, all five users have increased access. To increase the access for only one of the five users, you must assign a different command profile to that one user.

The NCSP screen is shown below, followed by descriptions of its fields and function keys. In the example, the first page of NODE commands for the OPERATOR profile record is displayed on the screen.

```

NET24-NCSP   NCS PROFILE                               LLLL           YY/MM/DD  HH:MM  01 OF 01

PROFILE NAME: OPERATOR_____ OBJECT TYPE: NODE_____ (CPConf IN USE)
COMMAND      OPTION          ACCESS DESCRIPTION          PAGE: 01 OF 11
ABORT                                     Y TERMINATE OPERATION IMMEDIATE
ADD                                                  Y CREATE NODE OBJECT
ALTER          ADEXTENT          Y ALTER NEXT AUDIT FILE EXTENT SIZE
ALTER          ADMAXEXTENTS      Y ALTER NEXT AUDIT FILE MAXEXTENTS
ALTER          ALTLOGFILE        Y ALTER XPNET BACKUP EMS COLLECTOR
ALTER          AUDERROR          Y ALTER AUDIT ERROR ACTION PROCEDURE
ALTER          AUDIT              Y ALTER AUDIT ON/OFF
ALTER          AUDITA             Y ALTER AUDIT FILE A
ALTER          AUDITB             Y ALTER AUDIT FILE B
ALTER          AUDITC             Y ALTER AUDIT FILE C
ALTER          AUDITIO            Y ALTER AUDIT FILE IO OPTIONS
ALTER          BACKUPTYPE        Y ALTER XPNET BACKUP TYPE (HOT/WARM)
ALTER          BCPU              Y ALTER XPNET BACKUP CPU
DELIVER                                     C SEND MESSAGE TO SPECIFIED PROCESS
ALTER          BRETRYDELAY        Y ALTER XPNET BACKUP RETRY DELAY TIMER
RECORD LAST CHANGED: YY/MM/DD HH:SS BY USER: 0255 , 00000255 CHANGE
*****
NEW PAGE:  _ FILE DESTINATION:  _ NEW LOGICAL NETWORK ID:  _
F12-HELP SF2-RETRIEVE ONCF COMMANDS

```

PROFILE NAME — The name of a specific network control command profile.

Field Length: 1–16 alphabetic characters

Required Field: Yes

Default Value: No default value

OBJECT TYPE — The type of object for which network control commands are displayed. The object type specified in this field must be one of the following:

DEVICE
EXTERNAL
LINE
LINK
NODE
PROCESS
STATION

Field Length: 1–16 alphabetic characters

Required Field: Yes

Default Value: NODE

COMMAND — A network control command key word. This field identifies the network control command for which access information is being displayed.

Field Length: System-protected

OPTION — The name of an attribute, directive, or macro that is associated with the network control command displayed.

Field Length: System-protected

ACCESS — A code indicating the access level for the named command and attribute. Valid values are as follows:

- A = Audited access. A user with this access level can execute this command. If ENABLE-AUDIT is specified in the PATHCONF, each time the command is executed, an event message is generated indicating the XPNET node, command, user name, and the terminal from which the command was executed. If ENABLE-AUDIT is not specified in the PATHCONF, this setting is equivalent to the access code value Y.
- C = A value of C indicates that the command profile is defined in the Command Profile Configuration File (CPCConf). The CPCConf facility allows extended configuration of DELIVER commands, allowing them to be secured by the command text, object type, and object name pattern.
- N = No access. A user with this access level cannot execute this command. If the ENABLE-AUDIT parameter is specified in the PATHCONF, each time the command is attempted, an event message is generated indicating the XPNET node, command, user name, and the terminal from which the command was attempted.
- U = Unrestricted access. A user is allowed to execute this command without a valid password.
- V = View unrestricted. A user is allowed to execute an audited command without a valid password.
- Y = Access. A user with this access level can execute this command. No event messages are generated when the command is executed.

Field Length: 1 alphabetic character

Required Field: Yes

Default Value: N

DESCRIPTION — A text description of the command and attribute function.

Field Length: System-protected

Function Keys

The function keys used on the NCSP screen are shown in the following table. The first column shows the function keys. The second column describes the functions that can be accomplished with these keys on NCSP screen.

Key	Description
F1	VALIDATE DATA — Checks the data that has been entered on the screen for errors.
F2	READ RECORD — Reads a record from the file in which the user is working.
F3	ADD RECORD — Adds a record to the file in which the user is working. The record added must be unique within the file.
F4	DELETE RECORD — Deletes a record from the file in which the user is working.
F5	UPDATE RECORD — Changes a record already in the file in which the user is working.
F6	READ NEXT RECORD — Reads the next record in the file in which the user is working.

Key	Description
F8	CLEAR SCREEN — Clears any values on the screen in which the user is working and replaces them with spaces or default values. This key impacts all screens associated with the file currently being accessed, including the current screen, any previous screens, and any remaining screens. Once this function has been used, the update function cannot be completed until the read function has been completed. The key fields are also cleared to spaces or replaced with default values, so this information must be reentered before the record can be read.
F9	NEXT PAGE OF COMMANDS — Displays the next page of network control command access information for the object type entered in the OBJECT TYPE field.
F10	PRINT SCREEN — Sends the screen currently being displayed to the spooler location indicated on the Logon screen.
F11	PREV PAGE OF COMMANDS — Displays the previous page of network control command access information for the object type entered in the OBJECT TYPE field.
F12	DISPLAY HELP — Displays the Help screen. The Help screen displayed depends on the screen currently being viewed. The Help screen contains information about function keys or menu options.
F13	CHANGE CURRENT LNET — Changes the current logical network while in a file.

Key	Description
F16	EXIT OR GOTO — Displays the previous screen or menu or returns you to SEC screen 4. If you accessed the NCSP by pressing the Shift-F7 keys on SEC screen 4, this key returns you to SEC screen 4. When using the F16 key to return to SEC screen 4, the FILE DESTINATION field must be left blank. The profile that was displayed on the NCSP screen is then displayed on SEC screen 4. To add this profile to the SEC, however, you must update the SEC record. If you accessed the NCSP from a menu or by placing NCSP in the FILE DESTINATION field, the F16 key takes you to the last menu displayed.
Shift-F2	RETRIEVE COMMANDS BY OBJECT TYPE — Displays the network control commands for the object type entered in the OBJECT TYPE field. Note: A hyphen connecting two keys indicates the keys are pressed simultaneously (for example, Shift-F2 indicates the Shift and F2 keys are pressed simultaneously).
Shift-F16	LOGOFF — Logs you off the BASE24 system.

Procedures for Assigning Access

The following pages present sets of instructions for using the NCSP and the security screens to establish security records for a specified user. These instructions show you how to perform the following:

- Add an NCSP record
- Update an existing NCSP record
- Copy an NCSP record
- Add a security record for a specified user
- Add a security record for a specified user that is identical to your security record
- Update a security record for a specified user
- Reinstate access for a locked out user
- Delete all security records for a specified user

Adding an NCSP Record

The NCSP contains profile records that specify access to network control commands. Before a command profile can be assigned to a specific user via SEC screen 4, the profile record must exist in the NCSP. A new command profile record needs to be added to the NCSP any time a user is given network control command access different from the command access specified in an existing command profile.

To add an NCSP record, perform the following:

1. Access the NCSP screen. There are two methods of accessing the NCSP, depending on the screen that is currently displayed.

If SEC screen 4 is currently displayed, access the NCSP by pressing the **Shift-F7** keys. The NCSP screen is displayed. The profile name used on SEC screen 4 is carried to the PROFILE NAME field on the NCSP screen.

If any other screen is currently displayed, enter NCSP in the FILE DESTINATION field at the bottom of the user access screen. From a menu screen, press the **F1** key. From a file screen, press the **F16** key. The NCSP screen is displayed and the PROFILE NAME field is blank.

2. Enter the new profile name in the PROFILE NAME field.

3. Assign access to the node commands by performing the following:
 - a. Enter the value **NODE** in the **OBJECT TYPE** field and press the **Shift-F2** keys to display the node command access information.
 - b. Enter the access code (A, N, or Y) you want to assign for each command in the **ACCESS** field. When the access is assigned for all of the commands displayed, display the next page of node command information by pressing the **F9** key. Repeat this step until access has been assigned for all pages of node command information.
4. Assign access for the remaining object types and commands by performing the following:
 - a. Enter one of the following values in the **OBJECT TYPE** field and press the **Shift-F2** keys:

DEVICE
EXTERNAL
LINE
LINK
PROCESS
STATION
 - b. Enter the access code (A, N, or Y) you want to assign for each command in the **ACCESS** field. When the access is assigned for all of the commands displayed, display the next page of command information for the current object type by pressing the **F9** key. Repeat this step until access has been assigned for all pages of the current object type command information.
 - c. Repeat steps 4a and 4b for each of the remaining object types.
5. Press the **F3** key. A message is displayed at the bottom of the screen to indicate whether the information you entered has been added successfully.

Updating an Existing NCSP Record

The command access given to an individual network operator or a group of network operators does not always remain the same. A change in job function may require different access from what was initially assigned. Also, when new network control commands are added to the system, command access needs to be assigned for the new commands.

To update an existing NCSP command profile, perform the following steps on the NCSP screen:

1. Enter the profile name of the command profile that needs updated in the PROFILE NAME field.
2. Press the **F2** key to read the record.
3. Update the access assigned to the node commands by performing the following:
 - a. Enter the value NODE in the OBJECT TYPE field and press the **Shift-F2** keys to display the node command access information.
 - b. Enter the access code (A, N, or Y) you want to update for each command in the ACCESS field. When the access is updated for all of the commands displayed, display the next page of node command information by pressing the **F9** key. Repeat this step until access has been updated for all pages of node command information.
4. Update the access assigned for the remaining object types and commands by performing the following:
 - a. Enter one of the following values in the OBJECT TYPE field and press the **Shift-F2** keys:
DEVICE
EXTERNAL
LINE
LINK
PROCESS
STATION
 - b. Enter the access code (A, N, or Y) you want to update for each command in the ACCESS field. When the access is updated for all of the commands displayed, display the next page of command information for the current object type by pressing the **F9** key. Repeat this step until access has been updated for all pages of the current object type command information.

- c. Repeat steps 4a and 4b to assign access for the remaining object types.
5. Press the **F5** key. A message is displayed at the bottom of the screen to indicate whether the information you entered has been updated successfully.

Copying an NCSP Record

To copy an existing NCSP command profile to another command profile, perform the following steps on the NCSP screen:

1. Enter the profile name of the existing command profile you wish to copy in the PROFILE NAME field.
2. Press the **F2** key to read the record.
3. Edit the PROFILE NAME field by typing the new profile name.
4. Add the new command profile record by pressing the **F3** key.

Adding a Security Record

The security record defines an individual user's access to the BASE24 user access system. Without a security record, the user cannot log on to the BASE24 system, and therefore cannot perform any BASE24 user functions. A security record needs to be added for each user who should have access to the BASE24 user access system.

More than one security record can exist for each user. If your application runs on an XPNET network, additional security records may need to be added for users to specify unique command profiles for individual XPNET nodes.

To add a security record for a specified user, perform the following:

1. Enter SEC in the FILE DESTINATION field at the bottom of the user access screen. From a menu screen, press the **F1** key. From a file maintenance, table maintenance, or operator function screen, press the **F16** key. SEC screen 1 is displayed.
2. Add the base record on SEC screen 1, as follows:
 - a. Enter the user name of the user to whom you want to add a security record in the ALIAS field. The alias assigned to the user must be unique; two users cannot have the same alias.

- b. Enter the group number you want to assign to the user in the GROUP NUMBER field. Unless you are in group 255, the group number you assign must be the same as your group number.
 - c. Enter the user number you want to assign to the user in the USER NUMBER field. The combination of group number and user number must be unique. That is, two users in the same group cannot have the same user number.
 - d. Enter a name identifying the group number in the GROUP NAME field (if desired).
 - e. Enter a name identifying the user number in the USER NAME field (if desired).
 - f. Enter in the START TIME field the time before which you do not want the specified user to have access to the BASE24 user access system.
 - g. Enter in the END TIME field the time after which you do not want the specified user to have access to the BASE24 user access system.
 - h. Enter in the MAX LOGON ATTEMPTS field (if desired) the maximum number of consecutive unsuccessful logon attempts the user is allowed to make before being locked out of the BASE24 user access system.
 - i. Enter in the LOGOFF INTERVAL field (if desired) the number of seconds the user can remain inactive on the BASE24 user access system before being automatically logged off of the system.
 - j. Enter the terminal(s) you want the specified user to be able to log on with in the TERMINALS field(s).
 - k. Press the **F3** key. A message is displayed at the bottom of the screen to indicate whether the information you entered (that is, the base SEC record) has been added successfully.
3. Add an FIID/region/branch record for the specified user on SEC screen 2, as follows:
 - a. Press the **F14** key to display SEC screen 2.
 - b. Enter an FIID, region identifier, and branch identifier in each group of three fields for each FIID/region/branch relationship to which you want to restrict the specified user's access. Fill the first field with asterisks (*) if you want the specified user to have access to all FIIDs, regions, or branches.
 - c. Press the **F9** key if you need another SEC screen 2 page for entering additional FIID/region/branch relationships for the specified user. Repeat this step until you have entered all FIID/region/branch relationships you want to include in the record.

- d. Press the **F5** key to add the FIID/region/branch record. A message is displayed at the bottom of the screen to indicate whether the information you entered has been added successfully.
 4. Add a screen access record for the specified user on SEC screen 3, as follows:
 - a. Press the **F15** key to display SEC screen 3.
 - b. Enter the desired access code or codes (R, A, D, and U) in the ACCESS field for each displayed screen to which you want the specified user to have access. For utility screens like the report generator screens and operational screens like the Network Control Supervisor (NCS) screen, you need only enter the value R to assign full execution access.
 - c. Press the **F5** key to add the screen access information. A message is displayed at the bottom of the screen to indicate whether the information you entered has been added successfully.
 - d. Press the **F9** key if you need another SEC screen 3 page for entering the screen access information for the specified user.
 - e. Repeat steps 4b, 4c and 4d to add restrictions on each additional SEC screen 3 page until you have added the complete screen access record.
 5. Add a network control command security record for the specified user on SEC screen 4. Edit the SEC screen 4 to reflect the following new values for the new security record:
 - a. Press the **Shift-F7** keys to display SEC screen 4.
 - b. Edit the PASSWORD field by typing in the user password you wish to associate with this security record. You will be prompted to re-enter the password to verify that no typing errors were made on the first entry.
 - c. Edit the NODE field by typing in the name of the XPNET node you want to associate with this security record.
 - d. Edit the PROFILE field by typing in the name of the profile you want to associate with this security record. The profile named must previously have been added to the NCSP. For instructions on adding an NCSP record, see the topic “Adding an NCSP Record.”
 6. Press the **F3** key to add the UFIR, UPFR, and NCSS security records. A message is displayed at the bottom of the screen to indicate whether the information you entered has been added successfully.

Adding a Security Record Identical to Your Security Record

Users in the same group are often given similar access to the BASE24 user access system. The ability to add a security record identical to your security record allows you to add a new user with similar access more easily. Even if the new user requires slightly different access, this procedure can be used to add the basic record. Then the record can be updated (see the topic “Updating a Security Record”) with any differences.

Note: To perform this procedure, the user must have at least one record in each of these files: the SEC, UFIR, UPFR, and NCSS.

To add a security record for another user that is identical to your security record, perform the following steps:

1. Enter the value SEC in the FILE DESTINATION field at the bottom of the user access screen. From a menu screen, press the **F1** key. From a file maintenance, table maintenance, or operator function screen, press the **F16** key. SEC screen 1 is displayed.
2. Enter in the ALIAS field the user name of the user for whom you want to add a duplicate of your security record. The alias must be unique.
3. Tab past the entry in the GROUP NUMBER field since the specified user must, by definition, have the same group number you do.
4. Enter the user number you want to assign the user in the USER NUMBER field. The combination of group number and user number must be unique.
5. Press the **Shift-F15** keys. A message is displayed at the bottom of the screen to indicate whether the new record has been added successfully.

Note: This function is not available to the SUPER/SUPER user. It is, however, available to other users in group 255.

Updating a Security Record

The access given to a specific user does not always remain the same. As new users become more familiar with the system, they may be given more access. A promotion or change in job function may require different access from what was initially assigned. This procedure can be used to update the record of an individual user. It should be used any time the original record added for a user does not match the access the user should have.

To update a security record for a user who has an existing security record, perform the following:

1. Enter the value SEC in the FILE DESTINATION field at the bottom of the user access screen. From a menu screen, press the **F1** key. From a file maintenance, table maintenance, or operator function screen, press the **F16** key. SEC screen 1 is displayed.
2. Update the user's base record on SEC screen 1, as follows:
 - a. Enter the user name of the user whose security record you want to update in the ALIAS field.
 - b. Press the **F2** key to read the specified user's existing base SEC security record.
 - c. Enter the information you want to update in the applicable fields. This may involve entering data in fields that do not currently contain data or entering new data over previously entered data. When changing previous data, make sure that all characters from the old data are blanked out or overwritten by the new data.
 - d. Press the **F5** key. A message is displayed at the bottom of the screen to indicate whether the base SEC security record has been successfully updated with the information you entered.
3. Update the FIID/region/branch record for the specified user on SEC screen 2, as follows:
 - a. Press the **F14** key to display SEC screen 2.
 - b. Enter the information you want to update in the applicable FIID, region, and branch fields. This may involve entering data in fields that do not currently contain data or entering new data over previously entered data. When changing previous data, make sure that all characters from the old data are blanked out or overwritten by the new data.

- c. Press the **F9** key if you need another SEC screen 2 page for updating the FIID/region/branch record for the specified user. Repeat steps 3a and 3b until you have updated all FIID/region/branch relationships you want to include in the record.
 - d. Press the **F5** key to update the FIID/region/branch record. The record consists of all fields entered on all SEC screen 2 pages for the specified user. A message is displayed at the bottom of the screen to indicate whether the information you entered has been updated successfully.
 4. Update the screen access record for the specified user on SEC screen 3, as follows.
 - a. Press the **F15** key to display SEC screen 3.
 - b. Enter the access code or codes (R, A, D, and U) you want to update in the ACCESS field for each applicable screen. This may involve entering access codes that have not been previously entered or deleting old access codes. When changing access codes, make sure that all old codes are blanked out or overwritten by the new codes. For utility screens like the report generator screens and operational screens like the Refresh (REFR) screens, you need only enter the value R to assign full execution access.
 - c. Press the **F5** key to update the screen access record. A message is displayed at the bottom of the screen to indicate whether the information you entered has been updated successfully.
 - d. Press the **F9** key if you need another SEC screen 3 page for updating the screen access record for the specified user.
 - e. Repeat steps 4b, 4c, and 4d to update restrictions on each additional SEC screen 3 page until you have completely updated the screen access record.
 5. Update the command security record for the specified user on SEC screen 4. Edit SEC screen 4 to reflect the following updated values for the updated security record:
 - a. Press the **Shift-F7** keys to display SEC screen 4.
 - b. Edit the PASSWORD field by typing in the user password you wish to associate with this security record. You will be prompted to re-enter the password to verify that no typing errors were made on the first entry when the password for an existing record is being updated.
 - c. Edit the NODE field by typing in the name of the XPNET node you wish to associate with this security record.

- d. Edit the **PROFILE** field by typing in the name of an existing profile you wish to associate with this security record. The profile named must previously have been added to the NCSP. for instructions on adding an NCSP record, see the topic “Adding an NCSP Record.”
- e. Press the **F5** key to update the command security record. A message is displayed at the bottom of the screen to indicate whether the information you entered has been updated successfully.

Reinstating Access for a Locked Out User

BASE24 users may become *locked out* of the BASE24 user access system in one or both of the circumstances described below. When a user is locked out, he or she can no longer log on to the BASE24 user access system without supervisor intervention.

- When the user has unsuccessfully attempted to logon to the BASE24 user access system more times than is allowed according to either the MAX-LOGON-ATTEMPTS param in the LCONF or the MAX LOGON ATTEMPTS field on SEC screen 1.
- When the user has forgotten his or her password.

To reinstate access for a locked out user, perform the following steps on SEC screen 1:

1. Enter the user name of the user for whom you must reinstate BASE24 system access in the ALIAS field.
2. Press the **F2** key to read the specified user’s existing base security record. If you want, you can move to SEC screen 2 and SEC screen 3 to view the specified user’s FIID/region/branch record and screen access record. You must return to SEC screen 1, however, to perform the next step.
3. Update the CUR LOGON ATTEMPTS field, if needed. (If the CUR LOGON ATTEMPTS field contains a value of 0, go on to the next step.) To update the CUR LOGON ATTEMPTS field, perform the following:
 - a. Enter the value 0 over the value currently in the CUR LOGON ATTEMPTS field.
 - b. Press the **F5** key to update the record.
4. Change the user’s password to a new value, if needed. If the user knows his or her password, skip this step.

Deleting All Security Records for a Specified User

You must delete security records when users no longer require access to the BASE24 user access system. To delete all security records for a specified user, perform the following steps on SEC screen 1:

1. Enter the user name of the user whose security records you want to delete in the ALIAS field.
2. Press the **F2** key to read the specified user's existing base security record. If you want, you can move to SEC screen 2 and SEC screen 3 to view the specified user's FIID/region/branch record and screen access record. You must return to SEC screen 1, however, to perform the next step.
3. Press the **F4** key to delete all security records (base, FIID/region/branch, screen access, and network control command access) for the specified user. A message is displayed at the bottom of the screen to indicate whether all security records for the specified user have been deleted successfully.

ACI Worldwide, Inc.

6: Audit Reports

This section describes the reports BASE24 provides to meet the auditing requirements of the institution. The information contained in these reports enables institutions to track user authentication and user access to the BASE24 system.

The audit reports consist of the Security audit reports and the OMF audit reports.

The Security audit reports include:

- Last Logon Report (SEC01)
- Access Privileges Report (SEC02)

The OMF audit reports include:

- Logon/Logoff Access Report (OMF03)
- File Access Report (OMF04)

Security Audit Reports

The Security File (SEC) and the User/FIID Relation File (UFIR) contain information on every user who is authorized to access BASE24. These files are used to restrict access to BASE24. You can also use them to generate the Security audit reports.

The Security audit reports consist of the Last Logon Report (SEC01) and the Access Privileges Report (SEC02). These reports contain the same information. The difference between the two reports is the order in which the information is presented. The information included in the Last Logon Report is sorted by date and time of the last logon attempt, group description, user description, and password change date. The information included in the Access Privileges Report is sorted by group number and group description.

Summary and detail versions of both Security audit reports are available. The summary versions include the following information for each user in the SEC file:

- The user number and user description
- The group number and group description for the group to which the user belongs
- The user's alias
- The date of the user's last logon or logon attempt
- The number of consecutive failed logon attempts since the last successful logon attempt
- The maximum number of failed logon attempts the user is permitted before being locked out
- The date on which the user's password was last changed

The detail versions of the Security audit reports include the information contained in the summary versions, plus the following information:

- The time of day the user's access begins
- The time of day the user's access ends
- The XPNET nodes the user is allowed to access
- The terminals the user is allowed to access

- The FIID, region, and branch combinations the user is allowed to access
- The files, tables, and screens the user is allowed to access, broken out by screen number

Runfiles are used to initiate the Security audit reports. Generic runfiles are provided for both reports. You can modify a generic runfile to identify the report program and the input and temporary files to be used by the report program, define the report output location, and indicate whether you want the summary or detail version of the report. After the generic runfile has been modified to contain the desired settings, you can initiate the report using the OBEY command.

Generic Runfiles

Before initiating a Security audit report, edit the generic runfile for that report to ensure that the desired options have been selected. The generic runfiles for the Security audit reports are located in the BA60RPT subvolume.

The generic runfiles for both reports include the PRINT-DISK, UFIR-FILE, SORTIN-FILE, and SORTOUT-FILE assigns and RUN commands for the summary and detail versions of the reports.

The PRINT-DISK assign allows you to define the report output location. You can direct report output to a disk file or spooler location.

The UFIR-FILENAME assign identifies the User/FIID Relation File used as input to the report program.

The SORTIN-FILE and SORTOUT-FILE identify the temporary files used during processing to sort the records.

After you have edited the assigns, select the RUN command for either the summary or detail version of the report, depending upon which version you want to generate. Make sure that the RUN command you have chosen is uncommented and that the RUN command for the other version of the report is commented out.

When you are finished with the modifications, close the runfile.

The rest of this section provides additional information on the assigns and RUN commands in the generic runfiles for the Security audit reports.

PRINT-DISK Assign

The format of the PRINT-DISK assign is shown below followed by descriptions of the parameters.

```
PRINT-DISK <print-disk-filename>, EXT (4, 32), CODE 101
```

print-disk-filename — The fully-qualified location for the report output. This location can be a disk file or spooler location.

In addition to sending the report output to the specified disk file or spooler location, the report programs always send the report output to hardcoded spooler locations. The report output for the Last Logon Report is always sent to \$S.#RPSEC01. The report output for the Access Privileges Report is always sent to \$S.#RPSEC02.

Note: The Security audit reports are 132 columns wide and must be printed on a printer that can support 132 columns.

EXT — The size of the output file created. The extent numbers can be larger or smaller depending on the size of the anticipated output.

CODE 101 — The output file is an EDIT file.

If the file specified in the PRINT-DISK assign already exists, new report output will be added to the end of the file. If the specified file does not exist, it is created with the attributes specified in the assign.

UFIR-FILENAME Assign

The format of the UFIR-FILENAME assign is shown below followed by a description of the parameter.

```
UFIR-FILENAME <UFIR-filename>
```

UFIR-filename — The fully-qualified location for the User/FIID Relation File. This UFIR must be in the same subvolume as the Security File.

SORTIN-FILE Assign

The format of the SORTIN-FILE assign is shown below followed by a description of the parameter.

```
SORTIN-FILE <temporary file name>
```

temporary file name — The fully-qualified location of the SORTIN file. If this temporary file does not exist, the report program creates it. This file is purged at the end of the report program.

SORTOUT-FILE Assign

The format of the SORTOUT-FILE assign is shown below followed by a description of the parameter.

```
SORTOUT-FILE <temporary file name>
```

temporary file name — The fully-qualified location of the SORTOUT file. If this temporary file does not exist, the report program creates it. This file is purged at the end of the report program.

RUN Commands

The RUN command formats for the summary and detail versions of the Security audit reports are shown below followed by descriptions of the parameters. The only difference between the RUN commands for the summary and detail versions of the reports is the presence of the DETAIL parameter.

Summary Report RUN Command Format

```
RUN <report-program-filename>&  
  /IN <SEC-filename>/
```

Detail Report RUN Command Format

```
RUN <report-program-filename>&  
  /IN <SEC-filename>/&  
  DETAIL
```

report-program-filename — The fully-qualified name of the compiled report program, for example: \system.\$volume.ba60obj.barp02.

SEC-filename — The fully-qualified name of the Security File used as input to the report program.

DETAIL — This parameter produces the detail version of the report. The word DETAIL must be in uppercase letters.

Report Generation

You can generate a Security audit report after you have modified the associated runfile. To generate a report, volume to the BA60RPT subvolume and use the OBEY command to obey the runfile for the report you want to generate. The format for the OBEY command is shown below followed by a description of the parameter.

```
$<volume> BA60RPT 1> OBEY <runfile>
```

runfile — The name of the generic runfile. The name of the generic runfile for the Last Logon Report is BARPT01R. The name of the generic runfile for the Access Privileges Report is BARPT02R.

Error Messages

Standard COBOL error messages are displayed on the screen for file handling errors, such as when the program is unable to open the SEC or UFIR file specified in the runfile.

Report Samples and Field Descriptions

This section contains samples of the summary and detail versions of the Last Logon Report and the Access Privileges Report. The summary and detail versions of each report are shown below followed by descriptions of the fields.

Last Logon Report

On the following pages are samples of the summary and detail versions of the Last Logon Report. Because the fields on the summary version are also on the detail version, the report samples are followed by a single set of field descriptions. The differences between the summary and detail versions are described below.

- The first line of the summary version contains the identifier SEC01 - SUMMARY. The first line of the detail version contains the identifier SEC01 - DETAIL.
- The title of the summary version is LAST LOGON SUMMARY REPORT. The title of the detail version is LAST LOGON DETAIL REPORT.
- In the detail version of the report, the summary information for each user is followed by information about the user's security restrictions.

SEC01 - SUMMARY			LAST LOGON SUMMARY REPORT			DATE 09/02/06		PAGE 01	
INPUT FILE: \K9.\$B24NT2.TES2DATA.SEC									
LAST LOGON	GROUP	USER	GROUP DESCRIPTION	USER DESCRIPTION	ALIAS	LOGON ATTEMPTS	LOGON MAX	PASSWORD CHANGE DATE	
010529	32	998	R60	READ - PUBS, ED, PM	R60/READ	04	05	010402	
051201	36	200	H24	TESTER #4	H24/TEST4	00	05	051201	
051201	36	513	R60	TESTER #13	R60/TEST13	01	05	051201	
051201	36	503	R60	TESTER #3	R60/TEST3	00	05	051201	
051201	36	504	R60	TESTER #4	R60/TEST4	00	05	051201	
051201	36	505	R60	TESTER #5	R60/TEST5	00	05	051201	
051201	255	999	SUPER	DEFAULT	DEFAULT	02	99	051201	
051202	36	515	R60	TESTER #15	R60/TEST15	00	99	051201	
051202	36	508	R60	TESTER #8	R60/TEST8	00	99	051201	
051202	36	509	R60	TESTER #9	R60/TEST9	00	99	051201	
051207	36	500	R60	TESTER #0	R60/TEST0	00	99	051202	
051221	36	514	R60	TESTER #14	R60/TEST14	06	99	051201	
060111	36	507	R60	TESTER #7	R60/TEST7	00	99	060103	
060203	36	506	R60	TESTER #6	R60/TEST6	00	99	060103	
060208	36	501	R60	TESTER #1	R60/TEST1	00	99	060103	
060208	36	502	R60	TESTER #2	R60/TEST2	00	99	060103	
741231	36	510	R60	TESTER #10	R60/TEST10	00	99	000000	
741231	36	511	R60	TESTER #11	R60/TEST11	00	99	000000	
741231	36	512	R60	TESTER #12	R60/TEST12	00	99	000000	
741231	36	526	R60	TESTER #26	R60/TESTA	00	99	000000	
***** END OF REPORT *****									

SEC01 - DETAIL									
INPUT FILE: \K9.\$B24NT2.TES2DATA.SEC									
LAST LOGON DETAIL REPORT									
DATE 09/02/06									
PAGE 01									
LAST LOGON GROUP USER GROUP DESCRIPTION USER DESCRIPTION ALIAS LOGON LOGON PASSWORD									
ATTEMPTS MAX CHANGE DATE									

010529	32	998	R60	READ - PUBS,ED,PM	R60/READ	04	05	010402	

FIID REGION BRANCH FIID REGION BRANCH									

START TIME END TIME RESOURCE NODE(S) STATION(S)									

0000 2359 *****									

FILE SCRN FILE SCRN FILE SCRN FILE SCRN FILE SCRN									
ID NMBR RADU ID NMBR RADU ID NMBR RADU ID NMBR RADU ID NMBR RADU									

ACNF 1 RADU	ACNF 2 RADU	ACNF 3 RADU	ACNF 4 RADU	ACNF 5 RADU	ACNF 6 RADU				
ACNF 7 R	ACNF 8 R	ACNF 9 R							
.									
.									
CAF 1 RADU	CAF 2 RADU	CAF 3 RADU	CAF 4 RADU	CAF 5 RADU	CAF 7 RADU				
CAF 8 RADU	CAF 9 RADU	CAF 10 RADU	CAF 12 RADU	CAF 13 RADU	CAF 14 RADU				
CAF 15 RADU	CAF 16 RADU	CAF 20 RADU							
.									
.									
IDF 1 RADU	IDF 2 RADU	IDF 3 RADU	IDF 4 RADU	IDF 5 RADU	IDF 6 RADU				
IDF 7 RADU	IDF 9 RADU	IDF 10 RADU	IDF 11 RADU	IDF 12 RADU	IDF 13 RADU				
IDF 14 RADU	IDF 16 RADU	IDF 17 RADU	IDF 18 RADU	IDF 19 RADU	IDF 20 RADU				
IDF 21 RADU	IDF 24 RADU	IDF 25 RADU	IDF 26 RADU	IDF 27 RADU	IDF 28 RADU				
IDF 31 RADU	IDF 37 RADU	IDF 40 R	IDF 41 R	IDF 42 R	IDF 45 R				
.									
.									
PBF 1 RADU	PBF 3 RADU	PBF 5 RADU	PBF 6 RADU	PBF 8 RADU	PBF 10 RADU				
PBF 11 RADU	PBF 13 RADU	PBF 14 RADU							
.									
.									
SEC 1 RADU	SEC 2 RADU	SEC 3 RADU	SEC 4 RADU						
.									
.									
VVT 1 RADU	VVT 2 RADU								
WHFF 1 R									
XNI 1 R									
***** END OF REPORT *****									

The fields listed below are displayed on both the summary and detail versions of the Last Logon Report.

INPUT FILE — The fully-qualified location of the Security File (SEC).

LAST LOGON — The date of the user's last logon attempt. The date is displayed in YYMMDD format. If a logon has never been used, the last logon date is 741231.

GROUP — The numeric identifier for the group to which the user belongs.

USER — The numeric identifier for the user.

GROUP DESCRIPTION — The description of the group to which the user belongs.

USER DESCRIPTION — The description of the user.

ALIAS — The user's alias. This is the identifier the user enters in the USER NAME field on the Logon screen.

LOGON ATTEMPTS — The number of consecutive failed logon attempts since the user's last successful logon.

LOGON MAX — The maximum number of consecutive failed logon attempts that are allowed for this user before the user is locked out of the system.

PASSWORD CHANGE DATE — The date on which the user's password was last changed. The date is displayed in YYMMDD format. If a logon has never been used, the password change date is 000000.

The fields listed below are displayed only on the detail version of the Last Logon Report.

FIID — The identifier for a financial institution to which the user has access. If the user has access to all financial institutions, the field is filled with asterisks (*).

REGION — The identifier for a region within the associated financial institution to which the user has access. If the user has access to all regions within the associated financial institution, the field is filled with asterisks (*).

BRANCH — The identifier for a branch within the associated region to which the user has access. If the user has access to all branches within the associated region, the field is filled with asterisks (*).

START TIME — The time of day at which the user's access to BASE24 begins. The time is displayed in HHMM format.

END TIME — The time of day at which the user's access to BASE24 ends. The time is displayed in HHMM format.

RESOURCE NODE(S) — The name(s) of the XPNET node(s) to which the user can send commands from the Network Control Supervisor (NCS) and Device Control Terminal (DCT) screens or perform tasks using the EXTR, REFR, XNI, and ICF files and functions. If the user has access to all BASE24 XPNET nodes, the field is filled with asterisks (*).

STATION(S) — The name of the terminal through which the user can access BASE24 user functions. If the user has access to all terminals, the field is filled with asterisks (*).

FILE ID — The abbreviation for the file, table, or screen the user is allowed to access. Each new file ID begins on a new line.

SCRN NMBR — The page number of the associated file, table, or function screen the user is allowed to access.

RADU — The type of access the user has to the corresponding file, table, or function screen. The values that can be displayed in this field are as follows:

- R = Read access. Allows the user to read records from a file or rows from a table. For utility or function screens, this value denotes execution access.
- A = Add access. Allows the user to add records to a file or rows to a table.
- D = Delete access. Allows the user to delete records from a file or rows from a table.
- U = Update access. Allows the user to update records in a file or rows in a table.

Access Privileges Report

On the following pages are samples of the summary and detail versions of the Access Privileges Report. Because the fields on the summary version are also on the detail version, the report samples are followed by a single set of field descriptions. The differences between the summary and detail versions are described below.

- The first line of the summary version contains the identifier SEC02 - SUMMARY. The first line of the detail version contains the identifier SEC02 - DETAIL.
- The title of the summary version is ACCESS PRIVILEGES SUMMARY REPORT. The title of the detail version is ACCESS PRIVILEGES DETAIL REPORT.
- In the detail version of the report, the summary information for each user is followed by information about the user's security restrictions.

SEC02 - SUMMARY		ACCESS PRIVILEGES SUMMARY REPORT			DATE 09/02/06	PAGE 01
INPUT FILE: \K9.\$B24NT2.TES2DATA.SEC						
GROUP	GROUP DESCRIPTION					
32	R60					
USER NUM	USER DESCRIPTION	ALIAS	LAST LOGON DATE	LOGON ATTEMPTS	LOGON MAX	PASSWORD CHANGE DATE
998	READ - PUBS,ED,PM	R60/READ	010529	04	05	010402

SEC02 - SUMMARY		ACCESS PRIVILEGES SUMMARY REPORT				DATE 09/02/06	PAGE 02
INPUT FILE: \K9.\$B24NT2.TES2DATA.SEC							
GROUP	GROUP DESCRIPTION	ALIAS	LAST LOGON DATE	LOGON ATTEMPTS	LOGON MAX	PASSWORD CHANGE DATE	
36	H24						
USER NUM	USER DESCRIPTION	ALIAS	LAST LOGON DATE	LOGON ATTEMPTS	LOGON MAX	PASSWORD CHANGE DATE	
200	TESTER #4	H24/TEST4	051201	00	05	051201	
500	TESTER #0	R60/TEST0	051207	00	99	051202	
501	TESTER #1	R60/TEST1	060208	00	99	060103	
502	TESTER #2	R60/TEST2	060208	00	99	060103	
503	TESTER #3	R60/TEST3	051201	00	05	051201	
504	TESTER #4	R60/TEST4	051201	00	05	051201	
505	TESTER #5	R60/TEST5	051201	00	05	051201	
506	TESTER #6	R60/TEST6	060203	00	99	060103	
507	TESTER #7	R60/TEST7	060111	00	99	060103	
508	TESTER #8	R60/TEST8	051202	00	99	051201	
509	TESTER #9	R60/TEST9	051202	00	99	051201	
510	TESTER #10	R60/TEST10	741231	00	99	000000	
511	TESTER #11	R60/TEST11	741231	00	99	000000	
512	TESTER #12	R60/TEST12	741231	00	99	000000	
513	TESTER #13	R60/TEST13	051201	01	05	051201	
514	TESTER #14	R60/TEST14	051221	06	99	051201	
515	TESTER #15	R60/TEST15	051202	00	99	051201	
526	TESTER #26	R60/TESTA	741231	00	99	000000	

SEC02 - SUMMARY		ACCESS PRIVILEGES SUMMARY REPORT			DATE 09/02/06	PAGE 03
INPUT FILE: \K9.\$B24NT2.TES2DATA.SEC						
GROUP	GROUP DESCRIPTION					
255	SUPER					
USER NUM	USER DESCRIPTION	ALIAS	LAST LOGON DATE	LOGON ATTEMPTS	LOGON MAX	PASSWORD CHANGE DATE
999	DEFAULT	DEFAULT	051201	02	99	051201
***** END OF REPORT *****						

ACCESS PRIVILEGES DETAIL REPORT												DATE 09/02/06	PAGE 01
SEC02 - DETAIL INPUT FILE: \K9.\$B24NT2.TES2DATA.SEC													
GROUP GROUP DESCRIPTION													
32 R60													
USER NUM	USER DESCRIPTION	ALIAS	LAST LOGON DATE	LOGON ATTEMPTS	LOGON MAX	PASSWORD CHANGE DATE							
998	READ - PUBS,ED,PM	R60/READ	010529	04	05	010402							
FIID	REGION	BRANCH	FIID	REGION	BRANCH	FIID	REGION	BRANCH					
****	****	****	****	****	****	****	****	****					
START TIME		END TIME		RESOURCE NODE(S)				STATION(S)					
0000		2359		*****				*****					
FILE ID	SCRN NMBR	FILE ID	SCRN NMBR	FILE ID	SCRN NMBR	FILE ID	SCRN NMBR	FILE ID	SCRN NMBR	FILE ID	SCRN NMBR	FILE ID	SCRN NMBR
ACNF 1	RADU 7	ACNF 2	RADU 8	ACNF 3	RADU 9	ACNF 4	RADU 4	ACNF 5	RADU 5	ACNF 6	RADU 6	ACNF 7	RADU 7
CAF 1	RADU 8	CAF 2	RADU 9	CAF 3	RADU 10	CAF 4	RADU 12	CAF 5	RADU 13	CAF 7	RADU 14	CAF 13	RADU 13
CAF 15	RADU 15	CAF 16	RADU 16	CAF 20	RADU 20	CAF 26	RADU 26	CAF 27	RADU 27	CAF 28	RADU 28	CAF 45	RADU 45
IDF 1	RADU 1	IDF 2	RADU 2	IDF 3	RADU 3	IDF 4	RADU 4	IDF 5	RADU 5	IDF 6	RADU 6	IDF 13	RADU 13
IDF 7	RADU 7	IDF 9	RADU 9	IDF 10	RADU 10	IDF 11	RADU 11	IDF 12	RADU 12	IDF 13	RADU 13	IDF 20	RADU 20
IDF 14	RADU 14	IDF 16	RADU 16	IDF 17	RADU 17	IDF 18	RADU 18	IDF 19	RADU 19	IDF 20	RADU 20	IDF 27	RADU 27
IDF 21	RADU 21	IDF 24	RADU 24	IDF 25	RADU 25	IDF 26	RADU 26	IDF 27	RADU 27	IDF 28	RADU 28	IDF 42	RADU 42
IDF 31	RADU 31	IDF 37	RADU 37	IDF 40	RADU 40	IDF 41	RADU 41	IDF 42	RADU 42	IDF 45	RADU 45	IDF 45	RADU 45
PBF 1	RADU 1	PBF 3	RADU 3	PBF 5	RADU 5	PBF 6	RADU 6	PBF 8	RADU 8	PBF 10	RADU 10	PBF 10	RADU 10
PBF 11	RADU 11	PBF 13	RADU 13	PBF 14	RADU 14	PBF 18	RADU 18	PBF 27	RADU 27	PBF 42	RADU 42	PBF 42	RADU 42
SEC 1	RADU 1	SEC 2	RADU 2	SEC 3	RADU 3	SEC 4	RADU 4	SEC 5	RADU 5	SEC 6	RADU 6	SEC 6	RADU 6
VVT 1	RADU 1	VVT 2	RADU 2	VVT 3	RADU 3	VVT 4	RADU 4	VVT 5	RADU 5	VVT 6	RADU 6	VVT 6	RADU 6
WHFF 1	RADU 1	WHFF 2	RADU 2	WHFF 3	RADU 3	WHFF 4	RADU 4	WHFF 5	RADU 5	WHFF 6	RADU 6	WHFF 6	RADU 6
XNI 1	RADU 1	XNI 2	RADU 2	XNI 3	RADU 3	XNI 4	RADU 4	XNI 5	RADU 5	XNI 6	RADU 6	XNI 6	RADU 6
***** END OF REPORT *****													

The fields listed below are displayed on both the summary and detail versions of the Access Privileges Report.

INPUT FILE — The fully-qualified location of the Security File (SEC).

GROUP — The numeric identifier for the group to which the user belongs. A page break is inserted when the group number changes.

GROUP DESCRIPTION — The description of the group to which the user belongs.

USER NUM — The numeric identifier for the user.

USER DESCRIPTION — The description of the user.

ALIAS — The user's alias. This is the identifier the user enters in the USER NAME field on the Logon screen.

LAST LOGON DATE — The date of the user's last logon attempt. The date is displayed in YYMMDD format. If a logon has never been used, the last logon date is 741231.

LOGON ATTEMPTS — The number of consecutive failed logon attempts since the user's last successful logon.

LOGON MAX — The maximum number of consecutive failed logon attempts that are allowed for this user before the user is locked out of the system.

PASSWORD CHANGE DATE — The date on which the user's password was last changed. The date is displayed in YYMMDD format. If a logon has never been used, the password change date is 000000.

The fields listed below are displayed only on the detail version of the Access Privileges Report.

FIID — The identifier for a financial institution to which the user has access. If the user has access to all financial institutions, the field is filled with asterisks (*).

REGION — The identifier for a region within the associated financial institution to which the user has access. If the user has access to all regions within the associated financial institution, the field is filled with asterisks (*).

BRANCH — The identifier for a branch within the associated region to which the user has access. If the user has access to all branches within the associated region, the field is filled with asterisks (*).

START TIME — The time of day at which the user's access to BASE24 begins. The time is displayed in HHMM format.

END TIME — The time of day at which the user's access to BASE24 ends. The time is displayed in HHMM format.

RESOURCE NODE(S) — The name(s) of the XPNET node(s) to which the user can send commands from the Network Control Supervisor (NCS) and Device Control Terminal (DCT) screens or perform tasks using the EXTR, REFR, XNI, and ICF files and functions. If the user has access to all BASE24 XPNET nodes, the field is filled with asterisks (*).

STATION(S) — The name of the terminal through which the user can access BASE24 functions. If the user has access to all terminals, the field is filled with asterisks (*).

FILE ID — The abbreviation for the file, table, or screen the user is allowed to access. Each new file ID begins on a new line.

SCRN NMBR — The page number of the associated file, table, or function screen the user is allowed to access.

RADU — The type of access the user has to the corresponding file, table, or function screen. The values that can be displayed in this field are as follows:

- R = Read access. Allows the user to read records from a file or rows from a table. For utility or function screens, this value denotes execution access.
- A = Add access. Allows the user to add records to a file or rows to a table.
- D = Delete access. Allows the user to delete records from a file or rows from a table.
- U = Update access. Allows the user to update records in a file or rows in a table.

OMF Audit Reports

The Online Maintenance File (OMF) contains information on users who have logged on and logged off the Pathway system as well as information on users who have read, added, changed, or deleted records in BASE24 files accessed through the BASE24 Pathway system. For reads, a record is only written to the OMF if the record contains cardholder data, for example, a PAN.

In addition, OMF records are written when users attempt to read a record from the file or when a security violation occurs such as the following:

- The user does not have security access for the institution (FIID) to which the record belongs.
- The user does not have security access to the file or the screen or authority for the function attempted.
- The user does not have authority for the function attempted based on configuration settings in the CRT Authorization Security (CSEC) File.

If a user attempts a Read or Read Next function, but the record is not retrieved successfully, then no OMF record is written.

Note: OMF records are written when the user does not have security access to the screen or authority for the function attempted only if the record contains cardholder data, for example, a PAN.

The OMF is used to generate two reports: the Logon/Logoff Access Report (OMF03) and the File Access Report (OMF04). The Logon/Logoff Access Report provides information on users who have logged on to or attempted to log on to the BASE24 Pathway system and on users who have logged off using the **SF16** key from the Logon screen. The File Access Report provides information on users who have read, added, updated, or deleted records in BASE24 files accessed through the BASE24 Pathway system, as well as information on users who have logged on to the BASE24 Pathway system and users who have logged off using the **SF16** key from the Logon screen.

The OMF audit reports include the information from a single day's OMF file(s), displayed in timestamp order.

Runfiles are used to initiate the OMF audit reports. Generic runfiles are provided for both reports. You can modify a generic runfile to identify the report program and the initial input file to be used by the report program, define the report output location, specify record selection criteria, and indicate whether you want the

summary or detail version of the report. After the generic runfile has been modified to contain the desired settings, you can initiate the report using the OBEY command.

There are summary and detail versions of both OMF audit reports. Your configuration determines whether the data is available to create the summary and detail versions of these reports. Refer to [“Configuration”](#) in this section for information on the configuration settings that control the availability of data.

The summary version of the Logon/Logoff Access Report contains the following information for each logon and logoff record included in the report:

- The record number of the record created in the OMF when the user logged on, attempted to log on, or logged off
- The date and time the user logged on, attempted to log on, or logged off
- The user group and user number of the user who logged on, attempted to log on, or logged off
- The word LOGON or LOGOFF to identify the record as either a logon or logoff record
- The identifier for the logical network the user specified when logging on
- The identifier for the terminal used to log on, attempt to log on, or log off

The detail version of the Logon/Logoff Access Report contains the same information as the summary version of that report, plus an image of each logon and logoff record included in the report.

The summary version of the File Access Report contains the following information for each logon and logoff record included in the report:

- The record number of the record created in the OMF when the user logged on, attempted to log on, or logged off
- The date and time the user logged on, attempted to log on, or logged off
- The word LOGON or LOGOFF to identify the record as either a logon or logoff record
- The record type
- The user group and user number of the user who logged on, attempted to log on, or logged off
- The identifier for the logical network the user specified when logging on
- The identifier for the terminal used to log on, attempt to log on, or log off

The summary version of the File Access Report contains the following information for each added, updated, or deleted record included in the report:

- The record number of the record created in the OMF when the user read, added, updated, or deleted a record
- The date and time the user read, added, updated, or deleted the record
- The application code (file ID) of the file to which the added, updated, or deleted record or read record belongs
- The record type
- The user group and user number of the user who read, added, updated, or deleted the record
- The identifier for the logical network the user specified when logging on
- The FIID, region, and branch to which the added, updated, or deleted record or read record belongs
- The identifier for the terminal from which the record was read, added, updated, or deleted

The detail version of the File Access Report contains the same information as the summary version of that report, plus an image of each record included in the report.

It is not anticipated that the OMF audit reports will be run on a daily basis. When they are run, there could be an impact to system performance because both the input files and output reports could be very large and take some time to process.

OMF Description Table

The OMF Description Table (OMFTBL) is located in the BA60RPT subvolume. It contains a list of the OMF application codes and their associated BASE24 file IDs.

One of the selection criteria you can specify when you modify the generic runfile for the File Access Report is the file whose records you want included in the report output. Because of the OMFTBL, which is used by the report program, you can specify a familiar file ID instead of a less familiar application code. For example, you could specify the file ID “CAF” for Cardholder Authorization File instead of application code “70”.

In some cases, a BASE24 file ID is used to identify more than one file. If you specify one of those file IDs, the report output will include information on all of the files with that file ID. The 2-character application codes, however, are unique. If you use an application code instead of a file ID, the report output will include information on the single file identified by the specified application code.

Regardless of whether you specify a file ID or an application code, the report output contains file IDs.

Configuration

The OMF-AUDIT and OMF-SPECIAL parameters in the Logical Network Configuration File (LCONF) affect OMF audit reporting.

The OMF-AUDIT parameter controls the amount of information that is written to the OMF and is, therefore, available for reporting.

If the OMF-AUDIT parameter is set to 2, an OMF record is created when a user adds, updates, or deletes a record in a BASE24 file accessed through Pathway, logs on to Pathway, or logs off Pathway using the **SF16** key from the Logon screen. The OMF record that is created when a user adds, updates, or deletes a record includes the following information: application code (file ID), record type, user number, user group, logical network identifier, FIID, region, branch, terminal ID, date, and time. The OMF record that is created when a user logs on, attempts to log on, or logs off includes the following information: user number, user group, logical network identifier, terminal ID, date, and time. The information written to the OMF when the OMF-AUDIT parameter is set to 2 is considered *summary* information. Therefore, if the OMF-AUDIT parameter is set to 2, you are able to generate only the summary versions of the OMF audit reports.

If the OMF-AUDIT parameter is set to 1, an OMF record is created as described above. Added to the OMF is an image of the record that was added, updated, or deleted, an image of the logon, or an image of the logoff. In the case of an updated record, a before and after image of the updated record is added to the OMF. In the case of a failed logon attempt, information on the reason for the failure is also included. The information written to the OMF when the OMF-AUDIT parameter is set to 1 is considered *detail* information. Therefore, if the OMF-AUDIT parameter is set to 1, you are able to generate either the summary or detail versions of the OMF audit reports.

Note: If the OMF-AUDIT parameter is set to 0, no information is written to the OMF, and, therefore, no information is available for reporting.

The OMF-SPECIAL parameter determines whether data from the User Product/ File Relation File (UPFR) and the User/FIID Relation File (UFIR) is written to the OMF and, therefore, available for reporting. If the OMF-SPECIAL parameter is set to Y, data from the UPFR and UFIR is written to the OMF and can be included in the File Access Report. If the parameter is set to N, data from the UPFR and UFIR is not written to the OMF and, therefore, not included in the File Access Report.

Generic Runfiles

Before initiating an OMF audit report, edit the generic runfile for that report to ensure that the desired options have been selected. The generic runfiles for the OMF audit reports are located in the BA60RPT subvolume.

The generic runfiles for both reports include a PRINT-DISK assign and RUN commands for the summary and detail versions of the reports.

The PRINT-DISK assign allows you to define the report output location. You can direct report output to a disk file or spooler location.

After you have edited the PRINT-DISK assign, edit the RUN command for either the summary or detail version of the report, depending upon which version you are going to generate. The RUN command allows you to specify the record selection criteria for the report output. Make sure that the RUN command you have chosen to edit is uncommented and that the RUN command for the other version of the report is commented out.

The record selection criteria you specify in the RUN command for the Logon/ Logoff Access Report determines whether the report output contains all users in the specified day's OMF file(s), a single user group in the specified day's OMF file(s), or a single user group and user number in the specified day's OMF file(s).

The record selection criteria you specify in the RUN command for the File Access Report determines whether the report output contains all files or a single file; all record types or a single record type; all users, a single user group, or a single user group and user number; or a combination of the file, record type, and user criteria.

When you are finished with the modifications, close the runfile.

The rest of this section provides additional information on the PRINT-DISK assign and the RUN commands for the OMF audit reports.

PRINT-DISK Assign

The format of the PRINT-DISK assign is shown below followed by descriptions of the parameters.

```
PRINT-DISK <print-disk-filename>, EXT (4, 32), CODE 101
```

print-disk-filename — The fully-qualified location for the report output. This location can be a disk file or spooler location.

In addition to sending the report output to the specified disk file or spooler location, the report programs always send the report output to hardcoded spooler locations. The report output for the Logon/Logoff Access Report is always sent to \$S.#RPOMF03. The report output for the File Access Report is always sent to \$S.#RPOMF04.

Note: The OMF audit reports are 132 columns wide and must be printed on a printer that can support 132 columns.

EXT — The size of the output file to be created by the report program. The extent numbers can be larger or smaller depending on the size of the anticipated output.

CODE 101 — The output file is an EDIT file.

If the file specified in the PRINT-DISK assign already exists, new report output will be added to the end of the file when the report is run. If the specified file does not exist, it is created with the attributes specified in the assign.

RUN Commands for the Logon/Logoff Access Report

The RUN command formats for the summary and detail versions of the Logon/Logoff Access Report are shown below followed by descriptions of the parameters. The only difference between the RUN commands for the summary and detail versions of the report is the presence of the DETAIL parameter.

Logon/Logoff Summary Report RUN Command Format

```
RUN <report-program-filename>&  
    <OMF-filename>,&  
    <user-group>,&  
    <user-num>
```

Logon/Logoff Detail Report RUN Command Format

```
RUN <report-program-filename>&  
    <OMF-filename>, &  
    <user-group>, &  
    <user-num>, &  
    DETAIL
```

report-program-filename — The fully-qualified name of the compiled report program, for example: \system.\$volume.ba60obj.barp03.

OMF-filename — The fully-qualified name of the first OMF to be used to produce the report, for example: \system.\$volume.xxxOMFS.Ayymmdd0. This parameter is required for the report to run. If the report is being run again due to a full output file, an OMF file other than the first OMF for the day should be specified. Use the report output to determine the OMF file to use to begin the next report run.

Note: OMF files are created with a file name of Ayymmddx, where yymmdd is the current date and x is a number from 0 through 9. When the current OMF becomes full, another OMF is created for the current date appended with the next available number.

user-group — The numeric identifier for the user group to be selected. An asterisk (*) can be used to select all user groups. This parameter is optional. If not provided, all user groups and user numbers are selected.

user-num — The numeric identifier for the user number to be selected. An asterisk (*) can be used to select all user numbers in a group. This parameter is optional. If not provided, all user numbers in the specified user group are selected.

DETAIL — This parameter produces the detail version of the report, which includes record images. The word DETAIL must be in uppercase letters.

RUN Commands for the File Access Report

The RUN command formats for the summary and detail versions of the File Access Report are shown below followed by descriptions of the parameters. The only difference between the RUN commands for the summary and detail versions of the report is the presence of the DETAIL parameter.

File Access Summary Report RUN Command Format

```
RUN <report-program-filename>&  
    <OMF-filename>,&  
    <file-id/appl-code>,&  
    <rec-type>,&  
    <user-group>,&  
    <user-num>
```

File Access Detail Report RUN Command Format

```
RUN <report-program-filename>&  
    <OMF-filename>,&  
    <file-id/appl-code>,&  
    <rec-type>,&  
    <user-group>,&  
    <user-num>,&  
DETAIL
```

report-program-filename — The fully-qualified name of the compiled report program, for example: \system.\$volume.ba60obj.barp04.

OMF-filename — The fully-qualified name of the first OMF to be used to produce the report, for example: \system.\$volume.xxxOMFS.Ayymmdd0. This parameter is required for the report to run. If the report is being run again due to a full output file, an OMF file other than the first OMF for the day should be specified. Use the report output to determine the OMF file to use to begin the next report run.

Note: OMF files are created with a file name of Ayymmddx, where yymmdd is the current date and x is a number from 0 through 9. When the current OMF becomes full, another OMF is created for the current date appended with the next available number.

file-id/appl-code — Either the standard BASE24 abbreviation for a file (file ID) or the OMF application code for a file from the OMFTBL. If you specify a file ID, the report program converts it to an application code using the OMFTBL. If there are duplicate entries for a file ID in the OMFTBL, all of the associated application codes are used to select records. An asterisk (*) can be used to select all file IDs. This parameter is optional. If not provided, all file IDs are selected.

rec-type — The type of records to select and, for the detail version of the report, the type of image to include in the report output. The values that can be specified are as follows:

- A = Select records that were added. The detail version of the report includes an image of the record that was added.
- B = Select records that were updated. The detail version of the report includes an image of the record before it was updated.
- C = Select records that were updated. The detail version of the report includes an image of the record after it was updated.
- D = Select records that were deleted. The detail version of the report includes an image of the deleted record.
- E = The record was read. The detail version of the report includes key data from the record after it was read.
- F = The read next function was performed. The detail version of the report includes key data from the record after it was read.
- I = An institution security violation has occurred. A user does not have access for the institution FIID to which the record belongs. The record or records are logged with a file type of I for institution security error.
- J = A file operation security violation has occurred. A user does not have authority for the function attempted. The record or records are logged with a file type of J for file operation security error.
- S = Select logon and logoff records. The detail version of the report includes an image of the logon and logoff records and, for failed logon attempts, information on the reason for the failure.

An asterisk (*) may be used to select all record types. This parameter is optional. If not provided, all record types are selected.

user-group — The numeric identifier for the user group to be selected. An asterisk (*) can be used to select all user groups. This parameter is optional. If not provided, all user groups and user numbers are selected.

user-num — The numeric identifier for the user number to be selected. An asterisk (*) can be used to select all user numbers in a group. This parameter is optional. If not provided, all user numbers in the specified user group are selected.

DETAIL — This parameter produces the detail version of the report, which includes record images. The word DETAIL must be in uppercase letters.

Report Generation

You can generate an OMF audit report after you have modified the associated runfile. To generate a report, volume to the BA60RPT subvolume and use the OBEY command to obey the runfile for the report you want to generate. The format for the OBEY command is shown below followed by a description of the parameter.

```
$<volume> BA60RPT 1> OBEY <runfile>
```

runfile — The name of the generic runfile. The name of the generic runfile for the Logon/Logoff Access Report is BARPT03R. The name of the generic runfile for the File Access Report is BARPT04R.

Depending on the size of the day's OMF files and the specified selection criteria, it may be necessary to run the report more than once. If the output file fills before all of the selected records have been included in the report output, a message indicating that the output file is full displays on the screen. Use the report output to determine the OMF file to use to begin the next report run.

Error Messages

Standard COBOL error messages are displayed on the screen for file handling errors, such as when the program is unable to open the OMF file specified in the runfile or when the output file fills before all of the selected records have been added to the report.

In addition to the standard COBOL error messages, there are messages that are generated by the report programs and can be displayed in the report output. They are described below along with the action, if any, you can take to correct the error.

Specified OMF File Empty

If the OMF file specified in the runfile is empty, the report program produces the following report output:

```
FILENAME PROVIDED: <OMF-filename>
*** NO RECORDS FOUND IN THE OMF FILE SPECIFIED ***
*** END OF REPORT ***
```

You can specify a different OMF file in the runfile and then run the report again.

No OMF File Specified

If the RUN command in the runfile does not include the OMF-filename parameter, the report program produces the following report output:

```
*** NO OMF FILENAME PROVIDED ***
*** END OF REPORT ***
```

You can include the OMF-filename parameter in the runfile and then run the report again.

Selection Criteria Produces No Records

If the selection criteria you specified in the runfile for the Logon/Logoff Access Report does not match any of the records in the specified OMF file, the report program produces the following report output:

```
GRP: <user-group> USER: <user-num>
*** NO REPORTABLE RECORDS MATCH SELECTION CRITERION ***
*** END OF REPORT ***
```

If the selection criteria you specified in the runfile for the File Access Report does not match any of the records in the specified OMF file, the report program produces the following report output:

```
FILE-ID: <file-id> RECORD TYPE: <rec-ty> GRP: <user-group> USER:
<user-num>
*** NO REPORTABLE RECORDS MATCH SELECTION CRITERION ***
*** END OF REPORT ***
```

In both cases, you can specify different criteria in the runfile and then run the report again.

No Record Images for Detail Report

If the DETAIL parameter was included in the RUN command in the runfile and no record images are available, the report program produces the following report output:

```
GRP: <user-group> USER: <user-num>
*** NO RECORD IMAGES AVAILABLE TO PRODUCE DETAIL REPORT ***
*** END OF REPORT ***
```

Verify that the OMF-AUDIT parameter in the LCONF is set to 1.

Report Samples and Field Descriptions

This section contains samples of the summary and detail versions of the Logon/Logoff Access Report and the File Access Report. The summary and detail versions of each report are shown below followed by descriptions of the fields.

Logon/Logoff Access Report

On the following pages are samples of the summary and detail versions of the Logon/Logoff Access Report. Because the labeled fields are the same on both versions of the report, the report samples are followed by a single set of field descriptions. The differences between the summary and detail versions are described below.

- The first line of the summary version contains the identifier OMF03 - SUMMARY. The first line of the detail version contains the identifier OMF03 - DETAIL.
- The title of the summary version is LOGON/LOGOFF ACCESS SUMMARY REPORT. The title of the detail version is LOGON/LOGOFF ACCESS DETAIL REPORT.
- In the detail version of the report, the summary information for each record is followed by the image of each record. The record image is displayed for the length defined in the REC-IMAGE-LEN field. It is displayed across the width of the report with no formatting or conversion of the data fields within the image.

OMF03 - SUMMARY			LOGON/LOGOFF ACCESS SUMMARY REPORT					09 FEB 06		PAGE 00001
INPUT FILE: \K9.\$HOME.VOL10MF.A0509050										
REC NUM	DATE	TIME	GROUP	USER	LOGON/ LOGOFF	LNET	FIID	REGION	BRANCH	TERMINAL ID

000000	050806	1111	255	255	LOGON	DVL1				\pzn018 #PT7CPEP
INPUT FILE: \K9.\$HOME.VOL10MF.A0509058										
REC NUM	DATE	TIME	GROUP	USER	LOGON/ LOGOFF	LNET	FIID	REGION	BRANCH	TERMINAL ID

000001	050806	1314	255	255	LOGOFF	DVL1				\pzn018 #PT7CPEP
INPUT FILE: \K9.\$HOME.VOL10MF.A0509059										
REC NUM	DATE	TIME	GROUP	USER	LOGON/ LOGOFF	LNET	FIID	REGION	BRANCH	TERMINAL ID

000000	050806	1758	255	255	LOGON	DVL1				\pzn018 #PT7CP66
000001	050806	1758	255	255	LOGOFF	DVL1				\pzn018 #PT7CP66
000002	050806	1843	255	255	LOGON	DVL1				\pzn018 #PT7CPG6
000003	050806	1901	255	255	LOGON	DVL1				\pzn018 #PT7CPFQ
000004	050806	2137	255	255	LOGOFF	DVL1				\pzn018 #PT7CPG6
000005	050806	2138	255	255	LOGOFF	DVL1				\pzn018 #PT7CPFQ

[illegible]

INPUT FILE — The fully-qualified name of the first OMF file, as specified in the runfile. This information is displayed at the top of each page.

REC NUM — The record number from the OMF file that contains the information shown for this line of the report. These numbers start over from 0 for each input file. You can use the record number, which is the key to the OMF, to display an individual record or to capture a record image for further analysis. For example, you can use the FUP COPY command with a record number to display the OMF record associated with that record number.

DATE — The date on which the file maintenance operation, the logon attempt, or the logoff was performed. The date is displayed in YYMMDD format.

TIME — The time of day at which the file maintenance operation, the logon attempt, or the logoff was performed. The time is displayed in HHMM format.

GROUP — The numeric identifier for the group to which the user belongs.

USER — The numeric identifier for the user.

LOGON/LOGOFF — If the record is a logon record, LOGON is displayed. If the record is a logoff record, LOGOFF is displayed.

LNET — The identifier for the logical network that the user entered on the Logon screen.

FIID — The identifier for the financial institution for which the user performed file maintenance. This field is always blank.

REGION — The identifier for the region for which the user performed file maintenance. This field is always blank.

BRANCH — The identifier for the branch for which the user performed file maintenance. This field is always blank.

TERMINAL ID — The identifier for the terminal from which the user performed the file maintenance operation, logon attempt, or logoff.

File Access Report

On the following pages are samples of the summary and detail versions of the File Access Report. Because the labeled fields are the same on both versions of the report, the report samples are followed by a single set of field descriptions. The differences between the summary and detail versions are described below.

- The first line of the summary version contains the identifier OMF04 - SUMMARY. The first line of the detail version contains the identifier OMF04 - DETAIL.
- The title of the summary version is FILE ACCESS SUMMARY REPORT. The title of the detail version is FILE ACCESS DETAIL REPORT.
- In the detail version of the report, the summary information for each record is followed by the image of each record. The record image is displayed for the length defined in the REC-IMAGE-LEN field. It is displayed across the width of the report with no formatting or conversion of the data fields within the image.

OMF04 - SUMMARY			FILE ACCESS SUMMARY REPORT					09 FEB 06		PAGE 00001	
INPUT FILE: \K9.\$HOME.VOL10MF.A0509050											
REC NUM	DATE	TIME	FILE ID	RECORD TYPE	GROUP	USER	LN NET	FI ID	REGION	BRANCH	TERMINAL ID

000000	050806	1111	LOGON	S	255	255	DVL1				\pzn018 #PT7CPEP
000001	050806	1116	ATDD1	B	255	255	DVL1	HDFC			\pzn018 #PT7CPEP
INPUT FILE: \K9.\$HOME.VOL10MF.A0509051											
REC NUM	DATE	TIME	FILE ID	RECORD TYPE	GROUP	USER	LN NET	FI ID	REGION	BRANCH	TERMINAL ID

000000	050806	1116	ATDS1	B	255	255	DVL1	HDFC			\pzn018 #PT7CPEP
000001	050806	1116	ATDD1	C	255	255	DVL1	HDFC			\pzn018 #PT7CPEP
INPUT FILE: \K9.\$HOME.VOL10MF.A0509052											
REC NUM	DATE	TIME	FILE ID	RECORD TYPE	GROUP	USER	LN NET	FI ID	REGION	BRANCH	TERMINAL ID

000000	050806	1116	ATDS1	C	255	255	DVL1	HDFC			\pzn018 #PT7CPEP
000001	050806	1150	ATDD1	B	255	255	DVL1	HDFC	WEST	0499	\pzn018 #PT7CPEP
INPUT FILE: \K9.\$HOME.VOL10MF.A0509053											
REC NUM	DATE	TIME	FILE ID	RECORD TYPE	GROUP	USER	LN NET	FI ID	REGION	BRANCH	TERMINAL ID

000000	050806	1150	ATDS1	B	255	255	DVL1	HDFC			\pzn018 #PT7CPEP
000001	050806	1150	ATDD1	C	255	255	DVL1	HDFC	WEST	0499	\pzn018 #PT7CPEP
INPUT FILE: \K9.\$HOME.VOL10MF.A0509054											
REC NUM	DATE	TIME	FILE ID	RECORD TYPE	GROUP	USER	LN NET	FI ID	REGION	BRANCH	TERMINAL ID

000000	050806	1150	ATDS1	C	255	255	DVL1	HDFC			\pzn018 #PT7CPEP
000001	050806	1154	ATDD1	B	255	255	DVL1	HDFC	WEST	0499	\pzn018 #PT7CPEP
INPUT FILE: \K9.\$HOME.VOL10MF.A0509055											
REC NUM	DATE	TIME	FILE ID	RECORD TYPE	GROUP	USER	LN NET	FI ID	REGION	BRANCH	TERMINAL ID

000000	050806	1154	ATDS1	B	255	255	DVL1	HDFC			\pzn018 #PT7CPEP
000001	050806	1154	ATDD1	C	255	255	DVL1	HDFC	WEST	0499	\pzn018 #PT7CPEP

OMF04 - DETAIL

REC	DATE	TIME	FILE	RECORD	GROUP	USER	LNET	FIID	REGION	BRANCH	TERMINAL ID
-----	------	------	------	--------	-------	------	------	------	--------	--------	-------------

000000	050806	1111	LOGON	S	255	255	DVL1	\pzn018 #PT7CPEP
--------	--------	------	-------	---	-----	-----	------	------------------

[illegible]

INPUT FILE — The fully-qualified name of the first OMF file, as specified in the runfile. This information is displayed at the top of each page.

REC NUM — The record number from the file that contains the information shown for this line of the report. These numbers start over from 0 for each input file. You can use the record number, which is the key to the OMF, to display an individual record or to capture a record image for further analysis. For example, you can use the FUP COPY command with a record number to display the OMF record associated with that record number.

DATE — The date on which the file maintenance operation, the logon attempt, or the logoff was performed. The date is displayed in YYMMDD format.

TIME — The time of day at which the file maintenance operation, the logon attempt, or the logoff was performed. The time is displayed in HHMM format.

FILE ID — The standard BASE24 abbreviation for a file. OMF records are written with an application code. The OMFTBL is used to convert the application code to a standard abbreviation for display in this field.

RECORD TYPE — Identifies the type of record as defined in the OMF record structure and, for the detail version of the report, the type of image included in the report output. The values that can be displayed in this field are as follows:

- A = The record was added. The detail version of the report includes an image of the record that was added.
- B = The record was updated. The detail version of the report includes an image of the record before it was updated.
- C = The record was updated. The detail version of the report includes an image of the record after it was updated.
- D = The record was deleted. The detail version of the report includes an image of the deleted record.
- E = The record was read. The detail version of the report includes key data from the record after it was read.
- F = The read next function was performed. The detail version of the report includes key data from the record after it was read.

- I = An institution security violation has occurred. A user does not have access for the institution FIID to which the record belongs. The record or records are logged with a file type of I for institution security error.
- J = A file operation security violation has occurred. A user does not have authority for the function attempted. The record or records are logged with a file type of J for file operation security error.
- S = The record is either a logon or logoff record. The detail version of the report includes an image of the logon or logoff record and, for failed logon attempts, information on the reason for the failure.

GROUP — The numeric identifier for the group to which the user belongs.

USER — The numeric identifier for the user.

LNET — The identifier for logical network that the user entered on the Logon screen.

FIID — The identifier for the financial institution for which the user performed file maintenance. For logon and logoff records, this field is blank.

REGION — The identifier for the region for which the user performed file maintenance. For logon and logoff records, this field is blank.

BRANCH — The identifier for the branch for which the user performed file maintenance. For logon and logoff records, this field is blank.

TERMINAL ID — The identifier for the terminal from which the user performed the file maintenance operation, logon attempt, or logoff.

Index

A

- Access Privileges Report, [6-1](#)
- Acronyms, BASE24 file/function, [1-12](#)
- ATM Product Menu items
 - ATD (ATM Terminal Data files), [4-12](#)
 - BSF (Bin Sort File), [4-12](#)
 - CCF (Corporate Check File), [4-13](#)
 - CSF (Check Status File), [4-13](#)
 - OIF (Operator Identification File), [4-13](#)
 - RCPT (Receipt File), [4-13](#)
 - RPT (ATM Report screens), [4-13](#)
 - TLF (Transaction Log File), [4-13](#)
 - TRF (Terminal Receipt File), [4-13](#)
- Audit reports
 - Access Privileges Report, [6-1](#)
 - File Access Report, [6-1](#)
 - introduction, [6-1](#)
 - Last Logon Report, [6-1](#)
 - Logon/Logoff Access Report, [6-1](#)
 - OMF audit reports, [6-19](#)
 - Security audit reports, [6-2](#)

B

- Base Product Menu items
 - APCF (Acquirer Processing Code File), [4-15](#)
 - ARF (Account Routing File), [4-16](#)
 - ATT (Account Type Table File), [4-16](#)
 - CAF (Cardholder Authorization File), [4-16](#)
 - CPF (Card Prefix File), [4-16](#)
 - DCCD (Dynamic Currency Conversion Data File), [4-16](#)
 - ECF (Extract Configuration File), [4-16](#)
 - EMF (External Message File), [4-16](#)
 - ERF (Exchange Rate File), [4-17](#)
 - HCF (Host Configuration File), [4-17](#)
 - ICF (Interchange Configuration File), [4-17](#)
 - ICFE (Enhanced Interchange Configuration File), [4-17](#)
 - IDF (Institution Definition File), [4-17](#)
 - IPCF (Issuer Processing Code File), [4-18](#)
 - KEY6 (KEY6 File), [4-18](#)
 - KEYA (Key Authorization File), [4-18](#)
 - KEYD (Derivation Key File), [4-18](#)
 - KEYF (Key File), [4-18](#)
 - KEYI (EMV Key File), [4-18](#)
 - LNCF (Logical Network Configuration File), [4-19](#)
 - NCSF (Network Control Supervisor Profile File), [4-19](#)

- NEG (Negative Card File), [4-19](#)
- PBF (Positive Balance File), [4-19](#)
- PDF (Processing Code Description File), [4-19](#)
- PRE (Prefix File Build Utility screen), [4-20](#)
- SEC (Security screens), [4-20](#)
- SPF (Stop Payment File), [4-20](#)
- STF (Switch Terminal File), [4-20](#)
- SURF (Surcharge File), [4-20](#)
- TCF (Transaction Code File), [4-20](#)
- TKN (Token File), [4-21](#)
- UAF (Usage Accumulation File), [4-21](#)
- BASE24-atm self service banking (SSB)
 - Check Status File (CSF), [4-13](#)
 - Corporate Check File (CCF), [4-13](#)
- BASE24-atm self-service banking (SSB)
 - Bin Sort File (BSF), [4-12](#)
- Billpay Product Menu items
 - BKAV (Bank Transaction Advice Table), [4-23](#)
 - BKBR (Bank Branch Table), [4-23](#)
 - BKNT (Bank Notice Table), [4-24](#)
 - BLG (Billing Group Table), [4-24](#)
 - BLRT (Billing Rate Table), [4-24](#)
 - BLTY (Billing Type Table), [4-24](#)
 - CBPT (Customer Billpay Table), [4-24](#)
 - CLPT (Cleanup Configuration Table), [4-24](#)
 - CVND (Customer Vendor Table), [4-24](#)
 - HIST (Billpay History Table), [4-25](#)
 - RATE (Rate Table), [4-25](#)
 - RATG (Rate Group Table), [4-25](#)
 - RTRY (Retry Table), [4-25](#)
 - RTXT (Response Text Table), [4-25](#)
 - SVPT (Service Provider Table), [4-26](#)
 - VBUD (Vendor Budget Category Table), [4-26](#)
 - VNDB (Vendor Branch Table), [4-26](#)
 - VNDM (Vendor Mask Table), [4-26](#)
 - VNDR (Vendor Table), [4-26](#)
- BY USER field, [2-4](#)

C

- Card Management Product Menu items
 - CLST (Cardholder List Functions terminal), [4-28](#)
 - CMF (Card Management Functions terminal), [4-28](#)
 - COF (Card Operator Functions terminal), [4-28](#)
- Check Authorization User Menu items
 - CUST (Customer Information screens), [4-30](#)
 - SDT (Summarized Detail Perusal screen), [4-30](#)
 - TDT (Transaction Detail Perusal screen), [4-30](#)
 - VELO (Velocity by ID screens), [4-30](#)

Check Disbursements User Menu items
 DADR (Refund Check Address Update screen), [4-32](#)
 DAID (Refund Check Activity by ID screen), [4-32](#)
 DANM (Refund Check Activity by Name screen), [4-32](#)
 DARC (Check Activity by Refund Check Info screen), [4-32](#)
 DARI (Check Activity by Refund Info screen), [4-32](#)
 DASI (Refund Check Activity by Store Info screen), [4-32](#)
 DGLE (General Ledger Event screen), [4-32](#)
 DMCK (Manual Check Reference screen), [4-33](#)
Command profiles, copying records, [5-58](#)
Command security, auditing, [5-12](#)
Core Product Menu items
 CATT (Customer Allowed Transaction Table), [4-35](#)
 CSRC (Customer Service Representative screens), [4-35](#)
 CSTT (Customer Table), [4-36](#)
 FCF (File Control File), [4-36](#)
 IMTF (Internal Message Translation File), [4-36](#)
 IRCF (Institution Routing Configuration File), [4-36](#)
 ISF (Interface Security File), [4-37](#)
 ITLF (ITS Transaction Log File), [4-37](#)
 LCF (Log Configuration File), [4-37](#)
 PCDF (Processing Code Definition File), [4-37](#)
 PIT (Personal Information Table), [4-38](#)
 THCF (Transaction History Configuration File), [4-38](#)
 TTSC (Transaction Type By Source Code Table), [4-38](#)
 VCD (VRU Configuration Data screens), [4-38](#)
Customer Service Product Menu items
 CCIF (Customer/Cardholder Information File), [4-40](#)
 CIS (Customer Information Tables), [4-40](#)
 CSTP (Customer Service Transaction Perusal screens), [4-40](#)

D

Data Name caption, [2-13](#)
Default Value caption, [2-12](#)

E

Enscribe terminology, [vii](#), [2-13](#)

F

Field descriptions
 BASE24 Logon screen, [3-2](#)
 NCSP screen, [5-50](#)
 SEC screen 1, [5-20](#)
 SEC screen 2, [5-29](#)
 SEC screen 3, [5-33](#)
 SEC screen 4, [5-38](#)
Field Length caption, [2-12](#)
File Access Report, [6-1](#)
FILE DESTINATION field, [1-9](#), [1-12](#)

Files, moving to new, [1-9](#)
Frequent Shopper User Menu items
 CRAT (Customer Retailer Activity Inquiry screen), [4-42](#)
 DEMO (Demographics Maintenance screen), [4-42](#)
 DPND (Dependents Maintenance screen), [4-42](#)
 IDST (ID Status/Maintenance screen), [4-42](#)
 JID (Joined ID Status/Maintenance screen), [4-42](#)
 MHIS (Move ID History Maintenance screen), [4-42](#)
 NAMS (Name Search screen), [4-42](#)
 PHIS (Purchase History screen), [4-43](#)
 VADJ (Value Adjustment screen), [4-43](#)

Function keys

 NCSP function assignments, [5-52](#)
 SEC screen 1 function assignments, [5-26](#)
 SEC screen 2 function assignments, [5-30](#)
 SEC screen 3 function assignments, [5-35](#)
 SEC screen 4 function assignments, [5-46](#)
 standard function assignments, [2-17](#)

H

Help screens
 file and table, [2-15](#)
 menu, [2-14](#)
Hypercom Device Handler
 Hypercom Configuration File (HPCF), [4-58](#)
 Hypercom T7 Configuration File (HPTC), [4-58](#)

K

Kernel Product Menu items
 AORF (Assign/Object Relationship File), [4-45](#)
 APRF (Assign/Process Type Relationship File), [4-45](#)
 ASGN (Assign File), [4-46](#)
 AWB (Assign Warmboot screens), [4-46](#)
 CCS (Configuration Control screens), [4-46](#)
 DBG (Debug screen), [4-46](#)
 DEST (Destination File), [4-46](#)
 EMT (Extended Memory Table File), [4-46](#)
 EORF (EMT/Object Relationship File), [4-46](#)
 EPRF (EMT/Process Type Relationship File), [4-47](#)
 ESF (Event Suppression File), [4-47](#)
 EWB (EMT Warmboot screens), [4-47](#)
 LPF (Log Permission Process Partition File), [4-47](#)
 LWB (LCONF Warmboot screen), [4-47](#)
 OBJ (Object File), [4-47](#)
 PORF (Process/Object Relationship File), [4-47](#)
 PRO (Process File), [4-48](#)
 PTF (Process Type File), [4-48](#)
 PWB (Param Warmboot screen), [4-48](#)
 SCM (Source Class Map File), [4-48](#)
 SCS (Server Control screens), [4-48](#)
 SCT (Server Class Type File), [4-48](#)
 SPRF (Server Class Type/Process Relationship File), [4-49](#)
 STAT (Status screens), [4-49](#)
 TRC (Trace Control screens), [4-49](#)

L

Last Logon Report, [6-1](#)
 Logical network, moving to new, [1-11](#)
 Logon screen, BASE24
 accessing from TACL, [3-1](#)
 changing password, [3-10](#)
 configuring password, [3-8](#)
 field descriptions, [3-2](#)
 logging on, [3-7](#)
 moving to file or function from, [3-10](#)
 screen illustration, [3-2](#)
 Logon/Logoff Access Report, [6-1](#)

M

Mail Product Menu items
 HMBF (Host Mail Box File), [4-51](#)
 MBAF (Mail Box Address File), [4-51](#)
 MBF (Mail Box File), [4-51](#)
 SMA (Send Mail Terminal), [4-51](#)
 Menus, BASE24
 ATM Product Menu, [4-11](#)
 Base Product Menu, [4-14](#)
 Billpay Product Menu, [4-22](#)
 Card Management Product Menu, [4-27](#)
 Check Authorization User Menu, [4-29](#)
 Check Disbursements User Menu, [4-31](#)
 Core Product Menu, [4-34](#)
 Customer Service Product Menu, [4-39](#)
 Frequent Shopper User Menu, [4-41](#)
 how to access, [4-1](#)
 Kernel/IEP Product Menu, [4-44](#)
 Mail Product Menu, [4-50](#)
 Operator Product Menu, [4-52](#)
 POS Product Menu, [4-54](#)
 product menus, [1-6](#), [4-10](#)
 Refunds User Menu, [4-61](#)
 Retail Configuration Menu, [4-64](#)
 structure of, [1-4](#), [4-2](#)
 Teller Product Menu, [4-68](#)
 Virtual Menu, [1-6](#), [4-5](#)
 Merchant Host Interface
 Merchant Host Configuration File (MHCF), [4-58](#)
 Merchant Terminal Configuration File (MCNF), [4-58](#)
 Merchant Terminal Response Display File (MRSP), [4-59](#)
 Merchant Totals Configuration File (MTCF), [4-59](#)

N

NCSP
 see Network Control Supervisor Profile File (NCSP)
 NCSS
 see Network Control Supervisor Security File (NCSS)
 Network control command security, [5-10](#)
 Network Control Supervisor Profile File (NCSP)
 adding records, [5-55](#)
 command access limitations, [5-49](#)

 command auditing, [5-49](#)
 field descriptions, [5-50](#)
 function keys, [5-52](#)
 introduction, [5-49](#)
 screen illustration, [5-50](#)

Network Control Supervisor Security File (NCSS)
 assigning security records, [5-37](#)
 command profiles, [5-37](#)
 New file, moving to a, [3-10](#)
 NEW LOGICAL NETWORK ID field, [1-11](#)
 NEW PAGE field, [1-8](#)

O

OMF audit reports, [6-19](#)
 File Access Report, [6-1](#)
 Logon/Logoff Access Report, [6-1](#)
 Operator Product Menu items
 DCT (Device Control screens), [4-53](#)
 EXTR (Extract screens), [4-53](#)
 LMCF (Log Message Configuration File), [4-53](#)
 NCS (Network Control Supervisor screen), [4-53](#)
 REFR (Refresh screens), [4-53](#)
 XNI (X.25 Network Inquiry screen), [4-53](#)

P

Pages, moving to new, [1-8](#)
 Password
 complex password, [3-8](#)
 complex password parameter restriction, [3-9](#)
 configuring, [3-8](#)
 how to change, [3-10](#)
 reinstating locked out users, [5-64](#)
 standard password, [3-8](#)
 POS Product Menu items
 ACNF (ACI Standard Device Configuration File), [4-56](#), [4-57](#), [4-58](#), [4-59](#), [4-60](#)
 ADMN (Administrative Card File), [4-56](#)
 ARSP (ACI Standard Device Response File), [4-56](#)
 AST (Authorization Selection Table File), [4-56](#)
 CAPF (Card Authorization Parameters File), [4-56](#)
 CART (Check Authorization Routing Table File), [4-57](#)
 CHF (Card History File), [4-57](#)
 CRED (Credibility History screen), [4-57](#)
 CRTA (CRT Administration Maintenance screens), [4-57](#)
 CRUF (CRT Authorization Retailer Usage File), [4-57](#)
 CSEC (CRT Authorization Security File), [4-58](#)
 HPCF (Hypercom Configuration File), [4-58](#)
 HPTC (Hypercom T7 Configuration File), [4-58](#)
 MCNF (Merchant Terminal Configuration File), [4-58](#)
 MHCF (Merchant Host Configuration File), [4-58](#)
 MREG (Merchant Regulation E File), [4-58](#)
 MRF (Multiple Referrals screen), [4-58](#)
 MRSP (Merchant Terminal Response Display File), [4-59](#)
 MTCF (Merchant Totals Configuration File), [4-59](#)

POS Product Menu items *continued*

- NNF (National Negative Card File), [4-59](#)
- OLT (Online Transaction screen), [4-59](#)
- PRDF (POS Retailer Definition File), [4-59](#)
- PRF (POS Referral File), [4-59](#)
- PRG (POS Report Generator screen), [4-59](#)
- PTD (POS Terminal Data files), [4-60](#)
- PTLF (POS Transaction Log File), [4-60](#)
- RTBL (Routing Table File), [4-60](#)
- SVHF (Stored Value History File), [4-60](#)
- VVT (VISA II Terminal and Configuration Maintenance File), [4-60](#)

Product menus, how to access, [4-10](#)

R

RECORD LAST CHANGED field, [2-4](#)

Refunds User Menu items

- ACTA (Refund Activity by Address screen), [4-62](#)
- ACTF (Refund Activity by Refund Info screen), [4-62](#)
- ACTI (Refund Activity by ID screen), [4-62](#)
- ACTP (Refund Activity by Orig Purchase screen), [4-62](#)
- CMTS (Comments screen), [4-62](#)
- NSEA (Name Search screen), [4-62](#)
- SPAS (Secondary to Primary Address Swap screen), [4-63](#)
- VREF (Mail Refund Transactions screen), [4-63](#)
- VSAL (View Original Sales History screen), [4-63](#)

Required Field caption, [2-12](#)

Retail Configuration Menu items

- ACT (Application Configuration screen), [4-65](#)
- ART (Authorization Routing screen), [4-65](#)
- EACT (External Authorization Configuration screen), [4-65](#)
- FSCS (Funding Scheme Configuration screen), [4-65](#)
- IDTD (ID Type Configuration screen), [4-65](#)
- LCT (Check Authorization Limits Configuration screens), [4-66](#)
- MERC (Merchant Interface Configuration screen), [4-66](#)
- MSG (Error Message Configuration screen), [4-66](#)
- PCDU (Postal Code Update screen), [4-66](#)
- RATD (Rating Configuration screens), [4-66](#)
- RETL (Retailer Configuration screens), [4-66](#)
- RLCT (Refund Limits Configuration screen), [4-67](#)
- STOR (Store Configuration screen), [4-67](#)
- STPD (State/Province Configuration screen), [4-67](#)

S

Screen documentation, BASE24

- Column Name caption, [2-13](#)
- Data Name caption, [2-13](#)
- Default Value caption, [2-12](#)
- Field Length caption, [2-12](#)
- Required Field caption, [2-12](#)

Screen messages, BASE24, [2-16](#)

Screen organization, BASE24, [2-2](#)

Screen types, BASE24

- files maintenance screens, [2-7](#)
- operator command screens, [2-8](#)
- tables maintenance screens, [2-7](#)

Screens, BASE24

- documentation, [2-9](#)
- help screens, [2-14](#)
- how to access, [4-1](#)
- Logon screen, [1-6](#), [3-1](#)
- moving to new, [1-8](#)
- organization, [1-6](#), [2-2](#)
- screen messages, [2-16](#)
- types, [2-6](#)

SEC

see Security File (SEC)

SEC screen 1

- field descriptions, [5-20](#)
- function keys, [5-26](#)
- introduction, [5-19](#)
- screen illustration, [5-20](#)

SEC screen 2

- field descriptions, [5-30](#)
- function keys, [5-30](#)
- introduction, [5-29](#)
- screen illustration, [5-29](#)

SEC screen 3

- field descriptions, [5-33](#)
- function keys, [5-35](#)
- introduction, [5-32](#)
- screen illustration, [5-33](#)

SEC screen 4

- field descriptions, [5-38](#)
- function keys, [5-46](#)
- introduction, [5-37](#)
- screen illustration, [5-38](#)

Security

- enabling, [5-11](#)
- see also* Command profiles

Security audit reports, [6-2](#)

- Access Privileges Report, [6-1](#)
- Last Logon Report, [6-1](#)

Security File (SEC)

- SEC screen 1, [5-19](#)
- SEC screen 2, [5-29](#)
- SEC screen 3, [5-32](#)
- SEC screen 4, [5-37](#)

Security records

- adding identical records, [5-61](#)
- adding new records, [5-58](#)
- deleting records, [5-65](#)
- reinstating records, [5-64](#)
- updating records, [5-57](#), [5-62](#)

Security, BASE24

- adding an identical security record, [5-61](#)
- adding NCSP records, [5-55](#)
- adding security records, [5-58](#)
- assigning BASE24 access, [5-13](#)
- complex password parameter restriction, [3-9](#)
- deleting security records, [5-65](#)

Security, BASE24 *continued*

- files, [5-3](#)
- reinstating BASE24 access, [5-64](#)
- restricting BASE24 access, [5-3](#)
- screens, [5-49](#)
- SEC screen 1, [5-19](#)
- SEC screen 2, [5-29](#)
- SEC screen 3, [5-32](#)
- SEC screen 4, [5-37](#)
- updating NCSP records, [5-57](#)
- updating security records, [5-62](#)

SQL terminology, [vii](#), [2-13](#)

System-protected fields, [2-5](#)

T

TACL, accessing Logon screen from, [3-7](#)

Teller Product Menu items

- NBF (No Book File), [4-69](#)
- ORF (Override Response File), [4-69](#)
- TRPT (Teller Report Generator screen), [4-69](#)
- TTDF (Teller Terminal Data File), [4-69](#)
- TTF (Teller Transaction File), [4-69](#)
- TTLF (Teller Transaction Log File), [4-70](#)
- WHFF (Warning/Hold/Float File), [4-70](#)

U

User access system functions, [1-2](#)

User terminal functions, [2-17](#)

V**Virtual Menu items**

- ATM (ATM Product Menu), [4-6](#)
- BASE (Base Product Menu), [4-6](#)
- BILLPAY (Billpay Product Menu), [4-6](#)
- CARD MANAGEMENT (Card Management Product Menu), [4-7](#)
- CHECK AUTHORIZATION (Check Authorization User Menu), [4-7](#)
- CHECK DISBURSEMENTS (Check Disbursements User Menu), [4-7](#)
- CORE (Core Product Menu), [4-7](#)
- CUSTOMER SERVICE (Customer Service Product Menu), [4-7](#)
- FREQUENT SHOPPER (Frequent Shopper User Menu), [4-7](#)
- KERNEL/IEP (Kernel/IEP Product Menu), [4-8](#)
- MAIL (Mail Product Menu), [4-8](#)
- OPERATOR FUNCTIONS (Operator Product Menu), [4-8](#)
- POS (POS Product Menu), [4-8](#)
- REFUNDS (Refunds User Menu), [4-8](#)
- RETAIL CONFIGURATION (Retail Configuration Menu), [4-8](#)
- TELLER (Teller Product Menu), [4-9](#)

Virtual Menu, BASE24

- how to access, [4-5](#)
- menu items, [4-6](#)

VISA II Device Handler, VISA II Terminal and Configuration Maintenance File (VVT), [4-60](#)

ACI Worldwide, Inc.