

MERCHANT LINK



ML RELEASE 6.0

INSTALLATION GUIDE

Version A

This document contains **PROPRIETARY** and **CONFIDENTIAL** information and such information may not be disclosed to others for any purpose without written permission from:

ACI Worldwide (Canada) Inc.

200 Wellington Street West,
Suite 700,
Toronto, Ontario M5V 3C7
(416) 813-3000

©2004 by ACI Worldwide (Canada) Inc.

All rights reserved. All information contained in this manual is confidential and proprietary to ACI Worldwide Inc. and has been delivered for use pursuant to license. No part of this manual may be photocopied, electronically transferred, modified, or reproduced in any manner that is contrary to license without the prior written consent of ACI Worldwide Inc.

ACI, ACI Worldwide, ACI Worldwide Inc., BASE24, BASE24-atm, BASE24-atm non-currency dispense, BASE24-atm self-service banking, BASE24-billpay, BASE24-CARD, base24-check auth, BASE24-debit/credit auth, BASE24-fraud control, BASE24-frequent shopper, BASE24-from host maintenance, BASE24-gift certificates, BASE24-InfoBase, BASE24-mail, BASE24-pos, BASE24-refunds auth, BASE24 Remote Banking, BASE24-telebanking, BASE24-teller, BASE24 Visa Cash, CO-ach, ICE, NET24, NET24-XPNET, Perfmon, and TSA are trademarks or registered trademarks of ACI Worldwide Inc., Transaction Systems Architects, Inc., or their subsidiaries.

Other companies' trademarks, service marks or registered trademarks and service marks are trademarks, service marks or registered trademarks and service marks of their respective companies.

REVISION HISTORY

Record of Changes

Author	Date	Version	Comments
M. Eaton	Apr 2004	A	Initial Version for Release 6.0

Change Control Index

Change Control Reference	Description of Change	Modules Effected

TABLE OF CONTENTS

<u>1.</u>	<u>INTRODUCTION.....</u>	<u>1</u>
<u>1.1</u>	<u>DOCUMENT SCOPE</u>	<u>1</u>
<u>2.</u>	<u>INTRODUCTION TO THE MERCHANT LINK.....</u>	<u>2</u>
<u>2.1</u>	<u>ML DESCRIPTION</u>	<u>2</u>
<u>3.</u>	<u>BASE24 ML INSTALLATION</u>	<u>3</u>
<u>4.</u>	<u>THE ML 6.0 RELEASE</u>	<u>4</u>
<u>4.1</u>	<u>PROCESSES</u>	<u>4</u>
<u>4.2</u>	<u>NEW AFT SCREENS</u>	<u>5</u>
<u>4.2.1</u>	<u><i>The MLCF Requester</i>.....</u>	<u>5</u>
<u>4.2.2</u>	<u><i>The MLMF Screen</i>.....</u>	<u>7</u>
<u>5.</u>	<u>BASE24 FILE UPDATES</u>	<u>8</u>
<u>5.1</u>	<u>LNCF.....</u>	<u>8</u>

1. INTRODUCTION

This document is intended as a guideline for the installation of Merchant Link (ML) interface.

1.1 Document Scope

The purpose of this document is to specify the installation steps which are specific to the ML.

The user of this document should have knowledge of the Tandem environment.

This document has **NOT** been designed with a specific BASE24 customer or particular network environment in mind.

2. INTRODUCTION TO THE MERCHANT LINK


2.1 ML Description

Merchant Link enables Canadian merchants to link up their BASE24-pos system to the Interac Debit network or to other Credit Networks.

The ML product consists of the following items:

1. A standard SPDH/Router/Auth to handle ML transactions
2. Two separate ML interface modules, one for the acquirer and one for the acquirer
3. A Merchant Log Configuration File (MLCF) which keeps the static configuration information for the Merchant Link
4. A Merchant Totals File (MTF) that is used to accumulate totals for all transactions
5. A Merchant Link Mapping File (MLMF) that is used to change the name of a terminal, so that two merchants can have the same terminal ID, but go to different terminals on the acceptor
6. A Store and Forward transaction file

The entire system is shown below



3. *BASE24 ML INSTALLATION*

The global make will create FUP directives to create the following ML specific files:

- The ML SAF file (Merchant Link Store and Forward File)
- The MLCF (Merchant Link Configuration File)
- The MLMF (Merchant Link Mapping File)
- The MTF (Merchant Totals Files)

> volume to your system data subvol (i.e TESTDATA)

> fup / in sw60ml.ddlfup, out \$s.#mlfup/

Verify the creation of the your data files in the correct location with appropriate file attributes.

4. *THE ML 6.0 RELEASE*

4.1 Processes

In order to implement the Merchant Link two processes have been created:

- (1) The acquirer process, which will receive transactions from the point of sale.
- (2) The acceptor process, which will be responsible for authorizing the transactions.

Both of these processes will be built automatically by the installation procedure.

4.2 New AFT Screens

4.2.1 The MLCF Requester

In order to configure the Merchant Link then you will need to configure at least one MLCF record per ML process. The MLCF contains information on how the link is configured, what the format of the messages will be, how far back totals will be kept and whether pinpad mapping will be done (this can only be done on the acceptor process).

The MLCF is updated by using the MLCF requester/server.

BASE24-POS	MERCHANT CONFIGURATION	MAC1	04/02/23	15:28	01 OF 01
	DPC NUMBER: 1111	ML NAME:	P1A^ML		
	TIMER LIMITS		PROCESSING FLAGS		
	NETWORK MANAGEMENT: 30 (SEC)		NMM ENABLED: Y (Y/N)		
	EXTENDED NETWORK: 360 (SEC)		PIN PAD ID MAP: Y (Y/N)		
	WAIT FOR TRAFFIC: 360 (SEC)		AUTO SIGNON START: N (Y/N)		
	PERFORMANCE PERIOD: 20 (MIN)		MAXIMUM TIMEOUTS: 9		
	INBOUND: 30 (SEC)		TOTALS RETENTION: 07 (DAYS)		
	OUTBOUND: 30 (SEC)		MAX SAF RETRIES: 3		
	STORE AND FORWARD: 180 (SEC)		EXT MESSAGE FORMAT: 2 (ISO TEXT)		
MAX OUTSTANDING	OUTBOUND: 15		AUTH PROCESS: P1A^SPDH		
	INBOUND: 10				
STATIONS:	S1A^ML				
RECORD LAST CHANGED:	00/02/02 16:12	BY USER:	0255 , 00000255	CHANGE	
*****	***** BASE24	*****	*****	*****	
NEW PAGE:	FILE DESTINATION:	NEW LOGICAL NETWORK ID:			
	F12-HELP				
RECORD RETRIEVED FROM	\ACCIS1.\$CDN60.MAC1DATA.MLCF			0000	

The following fields are defined on the MLCF screen:

Field	Description
Timer – Network Management	Number of seconds the ML interface will wait for a reply to a network management message.
Timer – Extended Network	After the above timer expires then the ML interface will wait this number of seconds before retrying it sends another Network Management Message
Timer – Wait For Traffic	Number of seconds with no traffic before an echo test message will be sent to keep the line active
Timer - Performance	Number of minutes that performance statistics will be kept for
Counter Inbound	Number of seconds that the ML will wait before sending a declined message at the acquirer DPC
Outbound	Number of seconds that the ML will wait before timing out the transaction to the originating terminal,
SAF	The number of seconds that the ML interface will wait before attempting to send the message again.
Station (16 occurrences)	Specifies all of the stations that can be by this ML interface.
Maximum Timeouts	The number of times that a station can time out before being marked down.
Maximum Pending – Inbound	The maximum number of inbound concurrent messages that can be handled.
Maximum Pending – Outbound	The maximum number of outbound concurrent messages that can be handled.
NMM Enabled	Determines if the ML interface processes will exchange Network Management Messages. (Y/N)
Pin Pad ID Map	Determines if the ML interface processes will map pinpad ID's, (this assumes that the MLMF is set up). Valid values are Y/N.
Totals Retention	Number of days that totals will be kept in the MTF
Ext Message Format	The method that the ML interface will use to communicate with. Valid values are: 1 – MLSPDH format 2 – ISO Text Mode 3 – ISO Binary Mode 4 – ISO Text Mode (Bank of Montreal version) 5 – ISO Binary Mode (Bank of Montreal Version)
Auth Process	The SPDH process that will receive the replies.

4.2.2 The MLMF Screen

The MLMF is used to allow the acceptor to re map the terminal name from one that makes sense to the acquirer to one that is unique to the acceptor.

The screen is organized by DPC, allowing all terminals from a single DPC to be remapped appropriately.

BASE24-POS	MERCHANT MAPPING	MAC1	04/02/23	16:59	01 OF 01
DPC NUMBER: 1111					
ACQUIRER PIN PAD ID: OLDPINPAD					
MAPS TO - ACCEPTOR PIN PAD ID: NEWPINPAD					
RECORD LAST CHANGED: 00/01/31 15:08 BY USER: 0255 , 00000255 ADD					
***** BASE24 *****					
NEW PAGE: FILE DESTINATION: NEW LOGICAL NETWORK ID:					
F12-HELP					
RECORD RETRIEVED FROM \ACCIS1.\$CDN60.MAC1DATA.MLMF 0000					

Field	Description
DPC	Contains the Data Processing Center for which this mapping applies to
OLDPINPAD	Contains the old terminal ID that will be used
NEWPINPAD	Contains the new terminal ID (or Pinpad) that will be used to verify the transaction.

5. *BASE24 FILE UPDATES*

5.1 LNCF

The Logical Network Configuration file (LNCF) contains all assigns and parameters for all BASE24 Classic products.

Alter the LNCF assigns and parameters according to your products, modules and processing needs. We have supplied all the assigns and parameters that will be used for Merchant Link processing.

The following Assigns must be set for the ML Interface processes:

Assign	Module	Explanation/Value
POS-MTF	ML Interface	Assigns the file that will be used to keep the Merchant Totals
POS-MMF	ML Interface	Assigns the file that will be used to allow the acceptor to re map a Pinpad from the acceptor to the acquirer.
POS-MLCF	ML Interface	Assigns the file that will be used to hold information concerning the ML interface processes.
LMCF	ML Interface	Assigns the standard Base24 file that is used to change the text of a message
SAF	ML Interface	Assigns the ML specific file that is used to keep the Store and Forward (SAF) transactions.

The following Parameters should be set:

Parameter Name	Module	Value
Internal-Trace-Bits:		Turns on the trace bits used for tracing the internal state of the ML interface. Default is '0'.
ML-MAX-SUSPENSE		Determines the maximum number of transactions that can be kept in suspense at any one time. See "ML-SUSP-NOTIFY-PERCENT" below. Default is 128.
ML-PRODUCTION-TEST		Determines if the interface is in production or in test mode Default is "PRODUCTION".
ML-MERCHATNT-ID		Specifies the Merchant Id to be used for Bank of Montreal Debit ISO only. The value is a 12 digit number. Default value is "000000000000"
ML-MERCHANT-ID-CR		Specifies the Merchant Id to be used for Bank of Montreal Credit ISO only. The value is a 12 digit number. Default value is "000000000000"
ML-SUSP-NOTIFY-PERCENT		Determines at what percent full the SAF transactions must be before a warning message is sent to the logger. Value should range between 1 and 100. Default value is 100.
POS-LN-CUTOVER	ML Interface	This is the POS cutover time. If none is specified then 12:00 will be used as default.